Plan 9[™]

Programmer's Manual Volume 1

Fourth Edition 2002

Computing Science Research Center Bell Laboratories Lucent Technologies Murray Hill, New Jersey Copyright © 2002 Lucent Technologies Inc. All Rights Reserved. Portions Copyright © 2000, 1998, 1995 Aladdin Enterprises. All Rights Reserved. Portions Copyright © 1994 by Sun Microsystems Computer Company. All rights reserved. Portions Copyright © 2000 Compaq Computer Corporation. Portions Copyright © 1999, Keith Packard.

Cover Design: Gerard J. Holzmann

Trademarks referenced in this document:

Plan 9 is a trademark of Lucent Technologies Inc. Aladdin Ghostscript is a trademark of Aladdin Enterprises. ARM is a trademark of ARM Limited. Avanstar is a registered trademark of Star Gate Technologies, Inc. CGA and VGA are trademarks of International Business Machines Corporation. Silicon Graphics, IRIS Indigo, IRIS, IRIX, Challenge, and Indigo are registered trademarks of Silicon Graphics, Inc. Indy and POWER Series are trademarks of Silicon Graphics, Inc. Ethernet is a trademark of Xerox Corporation. IBM, PS/2, and PowerPC are registered trademarks of International Business Machines Corporation. Intel and Pentium are registered trademarks of Intel Corporation. 8088, 80286, 80386, and 80486 are trademarks of Intel Corporation. Lucida is a registered trademark of Bigelow & Holmes. Pellucida is a trademark of Bigelow & Holmes. MIPS, R3000, R4000, and R4400 are registered trademarks of MIPS Technologies, Inc. R2000 and R6000 are trademarks of MIPS Technologies, Inc. Microsoft, Microsoft Word and Microsoft Office, and MS-DOS are registered trademarks of Microsoft Corporation. NFS is a registered trademark of Sun Microsystems, Inc. PDP and VAX are registered trademarks of Digital Equipment Corp. PostScript is a registered trademark of Adobe Systems Incorporated. R2000, R6000, R4000, and R4400 are trademarks of MIPS Technologies, Inc. SecureNet is a trademark of Digital Pathways, Inc. Sound Blaster is a registered trademark of Creative Labs, Inc. SPARC is a registered trademark of SPARC International, Inc. Unicode is a registered certification mark of Unicode, Inc. UNIX is a registered trademark in the USA and other countries licensed exclusively through X/Open Company Limited.

Preface to the Fourth (2002) Edition

Plan 9 continues to grow and adapt. The fourth major release of the system incorporates a number of changes, but the most central is the conversion to a new version of the 9P file system protocol. This new version was motivated by a desire to support files with name elements longer than 27 bytes (the old NAMELEN), but the opportunity was taken to change a number of other things about the protocol, making it more efficient, more flexible, and easier to encapsulate. One simple but indispensable new feature made possible by the protocol change is that the system now records the user who last modified a file; try ls -m to identify the culprit.

Many aspects of system security have been improved. The new security agent *factotum*(4) maintains user passwords, while *secstore*(4) keeps them safe and enables single sign-on to multiple domains and machines using a variety of secure protocols and services.

Throughout the system, components have been rewritten and interfaces modified to eliminate restrictions, improve performance, and clarify design. The full list is too long to include here, but significant changes have occurred in a number of system calls (*wait*(2), *stat*(2), *mount*(2), and *errstr*(2)), the thread library (*thread*(2)), formatted printing (*print*(2) and *fmtinstall*(2)), security (many pages in section 2, including *auth*(2), *authsrv*(2)), and many others.

The changes are sweeping and are accompanied by many new programs, tools, services, and libraries. See the manual pages and the accompanying documents for more information.

Bell Labs Computing Science Research Center Murray Hill NJ April, 2002

Preface to the Third (2000) Edition

A great deal has happened to Plan 9 in the five years since its last release. Although much of the system will seem familiar, hardly any aspect of it is unchanged. The kernel has been heavily reworked; the graphical environment completely rewritten; many commands added, deleted, or replaced; and the libraries greatly expanded. Underneath, though, the same approach to computing remains: a distributed system that uses file-like naming to access and control resources both local and remote.

Some of the changes are sweeping:

Alef is gone, a casualty of the cost of maintaining multiple languages, compilers, and libraries in a diverse world, but its model for processes, tasks, and communication lives on in a new thread library for C.

Support for color displays is much more general, building on a new alpha-blending graphical operator called draw that replaces the old bitblt. Plan 9 screens are now, discreetly, colorful.

A new mechanism called plumbing connects applications together in a variety of ways, most obviously in the support of multimedia.

The interfaces to the panoply of rotating storage devices have been unified and extended, while providing better support for having Plan 9 coexist with other operating systems on a single disk.

Perhaps most important, this release of the system is being done under an open source agreement, providing cost-free source-level access to the software.

Plan 9 continues to be the work of many people. Besides those mentioned in the old preface, these people deserve particular note: Russ Cox did much of the work updating the graphics and creating the new disk and bootstrap model as well as providing a number of new commands; David Hogan ported Plan 9 to the Dec Alpha; and Sape Mullender wrote the new thread library.

Other new contributors include Bruce Ellis, Charles Forsyth, Eric Van Hensbergen, and Tad Hunt.

Bell Labs Computing Science Research Center Murray Hill NJ June, 2000

Preface to the Second (1995) Edition

Plan 9 was born in the same lab where Unix began. Old Unix hands will recognize the cultural heritage in this manual, where venerable Unix commands live on, described in the classic Unix style. Underneath, though, lies a new kind of system, organized around communication and naming rather than files and processes.

In Plan 9, distributed computing is a central premise, not an evolutionary add-on. The system relies on a uniform protocol to refer to and communicate with objects, whether they be data or processes, and whether or not they live on the same machine or even similar machines. A single paradigm (writing to named places) unifies all kinds of control and interprocess signaling.

Name spaces can be built arbitrarily. In particular all programs available to a given user are customarily united in a single logical directory. Temporary files and untrusted activities can be confined in isolated spaces. When a portable machine connects to the central, archival file system, the machine's local name space is joined smoothly to that of the archival file system. The architecture affords other unusual abilities, including:

Objects in name spaces imported from other machines (even from foreign systems such as MS-DOS) are transparently accessible.

Windows appear in name spaces on a par with files and processes.

A historical file system allows one to navigate the archival file system in time as well as in space; backup files are always at hand.

A debugger can handle simultaneously active processes on disparate kinds of hardware.

The character set of Plan 9 is Unicode, which covers most of the world's major scripts. The system has its own programming languages: a dialect of C with simple inheritance, a simplified shell, and a CSP-like concurrent language, Alef. An ANSI-POSIX emulator (APE) admits unreconstructed Unix code.

Plan 9 is the work of many people. The protocol was begun by Ken Thompson; naming was integrated by Rob Pike and networking by Dave Presotto. Phil Winterbottom simplified the management of name spaces and re-engineered the system. They were joined by Tom Killian, Jim McKie, and Howard Trickey in bringing the system up on various machines and making device drivers. Thompson made the C compiler; Pike, window systems; Tom Duff, the shell and raster graphics; Winterbottom, Alef; Trickey, Duff, and Andrew Hume, APE. Bob Flandrena ported a myriad of programs to Plan 9. Other contributors include Alan Berenbaum, Lorinda Cherry, Bill Cheswick, Sean Dorward, David Gay, Paul Glick, Eric Grosse, John Hobby, Gerard Holzmann, Brian Kernighan, Bart Locanthi, Doug McIlroy, Judy Paone, Sean Quinlan, Bob Restrick, Dennis Ritchie, Bjarne Stroustrup, and Cliff Young.

Plan 9 is made available as is, without formal support, but substantial comments or contributions may be communicated to the authors.

Doug McIlroy March, 1995

intro - introduction to Plan 9

DESCRIPTION

Plan 9 is a distributed computing environment assembled from separate machines acting as terminals, CPU servers, and file servers. A user works at a terminal, running a window system on a raster display. Some windows are connected to CPU servers; the intent is that heavy computing should be done in those windows but it is also possible to compute on the terminal. A separate file server provides file storage for terminals and CPU servers alike.

Name Spaces

In Plan 9, almost all objects look like files. The object retrieved by a given name is determined by a mapping called the *name space*. A quick tour of the standard name space is in *namespace*(4). Every program running in Plan 9 belongs to a *process group* (see *rfork* in *fork*(2)), and the name space for each process group can be independently customized.

A name space is hierarchically structured. A full file name (also called a *full path name*) has the form

/e1/e2/.../en

This represents an object in a tree of files: the tree has a root, represented by the first /; the root has a child file named e_1 , which in turn has child e_2 , and so on; the descendent e_n is the object represented by the path name.

There are a number of Plan 9 *services* available, each of which provides a tree of files. A name space is built by *binding* services (or subtrees of services) to names in the name-space-so-far. Typically, a user's home file server is bound to the root of the name space, and other services are bound to conventionally named subdirectories. For example, there is a service resident in the operating system for accessing hardware devices and that is bound to /dev by convention. Kernel services have names (outside the name space) that are a # sign followed by a single letter; for example, #c is conventionally bound to /dev.

Plan 9 has *union directories*: directories made of several directories all bound to the same name. The directories making up a union directory are ordered in a list. When the bindings are made (see *bind*(1)), flags specify whether a newly bound member goes at the head or the tail of the list or completely replaces the list. To look up a name in a union directory, each member directory is searched in list order until the name is found. A bind flag specifies whether file creation is allowed in a member directory: a file created in the union directory goes in the first member directory in list order that allows creation, if any.

The glue that holds Plan 9 together is a network protocol called *9P*, described in section 5 of this manual. All Plan 9 servers read and respond to 9P requests to navigate through a file tree and to perform operations such as reading and writing files within the tree.

Booting

When a terminal is powered on or reset, it must be told the name of a file server to boot from, the operating system kernel to boot, and a user name and password. How this dialog proceeds is environment- and machine-dependent. Once it is complete, the terminal loads a Plan 9 kernel, which sets some environment variables (see env(3)) and builds an initial name space. See namespace(4), boot(8), and init(8) for details, but some important aspects of the initial name space are:

- The environment variable \$cputype is set to the name of the kernel's CPU's architecture: one of mips, sparc, power (Power PC), 386 (386, 486, Pentium, ...) etc. The environment variable \$objtype is initially the same as \$cputype.
- The environment variable *terminal* is set to a description of the machine running the kernel, such as generic pc. Sometimes the middle word of *terminal* encodes the file from which the kernel is booted.
- The environment variable \$service is set to terminal. (Other ways of accessing Plan 9 may set \$service to one of cpu, con, or rx.)
- The environment variable \$user is set to the name of the user who booted the terminal. The environment variable \$home is set to that user's home directory.

• /\$cputype/bin and /rc/bin are unioned into /bin.

After booting, the terminal runs the command interpreter, *rc*(1), on /usr/\$user/lib/profile after moving to the user's home directory.

Here is a typical profile:

```
bind -a $home/bin/rc /bin
bind -a $home/bin/$cputype /bin
bind -c $home/tmp /tmp
font = /lib/font/bit/pelm/euro.9.font
upas/fs
switch($service){
case terminal
     plumber
     prompt=('term%' ' '
                        ')
     exec rio -f $font
case cpu
     bind /mnt/term/dev/cons /dev/cons
     bind /mnt/term/dev/consctl /dev/consctl
     bind -a /mnt/term/mnt/wsys /dev
     prompt=('cpu% ' '
                          ')
     news
case con
     prompt=('cpu% ' '
                         ')
     news
}
```

The first three lines replace /tmp with a tmp in the user's home directory and union personal bin directories with /bin, to be searched after the standard bin directories. The next starts the mail file system; see *mail*(1). Then different things happen, depending on the \$service environment variable, such as running the window system *rio*(1) on a terminal.

To do heavy work such as compiling, the cpu(1) command connects a window to a CPU server; the same environment variables are set (to different values) and the same profile is run. The initial directory is the current directory in the terminal window where cpu was typed. The value of service will be cpu, so the second arm of the profile switch is executed. The root of the terminal's name space is accessible through /mnt/term, so the *bind* is a way of making the window system's graphics interface (see draw(3)) available to programs running on the CPU server. The *news*(1) command reports current Plan 9 affairs.

The third possible service type, con, is set when the CPU server is called from a non-Plan-9 machine, such as through *telnet* (see *con*(1)).

Using Plan 9

The user commands of Plan 9 are reminiscent of those in Research Unix, version 10. There are a number of differences, however.

The standard shell is rc(1), not the Bourne shell. The most noticeable differences appear only when programming and macro processing.

The character-delete character is backspace, and the line-kill character is control-U; these cannot be changed.

DEL is the interrupt character: typing it sends an interrupt to processes running in that window. See *keyboard*(6) for instructions on typing characters like DEL on the various keyboards.

If a program dies with something like an address error, it enters a 'Broken' state. It lingers, available for debugging with db(1) or *acid*(1). *Broke* (see *kill*(1)) cleans up broken processes.

The standard editor is one of *acme*(1) or *sam*(1). There is a variant of *sam* that permits running the file-manipulating part of *sam* on a non-Plan-9 system:

sam -r tcp!kremvax

For historical reasons, *sam* uses a tab stop setting of 8 spaces, while the other editors and window systems use 4 spaces. These defaults can be overridden by setting the value of the environment variable *stabstop* to the desired number of spaces per tab.

Machine names may be prefixed by the network name, here tcp; and net for the system default. Login connections and remote execution on non-Plan-9 machines are usually done by saying, for example,

con kremvax

or

rx deepthought chess

(see con(1)).

9fs connects to file systems of remote systems (see srv(4)). For example,

9fs kremvax

sets things up so that the root of kremvax's file tree is visible locally in /n/kremvax.

Faces(1) gives graphical notification of arriving mail.

The Plan 9 file server has an integrated backup facility. The command

9fs dump

binds to /n/dump a tree containing the daily backups on the file server. The dump tree has years as top level file names, and month-day as next level file names. For example, /n/dump/2000/0120 is the root of the file system as it appeared at dump time on January 20, 2000. If more than one dump is taken on the same day, dumps after the first have an extra digit. To recover the version of this file as it was on June 15, 1999,

cp /n/dump/1999/0615/sys/man/1/0intro .

or use *yesterday*(1).

SEE ALSO

This section for general publicly accessible commands.

Section (2) for library functions, including system calls.

Section (3) for kernel devices (accessed via *bind*(1)).

Section (4) for file services (accessed via *mount*).

Section (5) for the Plan 9 file protocol.

Section (6) for file formats.

Section (7) for databases and database access programs.

Section (8) for things related to administering Plan 9.

/sys/doc for copies of papers referenced in this manual.

The back of this volume has a permuted index to aid searches.

DIAGNOSTICS

Upon termination each program returns a string called the *exit status*. It was either supplied by a call to *exits*(2) or was written to the command's /proc/pid/note file (see *proc*(3)), causing an abnormal termination. The empty string is customary for successful execution; a non-empty string gives a clue to the failure of the command.

0a, 1a, 2a, 5a, 6a, 8a, ka, qa, va - assemblers

SYNOPSIS

2a [*option* ...] [*name* ...] etc.

DESCRIPTION

These programs assemble the named files into object files for the corresponding architectures; see 2c(1) for the correspondence between an architecture and the character (1, 2, etc.) that specifies it. The assemblers handle the most common C preprocessor directives and the associated command-line options -D and -I. Other options are:

–o *obj*

Place output in file *obj* (allowed only if there is just one input file). Default is to take the last element of the input path name, strip any trailing .s, and append .O, where O is first letter of the assembler's name.

FILES

The directory /sys/include is searched for include files after machine-dependent files in /\$objtype/include.

SOURCE

/sys/src/cmd/2a, etc.

SEE ALSO

2c(1), *2l*(1).

Rob Pike, "A manual for the Plan 9 assembler"

BUGS

The list of assemblers given above is only partial, not all architectures are supported on all systems, some have been retired and some are provided by third parties.

0c, 1c, 2c, 5c, 6c, 7c, 8c, kc, qc, vc - C compilers

SYNOPSIS

2c [option ...] [file ...] etc

DESCRIPTION

These commands compile the named C *files* into object files for the corresponding architecture. If there are multiple C *files*, the compilers will attempt to keep \$NPROC compilations running concurrently. Associated with each compiler is a string *objtype*, for example

- Oc spim little-endian MIPS 3000 family
- 1c 68000 Motorola MC68000
- 2c 68020 Motorola MC68020
- 5c arm little-endian ARM
- 6c amd64 AMD64 and compatibles (e.g., Intel EM64T)
- 7c arm64 ARM64 (ARMv8)
- 8c 386 Intel i386, i486, Pentium, etc.
- kc sparc Sun SPARC
- qc power Power PC
- vc mips big-endian MIPS 3000 family

The compilers handle most preprocessing directives themselves; a complete preprocessor is available in cpp(1), which must be run separately.

Let the first letter of the compiler name be O = 0, 1, 2, 5, 6, 7, 8, k, q, or v. The output object files end in .O. The letter is also the prefix of related programs: Oa is the assembler, Ol is the loader. Plan 9 conventionally sets the <code>\$objtype</code> environment variable to the *objtype* string appropriate to the current machine's type. Plan 9 also conventionally has */objtype* directories, which contain among other things: include, for machine-dependent include files; lib, for public object code libraries; bin, for public programs; and mkfile, for preconditioning mk(1).

The compiler options are:

- -o *obj* Place output in file *obj* (allowed only if there is just one input file). Default is to take the last element of the input file name, strip any trailing . c, and append . O.
- -w Print warning messages about unused variables, etc.
- -B Accept functions without a new-style ANSI C function prototype. By default, the compilers reject functions used without a defined prototype, although ANSI C permits them.

–Dname=def

- -Dname Define the name to the preprocessor, as if by #define. If no definition is given, the name is defined as 1.
- -F Enable type-checking of calls to *print*(2) and other formatted print routines. See the discussion of extensions, below.
- -Idir An #include file whose name does not begin with slash or is enclosed in double quotes is always sought first in the directory of the *file* argument. If this fails, the -. flag is given or the name is enclosed in <>, it is then sought in directories named in -I options, then in /sys/include, and finally in /\$objtype/include.
- -. Suppress the automatic searching for include files in the directory of the file argument.
- -N Suppress automatic registerization and optimization.
- -S Print an assembly language version of the object code on standard output as well as generating the .*O* file.

- -T Pass type signatures on all external and global entities. The signature is based on the C signof operator.
- -V By default, the compilers are non-standardly lax about type equality between void* values and other pointers; this flag requires ANSI C conformance.
- -p Invoke a standard ANSI C preprocessor before compiling.
- -a Instead of compiling, print on standard output acid functions (see *acid*(1)) for examining structures declared in the source files.
- -aa Like -a except suppress information about structures declared in included header files.
- -n When used with -a or -aa, places acid functions in *file*.acid for input *file*.c, and not on standard output.

The compilers support several extensions to ANSI C:

- A structure or union may contain unnamed substructures and subunions. The fields of the substructures or subunions can then be used as if they were members of the parent structure or union (the resolution of a name conflict is unspecified). When a pointer to the outer structure or union is used in a context that is only legal for the unnamed substructure, the compiler promotes the type and adjusts the pointer value to point at the substructure. If the unnamed structure or union is of a type with a tag name specified by a typedef statement, the unnamed structure or union can be explicitly referenced by <struct variable>.<tagname>.
- A structure value can be formed with an expression such as (struct S){v1, v2, v3}
 where the list elements are values for the fields of struct S.
 - where the list elements are values for the fields of struct S.
- Array initializers can specify the indices of the array in square brackets, as

int a[] = { [3] 1, [10] 5 };

which initializes the third and tenth elements of the eleven-element array a.

- Structure initializers can specify the structure element by using the name following a period, as
 struct { int x; int y; } s = { .y 1, .x 5 };

which initializes elements y and then x of the structure s. These forms also accept the new ANSI C notation, which includes an equal sign:

int a[] = { [3] = 1, [10] = 5 };

- struct { int x; int y; } s = { .y = 1, x = 5 };
- A global variable can be dedicated to a register by declaring it extern register in *all* modules and libraries.
- A #pragma of the form

#pragma lib "libbio.a"

records that the program needs to be loaded with file /\$objtype/lib/libbio.a; such lines, typically placed in library header files, obviate the -l option of the loaders. To help identify files in non-standard directories, within the file names in the #pragmas the string \$M represents the name of the architecture (e.g., mips) and \$O represents its identifying character (e.g., v).

- A #pragma of the form

#pragma varargck argpos error 2

tells the compiler that the second argument to error is a print-like format string (see *print*(2)) that identifies the handling of subsequent arguments. The #pragma

#pragma varargck type "s" char*

says that the format verb s processes an argument of type char*. The #pragma
#pragma varargck flag 'c'

says that c is a flag character. These #pragmas are used, if the -F option is enabled, to type-check calls to print and other such routines.

- A #pragma with any of the following forms:
 - #pragma incomplete type

#pragma incomplete struct tag

#pragma incomplete union tag

where type is a typedef'd name for a structure or union type, and tag is a structure or union

tag, tells the compiler that the corresponding type should have its signature calculated as an incomplete type even if it is subsequently fully defined. This allows the type signature mechanism to work in the presence of opaque types declared in header files, with their full definitions visible only to the code which manipulates them. With some imported software it might be necessary to turn off the signature generation completely for a large body of code (typically at the start and end of a particular include file). If type is the word $_off_-$, signature generation is turned off; if type is the word $_on_-$, the compiler will generate signatures.

- The C++ comment (// to end of line) is accepted as well as the normal convention of /* */.
- The compilers accept long long variables as a 64-bit type. The standard header typedefs this to vlong. Arithmetic on vlong values is usually emulated by a run-time library, though in at least *8c*, only division and modulus use the run-time library and the other operators generate in-line code (and *uvlong-expression division-or-modulus* (1<<constant) will turn into in-line bit operations, as is done for shorter *unsigned* expressions).

Other differences with ANSI C include

- The compilers use the original "unsigned preserving", rather than ANSI C "value preserving" rules, which means that, e.g., unsigned char gets promoted to unsigned int rather than int.
- Parameters in macros are substituted inside of strings.

EXAMPLE

For the 68020, produce a program prog from C files main.c and sub.c:

2c -FVw main.c sub.c
2l -o prog main.2 sub.2

FILES

```
/sys/include system area for machine-independent #include directives.
/$objtype/include system area for machine-dependent #include directives.
```

SOURCE

/sys/src/cmd/cc	machine-independent part
/sys/src/cmd/2c,etc.	machine-dependent part

SEE ALSO

2a(1), 2l(1), cpp(1), mk(1), nm(1), pcc(1), db(1), acid(1)

Rob Pike, "How to Use the Plan 9 C Compiler"

BUGS

The list of compilers given above is only partial, not all architectures are supported on all systems, some have been retired and some are provided by third parties.

The default preprocessor only handles #define, #include, #undef, #ifdef, #line, and #ifndef. For a full ANSI preprocessor, use the p option.

The default search order for include files differs to that of cpp(1).

Some features of C99, the 1999 ANSI C standard, are implemented.

switch expressions may not be either signedness of vlong on 32-bit architectures (8c at least).

The implementation of vlong assignment can use a static location and this can be disturbed by interrupts (e.g., notes) (8c at least).

0l, 1l, 2l, 5l, 6l, 8l, kl, ql, vl - loaders

SYNOPSIS

21 [*option* ...] [*file* ...] etc

DESCRIPTION

These commands load the named *files* into executable files for the corresponding architectures; see 2c(1) for the correspondence between an architecture and the character (1, 2, etc.) that specifies it. The files should be object files or libraries (archives of object files) for the appropriate architecture. Also, a name like -lext represents the library libext.a in /\$objtype/lib, where *objtype* is one of 68000, etc. as listed in 2c(1). The libraries must have tables of contents (see ar(1)).

In practice, -1 options are rarely necessary as the header files for the libraries cause their archives to be included automatically in the load (see 2c(1)). For example, any program that includes header file libc.h causes the loader to search the C library /\$objtype/lib/libc.a. Also, the loader creates an undefined symbol _main (or _mainp if profiling is enabled) to force load-ing of the startup linkage from the C library.

The order of search to resolve undefined symbols is to load all files and libraries mentioned explicitly on the command line, and then to resolve remaining symbols by searching in topological order libraries mentioned in header files included by files already loaded. When scanning such libraries, the algorithm is to scan each library repeatedly until no new undefined symbols are picked up, then to start on the next library. Thus if library *A* needs *B* which needs *A* again, it may be necessary to mention *A* explicitly so it will be read a second time.

The loader options are:

- -1 (As a bare option.) Suppress the default loading of the startup linkage and libraries specified by header files.
- -o out Place output in file out. Default is O.out, where O is the first letter of the loader name.
- -p Insert profiling code into the executable output; no special action is needed during compilation or assembly.
- -e Insert (embedded) tracing code into the executable output; no special action is needed during compilation or assembly. The added code calls _tracein at function entries and _traceout at function exits.
- -F (ARM only) Don't generate VFP hardware floating point instructions.
- -s Strip the symbol tables from the output file.
- -a Print the object code in assembly language, with addresses.
- -v Print debugging output that annotates the activities of the load.
- -M (*Kl* only) Generate instructions rather than calls to emulation routines for multiply and divide.
- -Esymbol The entry point for the binary is symbol (default _main; _mainp under -p).
- -x [file] Produce an export table in the executable. The optional file restricts the exported symbols to those listed in the file.
- -u [file] Produce an export table, import table and a dynamic load section in the executable. The optional file restricts the imported symbols to those listed in the file.
- -t (51 and v1 only) Move strings into the text segment.
- -H*n* Executable header is type *n*. The meaning of the types is architecture-dependent; typically type 1 is Plan 9 boot format and type 2 is the regular Plan 9 format, the default. These are reversed on the MIPS. The Next boot format is 3. Type 4 in *vl* creates a MIPS executable for an SGI Unix system.

- -Tt The text segment starts at address t.
- -Dd The data segment starts at address d.
- $-\mathbf{R}\mathbf{r}$ The text segment is rounded to a multiple of \mathbf{r} (if \mathbf{r} is nonzero).

The numbers in the above options can begin with 0x or 0 to change the default base from decimal to hexadecimal or octal. The defaults for the values depend on the compiler and the header type.

The loaded image has several symbols inserted by the loader: etext is the address of the end of the text segment; bdata is the address of the beginning of the data segment; edata is the address of the end of the data segment; and end is the address of the end of the bss segment, and of the program.

FILES

/\$objtype/lib for -1*lib* arguments.

SOURCE

/sys/src/cmd/2l etc.

SEE ALSO

2c(1), *2a*(1), *ar*(1), *nm*(1), *db*(1), *prof*(1)

Rob Pike, "How to Use the Plan 9 C Compiler"

BUGS

The list of loaders given above is only partial, not all architectures are supported on all systems, some have been retired and some are provided by third parties.

5e - user-mode ARM emulation

SYNOPSIS

5e [-npbF] text [arguments]

DESCRIPTION

5e simulates the execution of an ARM binary in a Plan 9 environment. Unlike its predecessor vi(1) it supports, among others, the syscalls rfork (see *fork*(2)) and *exec*(2), which allows for the execution of threaded programs (e.g., *rio*(1) or catclock (see *games*(1)).

5e executes the specified binary *text*, which is prepended by /bin if it does not begin with a slash, dot or hash sign. Unless -n is specified, /bin is replaced by the union of /arm/bin and /rc/bin.

Unlike vi(1), 5e(1) does not provide built-in debugging facilities. It *does* provide emulation of the /proc directory, if the -p flag is specified, to attach a proper debugger like acid(1). There is no equivalent of the profiling facilities, no caches or TLBs are simulated, either.

5e(1) currently has three options.

- -n By default, *5e*(1) replaces /bin as mentioned above and also sets the variables cputype and objtype to arm. Supplying the -n option suppresses this behaviour.
- -p The -p option activates emulation of a /proc file system, which is mounted at /proc and also posted as /srv/armproc, cf. *srv*(3).
- -b Supplying –b causes failing processes to call *abort*(2) instead of *sysfatal*. See below.
- -F Disable emulation of VFP floating point instructions.

SOURCE

/sys/src/cmd/5e

SEE ALSO

vi(1)

BUGS

The host is required to be little endian and is assumed to have a floating point implementation conforming to IEEE 754.

Broken processes are simulated in a rather unsatisfactory manner. The -b option leaks memory. The emulator does not post sys: notes.

Obscure opcodes, in particular uncommon operations on R15, are not implemented.

Accesses spanning segment boundaries will be treated as page faults. Many syscalls such as pread (see *read*(2)) will shuffle data around (in most cases unnecessarily) if invoked on potentially shared segments of variable length, in particular the bss segment.

FPA emulation leaves much to be desired, rounding modes are ignored, all calculations are performed at extended precision. Floating point exceptions crash the emulator.

Several syscalls, most notably the *segattach*(2) family, are not implemented (this should not be hard to fix). The emulator notes the value of *errstr*(2) only under obvious circumstances; with most syscalls only if the return value is negative.

/proc emulation is more than unsatisfactory.

The *text* argument should behave more like it would if it had been entered as an argument to rc(1).

HISTORY

5e first appeared in 9front (June, 2011).

abaco - browse the World-Wide Web

SYNOPSIS

abaco[-p][-c ncols][-m mtpt][-t charset][url]

DESCRIPTION

Abaco is a lightweight web browser with the appearance of acme(1) with *ncols* columns (one by default). Given a *url*, it will start by displaying that page. Clicking mouse button 3 on a link opens it in a new *abaco* window. -t selects an alternate character set; -m an alternate mount point for *webfs*. Normally the standard error of subshells is closed, but -p prevents this.

FILES

/mnt/web default *webfs* mount point

SOURCE

/sys/src/cmd/abaco

SEE ALSO

mothra(1), webfs(4)

BUGS

Abaco is a work in progress; many features of giant web browsers are absent.

acid, truss, trump – debugger

SYNOPSIS

acid [-kqw] [-l library] [-m machine] [pid] [textfile]

acid -l truss *textfile*

acid -l trump [pid] [textfile]

DESCRIPTION

Acid is a programmable symbolic debugger. It can inspect one or more processes that share an address space. A program to be debugged may be specified by the process id of a running or defunct process, or by the name of the program's text file (8.out by default). At the prompt, *acid* will store function definitions or print the value of expressions. Options are

-w Allow the textfile to be modified.

-q Print variable renamings at startup.

- -1 *library* Load from *library* at startup; see below.
- -m machine Assume instructions are for the given CPU type (one of amd64, 386, etc., as listed in 2c(1), or sunsparc or mipsco for the manufacturer-defined instruction notation for those processors) instead of using the magic number to select the CPU type.
- -k Debug the kernel state for the process, rather than the user state.

standard function definitions the file At startup, acid obtains from library /sys/lib/acid/port, architecture-dependent functions from /sys/lib/acid/\$objtype, user-specified functions from \$home/lib/acid, and further functions from -1 files. Definitions in any file may override previously defined functions. If the function *acidinit()* is defined, it will be invoked after all libraries have been loaded. See 2c(1) for information about creating *acid* functions for examining data structures.

Language

Symbols of the program being debugged become integer variables whose values are addresses. Contents of addresses are obtained by indirection. Local variables are qualified by function name, for example main:argv. When program symbols conflict with *acid* words, distinguishing signs are prefixed. Such renamings are reported at startup if the option -q is enabled.

Variable types (*integer, float, list, string*) and formats are inferred from assignments. Truth values false/true are attributed to zero/nonzero integers or floats and to empty/nonempty lists or strings. Lists are sequences of expressions surrounded by {} and separated by commas.

Expressions are much as in C, but yield both a value and a format. Casts to complex types are allowed. Lists admit the following operators, with subscripts counted from 0.

head list tail list append list, element delete list, subscript

Format codes are the same as in db(1). Formats may be attached to (unary) expressions with $\,$ e.g. (32*7) D. There are two indirection operators, * to address a core image, @ to address a text file. The type and format of the result are determined by the format of the operand, whose type must be integer.

Statements are

if expr then statement [else statement]
while expr do statement
loop expr, expr do statement
defn name(args) { statement }
defn name
name(args)
builtin name(args)
local name

return expr
whatis [name]

The statement defn *name* clears the definition for *name*. A defn may override a built-in function; prefixing a function call with builtin ignores any overriding defn, forcing the use of the built-in function.

Here is a partial list of functions; see the manual for a complete list.

stk()	Print a stack trace for current process.
lstk()	Print a stack trace with values of local variables.
gpr()	Print general registers. Registers can also be accessed by name, for example
	*R0.
<pre>spr()</pre>	Print special registers such as program counter and stack pointer.
<pre>fpr()</pre>	Print floating-point registers.
regs()	Same as spr();gpr().
fmt (expr , format	
	Expression <i>expr</i> with format given by the character value of expression
	format.
<pre>src(address)</pre>	Print 10 lines of source around the program address.
Bsrc(address)	Get the source line for the program address into a window of a running
D31C(0001033)	sam(1) and select it.
line(<i>address</i>)	Print source line nearest to the program address.
source()	List current source directories.
addsrcdir(strin	
£-1	Add a source directory to the list.
<pre>filepc(where)</pre>	
) Convert a machine address to a source file name.
	Convert a machine address to a source line number.
<pre>bptab()</pre>	List breakpoints set in the current process.
<pre>bpset(address)</pre>	Set a breakpoint in the current process at the given address.
<pre>bpdel(address)</pre>	Delete a breakpoint from the current process.
wptab()	List watchpoints set in the current process.
wpset(<i>type</i> , <i>addr</i>	
	Set a watchpoint for the <i>len</i> bytes at the given address. <i>type</i> is "r", "w" or
	" rw " to trap read accesses, write accesses or both, respectively.
<pre>wpdel(address)</pre>	Delete all watchpoints set for the given address.
cont()	Continue execution of current process and wait for it to stop.
<pre>step()</pre>	Execute a single machine instruction in the current process.
func()	Step repeatedly until after a function return.
<pre>stopped(pid)</pre>	This replaceable function is called automatically when the given process
	stops. It normally prints the program counter and returns to the prompt.
asm(<i>address</i>)	Disassemble 30 machine instructions beginning at the given address.
mem(address, stri	
	Print a block of memory interpreted according to a string of format codes.
dump(address, n	
admp(address; m	Like mem(), repeated for <i>n</i> consecutive blocks.
nnint(avor)	Print the values of the expressions.
newproc(<i>argume</i>	
newproc(urguine	Start a new process with arguments given as a string and halt at the first
	instruction.
new()	Like <i>newproc(</i>), but take arguments (except $argv[0]$) from string variable
	progargs.
win()	Like <i>new</i> (), but run the process in a separate window.
<pre>start(pid)</pre>	Start a stopped process.
kill(pid)	Kill the given process.
<pre>setproc(pid)</pre>	Make the given process current.
<pre>rc(string)</pre>	Escape to the shell, <i>rc</i> (1), to execute the command string.

Libraries

There are a number of *acid* 'libraries' that provide higher-level debugging facilities. Two notable examples are *truss* and *trump*, which use *acid* to trace system calls (*truss*) and memory allocation

(*trump*). Both require starting *acid* on the program, either by attaching to a running process or by executing new() on a binary (perhaps after setting progargs), stopping the process, and then running truss() or trump() to execute the program under the scaffolding. The output will be a trace of the system calls (*truss*) or memory allocation and free calls (*trump*) executed by the program. When finished tracing, stop the process and execute untruss() or untrump() followed by cont() to resume execution.

EXAMPLES

Start to debug /bin/ls; set some breakpoints; run up to the first one:

```
% acid /bin/ls
/bin/ls: mips plan 9 executable
/sys/lib/acid/port
/sys/lib/acid/mips
acid: new()
70094: system call
                    _main
                              ADD $-0x14,R29
70094: breakpoint
                    main+0x4 MOVW R31,0x0(R29)
acid: pid
70094
acid: argv0 = **main:argv\s
acid: whatis argv0
integer variable format s
acid: *argv0
/bin/ls
acid: bpset(ls)
acid: cont()
70094: breakpoint ls
                         ADD $-0x16c8,R29
acid:
```

Display elements of a linked list of structures:

```
complex Str { 'D' 0 val; 'X' 4 next; };
complex Str s;
s = *headstr;
while s != 0 do{
    print(s.val, "\n");
    s = s.next;
}
```

Note the use of the . operator instead of ->.

Display an array of bytes declared in C as char array[].

*(array\s)

This example gives array string format, then prints the string beginning at the address (in *acid* notation) *array.

Trace the system calls executed by *ls*(1):

```
% acid -l truss /bin/ls
/bin/ls:386 plan 9 executable
/sys/lib/acid/port
/sys/lib/acid/kernel
/sys/lib/acid/truss
/sys/lib/acid/386
acid: progargs = "-l lib/profile"
acid: new()
acid: truss()
open("#c/pid", 0)
return value: 3
pread(3, 0x7fffeeac, 20, -1)
return value: 12
data: " 166 "
```

```
stat("lib/profile", 0x0000f8cc, 113)
    return value: 65
open("/env/timezone", 0)
     return value: 3
pread(3, 0x7fffd7c4, 1680, -1)
    return value: 1518
     data: "EST -18000 EDT -14400
   9943200
           25664400
                        41392800
                                   57718800
                                              73447200
                                                          89168400
104896800 ..."
close(3)
     return value: 0
pwrite(1, "--rw-rw-r-- M 9 rob rob 2519 Mar 22 10:29 lib/profile
', 54, -1)
--rw-rw-r-- M 9 rob rob 2519 Mar 22 10:29 lib/profile
    return value: 54
                                   INTB $0x40
166: breakpoint
                    _exits+0x5
```

FILES

```
/proc/*/text
/proc/*/mem
/proc/*/ctl
/proc/*/note
/sys/lib/acid/$objtype
/sys/lib/acid/port
/sys/lib/acid/kernel
/sys/lib/acid/trump
/sys/lib/acid/truss
$home/lib/acid
```

acid: cont()

SOURCE

/sys/src/cmd/acid

SEE ALSO

2a(1), 2c(1), 2l(1), mk(1), db(1) Phil Winterbottom, "Acid Manual".

DIAGNOSTICS

At termination, kill commands are proposed for processes that are still active.

BUGS

There is no way to redirect the standard input and standard output of a new process.

Source line selection near the beginning of a file may pick an adjacent file.

With the extant stepping commands, one cannot step through instructions outside the text segment and it is hard to debug across process forks.

acme, win - interactive text windows

SYNOPSIS

acme [-aib][-c ncol][-f varfont][-F fixfont][-l loadfile | file ...]

win[command]

DESCRIPTION

Acme manages windows of text that may be edited interactively or by external programs. The interactive interface uses the keyboard and mouse; external programs use a set of files served by *acme*; these are discussed in *acme*(4).

Any named *files* are read into *acme* windows before *acme* accepts input. With the -1 option, the state of the entire system is loaded from *loadfile*, which should have been created by a Dump command (q.v.), and subsequent *file* names are ignored. Plain files display as text; directories display as columnated lists of the names of their components, as in 1s -p directory |mc except that the names of subdirectories have a slash appended.

The -f (-F) option sets the main font, usually variable-pitch (alternate, usually fixed-pitch); the default is /lib/font/bit/lucidasans/euro.8.font (.../lucm/unicode.9.font). Tab intervals are set to the width of 4 (or the value of \$tabstop) numeral zeros in the appropriate font.

Windows

Acme windows are in two parts: a one-line *tag* above a multi-line *body*. The body typically contains an image of a file, as in *sam*(1), or the output of a program, as in an *rio*(1) window. The tag contains a number of blank-separated words, followed by a vertical bar character, followed by anything. The first word is the name of the window, typically the name of the associated file or directory, and the other words are commands available in that window. Any text may be added after the bar; examples are strings to search for or commands to execute in that window. Changes to the text left of the bar will be ignored, unless the result is to change the name of the window.

If a window holds a directory, the name (first word of the tag) will end with a slash.

Scrolling

Each window has a scroll bar to the left of the body. The scroll bar behaves much as in sam(1) or rio(1) except that scrolling occurs when the button is pressed, rather than released, and continues as long as the mouse button is held down in the scroll bar. For example, to scroll slowly through a file, hold button 3 down near the top of the scroll bar. Moving the mouse down the scroll bar speeds up the rate of scrolling.

Layout

Acme windows are arranged in columns. By default, it creates two columns when starting; this can be overridden with the -c option. Placement is automatic but may be adjusted using the *layout box* in the upper left corner of each window and column. Pressing and holding any mouse button in the box drags the associated window or column. For windows, just clicking in the layout box grows the window in place: button 1 grows it a little, button 2 grows it as much as it can, still leaving all other tags in that column visible, and button 3 takes over the column completely, temporarily hiding other windows in the column. (They will return *en masse* if any of them needs attention.) The layout box in a window is normally white; when it is black in the center, it records that the file is 'dirty': *acme* believes it is modified from its original contents.

Tags exist at the top of each column and across the whole display. *Acme* pre-loads them with use-ful commands. Also, the tag across the top maintains a list of executing long-running commands.

Typing

The behavior of typed text is similar to that in rio(1) except that the characters are delivered to the tag or body under the mouse; there is no 'click to type'. (The experimental option -b causes typing to go to the most recently clicked-at or made window.) The usual backspacing conventions apply. As in *sam*(1) but not *rio*, the ESC key selects the text typed since the last mouse action, a feature particularly useful when executing commands. A side effect is that typing ESC with text already selected is identical to a Cut command (*q.v.*).

Most text, including the names of windows, may be edited uniformly. The only exception is that the command names to the left of the bar in a tag are maintained automatically; changes to them are repaired by *acme*.

When a window is in autoindent mode (see the Indent command below) and a newline character is typed, acme copies leading white space on the current line to the new line. The option -a causes each window to start in autoindent mode.

When a window is in spaces indent mode (see the Spaces command below) and a tab character is typed, acme indents the line with spaces equal to the current tabstop for the window. The option -i causes each window to start in spaces indent mode.

Directory context

Each window's tag names a directory: explicitly if the window holds a directory; implicitly if it holds a regular file (e.g. the directory /adm if the window holds /adm/users). This directory provides a *context* for interpreting file names in that window. For example, the string users in a window labeled /adm/ or /adm/keys will be interpreted as the file name /adm/users. The directory is defined purely textually, so it can be a non-existent directory or a real directory associated with a non-existent file (e.g. /adm/not-a-file). File names beginning with a slash are assumed to be absolute file names.

Errors

Windows whose names begin with - or + conventionally hold diagnostics and other data not directly associated with files. A window labeled +Errors receives all diagnostics produced by *acme* itself. Diagnostics from commands run by *acme* appear in a window named *directory*/+Errors where *directory* is identified by the context of the command. These error windows are created when needed.

Mouse button 1

Mouse button 1 selects text just as in *sam*(1) or *rio*(1), including the usual double-clicking conventions.

Mouse button 2

By an action similar to selecting text with button 1, button 2 indicates text to execute as a command. If the indicated text has multiple white-space-separated words, the first is the command name and the second and subsequent are its arguments. If button 2 is 'clicked'—indicates a null string—*acme expands* the indicated text to find a command to run: if the click is within button-1selected text, *acme* takes that selection as the command; otherwise it takes the largest string of valid file name characters containing the click. Valid file name characters are alphanumerics and _ . - + /. This behavior is similar to double-clicking with button 1 but, because a null command is meaningless, only a single click is required.

Some commands, all by convention starting with a capital letter, are *built-ins* that are executed directly by *acme*:

Cut Delete most recently selected text and place in snarf buffer.

Del Delete window. If window is dirty, instead print a warning; a second Del will succeed. Delcol

Delete column and all its windows, after checking that windows are not dirty.

Delete

Delete window without checking for dirtiness.

- Dump Write the state of *acme* to the file name, if specified, or \$home/acme.dump by default.
- Edit Treat the argument as a text editing command in the style of *sam*(1). The full Sam language is implemented except for the commands k, n, q, and !. The = command is slightly different: it includes the file name and gives only the line address unless the command is explicitly =#. The 'current window' for the command is the body of the window in which the Edit command is executed. Usually the Edit command would be typed in a tag; longer commands may be prepared in a scratch window and executed, with Edit itself in the current window, using the 2-1 chord described below.
- Exit Exit *acme* after checking that windows are not dirty.

- Font With no arguments, change the font of the associated window from fixed-spaced to proportional-spaced or *vice versa*. Given a file name argument, change the font of the window to that stored in the named file. If the file name argument is prefixed by var (fix), also set the default proportional-spaced (fixed-spaced) font for future use to that font. Other existing windows are unaffected.
- Get Load file into window, replacing previous contents (after checking for dirtiness as in Del). With no argument, use the existing file name of the window. Given an argument, use that file but do not change the window's file name.
- ID Print window ID number (q.v.).
- Incl When opening 'include' files (those enclosed in <>) with button 3, acme searches in directories /\$objtype/include and /sys/include. Incl adds its arguments to a supplementary list of include directories, analogous to the -I option to the compilers. This list is per-window and is inherited when windows are created by actions in that window, so *Incl* is most usefully applied to a directory containing relevant source. With no arguments, *Incl* prints the supplementary list. This command is largely superseded by plumbing (see *plumb*(6)).

Indent

Set the autoindent mode according to the argument: on and off set the mode for the current window; ON and OFF set the mode for all existing and future windows.

- Kill Send a kill note to *acme*-initiated commands named as arguments.
- Load Restore the state of *acme* from a file (default \$home/acme.dump) created by the Dump command.
- Local

When prefixed to a command run the command in the same file name space and environment variable group as *acme*. The environment of the command is restricted but is sufficient to run *bind*(1), *9fs* (see *srv*(4)), *import*(4), etc., and to set environment variables such as objtype.

- Look Search in body for occurrence of literal text indicated by the argument or, if none is given, by the selected text in the body.
- New Make new window. With arguments, load the named files into windows.

Newcol

Make new column.

Paste

Replace most recently selected text with contents of snarf buffer.

Put Write window to the named file. With no argument, write to the file named in the tag of the window.

Putall

Write all dirty windows whose names indicate existing regular files.

- Redo Complement of Undo.
- Send Append selected text or snarf buffer to end of body; used mainly with win.

Snarf

Place selected text in snarf buffer.

Sort Arrange the windows in the column from top to bottom in lexicographical order based on their names.

Spaces

Set the spaces indent mode according to the argument: on and off set the mode for the current window; ON and OFF set the mode for all existing and future windows.

- Tab Set the width of tab stops for this window to the value of the argument, in units of widths of the zero character. With no arguments, it prints the current value.
- Undo Undo last textual change or set of changes.

Zerox

Create a copy of the window containing most recently selected text.

<|> If a regular shell command is preceded by a <, |, or > character, the selected text in the body of the window is affected by the I/O from the command. The < character causes the selection to be replaced by the standard output of the command; > causes the selection to be sent as standard input to the command; and | does both at once, 'piping' the selection through the command and replacing it with the output.

A common place to store text for commands is in the tag; in fact *acme* maintains a set of commands appropriate to the state of the window to the left of the bar in the tag.

If the text indicated with button 2 is not a recognized built-in, it is executed as a shell command. For example, indicating date with button 2 runs date(1). The standard and error outputs of commands are sent to the error window associated with the directory from which the command was run, which will be created if necessary. For example, in a window /adm/users executing pwd will produce the output / adm in a (possibly newly-created) window labeled / adm/+Errors; in a window containing /sys/src/cmd/sam/sam.c executing mk will run mk(1) in /sys/src/cmd/sam, producing labeled output in window а /sys/src/cmd/sam/+Errors. The environment of such commands contains the variable \$% with value set to the filename of the window in which the command is run, and \$winid set to the window's id number (see *acme*(4)).

Mouse button 3

Pointing at text with button 3 instructs *acme* to locate or acquire the file, string, etc. described by the indicated text and its context. This description follows the actions taken when button 3 is released after sweeping out some text. In the description, *text* refers to the text of the original sweep or, if it was null, the result of applying the same expansion rules that apply to button 2 actions.

If the text names an existing window, *acme* moves the mouse cursor to the selected text in the body of that window. If the text names an existing file with no associated window, *acme* loads the file into a new window and moves the mouse there. If the text is a file name contained in angle brackets, *acme* loads the indicated include file from the directory appropriate to the suffix of the file name of the window holding the text. (The Incl command adds directories to the standard list.)

If the text begins with a colon, it is taken to be an address, in the style of sam(1), within the body of the window containing the text. The address is evaluated, the resulting text highlighted, and the mouse moved to it. Thus, in *acme*, one must type :/regexp or :127 not just /regexp or 127. (There is an easier way to locate literal text; see below.)

If the text is a file name followed by a colon and an address, *acme* loads the file and evaluates the address. For example, clicking button 3 anywhere in the text file.c:27 will open file.c, select line 27, and put the mouse at the beginning of the line. The rules about Error files, directories, and so on all combine to make this an efficient way to investigate errors from compilers, etc.

If the text is not an address or file, it is taken to be literal text, which is then searched for in the body of the window in which button 3 was clicked. If a match is found, it is selected and the mouse is moved there. Thus, to search for occurrences of a word in a file, just click button 3 on the word. Because of the rule of using the selection as the button 3 action, subsequent clicks will find subsequent occurrences without moving the mouse.

In all these actions, the mouse motion is not done if the text is a null string within a non-null selected string in the tag, so that (for example) complex regular expressions may be selected and applied repeatedly to the body by just clicking button 3 over them.

Chords of mouse buttons

Several operations are bound to multiple-button actions. After selecting text, with button 1 still down, pressing button 2 executes Cut and button 3 executes Paste. After clicking one button, the other undoes the first; thus (while holding down button 1) 2 followed by 3 is a Snarf that leaves the file undirtied; 3 followed by 2 is a no-op. These actions also apply to text selected by double-clicking because the double-click expansion is made when the second click starts, not when it ends.

Commands may be given extra arguments by a mouse chord with buttons 2 and 1. While holding down button 2 on text to be executed as a command, clicking button 1 appends the text last pointed to by button 1 as a distinct final argument. For example, to search for literal text one may execute Look text with button 2 or instead point at text with button 1 in any window, release button 1, then execute Look, clicking button 1 while 2 is held down.

When an external command (e.g. echo(1)) is executed this way, the extra argument is passed as expected and an environment variable acmeaddr is created that holds, in the form interpreted by button 3, the fully-qualified address of the extra argument.

Support programs

Win creates a new *acme* window and runs a *command* (default /bin/rc) in it, turning the window into something analogous to an *rio*(1) window. Executing text in a *win* window with button 2 is similar to using Send.

Applications and guide files

In the directory /acme live several subdirectories, each corresponding to a program or set of related programs that employ *acme's* user interface. Each subdirectory includes source, binaries, and a readme file for further information. It also includes a guide, a text file holding sample commands to invoke the programs. The idea is to find an example in the guide that best matches the job at hand, edit it to suit, and execute it.

Whenever a command is executed by *acme*, the default search path includes the directory of the window containing the command and its subdirectory \$cputype. The program directories in /acme contain appropriately labeled subdirectories of binaries, so commands named in the guide files will be found automatically when run. Also, *acme* binds the directories /acme/bin and /acme/bin/\$cputype to the beginning of /bin when it starts; this is where *acme*-specific programs such as *win* reside.

FILES

\$home/acme.dump default file for Dump and Load; also where state is written if acme dies

deraute me for Damp and Doad, also miere state is mitten in deme ares
or is killed unexpectedly, e.g. by deleting its window.
template files for applications
informal documentation for applications
source for applications
MIPS-specific binaries for applications

SOURCE

/sys/src/cmd/acme
/acme/bin/source/win

SEE ALSO

emacs(1) acme(4) Rob Pike, Acme: A User Interface for Programmers.

BUGS

With the -1 option or Load command, the recreation of windows under control of external programs such as *win* is just to rerun the command; information may be lost.

alarm - ask for delayed note

SYNOPSIS

alarm time command [arg ...]

DESCRIPTION

Alarm causes an alarm note (see *notify*(2)) to be sent to the process indicated by *command* after *time* seconds.

SOURCE

/sys/src/cmd/alarm.c

SEE ALSO

sleep(2)

ap - fetch Associated Press news articles

SYNOPSIS

ap[article-name]

DESCRIPTION

ap fetches Associated Press news articles from http://www.newsday.com. Without any arguments it provides a two column list of article keys and descriptions. When invoked with an article key it fetches that article.

SOURCE

/rc/bin/ap

ar - archive and library maintainer

SYNOPSIS

ar key [posname] afile [file ...]

DESCRIPTION

Ar maintains groups of files combined into a single archive file, *afile*. The main use of *ar* is to create and update library files for the loaders 2l(1), etc. It can be used, though, for any similar purpose.

Key is one character from the set drqtpmx, optionally concatenated with one or more of vuaibclo. The *files* are constituents of the archive *afile*. The meanings of the *key* characters are:

- d Delete *files* from the archive file.
- r Replace *files* in the archive file, or add them if missing. Optional modifiers are
 - u Replace only files with modified dates later than that of the archive.
 - a Place new files after *posname* in the archive rather than at the end.

b or i Place new files before *posname* in the archive.

- q Quick. Append *files* to the end of the archive without checking for duplicates. Avoids quadratic behavior in for (i in *.v) ar r lib.a \$i.
- t List a table of contents of the archive. If names are given, only those files are listed.
- p Print the named files in the archive.
- m Move the named files to the end or elsewhere, specified as with r.
- o Preserve the access and modification times of files extracted with the x command.
- x Extract the named files. If no names are given, all files in the archive are extracted. In neither case does x alter the archive file.
- V Verbose. Give a file-by-file description of the making of a new archive file from the old archive and the constituent files. With p, precede each file with a name. With t, give a long listing of all information about the files, somewhat like a listing by *ls*(1), showing mode uid/gid size date name
- Local. Normally *ar* places its temporary files in the directory /tmp. This option causes them to be placed in the local directory.

When a d, r, or m key is specified and all members of the archive are valid object files for the same architecture, *ar* inserts a table of contents, required by the loaders, at the front of the library. The table of contents is rebuilt whenever the archive is modified, except when the q *key* is specified or when the table of contents is explicitly moved or deleted.

EXAMPLE

ar cr lib.a *.v

Replace the contents of library lib. a with the object files in the current directory.

FILES

/tmp/v* temporaries

SOURCE

/sys/src/cmd/ar.c

SEE ALSO

21(1), *ar*(6)

BUGS

If the same file is mentioned twice in an argument list, it may be put in the archive twice. This command predates Plan 9 and makes some invalid assumptions, for instance that user id's are numeric.

ascii, unicode - interpret ASCII, Unicode characters

SYNOPSIS

ascii[-8cnt][-dox | -b n][text]

unicode hexmin-hexmax

unicode [-t] hex [...]

unicode [–n] characters

look hex /lib/unicode

DESCRIPTION

Ascii prints the ASCII values corresponding to characters and *vice versa*; under the -8 option, the ISO Latin-1 extensions (codes 0200-0377) are included. The values are interpreted in a settable numeric base; -0 specifies octal, -d decimal, -x hexadecimal (the default), and -bn base n.

With no arguments, *ascii* prints a table of the character set in the specified base. Characters of *text* are converted to their ASCII values, one per line. If, however, the first *text* argument is a valid number in the specified base, conversion goes the opposite way. Control characters are printed as two- or three-character mnemonics. Other options are:

- -n Force numeric output.
- -c Force character output.
- -t Convert from numbers to running text; do not interpret control characters or insert newlines.

Unicode is similar; it converts between UTF and character values from the Unicode Standard (see utf(6)). If given a range of hexadecimal numbers, *unicode* prints a table of the specified Unicode characters — their values and UTF representations. Otherwise it translates from UTF to numeric value or vice versa, depending on the appearance of the supplied text; the -n option forces numeric output to avoid ambiguity with numeric characters. If converting to UTF, the characters are printed one per line unless the -t flag is set, in which case the output is a single string containing only the specified characters. Unlike *ascii*, *unicode* treats no characters specially.

The output of *ascii* and *unicode* may be unhelpful if the characters printed are not available in the current font.

The file /lib/unicode contains a table of characters and descriptions, sorted in hexadecimal order, suitable for *look*(1) on the lower case *hex* values of characters.

EXAMPLES

ascii –d Print the ASCII table base 10.

```
unicode p
```

Print the hex value of 'p'.

```
unicode 2200-22f1
```

Print a table of miscellaneous mathematical symbols.

```
look 039 /lib/unicode
```

See the start of the Greek alphabet's encoding in the Unicode Standard.

FILES

/lib/unicode table of characters and descriptions.

SOURCE

/sys/src/cmd/ascii.c
/sys/src/cmd/unicode.c

SEE ALSO

look(1), *tcs*(1), *utf*(6), *font*(6)

2600 - emulator

SYNOPSIS

games/2600[-a][-x scale] romfile

DESCRIPTION

2600 is an emulator for the Atari 2600. It exectues the romfile given as an argument, and controls as if using a regular 4-direction 1-button joystick, using **space** button and directional keys. The **q**, **w**, **e** and **r** keys correspond respectively to the reset, select, player 1 difficulty and color mode switches. Other keys:

- F1 Pause the emulator. If already paused it will step one video frame.
- F12 Toggle the emulator's speedometer. It shows in the upper left, off-viewport corner, the ratio between the expected and observed time it took to draw 60 frames.
- t Toggle tracing of the emulator.
- ' It uncaps the 60fps frame rate and lets emulation go as fast as possible.
- Esc Pause the emulator.
- Del Exit the emulator.

Command line options:

- -a Enable audio output.
- -x Scale the screen to a given factor regardless of the window's size.
- SOURCE

/sys/src/games/2600

BUGS

Yes.

HISTORY

2600 first appeared in 9front (November, 2014).

mp3dec, mp3enc, oggdec, oggenc, flacdec, flacenc, sundec, wavdec, pcmconv, mixfs - decode and encode audio files

SYNOPSIS

```
audio/mp3dec [ -s seconds ] [ -d ]
audio/oggdec [ -s seconds ]
audio/flacdec [ -s seconds ]
audio/wavdec [ -s seconds ]
audio/sundec
```

```
audio/oggenc
audio/mp3enc[-hprv][-b bitrate][-B bitrate][-m mode][-q q][-s sfreq][-V q][
long or silly options]
audio/flacenc[-b bitspersample][-c channels][-l compresslevel][-s sfreq][-P
padding][-T field=value]
```

audio/pcmconv[-i fmt][-0 fmt][-1 length]

audio/mixfs[-D][-s srvname][-m mtpt]

DESCRIPTION

These programs decode and encode various audio formats from and to 16-bit stereo PCM (little endian). The decoders read the compressed audio data from standard input and produce PCM on standard output at a sampling frequency of 44.1KHz.

Mp3dec decodes MPEG audio (layer 1, 2 and 3). The -d option enables debug output to standard error. *Oggdec, flacdec, sunwdec* and *wavdec* are like *mp3dec* but decode OGG Vorbis, FLAC loss-less audio, Sun audio and RIFF wave.

Decoding options

-s *seconds* seek to a specific position in seconds before decoding.

The encoders read PCM on standard input and produce compressed audio on standard output.

Flacenc, oggenc and *mp3enc* produce FLAC, OGG Vorbis and MP3 audio. For *mp3enc*, the MP3 file will use 'constant bit-rate' (CBR) encoding by default, but that can be changed via -abr (average bitrate desired, ABR) or -v (variable bitrate, VBR).

Flacenc and *oggenc* accept raw PCM in the same byte order as /dev/audio (little-endian), while *mp3enc* -*r* expects big-endian.

Encoding options

- -b set minimum allowed *bitrate* in Kb/s for VBR, default 32Kb/s. For CBR, set the exact bitrate in Kb/s, which defaults to 128Kb/s.
- -B set maximum allowed *bitrate* in Kb/s for VBR, default 256Kb/s.
- -h same as -q 2.
- -m mode may be (s)tereo, (j)oint, (f)orce or (m)ono (default j). force forces mid/side stereo on all frames.
- -p add CRC error protection (adds an additional 16 bits per frame to the stream). This seems to break playback.
- -q sets output quality to q (see -V).
- -r input is raw pcm
- -s set sampling frequency of input file (in KHz) to *sfreq*, default is 44.1.
- -v use variable bitrate (VBR) encoding
- -V set quality setting for VBR to q. Default q is 4; 0 produces highest-quality and largest files, and 9 produces lowest-quality and smallest files.

Long options

- --abr bitrate sets average bitrate desired in Kb/s, instead of setting quality, and generates ABR encoding.
- --resample *sfreq* set sampling frequency of output file (in KHz) to *sfreq*, default is input sfreq. --mp3input *input* is an MP3 file

Silly options	
-f	same as –q 7. Such a deal.
-0	mark as non-original (i.e. do not set the original bit)
-C	mark as copyright
$-\mathbf{k}$	disable sfb=21 cutoff
-е <i>етр</i>	de-emphasis n/5/c (default n)
-d	allow channels to have different blocktypes
-t	disable Xing VBR informational tag
-a	autoconvert from stereo to mono file for mono encoding
-x	force byte-swapping of input (see <i>dd</i> (1) instead)
-S	don't print progress report, VBR histograms
athonly	only use the ATH for masking
nohist	disable VBR histogram display
voice	experimental voice mode

Pcmconv is a helper program used to convert various PCM sample formats. The -i and -o options specify the input and output format *fmt* of the conversion. *Fmt* is a concatenated string of the following parts:

- s# sample format is little-endian signed integer where # specifies the number of bits
- u# unsigned little-endian integer format
- S# singed big-endian integer format
- U# unsigned big-endian integer format
- f# floating point format where # has to be 32 or 64 for single- or double-precision
- a8 8-bit a-law format
- μ8 8-bit μ-law format
- c# specifies the number of channels
- r# gives the samplerate in Hz

The program reads samples from standard input converting the data and writes the result to standard output until it reached end of file or, if -1 was given, a number of *length* bytes have been consumed from input.

Mixfs is a fileserver serving a single audio file which allows simultaneous playback of audio streams. When run, it binds over /dev/audio and mixes the audio samples that are written to it. A service name *srvname* can be given with the -s option which gets posted to /srv. By default, *mixfs* mounts itself on /mnt/mix and then binds /mnt/mix/audio over /dev. A alternative mountpoint *mtpt* can be specified with the -m option. The -D option causes 9p debug messages to be written to file-descriptor 2.

EXAMPLE

Play back an .mp3

audio/mp3dec <foo.mp3 >/dev/audio

Encode a . wav file as highest-quality MP3.

audio/mp3enc -q 0 -b 320 <foo.wav >foo.mp3

Create a fixed 128Kb/s MP3 file from a .wav file.

audio/mp3enc -h <foo.wav >foo.mp3

Streaming from stereo 44.1KHz raw PCM data, encoding mono at 16KHz (you may not need *dd*):

dd -conv swab | audio/mp3enc -a -r -m m --resample 16 -b 24

SOURCE

/sys/src/cmd/audio

SEE ALSO

play(1), juke(7), playlistfs(7)
http://www.underbit.com/products/mad/
http://xiph.org/doc/

http://flac.sourceforge.net/documentation.html

HISTORY

Pcmconv first appeared in 9front (December, 2012). *Mixfs* first appeared in 9front (December, 2013). *Flacenc* first appeared in 9front (January, 2021).

awk - pattern-directed scanning and processing language

SYNOPSIS

awk [-F fs][-d][-mf n][-mr n][-safe][-v var=value][-f progfile | prog][file ...]

DESCRIPTION

Awk scans each input *file* for lines that match any of a set of patterns specified literally in *prog* or in one or more files specified as -f *progfile*. With each pattern there can be an associated action that will be performed when a line of a *file* matches the pattern. Each line is matched against the pattern portion of every pattern-action statement; the associated action is performed for each matched pattern. The file name – means the standard input. Any *file* of the form *var=value* is treated as an assignment, not a file name, and is executed at the time it would have been opened if it were a file name. The option -v followed by *var=value* is an assignment to be done before the program is executed; any number of -v options may be present. -F *fs* option defines the input field separator to be the regular expression *fs*.

An input line is normally made up of fields separated by white space, or by regular expression FS. The fields are denoted \$1, \$2, ..., while \$0 refers to the entire line. If FS is null, the input line is split into one field per character.

To compensate for inadequate implementation of storage management, the -mr option can be used to set the maximum size of the input record, and the -mf option to set the maximum number of fields.

The -safe option causes *awk* to run in "safe mode," in which it is not allowed to run shell commands or open files and the environment is not made available in the ENVIRON variable.

A pattern-action statement has the form

pattern { action }

A missing { *action* } means print the line; a missing pattern always matches. Pattern-action statements are separated by newlines or semicolons.

An action is a sequence of statements. A statement can be one of the following:

<pre>if(expression) statement[else statement] while(expression) statement for(expression ; expression ; expression) statement</pre>				
for(var in array) statement				
do statement while(expression)				
break				
continue				
{ [statement] }				
expression	# commonly var = expression			
<pre>print[expression-list][> expression]</pre>				
<pre>printf format[, expression-list][> expression]</pre>				
return [expression]				
next	# skip remaining patterns on this input line			
nextfile	# skip rest of this file, open next, start at top			
<pre>delete array[expression]</pre>	# delete an array element			
delete array	# delete all elements of array			
exit[expression]	# exit immediately; status is <i>expression</i>			

Statements are terminated by semicolons, newlines or right braces. An empty *expression-list* stands for \$0. String constants are quoted " ", with the usual C escapes recognized within. Expressions take on string or numeric values as appropriate, and are built using the operators + - * / % \wedge (exponentiation), and concatenation (indicated by white space). The operators $! ++ -- += -= *= /= \% = ^{=} > = < <= = != ?:$ are also available in expressions. Variables may be scalars, array elements (denoted x[i]) or fields. Variables are initialized to the null string. Array subscripts may be any string, not necessarily numeric; this allows for a form of associative memory. Multiple subscripts such as [i, j, k] are permitted; the constituents are concatenated, separated by the value of SUBSEP.

The print statement prints its arguments on the standard output (or on a file if > file or >> file is present or on a pipe if | cmd is present), separated by the current output field separator, and terminated by the output record separator. file and cmd may be literal names or parenthesized expressions; identical string values in different statements denote the same open file. The printf statement formats its expression list according to the format (see fprintf(2)). The builtin function close(expr) closes the file or pipe expr. The built-in function fflush(expr) flushes any buffered output for the file or pipe expr. If expr is omitted or is a null string, all open files are flushed.

The mathematical functions exp, log, sqrt, sin, cos, and atan2 are built in. Other built-in functions:

- length If its argument is a string, the string's length is returned. If its argument is an array, the number of subscripts in the array is returned. If no argument, the length of \$0 is returned.
- rand random number on (0,1)
- srand sets seed for rand and returns the previous seed.
- int truncates to an integer value
- utf converts its numerical argument, a character number, to a UTF string
- substr(s, m)

the maximum length substring of s that begins at position m counted from 1. substr(s, m, n)

- the n-character substring of s that begins at position m counted from 1.
- index(s, t)

the position in *s* where the string *t* occurs, or 0 if it does not.

match(s, r)

the position in *s* where the regular expression r occurs, or 0 if it does not. The variables RSTART and RLENGTH are set to the position and length of the matched string.

split(s, a, fs)

splits the string s into array elements a[1], a[2], ..., a[n], and returns n. The separation is done with the regular expression fs or with the field separator FS if fs is not given. An empty string as field separator splits the string into one array element per character.

sub(*r*, *t*, *s*)

substitutes t for the first occurrence of the regular expression r in the string s. If s is not given, \$0 is used. & in t is replaced by the match.

gsub same as sub except that all occurrences of the regular expression are replaced; sub and gsub return the number of replacements.

sprintf(fmt, expr, ...)

the string resulting from formatting expr ... according to the printf format fmt

system(cmd)

executes *cmd* and returns its exit status

tolower(str)

returns a copy of *str* with all upper-case characters translated to their corresponding lower-case equivalents.

toupper(str)

returns a copy of *str* with all lower-case characters translated to their corresponding upper-case equivalents.

The "function" getline sets \$0 to the next input record from the current input file; getline < file sets \$0 to the next record from *file*. getline *x* sets variable *x* instead. Finally, *cmd* | getline pipes the output of *cmd* into getline; each call of getline returns the next line of output from *cmd*. In all cases, getline returns 1 for a successful input, 0 for end of file, and -1 for an error.

Patterns are arbitrary Boolean combinations (with ! | | &&) of regular expressions and relational expressions. Regular expressions are as in regexp(6). Isolated regular expressions in a pattern apply to the entire line. Regular expressions may also occur in relational expressions, using the operators ~ and !~. /re/ is a constant regular expression; any string (constant or variable) may be used as a regular expression, except in the position of an isolated regular expression in a pattern.

A pattern may consist of two patterns separated by a comma; in this case, the action is performed for all lines from an occurrence of the first pattern though an occurrence of the second.

A relational expression is one of the following:

expression matchop regular-expression expression relop expression expression in array-name (expr, expr,...) in array-name

where a *relop* is any of the six relational operators in C, and a *matchop* is either \sim (matches) or $! \sim$ (does not match). A conditional is an arithmetic expression, a relational expression, or a Boolean combination of these.

The special patterns BEGIN and END may be used to capture control before the first input line is read and after the last. BEGIN and END do not combine with other patterns.

Variable names with special meanings:

CONVFMT	conversion format used when converting numbers (default %.6g)
FS	regular expression used to separate fields; also settable by option $-Ffs$.
NF	number of fields in the current record
NR	ordinal number of the current record
FNR	ordinal number of the current record in the current file
FILENAME	the name of the current input file
RS	input record separator (default newline)
OFS	output field separator (default blank)
ORS	output record separator (default newline)
OFMT	output format for numbers (default %.6g)
SUBSEP	separates multiple subscripts (default 034)
ARGC	argument count, assignable
ARGV	argument array, assignable; non-null members are taken as file names
ENVIRON	array of environment variables; subscripts are names.

Functions may be defined (at the position of a pattern-action statement) thus:

function foo(a, b, c) { ...; return x }

Parameters are passed by value if scalar and by reference if array name; functions may be called recursively. Parameters are local to the function; all other variables are global. Thus local variables may be created by providing excess parameters in the function definition.

EXAMPLES

length(\$0) > 72Print lines longer than 72 characters. { print \$2, \$1 } Print first two fields in opposite order. BEGIN { FS = ", [t] * | [t] + "} { print \$2, \$1 } Same, with input fields separated by comma and/or blanks and tabs. { s += \$1 } END { print "sum is", s, " average is", s/NR } Add up first column, print sum and average. /start/, /stop/ Print all lines between start/stop pairs. # Simulate echo(1) BEGIN { for (i = 1; i < ARGC; i++) printf "%s ", ARGV[i] printf "\n" exit } SOURCE /sys/src/cmd/awk SEE ALSO

sed(1), regexp(6),

A. V. Aho, B. W. Kernighan, P. J. Weinberger, *The AWK Programming Language*, Addison-Wesley, 1988. ISBN 0-201-07981-X

BUGS

There are no explicit conversions between numbers and strings. To force an expression to be treated as a number add 0 to it; to force it to be treated as a string concatenate "" to it. The scope rules for variables in functions are a botch; the syntax is worse.

UTF is not always dealt with correctly, though *awk* does make an attempt to do so. The *split* function with an empty string as final argument now copes with UTF in the string being split.

basename – strip file name affixes

SYNOPSIS

basename [-d] string [suffix]

DESCRIPTION

Basename deletes any prefix ending in slash (/) and the *suffix*, if present in *string*, from *string*, and prints the result on the standard output.

The -d option instead prints the directory component, that is, *string* up to but not including the final slash. If the string contains no slash, a period and newline are printed.

SOURCE

/sys/src/cmd/basename.c

bc - arbitrary-precision arithmetic language

SYNOPSIS

bc [-cdls] [file ...]

DESCRIPTION

Bc is an interactive processor for a language that resembles C but provides arithmetic on numbers of arbitrary length with up to 100 digits right of the decimal point. It takes input from any files given, then reads the standard input.

The -d option enables debugging output. The -l option stands for the name of an arbitrary precision math library. The -s option suppresses the automatic display of calculation results; all output is via the print command.

The following syntax for *bc* programs is like that of C; *L* means letter a-z, *E* means expression, *S* means statement.

Lexical

Lexical	
	comments are enclosed in /* */
	newlines end statements
Names	
	simple variables: L
	array elements: L[E]
	The words ibase, obase, and scale
Other operands	
•	arbitrarily long numbers with optional sign and decimal point.
	(E)
	sqrt(E)
	length(E)
	number of significant decimal digits
	scale(E)
	number of digits right of decimal point
	L(E,, E)
	function call
Operators	
operators	+ – * / % ^ (% is remainder; ^ is power)
	++
	== <= >= != < >
	= += -= *= /= %= ^=
Statements	/- /- //-
Statements	E
	—
	{ S; ; S }
	print E
	if (E) S
	while (E)S
	for (E; E; E) S
	null statement
	break
	quit
	"text"
Function definit	
	define L(L,, L){
	auto <i>L</i> , , <i>L</i>
	S;;S
	return E
	}
Functions in	-1 math library
	s(x) sine
	c(x) cosine

e(x) exponential l(x) log a(x) arctangent j(n, x) Bessel function

All function arguments are passed by value.

The value of an expression at the top level is printed unless the main operator is an assignment or the -s command line argument is given. Text in quotes, which may include newlines, is always printed. Either semicolons or newlines may separate statements. Assignment to scale influences the number of digits to be retained on arithmetic operations in the manner of dc(1). Assignments to ibase or obase set the input and output number radix respectively.

The same letter may be used as an array, a function, and a simple variable simultaneously. All variables are global to the program. Automatic variables are pushed down during function calls. In a declaration of an array as a function argument or automatic variable empty square brackets must follow the array name.

Bc is actually a preprocessor for dc(1), which it invokes automatically, unless the -c (compile only) option is present. In this case the dc input is sent to the standard output instead.

EXAMPLE

Define a function to compute an approximate value of the exponential. Use it to print 10 values. (The exponential function in the library gives better answers.)

```
scale = 20
     define e(x) {
           auto a, b, c, i, s
           a = 1
           b = 1
           s = 1
           for(i=1; 1; i++) {
                 a *= x
                 b *= i
                 c = a/b
                 if(c == 0) return s
                 s += c
           }
     for(i=1; i<=10; i++) print e(i)</pre>
FILES
     /sys/lib/bclib mathematical library
SOURCE
     /sys/src/cmd/bc.y
SEE ALSO
     dc(1), hoc(1)
```

BUGS

No &&, ||, or ! operators.

A for statement must have all three Es.

A quit is interpreted when read, not when executed.

bind, mount, unmount - change name space

SYNOPSIS

bind [option ...] new old

mount [option ...] servename old [spec]

unmount [new] old

DESCRIPTION

Bind and *mount* modify the file name space of the current process and other processes in the same name space group (see *fork*(2)). For both calls, *old* is the name of an existing file or directory in the current name space where the modification is to be made.

For *bind*, *new* is the name of another (or possibly the same) existing file or directory in the current name space. After a successful *bind*, the file name *old* is an alias for the object originally named by *new*; if the modification doesn't hide it, *new* will also still refer to its original file. The evaluation of *new* (see *intro*(2)) happens at the time of the *bind*, not when the binding is later used.

The *servename* argument to *mount* is the name of a file that, when opened, yields an existing connection to a file server. Almost always, *servename* will be a file in /srv (see srv(3)). In the discussion below, *new* refers to the file named by the *new* argument to *bind* or the root directory of the service available in *servename* after a *mount*. Either both *old* and *new* files must be directories, or both must not be directories.

Options control aspects of the modification to the name space:

- (none) Replace the *old* file by the new one. Henceforth, an evaluation of *old* will be translated to the new file. If they are directories (for *mount*, this condition is true by definition), *old* becomes a *union directory* consisting of one directory (the new file).
- -b Both files must be directories. Add the new directory to the beginning of the union directory represented by the old file.
- -a Both files must be directories. Add the new directory to the end of the union directory represented by the old file.
- -c This can be used in addition to any of the above to permit creation in a union directory. When a new file is created in a union directory, it is placed in the first element of the union that has been bound or mounted with the -c flag. If that directory does not have write permission, the create fails.
- -C (Only in *mount*.) By default, file contents are always retrieved from the server. With this option, the kernel may instead use a local cache to satisfy *read*(5) requests for files accessible through this mount point. The currency of cached data for a file is verified at each *open*(5) of the file from this client machine.
- -q Exit silently if the bind or mount operation fails.

Mount takes three additional options. The first, -k *keypattern*, constrains the set of *factotum*(4) keys used for an authenticated mount. The second, -n, causes *mount* to skip authentication entirely. The third, -N, skips authentication and specifies none as the username to the fileserver.

The *spec* argument to *mount* is passed in the *attach*(5) message to the server, and selects among different file trees served by the server.

The srv(3) service registry device, normally bound to /srv, is a convenient rendezvous point for services that can be mounted. After bootstrap, the file /srv/boot contains the communications port to the file system from which the system was loaded.

The effects of *bind* and *mount* can be undone with the *unmount* command. If two arguments are given to *unmount*, the effect is to undo a *bind* or *mount* with the same arguments. If only one argument is given, everything bound to or mounted upon *old* is unmounted.

EXAMPLES

To compile a program with the C library from July 16, 1992:

```
mount /srv/boot /n/dump dump
bind /n/dump/1992/0716/mips/lib/libc.a /mips/lib/libc.a
mk
```

SOURCE

```
/sys/src/cmd/bind.c
/sys/src/cmd/mount.c
/sys/src/cmd/unmount.c
```

SEE ALSO

bind(2), *open*(2), *srv*(3), *srv*(4)

bitsyload, light, pencal, keyboard, params, prompter - bitsy-specific utilities

SYNOPSIS

bitsy/bitsyload k|r[file]

bitsy/light[intensity]

bitsy/params[-f]

bitsy/pencal

bitsy/keyboard[-n]

bitsy/prompter[-n]file

DESCRIPTION

Bitsyload erases a section of flash memory on the Bitsy (iPAQ 3650 or 3830) and copies new information into it, using the format required by the Compaq boot loader. The required first argument is the destination, either k for /dev/flash/kernel or r for /dev/flash/ramdisk. The optional second argument is the name of the file to load. The default kernel file is /sys/src/9/bitsy/9bitsy and the default ramdisk file is /sys/src/9/bitsy/ramdisk.

Light sets the intensity of the display backlight. The values for *intensity* are:

on set intensity to maximum, the default

- off turn off backlight
- *n* sets the intensity to *n*, where *n* is a value between 0 and 128. Intensity 0 doesn't turn off the backlight, it just sets it to the dimmest value.

Pencal calibrates the display with the touch screen on a Bitsy. It loops prompting the user with crosses whose center that the user must touch with the stylus. After a consistent set of touches, it writes the calibration both to the kernel and to standard out. It is normally called by the bitsy's /bin/cpurc.

Params copies the contents of the file /dev/tmpparams, into the flash partition, /dev/flash/params, or if the -f flag it set copies in the opposite direction.

Keyboard creates a virtual on-screen keyboard and, unless the -n option is specified, a scribble area. A user inputs characters by tapping the keys or by drawing characters in the scribble area (see *scribble*(2)). It is usually run as the keyboard command for *rio*(1) using rio's -k option.

Prompter is a small editor used to configure parameters when a Bitsy boots. It displays the file and starts up a keyboard and scribble pad for input. Clicking with the stylus in the text selects where input characters will go. Pressing Button 5 (top left side of the Bitsy) or typing the Esc key on the keyboard causes *prompter* to write back the updated file and exit; Del causes *prompter* to exit without writing the file. The -n flag suppresses the scribble area.

EXAMPLE

Prompter, params, and calibrate are used in only one place, the Bitsy's /rc/bin/cpurc:

```
# set variables
ramfs
bitsy/params -f
if(! grep -s '^calibrate=' /tmp/tmpparams)
        bitsy/pencal >>/tmp/tmpparams
if not {
        eval '{grep '^calibrate=' /tmp/tmpparams}
        echo calibrate $calibrate > '#m/mousectl'
}
bitsy/prompter /tmp/tmpparams
bitsy/params
```

SOURCE

/sys/src/cmd/bitsy

blit - Blit emulator

SYNOPSIS

games/blit[-m][-b baud][-C bg,fg]-d |-t [net!]machine[!port]

DESCRIPTION

Blit is an emulator for the Blit terminal. It connects to the host specified by the dial(2) string [net!]machine[!port].

The colors are configurable with the -C option in the format *rrggbb*, *rrggbb*, where the first color is the background (normally white) and the second color is the foreground (normally black).

The emulator has accurate relative timing but runs as fast as it can. By default, however, it uses a baudrate of 40,000 baud (real hardware used 19,200). This is configurable with the -b option. Beware that the Blit software is not able to handle baud rates that are too high.

If the -m option is set, the Plan 9 mouse cursor is not hidden.

If -d is specified instead of -t, the diagnostic ROM is booted instead.

SOURCE

/sys/src/games/blit

BUGS

It should support connections via a pipe rather than telnet.

HISTORY

Blit first appeared in 9front (Mar, 2017).

bullshit - assemble a stream of bullshit from words in a file

SYNOPSIS

bullshit[file]

DESCRIPTION

Bullshit prints a one-line nonsense phrase assembled from random words. If a *file* is specified, the words are taken from that file; otherwise they are selected from /lib/bullshit.

FILES

/lib/bullshit

SOURCE

/rc/bin/bullshit

HISTORY

Bullshit first appeared in 9front (August, 2011).

bundle - collect files for distribution

SYNOPSIS

bundle file ...

DESCRIPTION

Bundle writes on its standard output a shell script for rc(1) or a Bourne shell which, when executed, will recreate the original *files*. Its main use is for distributing small numbers of text files by mail(1).

Although less refined than standard archives from ar(1) or tar(1), a bundle file is selfdocumenting and complete; little preparation is required on the receiving machine.

EXAMPLES

bundle mkfile *.[ch] | mail kremvax!boris

Send a makefile to Boris together with related .c and .h files. Upon receiving the mail, Boris may save the file sans postmark, say in gift/horse, then do

cd gift; rc horse; mk

SOURCE

/rc/bin/bundle

SEE ALSO

ar(1), *tar*(1), *mail*(1)

BUGS

Bundle will not create directories and is unsatisfactory for non-text files.

Beware of gift horses.

cal - print calendar

SYNOPSIS

cal[-s 1..7][month][year]

DESCRIPTION

Cal prints a calendar. *Month* is either a number from 1 to 12, a lower case month name, or a lower case three-letter prefix of a month name. *Year* can be between 1 and 9999. If either *month* or *year* is omitted, the current month or year is used. If only one argument is given, and it is a number larger than 12, a calendar for all twelve months of the given year is produced; otherwise a calendar for just one month is printed. The calendar produced is that for England and her colonies.

-s N makes *cal* display N, specified as a number between 1 to 7 (Monday to Sunday), as the first day of the week. The default is Sunday.

Try

cal sep 1752

SOURCE

/sys/src/cmd/cal.c

BUGS

The year is always considered to start in January even though this is historically naive.

Beware that cal 90 refers to the early Christian era, not the 20th century.

calendar - print upcoming events

SYNOPSIS

calendar [-dy][-p days][file ...]

DESCRIPTION

Calendar reads the named files, default /usr/\$user/lib/calendar, and writes to standard output any lines containing today's or tomorrow's date. Examples of recognized date formats are "4/11", "April 11", "Apr 11", "11 April", and "11 Apr". A special form may be used to represent weekly and monthly events: "Every Tuesday" "The third Wednesday" All comparisons are case insensitive.

If the -y flag is given, an attempt is made to match on year too. In this case, dates of the forms listed above will be accepted if they are followed by the current year (or last two digits thereof) or not a year — digits not followed by white space or non-digits.

If the -p flag is given, its argument is the number of days ahead to match dates. This flag is not repeatable, and it performs no special processing at the end of the week.

The -d flag enables debugging output.

On Friday and Saturday, events through Monday are printed.

To have your calendar mailed to you every day, use *cron*(8).

FILES

/usr/\$user/lib/calendar personal calendar

SOURCE

/sys/src/cmd/calendar.c

cat, read - catenate files

SYNOPSIS

cat [file ...] read [-m] [-n nlines] [-c nbytes] [file ...]

DESCRIPTION

Cat reads each file in sequence and writes it on the standard output. Thus

cat file

prints a file and

cat file1 file2 >file3

concatenates the first two files and places the result on the third.

If no *file* is given, *cat* reads from the standard input. Output is buffered in blocks matching the input.

Read copies to standard output exactly one line from the named *file*, default standard input. It is useful in interactive rc(1) scripts.

The -m flag causes it to continue reading and writing multiple lines until end of file; -n causes it to read no more than *nlines* lines.

With the -c flag, *read* copies exactly *nbytes* of characters instead of lines. It is mutually exclusive with -n and -m flag.

Read always executes a single write for each line of input, which can be helpful when preparing input to programs that expect line-at-a-time data. It never reads any more data from the input than it prints to the output.

SOURCE

/sys/src/cmd/cat.c
/sys/src/cmd/read.c

SEE ALSO

cp(1)

DIAGNOSTICS

Read exits with status eof on end of file or, in the -n case, if it doesn't read *nlines* lines.

BUGS

Beware of cat a b > a and cat a b > b, which destroy input files before reading them.

cb - C program beautifier

SYNOPSIS

cb[-js][-1 *length*][*file* ...]

DESCRIPTION

Cb reads syntactically correct C programs from its input or the given files, and writes them to its stdout with a more visually pleasing spacing and indentation. *Cb* understands no C++ syntax bar newline-terminated comments; and by default all user new-lines are preserved in the output.

The options are:

- -j Join split lines.
- -s Print code in the so-called K&R style used in *The C Programming Language*.
- -1 Split lines that are longer than *length*.

SOURCE

/sys/src/cmd/cb

BUGS

Cb does not reformat structure initializers. Punctuation hidden in macros can cause indentation errors.

chgrp - change file group

SYNOPSIS

chgrp [–ou] group file ...

DESCRIPTION

The group of each named file is changed to *group*, which should be a name known to the server holding the file.

A file's group can be changed by the file's owner, if the owner is a member of the new group, or by the leader of both the file's current group and the new group.

The -o and -u option are synonyms; they specify that the *owner* is to be set, rather than the group. They are ineffectual unless the file server is in the bootstrap state that permits changing file ownership.

SOURCE

/sys/src/cmd/chgrp.c

SEE ALSO

ls(1), *chmod*(1), *stat*(2)

chmod - change mode

SYNOPSIS

chmod mode file ...

DESCRIPTION

The mode of each named file is changed according to *mode*, which may be an octal number or a symbolic change to the existing mode. A *mode* is an octal number constructed from the OR of the following modes.

0400 read by owner

0200 write by owner

0100 execute (search in directory) by owner

- 0070 read, write, execute (search) by group
- 0007 read, write, execute (search) by others

A symbolic *mode* has the form:

[who] op permission

The *who* part is a combination of the letters u (for user's permissions), g (group) and o (other). The letter a stands for ugo. If *who* is omitted, the default is a.

Op can be + to add *permission* to the file's mode, - to take away *permission*, and = to assign *permission* absolutely (all other bits will be reset).

Permission is any combination of the letters r (read), w (write), x (execute), a (append only), 1 (exclusive access), and t (temporary file).

Only the owner of a file or the group leader of its group may change the file's mode.

SOURCE

/sys/src/cmd/chmod.c

SEE ALSO

ls(1), *stat*(2), *stat*(5)

cleanname - clean a path name

SYNOPSIS

cleanname [-d pwd] names ...

DESCRIPTION

For each file name argument, *cleanname*, by lexical processing only, prints the shortest equivalent string that names the same (possibly hypothetical) file. It eliminates multiple and trailing slashes, and it lexically interprets . and . . directory components in the name. If the -d option is present, unrooted names are prefixed with *pwd*/ before processing.

SOURCE

/sys/src/cmd/cleanname.c

SEE ALSO

cleanname(2).

cmp – compare two files

SYNOPSIS

cmp [-lls] file1 file2 [offset1 [offset2]]

DESCRIPTION

Cmp compares the two files and prints a message if the contents differ.

The options are:

- -1 Print the byte number (decimal) and the differing bytes (hexadecimal) for each difference.
- -L Print the line number of the first differing byte.
- -s Print nothing for differing files, but set the exit status.

If offsets are given, comparison starts at the designated byte position of the corresponding file. Offsets that begin with 0x are hexadecimal; with 0, octal; with anything else, decimal.

SOURCE

/sys/src/cmd/cmp.c

SEE ALSO

diff(1)

DIAGNOSTICS

If a file is inaccessible or missing, the exit status is open. If the files are the same, the exit status is empty (true). If they are the same except that one is longer than the other, the exit status is EOF. Otherwise *cmp* reports the position of the first disagreeing byte and the exit status is differ.

col - column alignment

SYNOPSIS

col[-bfx]

DESCRIPTION

Col overlays lines to expunge reverse line feeds (ESC-7) and half line feeds (ESC-9 and ESC-8) as produced by *nroff* for .2C in *ms*(6) or *man*(6) and for *tbl*(1). *Col* is a pure filter. It normally emits only full line feeds; option -f (fine) allows half line feeds too. Option -b removes backspaces, printing just one of each pile of overstruck characters. *Col* normally converts white space to tabs; option -x overrides this feature. Other escaped characters and non-printing characters are ignored.

EXAMPLES

tbl file | nroff -ms | col | p

Format some tables for printing on typewriters; use *col* to remove reverse line feeds, and paginate the output.

SOURCE

/sys/src/cmd/col.c

SEE ALSO

pr(1)

BUGS

Col can't back up more than 128 lines or handle more than 800 characters per line, and understands VT (013) as reverse line feed.

getmap, colors - display color map

SYNOPSIS

colors[-rx]

getmap[colormap]

DESCRIPTION

Colors presents a grid showing the colors in the current color map. If the display is true color, *colors* shows a grid of the RGBV color map (see *color*(6)).

Clicking mouse button 1 over a color in the grid will display the map index for that color, its red, green, and blue components, and the 32-bit hexadecimal color value as defined in *allocimage*(2). If the -x option is specified, the components will also be listed in hexadecimal.

The -r option instead shows, in the same form, a grey-scale ramp.

A menu on mouse button 3 contains a single entry, to exit the program.

On 8-bit color-mapped displays, *getmap* loads the display's color map (default rgbv). The named *colormap* can be a file in the current directory or in the standard repository /lib/cmap. It can also be a string of the form gamma or gammaN, where N is a floating point value for the gamma, defining the contrast for a monochrome map. Similarly, rgamma and rgammaN define a reverse-video monochrome map. Finally, the names screen or display or vga are taken as synonyms for the current color map stored in the display hardware.

FILES

/lib/cmap directory of color map files

SOURCE

```
/sys/src/cmd/colors.c
/sys/src/cmd/getmap.c
```

SEE ALSO

color(6)

comm - select or reject lines common to two sorted files

SYNOPSIS

comm [-123] file1 file2

DESCRIPTION

Comm reads *file1* and *file2*, which are in lexicographical order, and produces a three column output: lines only in *file1*; lines only in *file2*; and lines in both files. The file name – means the standard input.

Flag 1, 2, or 3 suppresses printing of the corresponding column.

EXAMPLE

comm -12 file1 file2

Print lines common to two sorted files.

SOURCE

/sys/src/cmd/comm.c

SEE ALSO

sort(1), cmp(1), diff(1), uniq(1)

con, telnet, rx, hayes, xms, xmr - remote login, execution, and XMODEM file transfer

SYNOPSIS

con [-CdnrRsTv][-b baud][-1[user]][-S svc][-c cmd][net!]machine

telnet[-dCrn][-s svc][net!]machine

rx [-eTr] [-1 user] [net!] machine [command-word ...]

hayes [-pv] number [device]

xms [-1p] file

xmr file

DESCRIPTION

Con connects to the computer whose network address is *net*! *machine* and logs in if possible. With no options, the account name used on the remote system is the same as that on the local system. Standard input and output go to the local machine.

Options are:

- -b sets the baud rate of a dial-up connection to *baud*.
- -n if the input is a file or pipe, do not hang up the connection when EOF is received, but instead wait for the remote end to hang up.
- -1 with an argument causes *user* to be used as the account name on the remote system when performing BSD *rlogin* authentication. Without an argument this option disables automatic login and a normal login session ensues.
- -C forces cooked mode, that is, local echo.
- -c runs *cmd* as if it had been typed as a command from the escape mode.
- -v (verbose mode) causes information about connection attempts to be output to standard error. This can be useful when trying to debug network connectivity.
- -d causes debugging information to be output to standard error.
- -r suppresses printing of any carriage return followed by a new line. This is useful since carriage return is a printable character in Plan 9.
- -R translates newlines to carriage returns and *vice versa*.
- -T translates incoming carriage returns to newlines.
- -s strips received characters to 7 bits to forestall misinterpretation of ASCII with parity as UTF.
- -S Post a pipe as /srv/svc and connect it to standard input and output. This can be used with -n to create a standing connection that *consolefs*(4), for example, can then open. For *telnet*, this option is -s.

The control- $\$ character is a local escape. It prompts with >>>. Legitimate responses to the prompt are

i Send a quit [sic] signal to the remote machine.

- b Send a break.
- . Return from the escape.
- ! cmd Run the command with the network connection as its standard input and standard output. Standard error will go to the screen. This is useful for transmitting and receiving files over the connections using programs such as *xms*.
- r Toggle printing of carriage returns.

Telnet is similar to con, but uses the *telnet* protocol to communicate with the remote machine. It shares *con's* -C, -d, -n, and -r options.

Rx executes one shell command on the remote machine as if logged in there, but with local standard input and output. A rudimentary shell environment is provided. If the target is a Plan 9 machine, \$service there will be rx. Options are:

q Exit.

- -e a zero length message will not be written to the connection when standard input is closed.
- -1 runs as *user* on the remote machine if the remote is a BSD machine.
- -r same as for *con*
- -T same as for *con*

Network addresses for both *con* and *rx* have the form *network* ! *machine*. Supported networks are those listed in /net.

Hayes dials number on a Hayes-compatible modem, *device*. Under -p, it uses pulse dialing. Upon connecting, bytes are copied bidirectionally between the connection and standard input and output.

The commands *xms* and *xmr* respectively send and receive a single file using the XMODEM protocol. They use standard input and standard output for communication and are intended for use with *con*. The -1 option to *xms* causes it to use kilobyte packet size of 1024 bytes. The -p option causes it to print a progress message every ten kilobytes.

EXAMPLES

```
rx kremvax cat file1 >file2
Copy remote file1 to local file2.
```

rx kremvax cat file1 '>file2'
 Copy remote file1 to remote file2.

eqn paper | rx kremvax troff -ms | rx deepthought lp Parallel processing: do each stage of a pipeline on a different machine.

SOURCE

```
/sys/src/cmd/rx.c
/sys/src/cmd/ip/telnet.c
/sys/src/cmd/con for all other commands
```

BUGS

SEE ALSO

cpu(1), telco(4)

Con and *telnet* are merely obsolescent; the other commands are obsolete and deprecated.

Under rx, a program that should behave specially towards terminals may not: e.g., remote shells will not prompt. Also under rx, the remote standard error and standard output are combined and go inseparably to the local standard output. Rx will consume its standard input by copying it to the remote system, so redirect it from /dev/null if that's not what you want.

cp, fcp, mv - copy, move files

SYNOPSIS

cp [-gux] file1 file2 cp [-gux] file ... directory fcp [-gux] file1 file2

fcp [-gux] file ... directory

mv file1 file2

mv file ... directory

DESCRIPTION

In the first form *file1* is any name and *file2* is any name except an existing directory. In the second form the commands copy or move one or more *files* into a *directory* under their original file names, as if by a sequence of commands in the first form. Thus $cp \ f1 \ f2 \ dir$ is equivalent to $cp \ f1 \ dir/f1$; $cp \ f2 \ dir/f2$.

Cp copies the contents of plain *file1* to *file2*. The mode and owner of *file2* are preserved if it already exists; the mode of *file1* is used otherwise. The -x option sets the mode and modified time of *file2* from *file1*; -g sets the group id; and -u sets the group id and user id (which is usually only possible if the file server is in an administrative mode).

Fcp behaves like *cp* but transfers multiple blocks in parallel while copying; it is noticeably faster than *cp* when the files involved are stored on servers connected over long-distance lines. It is only appropriate to use *fcp* with file servers that respect the *offset* in *read*(5) and *write* messages. This includes the disk-based file systems and ramfs but excludes most device file systems.

Mv moves file1 to file2. If the files are in the same directory, file1 is just renamed; otherwise mv behaves like cp - x followed by rm file1. Mv will rename directories, but it refuses to move a directory into another directory.

SOURCE

/sys/src/cmd/cp.c /sys/src/cmd/fcp.c /sys/src/cmd/mv.c

SEE ALSO

cat(1), dircp in tar(1), stat(2), read(5)

DIAGNOSTICS

Cp, fcp, and mv refuse to copy or move files onto themselves.

cpp - C language preprocessor

SYNOPSIS

cpp [option ...] [ifile [ofile]]

DESCRIPTION

Cpp interprets ANSI C preprocessor directives and does macro substitution. The input *ifile* and output *ofile* default to standard input and standard output respectively.

The options are:

–Dname

–Dname=def

-I dir Same as in 2c(1): add dir to the search for directives.

- -M Generate no output except a list of include files in a form suitable for specifying dependencies to mk(1). Use twice to list files in angle brackets.
- -N Turn off default include directories. All must be specified with -I, or in the environment variable include. Without this option, /\$objtype/include and /sys/include are used as the last two searched directories for include directives, where \$objtype is read from the environment.
- -V Print extra debugging information.
- -P Do not insert "#line" directives into the output.
- -. Inhibit include search in the source's directory.
- -i Print the list of directories searched when *#include* is found. Last listed are searched first.

In the absence of the -P option, the processed text output is sprinkled with lines that show the original input line numbering:

#line linenumber "ifile"

The command reads the environment variable *include* and adds its (blank-separated) list of directories to the standard search path for directives. They are looked at before any directories specified with -I, which are looked at before the default directories.

The input language is as described in the ANSI C standard. The standard Plan 9 C compilers do not use *cpp*; they contain their own simple but adequate preprocessor, so *cpp* is usually superfluous.

FILES

/sys/include directory for machine-independent include files
/\$objtype/include directory for machine-dependent include files

SOURCE

/sys/src/cmd/cpp

SEE ALSO

2c(1)

cpu - connection to CPU server

SYNOPSIS

cpu [-p][-h server][-u user][-a auth-method][-P patternfile][-e encryption-hash-algs][-k keypattern][-c cmd args ...]

cpu [-n] [-A *address*] [-R]

DESCRIPTION

This tool is deprecated and has been replaced by *rcpu*(1).

Cpu starts an rc(1) running on the *server* machine, or the machine named in the \$cpu environment variable if there is no -h option. *Rc*'s standard input, output, and error files will be /dev/cons in the name space where the *cpu* command was invoked. Normally, *cpu* is run in an rio(1) window on a terminal, so *rc* output goes to that window, and input comes from the keyboard when that window is current. *Rc*'s current directory is the working directory of the *cpu* command itself.

The name space for the new *rc* is an analogue of the name space where the *cpu* command was invoked: it is the same except for architecture-dependent bindings such as /bin and the use of fast paths to file servers, if available.

If a -u argument is present, *cpu* uses the argument as the remote user id.

If a -c argument is present, the remainder of the command line is executed by rc on the server, and then cpu exits.

If a -P argument is present, the *patternfile* is passed to *oexportfs*(4) to control how much of the local name space will be exported to the remote system.

The -a command allows the user to specify the authentication mechanism used when connecting to the remote system. The two possibilities for *auth-method* are:

- p9 This is the default. Authentication is done using the standard Plan 9 mechanisms, (see *authsrv*(6)). No user interaction is required.
- netkey Authentication is done using challenge/response and a hand held authenticator or the *netkey* program (see *passwd*(1)). The user must encrypt the challenge and type the encryption back to *cpu*. This is used if the local host is in a different protection domain than the server or if the user wants to log into the server as a different user.
- none This skips authentication. This requires the -n flag to be specified on the remote side.

The -e option specifies an encryption and/or hash algorithm to use for the connection. If both are specified, they must be space separated and comprise a single argument, so they must be quoted if in a shell command. The default is $rc4_256$ encryption and sha1 hashing. See *ssl*(3) for details on possible algorithms. The argument clear specifies no encryption algorithm and can be used to talk to older versions of the *cpu* service.

The -k flag specifies a key pattern to use to restrict the keys selected by the *auth_proxy* call used for authentication.

The name space is built by running /usr/\$user/lib/profile with the root of the invoking name space bound to /mnt/term. The service environment variable is set to cpu; the cputype and objtype environment variables reflect the server's architecture.

The -R flag causes *cpu* to run the server (remote) side of the protocol. It is run from service files such as /bin/service/tcp17010. The -n option allows using the none authentication method for incoming connections and must be specified before the -R flag.

The -p flag pushes the *aan*(8) filter onto the connection to protect against temporary network outages.

The -A flag sets the announce-string *address* to use for *aan*(8) connections, if requested by the initial protocol.

FILES

The name space of the terminal side of the *cpu* command is mounted, via *oexportfs*(4), on the CPU side on directory /mnt/term. The files such as /dev/cons are bound to their standard

locations from there.

SOURCE

/sys/src/cmd/cpu.c

SEE ALSO

rcpu(1), *rc*(1), *rio*(1), *oexportfs*(4), *aan*(8)

BUGS

Binds and mounts done after the terminal lib/profile is run are not reflected in the new name space.

By default, the entire namespace of the local system is exported to the remote system. Use of the -P option in conjunction with a customized patternfile can limit this exposure, but also limits the usefulness of /mnt/term.

crop, iconv - frame, crop, and convert image

SYNOPSIS

crop [-b red green blue][-c red green blue][-i n | -r minx miny maxx maxy | -x dx | -y dy][-t tx ty][file]

iconv[-u][-c chandesc][file]

DESCRIPTION

Crop reads an *image*(6) file (default standard input), crops it, and writes it as a compressed *image*(6) file to standard output. There are two ways to specify a crop, by color value or by geometry. They may be combined in a single run of *crop*, in which case the color value crop will be done first.

The -c option takes a red-green-blue triplet as described in *color*(2). (For example, white is 255 255 255.) The corresponding color is used as a value to be cut from the outer edge of the picture; that is, the image is cropped to remove the maximal outside rectangular strip in which every pixel has the specified color.

The -i option insets the image rectangle by a constant amount, n, which may be negative to generate extra space around the image. The -x and -y options are similar, but apply only to the x or y coordinates of the image.

The $-\mathbf{r}$ option specifies an exact rectangle.

The -t option specifies that the image's coordinate system should be translated by tx, ty as the last step of processing.

The -b option specifies a background color to be used to fill around the image if the cropped image is larger than the original, such as if the -i option is given a negative argument. This can be used to draw a monochrome frame around the image. The default color is black.

Iconv changes the format of pixels in the image *file* (default standard input) and writes the resulting image to standard output. Pixels in the image are converted according to the channel descriptor *chandesc*, (see *image*(6)). For example, to convert a 4-bit-per-pixel grey-scale image to an 8bit-per-pixel color-mapped image, *chandesc* should be m8. If *chandesc* is not given, the format is unchanged. The output image is by default compressed; the -u option turns off the compression.

EXAMPLE

To crop white edges off the picture and add a ten-pixel pink border,

crop -c 255 255 255 -i -10 -b 255 150 150 imagefile > cropped

SOURCE

/sys/src/cmd/crop.c

SEE ALSO

image(6), color(2)

BUGS

Iconv should be able to do Floyd-Steinberg error diffusion or dithering when converting to small image depths.

date, clock - date and time

SYNOPSIS

date[option][seconds]
clock

DESCRIPTION

Print the date, in the format

Tue Aug 16 17:03:52 CDT 1977

The options are

- -u Report Greenwich Mean Time (GMT) rather than local time.
- -n Report the date as the number of seconds since the epoch, 00:00:00 GMT, January 1, 1970.
- -i Report the date as ISO-8601 without time and timezone suffix.
- -t Report the date as ISO-8601 with time and timezone suffix.
- -m Report the date as an email compatible (RFC2822) time stamp.

The conversion from Greenwich Mean Time to local time depends on the \$timezone environment variable; see ctime(2).

If the optional argument *seconds* is present, it is used as the time to convert rather than the real time.

Clock draws a simple analog clock in its window.

FILES

/env/timezone	Current timezone name and adjustments.
/adm/timezone	A directory containing timezone tables.
/adm/timezone/local	Default timezone file, copied by <i>init</i> (8) into /env/timezone.

SOURCE

/sys/src/cmd/date.c
/sys/src/cmd/clock.c

db – debugger

SYNOPSIS

db [option ...] [textfile] [pid]

DESCRIPTION

Db is a general purpose debugging program. It may be used to examine files and to provide a controlled environment for the execution of Plan 9 programs.

A *textfile* is a file containing the text and initialized data of an executable program. A *memfile* is the memory image of an executing process. It is usually accessed via the process id (*pid*) of the process in /proc/*pid*/mem. A *memfile* contains the text, data, and saved registers and process state. A *map* associated with each *textfile* or *memfile* supports accesses to instructions and data in the file; see 'Addresses'.

An argument consisting entirely of digits is assumed to be a process id; otherwise, it is the name of a *textfile*. When a *textfile* is given, the textfile map is associated with it. If only a *pid* is given, the textfile map is associated with /proc/pid/text. When a *pid* is given, the memfile map is associated with /proc/pid/text. When a *pid* is given, the memfile are not permitted.

Commands to db are read from the standard input and responses are to the standard output. The options are

-k Use the kernel stack of process *pid* to debug the executing kernel process. If *textfile* is not specified, file / \$*cputype*/9*type* is used, where *type* is the second word in \$terminal.

-w Create *textfile* and *memfile* if they don't exist; open them for writing as well as reading.

-I path

Directory in which to look for relative path names in \$< and \$<< commands.

-m*machine*

Assume instructions are for the given CPU type (any standard architecture name, such as amd64 or 386, plus mipsco and sunsparc, which cause disassembly to the manufacturer's syntax) instead of using the magic number to select the CPU type.

Most *db* commands have the following form:

```
[address] [, count] [command]
```

If *address* is present then the current position, called 'dot', is set to *address*. Initially dot is set to 0. Most commands are repeated *count* times with dot advancing between repetitions. The default *count* is 1. *Address* and *count* are expressions. Multiple commands on one line must be separated by ;.

Expressions

Expressions are evaluated as long ints.

- . The value of dot.
- + The value of dot incremented by the current increment.
- The value of dot decremented by the current increment.
- " The last *address* typed.

integer

A number, in decimal radix by default. The prefixes 0 and 00 and 00 (zero oh) force interpretation in octal radix; the prefixes 0t and 0T force interpretation in decimal radix; the prefixes 0x, 0X, and # force interpretation in hexadecimal radix. Thus 020, 0020, 0t16, and #10 all represent sixteen.

integer. fraction

A single-precision floating point number.

'c' The 16-bit value of a character. \setminus may be used to escape a '.

<name

The value of *name*, which is a register name. The register names are those printed by the

\$r command.

symbol

A *symbol* is a sequence of upper or lower case letters, underscores or digits, not starting with a digit. $\$ may be used to escape other characters. The location of the *symbol* is calculated from the symbol table in *textfile*.

routine . name

The address of the variable *name* in the specified C routine. Both *routine* and *name* are *symbols*. If *name* is omitted the value is the address of the most recently activated stack frame corresponding to *routine*; if *routine* is omitted, the active procedure is assumed.

file : integer

The address of the instruction corresponding to the source statement at the indicated line number of the file. If the source line contains no executable statement, the address of the instruction associated with the nearest executable source line is returned. Files begin at line 1. If multiple files of the same name are loaded, an expression of this form resolves to the first file encountered in the symbol table.

(exp)

The value of the expression *exp*.

Monadic operators

- * *exp* The contents of the location addressed by *exp* in *memfile*.
- @*exp* The contents of the location addressed by *exp* in *textfile*.
- -exp Integer negation.
- ~*exp* Bitwise complement.
- %*exp* When used as an *address, exp* is an offset into the segment named *ublock*; see 'Addresses'.

Dyadic operators are left-associative and are less binding than monadic operators.

e1+e2 Integer addition.

- e1-e2 Integer subtraction.
- *e1* * *e2* Integer multiplication.
- e1%e2 Integer division.
- e1&e2 Bitwise conjunction.
- *e1* | *e2* Bitwise disjunction.
- *e1#e2 E1* rounded up to the next multiple of *e2*.

Commands

Most commands have the following syntax:

- ?f Locations starting at *address* in *textfile* are printed according to the format f.
- */f* Locations starting at *address* in *memfile* are printed according to the format *f*.
- = f The value of *address* itself is printed according to the format f.

A *format* consists of one or more characters that specify a style of printing. Each format character may be preceded by a decimal integer that is a repeat count for the format character. If no format is given then the last format is used.

Most format letters fetch some data, print it, and advance (a local copy of) dot by the number of bytes fetched. The total number of bytes in a format becomes the *current* increment.

- o Print two-byte integer in octal.
- O Print four-byte integer in octal.
- q Print two-byte integer in signed octal.
- Q Print four-byte integer in signed octal.
- d Print two-byte integer in decimal.
- D Print four-byte integer in decimal.

- V Print eight-byte integer in decimal.
- Z Print eight-byte integer in unsigned decimal.
- x Print two-byte integer in hexadecimal.
- X Print four-byte integer in hexadecimal.
- Y Print eight-byte integer in hexadecimal.
- u Print two-byte integer in unsigned decimal.
- U Print four-byte integer in unsigned decimal.
- f Print as a single-precision floating point number.
- F Print double-precision floating point.
- b Print the addressed byte in hexadecimal.
- c Print the addressed byte as an ASCII character.
- C Print the addressed byte as a character. Printable ASCII characters are represented normally; others are printed in the form \xnn .
- s Print the addressed characters, as a UTF string, until a zero byte is reached. Advance dot by the length of the string, including the zero terminator.
- S Print a string using the escape convention (see C above).
- r Print as UTF the addressed two-byte integer (rune).
- R Print as UTF the addressed two-byte integers as runes until a zero rune is reached. Advance dot by the length of the string, including the zero terminator.
- i Print as machine instructions. Dot is incremented by the size of the instruction.
- I As i above, but print the machine instructions in an alternate form if possible: sunsparc and mipsco reproduce the manufacturers' syntax.
- M Print the addressed machine instruction in a machine-dependent hexadecimal form.
- a Print the value of dot in symbolic form. Dot is unaffected.
- A Print the value of dot in hexadecimal. Dot is unaffected.
- z Print the function name, source file, and line number corresponding to dot (textfile only). Dot is unaffected.
- p Print the addressed value in symbolic form. Dot is advanced by the size of a machine address.
- t When preceded by an integer, tabs to the next appropriate tab stop. For example, 8t moves to the next 8-space tab stop. Dot is unaffected.
- n Print a newline. Dot is unaffected.
- "..." Print the enclosed string. Dot is unaffected.
- A Dot is decremented by the current increment. Nothing is printed.
- + Dot is incremented by 1. Nothing is printed.
- Dot is decremented by 1. Nothing is printed.

Other commands include:

newline

Update dot by the current increment. Repeat the previous command with a *count* of 1.

[?/]l value mask

Words starting at dot are masked with *mask* and compared with *value* until a match is found. If 1 is used, the match is for a two-byte integer; L matches four bytes. If no match is found then dot is unchanged; otherwise dot is set to the matched location. If *mask* is omitted then ~0 is used.

[?/]w value ...

Write the two-byte *value* into the addressed location. If the command is W, write four bytes.

[?/]m s b e f [?]

New values for (b, e, f) in the segment named *s* are recorded. Valid segment names are *text*, *data*, or *ublock*. If less than three address expressions are given, the remaining parameters are left unchanged. If the list is terminated by ? or / then the file (*textfile* or *memfile* respectively) is used for subsequent requests. For example, /m? causes / to refer to *textfile*.

>name

Dot is assigned to the variable or register named.

! The rest of the line is passed to *rc*(1) for execution.

\$ modifier

Miscellaneous commands. The available *modifiers* are:

- <f Read commands from the file f. If this command is executed in a file, further commands in the file are not seen. If f is omitted, the current input stream is terminated. If a *count* is given, and is zero, the command is ignored.
- << f Similar to < except it can be used in a file of commands without causing the file to be closed. There is a (small) limit to the number of << files that can be open at once.
- > f Append output to the file f, which is created if it does not exist. If f is omitted, output is returned to the terminal.
- ? Print process id, the condition which caused stopping or termination, the registers and the instruction addressed by pc. This is the default if *modifier* is omitted.
- r Print the general registers and the instruction addressed by pc. Dot is set to pc.
- R Like \$r, but include miscellaneous processor control registers and floating point registers.
- f Print floating-point register values as single-precision floating point numbers.
- F Print floating-point register values as double-precision floating point numbers.
- b Print all breakpoints and their associated counts and commands. 'B' produces the same results.
- c Stack backtrace. If *address* is given, it specifies the address of a pair of 32-bit values containing the sp and pc of an active process. This allows selecting among various contexts of a multi-threaded process. If C is used, the names and (long) values of all parameters, automatic and static variables are printed for each active function. If *count* is given, only the first *count* frames are printed.
- a Attach to the running process whose pid is contained in *address*.
- e The names and values of all external variables are printed.
- w Set the page width for output to *address* (default 80).
- q Exit from *db*.
- m Print the address maps.
- k Simulate kernel memory management.

Mmachine

Set the *machine* type used for disassembling instructions.

: modifier

Manage a subprocess. Available modifiers are:

- h Halt an asynchronously running process to allow breakpointing. Unnecessary for processes created under *db*, e.g. by :r.
- bc Set breakpoint at *address*. The breakpoint is executed *count*-1 times before causing a stop. Also, if a command c is given it is executed at each breakpoint and if it sets dot to zero the breakpoint causes a stop.
- d Delete breakpoint at *address*.
- **r** Run *textfile* as a subprocess. If *address* is given the program is entered at that point; otherwise the standard entry point is used. *Count* specifies how many breakpoints are to be ignored before stopping. Arguments to the subprocess may be supplied on the same line as the command. An argument starting with < or > causes the standard input or output to be established for the command.
- cs The subprocess is continued. If s is omitted or nonzero, the subprocess is sent the note that caused it to stop. If 0 is specified, no note is sent. (If the stop was due to a breakpoint or single-step, the corresponding note is elided before continuing.) Breakpoint skipping is the same as for r.
- ss As for c except that the subprocess is single stepped for *count* machine instructions. If a note is pending, it is received before the first instruction is executed. If there is no current subprocess then *textfile* is run as a subprocess as for r. In this case no note can be sent; the remainder of the line is treated as arguments to the subprocess.
- Ss Identical to s except the subprocess is single stepped for *count* lines of C source. In optimized code, the correspondence between C source and the machine instructions is approximate at best.

- x The current subprocess, if any, is released by *db* and allowed to continue executing normally.
- k The current subprocess, if any, is terminated.
- nc Display the pending notes for the process. If c is specified, first delete c'th pending note.

Addresses

The location in a file or memory image associated with an address is calculated from a map associated with the file. Each map contains one or more quadruples (*t*, *b*, *e*, *f*), defining a segment named *t* (usually, *text*, *data*, or *ublock*) mapping addresses in the range *b* through *e* to the part of the file beginning at offset *f*. The memory model of a Plan 9 process assumes that segments are disjoint. There can be more than one segment of a given type (e.g., a process may have more than one text segment) but segments may not overlap. An address *a* is translated to a file address by finding a segment for which $b \le a < e$; the location in the file is then *address*+*f*-*b*.

Usually, the text and initialized data of a program are mapped by segments called *text* and *data*. Since a program file does not contain bss, stack or ublock data, these data are not mapped by the data segment. The text segment is mapped similarly in a normal (i.e., non-kernel) *memfile*. However, the segment called *data* maps memory from the beginning of the program's data space to the base of the ublock. This region contains the program's static data, the bss, the heap and the stack. A segment called *ublock* maps the page containing its registers and process state.

Sometimes it is useful to define a map with a single segment mapping the region from 0 to 0xFFFFFFF; a map of this type allows the entire file to be examined without address translation.

Registers are saved at a machine-dependent offset in the ublock. It is usually not necessary to know this offset; the r, r, r, r, r and r commands calculate it and display the register contents.

The m command dumps the currently active maps. The m and m commands modify the segment parameters in the *textfile* and *memfile* maps, respectively.

EXAMPLES

To set a breakpoint at the beginning of write() in extant process 27:

```
% db 27
:h
write:b
:c
```

To examine the Plan 9 kernel stack for process 27:

% db -k 27 \$C

Similar, but using a kernel named test:

% db -k test 27 \$C

To set a breakpoint at the entry of function parse when the local variable argc in main is equal to 1:

parse:b *main.argc-1=X

This prints the value of $\arg c-1$ which as a side effect sets dot; when $\arg c$ is one the breakpoint will fire. Beware that local variables may be stored in registers; see the BUGS section.

Debug process 127 on remote machine kremvax:

```
% import kremvax /proc
% db 127
$C
```

FILES

```
/proc/*/text
/proc/*/mem
/proc/*/ctl
/proc/*/note
```

SEE ALSO

acid(1), nm(1), proc(3)

SOURCE

/sys/src/cmd/db

DIAGNOSTICS

Exit status is null, unless the last command failed or returned non-null status.

BUGS

Examining a local variable with *routine.name* returns the contents of the memory allocated for the variable, but with optimization (suppressed by the -N compiler flag) variables often reside in registers. Also, on some architectures, the first argument is always passed in a register.

Variables and parameters that have been optimized away do not appear in the symbol table, returning the error *bad local variable* when accessed by *db*.

Because of alignment incompatibilities, Motorola 68000 series machines can not be debugged remotely from a processor of a different type.

Breakpoints should not be set on instructions scheduled in delay slots. When a program stops on such a breakpoint, it is usually impossible to continue its execution.

dc – desk calculator

SYNOPSIS

dc [file]

DESCRIPTION

Dc is an arbitrary precision desk calculator. Ordinarily it operates on decimal integers, but one may specify an input base, output base, and a number of fractional digits to be maintained. The overall structure of dc is a stacking (reverse Polish) calculator. If an argument is given, input is taken from that file until its end, then from the standard input. The following constructions are recognized:

number

The value of the number is pushed on the stack. A number is an unbroken string of the digits 0-9A-F or 0-9a-f. A hexadecimal number beginning with a lower case letter must be preceded by a zero to distinguish it from the command associated with the letter. It may be preceded by an underscore _ to input a negative number. Numbers may contain decimal points.

+ - / * % ^

Add +, subtract -, multiply *, divide /, remainder %, or exponentiate \land the top two values on the stack. The two entries are popped off the stack; the result is pushed on the stack in their place. Any fractional part of an exponent is ignored.

s*x*

- Sx Pop the top of the stack and store into a register named x, where x may be any character. Under operation S register x is treated as a stack and the value is pushed on it.
- 1*x*
- Lx Push the value in register x onto the stack. The register x is not altered. All registers start with zero value. Under operation L register x is treated as a stack and its top value is popped onto the main stack.
- d Duplicate the top value on the stack.
- p Print the top value on the stack. The top value remains unchanged. P interprets the top of the stack as a text string, removes it, and prints it.
- f Print the values on the stack.
- q
- Q Exit the program. If executing a string, the recursion level is popped by two. Under operation Q the top value on the stack is popped and the string execution level is popped by that value.
- x Treat the top element of the stack as a character string and execute it as a string of *dc* commands.
- X Replace the number on the top of the stack with its scale factor.

[...]

Put the bracketed text string on the top of the stack.

<x >x

- =x Pop and compare the top two elements of the stack. Register x is executed if they obey the stated relation.
- v Replace the top element on the stack by its square root. Any existing fractional part of the argument is taken into account, but otherwise the scale factor is ignored.
- ! Interpret the rest of the line as a shell command.
- c Clear the stack.
- i The top value on the stack is popped and used as the number base for further input.

- I Push the input base on the top of the stack.
- o The top value on the stack is popped and used as the number base for further output. In bases larger than 10, each 'digit' prints as a group of decimal digits.
- O Push the output base on the top of the stack.
- k Pop the top of the stack, and use that value as a non-negative scale factor: the appropriate number of places are printed on output, and maintained during multiplication, division, and exponentiation. The interaction of scale factor, input base, and output base will be reasonable if all are changed together.
- z Push the stack level onto the stack.
- Z Replace the number on the top of the stack with its length.
- ? A line of input is taken from the input source (usually the terminal) and executed.
- ; : Used by *bc* for array operations.

The scale factor set by k determines how many digits are kept to the right of the decimal point. If s is the current scale factor, sa is the scale of the first operand, sb is the scale of the second, and b is the (integer) second operand, results are truncated to the following scales.

- +,- max(*sa*,*sb*)
- * min(sa+sb, max(s,sa,sb))
- / s
- % so that dividend = divisor*quotient + remainder; remainder has sign of dividend
- $\wedge \qquad \min(sa \times |b|, \max(s, sa))$
- v max(*s*,*sa*)

EXAMPLES

Print the first ten values of *n*!

[la1+dsa*pla10>y]sy Osa1 lyx

Print π .

```
1sq180sr60st2si[3li*1+d1+*3*suli27*12-lq*5lr*+lt
5*/d48+Psy10lqlid2*1-***10lulqli5*2-*lr+lylt*-**
srsqlult*stli1+silmx]smlmx
```

SOURCE

/sys/src/cmd/dc.c

SEE ALSO

bc(1), *hoc*(1)

DIAGNOSTICS

x is unimplemented, where x is an octal number: an internal error.'Out of headers' for too many numbers being kept around.'Nesting depth' for too many levels of nested execution.

BUGS

When the input base exceeds 16, there is no notation for digits greater than F.

Past its time.

dd - convert and copy a file

SYNOPSIS

dd [option value] ...

DESCRIPTION

Dd copies the specified input file to the specified output with possible conversions. The standard input and output are used by default. The input and output block size may be specified to take advantage of raw physical I/O. The options are

- -if f Open file f for input.
- -of f Open file f for output.
- -ibs n Set input block size to n bytes (default 512).
- -obs *n* Set output block size (default 512).
- -bs *n* Set both input and output block size, superseding *ibs* and *obs*. If no conversion is specified, preserve the input block size instead of packing short blocks into the output buffer. This is particularly efficient since no in-core copy need be done.
- -cbs *n* Set conversion buffer size.
- -skip *n* Skip *n* input records before copying.
- -iseek n

Seek *n* records forward on input file before copying.

-files n

Catenate *n* input files (useful only for magnetic tape or similar input device).

-oseek n

Seek *n* records from beginning of output file before copying.

-count n

Copy only *n* input records.

-trunc n

By default, dd truncates the output file when it opens it; -trunc 0 opens it without truncation.

-quiet n

By default, dd prints the number of blocks read and written once it is finished. -quiet 1 silences this summary.

-conv ascii	Convert EBCDIC to ASCII.
ebcdic	Convert ASCII to EBCDIC.
ibm	Like ebcdic but with a slightly different character map.
block	Convert variable length ASCII records to fixed length.
unblock	Convert fixed length ASCII records to variable length.
lcase	Map alphabetics to lower case.
ucase	Map alphabetics to upper case.
swab	Swap every pair of bytes.
noerror	Do not stop processing on an error.
sync	Pad every input record to <i>ibs</i> bytes.

Where sizes are specified, a number of bytes is expected. A number may end with a sequence of m, k or b to specify multiplications by 1048576, 1024, or 512 respectively; a pair of numbers may be separated by x to indicate a product. Multiple conversions may be specified in the style: $-conv \ ebcdic, ucase$.

Cbs is used only if ascii, unblock, ebcdic, ibm, or block conversion is specified. In the first two cases, *n* characters are copied into the conversion buffer, any specified character mapping is done, trailing blanks are trimmed and new-line is added before sending the line to the output. In the latter three cases, characters are read into the conversion buffer and blanks are added to make up an output record of size *n*. If cbs is unspecified or zero, the ascii, ebcdic, and ibm options convert the character set without changing the block structure of the input file; the

unblock and block options become a simple file copy.

SOURCE

/sys/src/cmd/dd.c

SEE ALSO

cp(1)

DIAGNOSTICS

Dd reports the number of full + partial input and output blocks handled.

delkey - delete keys from factotum

SYNOPSIS

delkey

DESCRIPTION

Delkey prints commands for deleting each key stored in factotum(4).

When run on a CPU server, *delkey* uses the terminal's factotum, if present, instead of the server's factotum.

FILES

/mnt/term/mnt/factotum
 First choice for factotum to use

/mnt/factotum Second choice

SOURCE

/rc/bin/delkey

deroff - remove formatting requests

SYNOPSIS

deroff [option ...] file ...

DESCRIPTION

Deroff reads each file in sequence and removes all *nroff* and *troff*(1) requests and non-text arguments, backslash constructions, and constructs of preprocessors such as eqn(1), pic(1), and tbl(1). Remaining text is written on the standard output. *Deroff* follows files included by .so and .nx commands; if a file has already been included, a .so for that file is ignored and a .nx terminates execution. If no input file is given, *deroff* reads from standard input.

The options are

- -w Output a word list, one 'word' (string of letters, digits, and properly embedded ampersands and apostrophes, beginning with a letter) per line. Other characters are skipped. Otherwise, the output follows the original, with the deletions mentioned above.
- -_ Like -w, but consider underscores to be alphanumeric rather than punctuation.
- -i Ignore .so and .nx requests.

-ms

- -mm Remove titles, attachments, etc., as well as ordinary *troff* constructs, from *ms*(6) or *mm* documents.
- -ml Same as -mm, but remove lists as well.

SOURCE

```
/sys/src/cmd/deroff.c
/sys/src/cmd/tex/local/delatex.c
```

SEE ALSO

troff(1), spell(1)

BUGS

This filter is not a complete interpreter of *troff*. For example, macro definitions containing $\$ cause chaos in *deroff* when the popular \$\$ delimiters for *eqn* are in effect.

Text inside macros is emitted at place of definition, not place of call.

derp - directory-examining recursive compare

SYNOPSIS

derp [-qcutDL] [-p perms] myfile oldfile yourfile

DESCRIPTION

Derp recursively compares the two directories *myfile* and *yourfile* using a third common backup directory *oldfile* as reference. The changes found are printed to standard output, one per line, with the file status describing either sides actions followed by tabulator and the relative file path which might be empty in case when the changed files refers to the ones given at program arguments.

The possible status codes:

- an File added in myfile
- na File added in *yourfile*
- aa! Both sides added different files with the same name
- mn File was modified in *myfile*
- nm File was modified in *yourfile*
- mm! File was changed differently in *myfile* and *yourfile*
- dn File was deleted in *myfile*
- nd File was deleted in yourfile
- md! File was modified in myfile but deleted in yourfile
- dm! File was modified in *yourfile* but deleted in *myfile*

Errors are printed to standard error unless -q option is specified. The program is terminated when errors are encountered unless the -c option is given. This can be useful if files are not accessible due to file permission or media corruption.

The -u option will consider changes of file owner and group. When omitted, file ownership is ignored.

The -p option sets the octal mask *perms* of bits to check in the file permissions. The default ignores file permissions.

When modification times are comparable then the -t option can be used to quickly find changes. If specified, files are considered unchanged if the name, file size and the modification time matches. This is useful when comparing /n/dump archives on the same fileserver.

Files are considered the same if they are from the same mount and their qid (see stat(5)) matches. For directories, the access time is also compared. If the access time was disabled on the fileserver, then all directories need to be compared using the -D option.

Some filesystems like hgfs(4) do not always return exact file size in stat, so the length check can be disabled with the -L option.

SOURCE

/sys/src/cmd/derp.c

SEE ALSO

cmp(1), *diff*(1), *history*(1), *fs*(4), *hgfs*(4)

DIAGNOSTICS

The exit status is set to 'errors' when errors were encountered.

HISTORY

Derp first appeared in 9front (November, 2012).

diff - differential file comparator

SYNOPSIS

diff[-abcefmnruw]file1 ... file2

DESCRIPTION

Diff tells what lines must be changed in two files to bring them into agreement. If one file is a directory, then a file in that directory with basename the same as that of the other file is used. If both files are directories, similarly named files in the two directories are compared by the method of diff for text files and cmp(1) otherwise. If more than two file names are given, then each argument is compared to the last argument as above. The $-\mathbf{r}$ option causes diff to process similarly named subdirectories recursively. When processing more than one file, diff prefixes file differences with a single line listing the two differing files, in the form of a diff command line. The $-\mathbf{m}$ flag causes this behavior even when processing single files.

The normal output contains lines of these forms:

```
n1 a n3,n4
n1,n2 d n3
n1,n2 c n3,n4
```

These lines resemble *ed* commands to convert *file1* into *file2*. The numbers after the letters pertain to *file2*. In fact, by exchanging 'a' for 'd' and reading backward one may ascertain equally how to convert *file2* into *file1*. As in *ed*, identical pairs where n1 = n2 or n3 = n4 are abbreviated as a single number.

Following each of these lines come all the lines that are affected in the first file flagged by '<', then all the lines that are affected in the second file flagged by '>'.

The -b option causes trailing blanks (spaces and tabs) to be ignored and other strings of blanks to compare equal. The -w option causes all white-space to be removed from input lines before applying the difference algorithm.

The -n option prefixes each range with *file*: and inserts a space around the a, c, and d verbs. The -e option produces a script of *a*, *c* and *d* commands for the editor *ed*, which will recreate *file2* from *file1*. The -f option produces a similar script, not useful with *ed*, in the opposite order. It may, however, be useful as input to a stream-oriented post-processor.

The -c option includes three lines of context around each change, merging changes whose contexts overlap. In this mode, *diff* prints – and + instead of < and > because the former are easier to distinguish when mixed. The –a flag displays the entire file as context.

The -u option provides a unix-compatible unified diff. This format is similar to that provided by -c. However, the + and - prefixes are not separated from the rest of the line by spaces, and the file header is in the following format:

```
--- filename.old
+++ filename.new
@@ -line,len +line,len @@
```

Except in rare circumstances, *diff* finds a smallest sufficient set of file differences.

FILES

/tmp/diff[12]

SOURCE /sys/src/cmd/diff

SEE ALSO

cmp(1), comm(1), ed(1), idiff(1)

DIAGNOSTICS

Exit status is the empty string for no differences, some for some, and error for trouble.

BUGS

Editing scripts produced under the -e or -f option are naive about creating lines consisting of a single '.'.

When running *diff* on directories, the notion of what is a text file is open to debate.

dmid - MIDI to OPL3 converter using GENMIDI-type instrument banks

SYNOPSIS

dmid [-2s] [-i bank] [file]

DESCRIPTION

Dmid decodes MIDI instructions either from *file* or from standard input, and produces OPL3 instructions suitable for playback by *opl3*(1). To program instruments, an OPL2 instrument bank formatted as GENMIDI lumps from *doom* must be provided. Since it is assumed that the bank is contained in a *doom WAD* file, its default location is /mnt/wad/genmidi. This may be overridden with the -i command line option.

The -s flag enables streaming mode, in which the input file is a stream of MIDI events. The file needn't provide any timing information such as MIDI tics. This is suitable for MIDI instruments.

In GENMIDI lumps, two voices are defined per instrument. For compatibility, the -2 flag disables the second voice, reducing the number of OPL channels needed. It also disables OPL3 specific features and produces an IMF-format stream, which can be used in other game engines.

EXAMPLES

Play a MUS file from a *doom WAD* file:

% games/wadfs /sys/games/lib/doom/doom2.wad createfile SW18_7: file already exists % games/mus /mnt/wad/d_doom | games/dmid | games/opl3 >/dev/audio

Play a MIDI stream from a USB device (see *usb*(3)):

% games/wadfs /sys/games/lib/doom/doom2.wad >[2]/dev/null

% games/dmid -s /dev/usb/ep10.1/data | games/opl3 >/dev/audio

SOURCE

```
/sys/src/games/dmid.c
```

SEE ALSO

games(1), mus(1), opl3(1), audio(3), usb(3), wadfs(4)

HISTORY

Dmid first appeared in 9front (July, 2018).

doc2txt, doc2ps, wdoc2txt, xls2txt, olefs, mswordstrings, msexceltables - extract printable text from Microsoft documents

SYNOPSIS

doc2txt [file.doc]
doc2ps [file.doc]
wdoc2txt [file.doc]
xls2txt [file.xls]
aux/olefs [-m mtpt] file.doc
aux/mswordstrings mtpt/WordDocument
aux/msexceltables [-qaDnt] [-d delim] [-c column-range] [-w worksheet-range]
mtpt/Workbook

DESCRIPTION

Doc2txt is an rc(1) script that uses *olefs* and *mswordstrings* to extract the printable text from the body of a Microsoft Word document and write it on the standard output. *Doc2ps* is similar, but emits PostScript corresponding to the document. *Wdoc2txt* is similar to *doc2txt*, but uses *plumb*(1) to send the output to a new *acme*(1) window instead. *Xls2txt* performs a similar function for Microsoft Excel documents.

Microsoft Office documents are stored in OLE (Object Linking and Embedding) format, which is a scaled down version of Microsoft's FAT file system. *Olefs* presents the contents of an MS Office document as a file system on *mtpt*, which defaults to /mnt/doc. *Mswordstrings* or *msexceltables* may then be used to parse the files inside, extracting a text stream. *Msexceltables* may be given options to control the formatting of its output.

- -a Attempt conversion of non-tabular sheets in the workbook (charts).
- -d *delim* Sets the inter-field delimiter to the string *delim*, by default a single space.
- -D Enables debugging output.
- -c range Range is a comma-separated list of column numbers and ranges. Ranges are separated by dashes. Limit processing to just those columns named; by default all columns are output.
- -n Disables field padding to column width.
- -q Disable quoting of textural fields (see *quote*(2).)
- -t Truncate fields to the column width.
- -w range Range is a comma-separated list of worksheet numbers and ranges, this limits the sheets output using the same syntax as the -c option above. Suppressed chart pages are always included in the sheet count.

EXAMPLE

Extract pieces of an MS Excel spreadsheet.

aux/olefs report.xls msexceltables -q -w 1,7,9-14 -c 3-5 -n -d '@' /mnt/doc/Workbook > rpt.txt unmount /mnt/doc

SOURCE

/rc/bin	doc2txt, doc2ps, wdoc2txt, and xls2txt
/sys/src/cmd/aux	the others

SEE ALSO

strings(1)

"Microsoft Word 97 Binary File Format", at Microsoft's developer (MSDN) home page. "LAOLA Binary Structures", http://user.cs.tu-berlin.de/~schwartz/pmh "OpenOffice.Org's Excel Documentation", http://sc.openoffice.org/excelfileformat.pdf

doctype - intuit command line for formatting a document

SYNOPSIS

doctype [-n] [-T *dev*] [*file*] ...

DESCRIPTION

Doctype examines a *troff*(1) input file to deduce the appropriate text formatting command and prints it on standard output. *Doctype* recognizes input for *troff*(1), related preprocessors like eqn(1), and the ms(6) and mm macro packages.

Option –n invokes *nroff* instead of *troff*. The –T option is passed to *troff*.

EXAMPLES

eval '{doctype chapter.?} | lp
Typeset files named chapter.0, chapter.1, ...

SOURCE

/rc/bin/doctype

SEE ALSO

troff(1), eqn(1), tbl(1), pic(1), grap(1), ms(6), man(6)

BUGS

In true A.I. style, its best guesses are inspired rather than accurate.

dpic, todpic - Doom picture decoder and encoder

SYNOPSIS

dpic [-f] [-p palette] [pic]

todpic [-fw] [-b bgcol] [-p palette] [image]

DESCRIPTION

Dpic reads a doom picture formatted image (default standard input), converts it to a Plan 9 *image*(6) and writes it to standard out. *Todpic* does the opposite transformation.

A color palette is needed for the process; its location is set to /mnt/wad/playpal by default. This may be overridden with the -p command line option. Both programs also accept an -f flag to indicate processing a doom 64x64 flat picture.

When encoding a doom picture, x and y offsets are set to the input's top left corner coordinates. The -w flag sets the offsets so as to center the picture when drawn by the doom engine, which is useful for wall patches. The -b option sets the RGB24 color to signal transparent pixels, 0x00FFFF by default.

EXAMPLES

Create a patch WAD (see *wadfs*(4)) replacing a sky texture. First, create a 256x128 image, mirror it, and convert it for use with *tweak*(1).

Next, use tweak(1) to tile the 128x128 picture. Then, mount an *IWAD* containing the base color palette, convert to a doom picture, create a patch *WAD*, then launch doom using it.

```
% games/wadfs /sys/games/lib/doom/doom2.wad
createfile SW18_7: file already exists
% games/wadfs -m /mnt/new
% games/todpic tuttlesky > /mnt/new/rsky1
% cp /mnt/new/WAD tuttle.wad
% games/doom -file tuttle.wad
```

Create a crude catclock weapon sprite.

SOURCE

```
/sys/src/games/dpic.c
/sys/src/games/todpic.c
```

SEE ALSO

games(1), tweak(1), wadfs(4)

HISTORY

Dpic and todpic first appeared in 9front (July, 2018).

dtracy - dynamic tracing language

SYNOPSIS

dtracy[-d]prog

DESCRIPTION

Dtracy is a language for dynamic tracing of the kernel. Essentially, it allows the user to define small programs in kernel space that are triggered by certain events (known as probes) upon which they are executed.

Dtracy uses an awk(1) inspired syntax. A dtracy program is a series of statements of one of the following forms

probes { actions }
probes if predicate { actions }

Probes is a comma-separated list of probes, such as sys:pwrite:entry. Each probe name consists of any number of parts separated by :. If a part is omitted (e.g. qsys::entry), it matches all probes that match the remaining parts. If the probe name is enclosed in quotation marks, the wildcards * and ? are available, e.g. "sys:*stat:entry".

Predicate, if specified, is an expression that must evaluate to a non-zero value for the actions to be executed.

Actions is a semicolon-separated list of statements of one of the following forms:

expr
print a, b, ...
printf "fmt", a, b, ...
@name[index] = aggregation-expr

Expressions follow C syntax and semantics and all C operators (including casts) are supported. Available integer types are u8, u16, u32, u64, s8, s16, s32 and s64; they correspond to the C types u8int, etc. Additionally, a string type *string* is available.

Expressions can use the following variables

probe	name of the probe that was triggered
pid	PID of the process triggering the probe
arg0, arg1,	for a syscall probe, the syscall arguments (cast to s64)
time	timestamp when the probe was triggered
machno	CPU number on which the probe was triggered

Print prints all its arguments, separated by spaces and followed by a newline. *Printf* prints its arguments using a format string with *print*(2) syntax. However, there is no need to specify the argument size, e.g. %d works for all integer types.

Statements of the form @*name[index] = aggregation-expr* collect statistics using a data structure referred to as an aggregation. Each time the statement is evaluated adds another datapoint to the aggregation, which will be printed in tabular form when *dtracy* finishes. *Index* is effectively a label for the datapoint; statistics are evaluated over all datapoints of the same index.

Aggregation-expr specifies the type of statistic to be collected. Available options are

count() number of datapoints avg(expr) average sum(expr) sum min(expr) minimum max(expr) maximum std(expr) average and standard deviation

EXAMPLES

sys:: { print probe, pid, arg0, arg1 }

The world's worst syscall tracer.

sys:pread:entry if pid == 42 { printf "time %d, fd %d\n", time, arg0 }

Every time the process with PID 42 executes pread(2), write down the timestamp and the file descriptor used.

sys:open:entry { print (string)arg0 }

Print the names of files as they are being opened.

sys:pread:entry { @size[pid] = avg(arg2) }

Determine the average *pread* buffer size for each process.

SOURCE

/sys/src/cmd/dtracy

BUGS

Yes.

HISTORY

Dtracy appeared in 9front in November, 2018.

du – disk usage

SYNOPSIS

du [-aefhnqstu][-b size][-p SI-prefix][file ...]

DESCRIPTION

Du gives the number of Kbytes allocated to data blocks of named *files* and, recursively, of files in named directories. It assumes storage is quantized in units of 1024 bytes (Kbytes) by default. Other values can be set by the -b option; *size* is the number of bytes, optionally suffixed k to specify multiplication by 1024. If *file* is missing, the current directory is used. The count for a directory includes the counts of the contained files and directories.

The -a option prints the number of blocks for every file in a directory. Normally counts are printed only for contained directories.

The -f option suppresses the printing of warning messages.

The -n option prints the size in bytes and the name of each file; it sets -a.

The -t option prints, in the format of du -n, the modified time of each file rather than the size. If the options -tu are specified then the accessed time is printed.

The -q option prints, in the format of du - n, the QID path of each file rather than the size.

The -s option causes *du* to descend the hierarchy as always, but to print only a summary line for each *file*.

The -e option causes du to print values (sizes, times or QID paths) in 'scientific notation' via print(2)'s %g.

The -h option causes *du* to print values (sizes, times or QID paths) in scientific notation, scaled to less than 1024, and with a suitable SI prefix (e.g., G for binary gigabytes).

The -p option causes *du* to print values (sizes, times or QID paths) in units of *SI*-prefix. Case is ignored when looking up *SI*-prefix. An empty *SI*-prefix corresponds to a scale factor of 1 (e.g., print sizes in bytes).

EXAMPLES

Print the size of /tmp in fractional binary gigabytes:

```
% du -sepg /tmp
.6960154 /tmp
```

Print the size of /tmp in bytes and in scientific notation:

% du -sep '' /tmp 7.473408e+08 /tmp

SOURCE

/sys/src/cmd/du.c

echo - print arguments

SYNOPSIS

echo [–n] [*arg* ...]

DESCRIPTION

Echo writes its arguments separated by blanks and terminated by a newline on the standard output. Option -n suppresses the newline.

SOURCE

/sys/src/cmd/echo.c

DIAGNOSTICS

If *echo* draws an error while writing to standard output, the exit status is write error. Otherwise the exit status is empty.

ecp - fast copy, handling errors

SYNOPSIS

ecp [-bcprvZ][-B block-size][-e max-errors][-i issect][-o ossect][-s sector-size] sectors input output

DESCRIPTION

Ecp copies *sectors* disk sectors of the specified *input* file to the specified *output* file. *Ecp* copies multiple sectors (a 'block') at a time for speed. When *ecp* encounters an I/O error, it transfers the current block again, assuming the file is seekable, one sector at a time, prints the sector number(s) of the error(s), and continues copying.

Options are:

- -b reblock *input* on short reads; this was used mainly when reading a pipe on standard input on 4.2+BSD systems.
- -B sets the block size (16,384 bytes by default) to *block-size*.
- -c ask for confirmation on /dev/cons before starting the copy.
- e sets a maximum number of consecutive I/O errors to permit at the beginning of the copy before quitting to max-errors. Lots of consecutive errors may indicate a deeper problem, such as missing media. By default there is no limit.
- -i seeks to sector *issect* (assuming zero-origin) before beginning input.
- -o seeks to sector ossect (assuming zero-origin) before beginning output.
- -p print reassuring progress reports; helpful mainly when dealing with cranky hardware.
- -r copy sector groups in reverse order, assuming the files are seekable; this is most useful when *input* and *output* overlap.
- -s sets the sector size (512 bytes by default) to sector-size.
- -v verify the copy by rereading the *input* and *output* files after copying all sectors. This is intended to force the disk to deliver the actual data written on it rather than some cached copy. The locations of any differences are printed.
- -Z 'Swizzle' the input: stir the bits around in some fashion. Intended for diagnosing bad disks by copying a disk to itself a few times with swizzling on (to defeat caching in operating systems or disk controllers).

SEE ALSO

fcp in *cp*(1), *dd*(1), *dup*(3)

BUGS

-i, -o, -r, -v and error retries only work on devices capable of seeking.

The set of options reflects decades of experience dealing with troublesome hardware.

If the input file is a tape and the last record on the tape before a file mark is less than *blocksize* bytes long, then *ecp* will read through past the file mark and into the next file.

ed – text editor

SYNOPSIS

ed [–] [–o] [file]

DESCRIPTION

Ed is the standard text editor.

If a *file* argument is given, *ed* simulates an e command (see below) on that file: it is read into *ed's* buffer so that it can be edited. The options are

- Suppress the printing of character counts by e, r, and w commands and of the confirming
 ! by ! commands.
- -o (for output piping) Write all output to the standard error file except writing by w commands. If no *file* is given, make /fd/1 the remembered file; see the e command below.

Ed operates on a 'buffer', a copy of the file it is editing; changes made in the buffer have no effect on the file until a w (write) command is given. The copy of the text being edited resides in a temporary file called the *buffer*.

Commands to *ed* have a simple and regular structure: zero, one, or two *addresses* followed by a single character *command*, possibly followed by parameters to the command. These addresses specify one or more lines in the buffer. Missing addresses are supplied by default.

In general, only one command may appear on a line. Certain commands allow the addition of text to the buffer. While *ed* is accepting text, it is said to be in *input mode*. In this mode, no commands are recognized; all input is merely collected. Input mode is left by typing a period . alone at the beginning of a line.

Ed supports the *regular expression* notation described in *regexp*(6). Regular expressions are used in addresses to specify lines and in one command (see *s* below) to specify a portion of a line which is to be replaced. If it is desired to use one of the regular expression metacharacters as an ordinary character, that character may be preceded by '\'. This also applies to the character bounding the regular expression (often /) and to \ itself.

To understand addressing in *ed* it is necessary to know that at any time there is a *current line*. Generally, the current line is the last line affected by a command; however, the exact effect on the current line is discussed under the description of each command. Addresses are constructed as follows.

- 1. The character ., customarily called 'dot', addresses the current line.
- 2. The character \$ addresses the last line of the buffer.
- 3. A decimal number *n* addresses the *n*-th line of the buffer.
- 4. 'x addresses the line marked with the name x, which must be a lower-case letter. Lines are marked with the k command.
- 5. A regular expression enclosed in slashes (/) addresses the line found by searching forward from the current line and stopping at the first line containing a string that matches the regular expression. If necessary the search wraps around to the beginning of the buffer.
- 6. A regular expression enclosed in queries ? addresses the line found by searching backward from the current line and stopping at the first line containing a string that matches the regular expression. If necessary the search wraps around to the end of the buffer.
- 7. An address followed by a plus sign + or a minus sign followed by a decimal number specifies that address plus (resp. minus) the indicated number of lines. The plus sign may be omitted.
- 8. An address followed by + (or -) followed by a regular expression enclosed in slashes specifies the first matching line following (or preceding) that address. The search wraps around if necessary. The + may be omitted, so 0/x/ addresses the *first* line in the buffer with an x. Enclosing the regular expression in ? reverses the search direction.

- 9. If an address begins with + or the addition or subtraction is taken with respect to the current line; e.g. -5 is understood to mean .-5.
- 10. If an address ends with + or -, then 1 is added (resp. subtracted). As a consequence of this rule and rule 9, the address refers to the line before the current line. Moreover, trailing + and characters have cumulative effect, so -- refers to the current line less 2.
- 11. To maintain compatibility with earlier versions of the editor, the character \land in addresses is equivalent to -.

Commands may require zero, one, or two addresses. Commands which require no addresses regard the presence of an address as an error. Commands which accept one or two addresses assume default addresses when insufficient are given. If more addresses are given than a command requires, the last one or two (depending on what is accepted) are used.

Addresses are separated from each other typically by a comma ,. They may also be separated by a semicolon ;. In this case the current line is set to the previous address before the next address is interpreted. If no address precedes a comma or semicolon, line 1 is assumed; if no address follows, the last line of the buffer is assumed. The second address of any two-address sequence must correspond to a line following the line corresponding to the first address.

In the following list of *ed* commands, the default addresses are shown in parentheses. The parentheses are not part of the address, but are used to show that the given addresses are the default. 'Dot' means the current line.

(.)a

<text>

- . Read the given text and append it after the addressed line. Dot is left on the last line input, if there were any, otherwise at the addressed line. Address 0 is legal for this command; text is placed at the beginning of the buffer.
- (.,.)b[+-][*pagesize*][pln]

Browse. Print a 'page', normally 20 lines. The optional + (default) or - specifies whether the next or previous page is to be printed. The optional *pagesize* is the number of lines in a page. The optional p, n, or 1 causes printing in the specified format, initially p. Pagesize and format are remembered between b commands. Dot is left at the last line displayed.

(.,.)c

<text>

Change. Delete the addressed lines, then accept input text to replace these lines. Dot is left at the last line input; if there were none, it is left at the line preceding the deleted lines.

(.,.)d

Delete the addressed lines from the buffer. Dot is set to the line following the last line deleted, or to the last line of the buffer if the deleted lines had no successor.

e filename

Edit. Delete the entire contents of the buffer; then read the named file into the buffer. Dot is set to the last line of the buffer. The number of characters read is typed. The file name is remembered for possible use in later e, r, or w commands. If *filename* is missing, the remembered name is used.

E filename

Unconditional e; see 'q' below.

f filename

Print the currently remembered file name. If *filename* is given, the currently remembered file name is first changed to *filename*.

- (1, \$)g/regular expression/command list
- (1, \$)g/regular expression/
- (1, \$)g/regular expression

Global. First mark every line which matches the given *regular* expression. Then for every such line, execute the *command list* with dot initially set to that line. A single command or the first of multiple commands appears on the same line with the global command. All lines of a multi-line list except the last line must end with $\$. The '.' terminating input

mode for an a, i, c command may be omitted if it would be on the last line of the command list. The commands g and v are not permitted in the command list. Any character other than space or newline may be used instead of / to delimit the regular expression. The second and third forms mean g/regular expression/p.

(.)i <text>

Insert the given text before the addressed line. Dot is left at the last line input, or, if there were none, at the line before the addressed line. This command differs from the *a* command only in the placement of the text.

(.,.+1)j

Join the addressed lines into a single line; intermediate newlines are deleted. Dot is left at the resulting line.

(.) kx Mark the addressed line with name x, which must be a lower-case letter. The address form ' x then addresses this line.

(.,.)1

List. Print the addressed lines in an unambiguous way: a tab is printed as t, a backspace as b, backslashes as h, and non-printing characters as a backslash, an x, and four hexadecimal digits. Long lines are folded, with the second and subsequent sub-lines indented one tab stop. If the last character in the line is a blank, it is followed by n. An 1 may be appended, like p, to any non-1/0 command.

(.,.)m*a*

Move. Reposition the addressed lines after the line addressed by a. Dot is left at the last moved line.

(.,.)n

Number. Perform p, prefixing each line with its line number and a tab. An n may be appended, like p, to any non-I/O command.

(.,.)p

Print the addressed lines. Dot is left at the last line printed. A p appended to any non-I/O command causes the then current line to be printed after the command is executed.

(.,.)P

This command is a synonym for p.

- q Quit the editor. No automatic write of a file is done. A q or e command is considered to be in error if the buffer has been modified since the last w, q, or e command.
- Q Quit unconditionally.
- (\$)r filename

Read in the given file after the addressed line. If no *filename* is given, the remembered file name is used. The file name is remembered if there were no remembered file name already. If the read is successful, the number of characters read is printed. Dot is left at the last line read from the file.

- (.,.) sn/regular expression/replacement/
- (.,.)sn/regular expression/replacement/g
- (.,.) sn/regular expression/replacement

Substitute. Search each addressed line for an occurrence of the specified regular expression. On each line in which *n* matches are found (*n* defaults to 1 if missing), the *n*th matched string is replaced by the replacement specified. If the global replacement indicator g appears after the command, all subsequent matches on the line are also replaced. It is an error for the substitution to fail on all addressed lines. Any character other than space or newline may be used instead of / to delimit the regular expression and the replacement. Dot is left at the last line substituted. The third form means s n/regular expression/replacement/p. The second / may be omitted if the replacement is empty.

An ampersand & appearing in the replacement is replaced by the string matching the regular expression. The characters n, where *n* is a digit, are replaced by the text matched by the *n*-th regular subexpression enclosed between (and). When nested parenthesized

subexpressions are present, n is determined by counting occurrences of (starting from the left.

A literal &, /, \setminus or newline may be included in a replacement by prefixing it with \setminus .

(.,.)t*a*

Transfer. Copy the addressed lines after the line addressed by a. Dot is left at the last line of the copy.

(.,.)u

Undo. Restore the preceding contents of the first addressed line (sic), which must be the last line in which a substitution was made (double sic).

(1, \$)v/regular expression/command list

This command is the same as the global command g except that the command list is executed with dot initially set to every line *except* those matching the regular expression.

(1, \$) w filename

Write the addressed lines to the given file. If the file does not exist, it is created with mode 666 (readable and writable by everyone). If no *filename* is given, the remembered file name, if any, is used. The file name is remembered if there were no remembered file name already. Dot is unchanged. If the write is successful, the number of characters written is printed.

(1,\$)W filename

Perform w, but append to, instead of overwriting, any existing file contents.

- (\$) = Print the line number of the addressed line. Dot is unchanged.
- ! shell command

Send the remainder of the line after the ! to rc(1) to be interpreted as a command. Dot is unchanged.

(.+1) <newline>

An address without a command is taken as a p command. A terminal / may be omitted from the address. A blank line alone is equivalent to .+1p; it is useful for stepping through text.

If an interrupt signal (DEL) is sent, ed prints a ? and returns to its command level.

When reading a file, *ed* discards NUL characters and all characters after the last newline.

FILES

/tmp/e*

ed.hup work is saved here if terminal hangs up

SOURCE

/sys/src/cmd/ed.c

SEE ALSO

sam(1), sed(1), regexp(6)

DIAGNOSTICS

?name for inaccessible file; ?TMP for temporary file overflow; ? for errors in commands or other overflows.

NAME emacs - editor macros SYNOPSIS emacs [options] DESCRIPTION This page intentionally left blank. SOURCE MIT SEE ALSO sam(1), vi(1) BUGS Yes.

eqn - typeset mathematics

SYNOPSIS

eqn [option ...] [file ...]

DESCRIPTION

Eqn is a *troff*(1) preprocessor for typesetting mathematics on a typesetter. Usage is almost always

eqn file ... | troff

If no files are specified, *eqn* reads from the standard input. *Eqn* prepares output for the typesetter named in the -T*dest* option (default -Tutf; see *troff*(1)). When run with other preprocessor filters, *eqn* usually comes last.

A line beginning with .EQ marks the start of an equation; the end of an equation is marked by a line beginning with .EN. Neither of these lines is altered, so they may be defined in macro packages to get centering, numbering, etc. It is also possible to set two characters as 'delimiters'; text between delimiters is also *eqn* input. Delimiters may be set to characters *x* and *y* with the option -dxy or (more commonly) with delim *xy* between .EQ and .EN. Left and right delimiters may be identical. (They are customarily taken to be \$\$). Delimiters are turned off by delim off. All text that is neither between delimiters nor between .EQ and .EN is passed through untouched.

Tokens within *eqn* are separated by spaces, tabs, newlines, braces, double quotes, tildes or circumflexes. Braces {} are used for grouping; generally speaking, anywhere a single character like x could appear, a complicated construction enclosed in braces may be used instead. Tilde ~ represents a full space in the output, circumflex \land half as much.

Subscripts and superscripts are produced with the keywords sub and sup. Thus x sub i makes x_i , a sub i sup 2 produces a_i^2 , and e sup {x sup 2 + y sup 2} gives $e^{x^2+y^2}$.

Over makes fractions: a over b yields $\frac{a}{b}$.

Sqrt produces square roots: 1 over sqrt {ax sup 2 +bx+c} results in $\frac{1}{\sqrt{ax^2+bx+c}}$.

The keywords from and to introduce lower and upper limits on arbitrary things: $\lim_{n\to\infty} \sum_{0}^{n} x_{i}$ is made with lim from $\{n \rightarrow inf\}$ sum from 0 to n x sub i.

Left and right brackets, braces, etc., of the right height are made with left and right: left [x sup 2 + y sup 2 over alpha right] ~=~1 produces $\left[x^2 + \frac{y^2}{\alpha}\right] = 1$. The

right clause is optional. Legal characters after left and right are braces, brackets, bars, c and f for ceiling and floor, and "" for nothing at all (useful for a right-side-only bracket).

Vertical piles of things are made with pile, lpile, cpile, and rpile: pile {a above b above c} produces b. There can be an arbitrary number of elements in a pile. lpile left-

justifies, pile and cpile center, with different vertical spacing, and rpile right justifies.

Matrices are made with matrix: matrix { lcol { x sub i above y sub 2 } ccol x_i l

{ 1 above 2 } produces $\frac{x_i}{v_2}$ 2. In addition, there is rcol for a right-justified column.

Diacritical marks are made with prime, dot, dotdot, hat, tilde, bar, under, vec, dyad, and under: x sub 0 sup prime = f(t) bar + g(t) under is $x'_0 = \overline{f(t)} + \underline{g(t)}$, and x vec = y dyad is $\overline{x} = \overline{y}$.

Sizes and fonts can be changed with prefix operators size n, size $\pm n$, fat, roman, italic, bold, or font n. Size and fonts can be changed globally in a document by gsize n and gfont n, or by the command-line arguments -sn and -fn.

Normally subscripts and superscripts are reduced by 3 point sizes from the previous size; this may be changed by the command-line argument -pn.

Successive display arguments can be lined up. Place mark before the desired lineup point in the first equation; place lineup at the place that is to line up vertically in subsequent equations.

Shorthands may be defined or existing keywords redefined with define: define thing % replacement % defines a new token called *thing* which will be replaced by *replacement* whenever it appears thereafter. The % may be any character that does not occur in replacement.

Keywords like sum (Σ) , int (\int) , inf (∞) , and shorthands like $>= (\geq), -> (\rightarrow)$, and $!= (\neq)$ are recognized. Greek letters are spelled out in the desired case, as in alpha or GAMMA. Mathematical words like sin, cos, log are made Roman automatically. *Troff*(1) four-character escapes like $\langle (lh (v)) \rangle$ can be used anywhere. Strings enclosed in double quotes " " are passed through untouched; this permits keywords to be entered as text, and can be used to communicate with *troff* when all else fails.

FILES

/sys/lib/troff/font/devutf font descriptions for PostScript

SOURCE

/sys/src/cmd/eqn

SEE ALSO

troff(1), *tbl*(1)

J. F. Ossanna and B. W. Kernighan, ''Troff User's Manual''. B. W. Kernighan and L. L. Cherry, ''Typesetting Mathematics—User's Guide'', *Unix Research System* Programmer's Manual, Tenth Edition, Volume 2.

BUGS

To embolden digits, parens, etc., it is necessary to quote them, as in bold "12.3".

at, drain, expect, pass - dialer scripting tools

SYNOPSIS

```
dial/at[-q][-t seconds] atcommand
dial/expect[-iq][-t seconds] goodstring[ badstring...]
dial/drain
dial/pass[-q]
```

DESCRIPTION

These commands are used to write telephone dialing scripts, mostly for PPP sessions. They all expect standard input and output to be connected to a communications device, e.g, a serial line to a modem. They communicate with the user using /dev/cons.

At sends atcommand to the modem prefixed with the string at. It then reads from the modem expecting an AT response. At will return success if it gets and OK of CONNECT response. Otherwise it will return the response as an error status. The options are:

- -t set the timeout to *seconds*. The default is 300.
- -q don't write to /dev/cons what is read from standard in. The default is to copy everything through.

Expect reads standard input looking for one of the strings given as arguments. Reading the first string causes a successul exit status. Reading any of the others causes an exit status equal to the string. The command also terminates on a timeout. The options are:

- -t set the timeout to *seconds*. The default is 300.
- -i ignore case when doing the matches.
- -q don't write to /dev/cons what is read from standard in. The default is to copy everything through.

Pass copies input from /dev/cons to standard output. It terminates on a newline. The only flag is -q and means the same as it does for *expect*.

Drain discards any input waiting on standard input. It is used to sync up the stream at the start of dialing or after an error.

EXAMPLE

The following rc script dials out through a Hayes compatible modem on /dev/eial and lets the user type in a user name and password before starting ppp.

```
#!/bin/rc
dev=/dev/eia1
telno=18005551212
fn initfn {
     dial/drain
     echo +++
     dial/at zh0
}
fn dialfn {
     dial/drain
     dial/at dt^$telno
}
{
     # set up uart
     if( test -e $dev^ctl ){
          echo -n b^{\$}baud
          echo -n m1  # cts/rts flow control
          echo -n q64000 # big buffer
          echo -n n1  # nonblocking writes
          echo -n r1
                         # rts on
```

```
echo -n d1  # dtr on
echo -n c1  # handup when we lose dcd
     } > $dev^ctl
     # get the modem's attention
     while( ! initfn )
           sleep 1
     # dial
     while( ! dialfn )
           sleep 30
     if( ! dial/expect -it 60 'username:' ){
           echo can''t connect >[1=2]
           exit connect
     }
     dial/pass
     if( ! dial/expect -it 60 'password:' ){
           echo can''t connect >[1=2]
           exit connect
     }
     dial/pass
     if( ! dial/expect -t 60 'ppp or telnet:' ){
     echo can''t connect >[1=2]
           exit connect
     }
     echo ppp
     dial/expect -t 5 something
     echo connected >[1=2]
     # start ppp
     ip/ppp $primary -f
} < $dev > $dev
/rc/bin/ipconf/* example dialer scripts for ppp
/sys/src/cmd/dial/*.c
```

SEE ALSO

SOURCE

FILES

ppp(8), *telco*(4)

faces, seemail, vwhois - mailbox interface

SYNOPSIS

```
faces[-ihc][-m maildir]
seemail
vwhois person ...
```

DESCRIPTION

The *faces* command monitors incoming mail and displays in its window a representation of the user's mail box using a small image for each message. The image is typically a portrait of the sender. Which image to display is determined by two directories /usr/\$user/lib/face and /lib/face. Entries in /usr/\$user/lib/face take priority over those in /lib/face. See *face*(6), for how these directories are organised.

If the user is running plumber(4), *faces* reacts to plumb messages to the seemail port, typically from upas/fs, and is thus notified of message additions and deletions.

Right-clicking on a message icon causes that message to be 'plumbed' to showmail. A typical plumb action will be to display the message, such as by the rule

plumb start window mail -s \$0

The *acme*(1) mail reader listens to the showmail port automatically.

If the user is not running *plumber*, *faces* reads the log file and right-clicking has no effect.

If arrows are visible, clicking on them will scroll the display. Middle-clicking on the arrows scrolls to the end.

Starting faces with the -i flag causes faces to read the messages in /mail/fs/mbox - or the mailboxes specified with the -m flag - upon startup.

The -m option directs *faces* to watch for messages arriving in *maildir* instead of /mail/fs/mbox. Multiple -m flags may be used to watch multiple mailboxes.

Starting *faces* with the -c flag allows the user to remove faces with a click with button 1.

The -h flag causes a different, venerable behavior in which the window displays the history of messages received rather than the current state of the mail box. In particular, faces are not removed from the screen when messages are deleted. Also, in this mode clicking button 1 in the display will clear the window.

Seemail is an rc(1) script that invokes faces -h.

Vwhois tells faces to display the icons of the named persons, without sending a message.

FILES

/mail/fs/mbox mail directory.

SOURCE

/sys/src/cmd/faces
/rc/bin/seemail
/rc/bin/vwhois

SEE ALSO

mail(1), marshal(1), nedmail(1), plumber(4), face(6), plumb(6)

factor, primes - factor a number, generate large primes

SYNOPSIS

factor[number]

primes start [finish]

DESCRIPTION

Factor prints *number* and its prime factors, each repeated the proper number of times. The number must be positive and less than 2^{54} (about 1.8×10^{16}).

If no *number* is given, *factor* reads a stream of numbers from the standard input and factors them. It exits on any input not a positive integer. Maximum running time is proportional to \sqrt{n} .

Primes prints the prime numbers ranging from *start* to *finish*, where *start* and *finish* are positive numbers less than 2⁵⁶. If *finish* is missing, *primes* prints without end; if *start* is missing, it reads the starting number from the standard input.

SOURCE

/sys/src/cmd/factor.c
/sys/src/cmd/primes.c

fedex, ups, usps - track shipments

SYNOPSIS

fedex tracking-number ups tracking-number usps tracking-number

DESCRIPTION

Fedex writes available shipment details for the given Federal Express 12-digit *tracking-number* on the standard output. *Ups* is similar, but takes a United Parcel Service 18-digit *tracking-number*. *Usps* takes a US Post Office *tracking-number*.

SOURCE

/rc/bin

BUGS

Redesigns of the source website can break these programs.

file – determine file type

SYNOPSIS

file[-m][*file*...]

DESCRIPTION

File performs a series of tests on its argument *files* in an attempt to classify their contents by language or purpose. If no arguments are given, the classification is performed on standard input.

If the -m flag is given, *file* outputs an appropriate MIME Content-Type specification describing the type and subtype of each file.

The file types it looks for include directory, device file, zero-filled file, empty file, Plan 9 executable, PAC audio file, cpio archive, tex dvi file, archive symbol table, archive, rc script, sh script, PostScript, troff output file for various devices, mail box, GIF, FAX, object code, C and Alef source, assembler source, compressed files, encrypted file, English text, compressed image, image, subfont, and font.

If a file has no apparent format, *file* looks at the character set it uses to classify it according to ASCII, extended ASCII, Latin ASCII, or UTF holding one or more of the following blocks of the Unicode Standard: Extended Latin, Greek, Cyrillic, Armenian, Hebrew, Arabic, Devanagari, Bengali, Gurmukhi, Gujarati, Oriya, Tamil, Telugu, Kannada, Malayalam, Thai, Lao, Tibetan, Georgian, Japanese, Chinese, or Korean.

If all else fails, *file* decides its input is binary.

SOURCE

/sys/src/cmd/file.c

BUGS

It can make mistakes.

filter, list, deliver, token, vf - filtering mail

SYNOPSIS

upas/filter[-bh] rcvr mailbox[regexp file]...

upas/list [-d] add | check patternfile addressfile ...

upas/deliver recipient fromfile mbox

upas/token key [tokenfile]

upas/vf[-r][-s savefile]

DESCRIPTION

A user may filter all incoming mail by creating a world readable/executable file /mail/box/username/pipeto. If the file is a shell script, it can use the commands described here to implement a filter.

Filter provides simple mail filtering. The first two arguments are the recipient's address and mailbox, that is, the same arguments provided to pipeto. The remaining arguments are all pairs of a regular expression and a file name. With no flags, the sender's address is matched against each regular expression starting with the first. If the expression matches, then the message is delivered to the file whose name follows the expression. The file must be world writable and should be append only. A message that matches none of the expressions is delivered into the user's standard mail box.

By default, *filter* matches each regular expression against the message's sender. The -h flag causes *filter* to match against the entire header, and the -b flag causes *filter* to match against the entire message (header and body).

For example, to delete any messages of precedence bulk, place in your pipeto file:

/bin/upas/filter -h \$1 \$2 'Precedence: bulk' /dev/null

Three other commands exist which, combined by an rc(1) script, allow you to build your own filter.

List takes two verbs; check and add. Check directs *list* to check each address contained in the *addressfiles* against a list of patterns in *patternfile*. Patterns come in four forms:

~*regular–expression* If any address matches the regular expression, *list* returns successfully.

=string. If any address exactly matches *string*, *list* returns successfully.

!~regular-expression If any address matches the regular expression and no other address matches a non '!' rule, *list* returns error status "!match".

!=string If any address exactly matches string and no other address matches a non '!' rule, *list* returns error status "!match".

If no addresses match a pattern, *list* returns "no match".

The pattern file may also contain lines of the form

#include filename

to allow pattern files to include other pattern files. All pattern matches are case insensitive. *List* searches the pattern file (and its includes) in order. The first matching pattern determines the action.

List add directs *list* to add a pattern to *patternfile* for each address in the *addressfiles* that doesn't already match a pattern.

Token, with only one argument, prints to standard output a unique token created from the current date and *key*. With two arguments, it checks *token* against tokens created over the last 10 days with *key*. If a match is found, it returns successfully.

Deliver delivers into mail box *mbox* the message read from standard input. It obeys standard mail file locking and logging conventions.

/sys/src/cmd/upas/filterkit/pipeto.sample is a sample pipeto using the filter
kit.

A sample pipefrom, /sys/src/cmd/upas/filterkit/pipefrom.sample, is provided which adds all addresses of your outgoing mail to your pattern file. You should copy it into a directory that normally gets bound by your profile onto /bin.

Vf (virus filter) takes a mail message as standard input and searches for executable MIME attachments, either rewriting them to be non-executable or rejecting the message. The behavior depends on the attachment's file name extension and MIME content type. /sys/lib/mimetype contains the list of known extensions and MIME content types. The fifth field of each line specifies the safety of a particular file type: y (yes), m (maybe; treated same as yes), n (no), p (previous), or r (reject). Vf allows attachments with safety y or m to pass through unaltered. Attachments with safety n both are wrapped in extra MIME headers and have . suspect appended to their file names, to avoid automatic execution by mail readers. Attachments with safety r (currently, .bat, .com, .exe, and .scr, all Microsoft executable extensions) are taken as cause for the entire message to be rejected. A safety of p (used for the x-gunzip mime type) causes the previous extension to be tested, so that x.tar.gz is treated the same as x.tar.

If /mail/lib/validateattachment exists and is executable, vf runs it on all attachments with safety n (attachments it would normally sanitize). If validateattachment's exit status contains the string discard, vf rejects the entire message. If the status contains the string accept, vf does not sanitize the attachment. Otherwise, vf sanitizes the attachment as before. The standard validateattachment uses file(1) to determine the file type. It accepts text and image files and discards messages containing executables or zip (see gzip(1)) archives of executables.

The -r option causes vf not to sanitize MIME attachments, but instead to reject messages it determines to be viruses. The -s option causes vf to log all attachments of safety r in the mail box savefile.

FILES

/mail/box/*/pipeto /sys/lib/mimetype /mail/lib/validateattachment attachment checker

mail filter MIME content types

SOURCE

/sys/src/cmd/upas/send /sys/src/cmd/upas/filterkit /sys/src/cmd/upas/vf

SEE ALSO

aliasmail(8), faces(1), mail(1), marshal(1), mlmgr(1), nedmail(1), qer(8), rewrite(6), send(8), smtp(8), upasfs(4)

fmt, htmlfmt - simple text formatters

SYNOPSIS

fmt [option ...] [file ...]

htmlfmt[-a][-c charset][-u url][file ...]

DESCRIPTION

Fmt copies the given *files* (standard input by default) to its standard output, filling and indenting lines. The options are

-1 n Output line length is *n*, including indent (default 70).

-w n A synonym for -1.

- -i n Indent *n* spaces (default 0).
- -j Do not join short lines: only fold long lines.

Empty lines and initial white space in input lines are preserved. Empty lines are inserted between input files.

Fmt is idempotent: it leaves already formatted text unchanged.

Htmlfmt performs a similar service, but accepts as input text formatted with HTML tags. It accepts *fmt*'s -1 and -w flags and also:

- -a Normally *htmlfmt* suppresses the contents of form fields and anchors (URLs and image files); this flag causes it to print them, in square brackets.
- −c charset

change the default character set from iso-8859-1 to *charset*. This is the character set assumed if there isn't one specified by the html itself in a <meta> directive.

-u url Use url as the base URL for the document when displaying anchors; sets -a.

SOURCE

/sys/src/cmd/fmt.c

/sys/src/cmd/htmlfmt

BUGS

Htmlfmt makes no attempt to render the two-dimensional geometry of tables; it just treats the table entries as plain, to-be-formatted text.

forp – formula prover

SYNOPSIS

forp[-m][file]

DESCRIPTION

Forp is a tool for proving formulae involving finite-precision arithmetic. Given a formula it will attempt to find a counterexample; if it can't find one the formula has been proven correct.

Forp is invoked on an input file with the syntax as defined below. If no input file is provided, standard input is used instead. The -m flag instructs *forp* to produce a table of all counterexamples rather than report just one. Note that counterexamples may report bits as ?, meaning that either value will lead to a counterexample.

The input file consists of statements terminated by semicolons and comments using C syntax (using // or /* */ syntax). Valid statements are

Variable definitions, roughly: type var ; Expressions (including assignments): expr ; Assertions: obviously expr ; Assumptions: assume expr ;

Assertions are formulae to be proved. If multiple assertions are given, they are effectively "and"ed together. Each input file must have at least one assertion to be valid. Assumptions are formulae that are assumed, i.e. counterexamples that would violate assumptions are never considered. Exercise care with them, as contradictory assumptions will lead to any formula being true (the logician's principle of explosion).

Variables can be defined with C notation, but the only types supported are bit and 1D arrays of bit (corresponding to machine integers of the specified size). Signed integers are indicated with the keyword signed. Like int in C, the bit keyword can be omitted in the presence of signed. For example,

```
bit a, b[4], c[8];
signed bit d[3];
signed e[16];
```

is a set of valid declarations.

Unlike a programming language, it is perfectly legitimate to use a variable before it is assigned value; this means the variable is an "input" variable. *Forp* tries to find assignments for all input variables that render the assertions invalid.

Expressions can be formed just as in C, however when used in an expression, all variables are automatically promoted to an infinite size signed type. The valid operators are listed below, in decreasing precedence. Note that logical operations treat all non-zero values as 1, whereas bitwise operators operate on all bits independently.

- [] Array indexing. The syntax is *var*[*a*:*b*], with *a* denoting the MSB and *b* denoting the LSB. Omiting : *b* addresses a single bit. The result is always treated as unsigned.
- $!, \sim, +, -$ (Unary operators) Logical and bitwise "not", unary plus (no-op), arithmetic negation. Because of promotion, \sim and - operate beyond the width of variables.
- *, /, % Multiplication, division, modulo. Division and modulo add an assumption that the divisor is non-zero.
- +, Addition, subtraction.
- <<, >> Left shift, arithmetic right shift. Because of promotion, this is effectively a logical right shift on unsigned variables.

<, <=, >, >= Less than, less than or equal to, greater than, greather than or equal to.

- ==, != Equal to, not equal to.
- & Bitwise "and".

٨	Bitwise "xor".
	Bitwise "or".
&&	Logical "and"
	Logical "or".
<=>, =>	Logical equivalence and logical implication (eq

<=>, => Logical equivalence and logical implication (equivalent to (a != 0) == (b != 0) and !a || b, respectively).

= Assignment.

One subtle point concerning assignments is that they forcibly override any previous values, i.e. expressions use the value of the latest assignments preceding them. Note that the values reported as the counterexample are always the values given by the last assignment.

EXAMPLES

We know that, mathematically, $a + b \ge a$ if $b \ge 0$ (which is always true for an unsigned number). We can ask *forp* to prove this using

bit a[32], b[32];
obviously a + b >= a;

Forp will report "Proved", since it cannot find a counterexample for which this is not true. In C, on the other hand, we know that this is not necessarily true. The reason is that, depending on the types involved, results are truncated. We can emulate this by writing

```
bit a[32], b[32], c[32];
c = a + b;
obviously c >= a;
```

Given this, *forp* will now report it as incorrect by providing a counterexample, for example

Can we use c < a to check for overflow? We can ask *forp* to confirm this using

```
bit a[32], b[32], c[32];
c = a + b;
obviously c < a <=> c != a+b;
```

Here the statement to be proved is "*c* is less than *a* if and only if *c* does not equal the mathematical sum a + b (i.e. overflow has occured)".

SOURCE

/sys/src/cmd/forp

SEE ALSO

spin(1)

BUGS

Any proof is only as good as the assumptions made, in particular care has to be taken with respect to truncation of intermediate results.

Array indices must be constants.

Left shifting can produce a huge number of intermediate bits. *Forp* will try to identify the minimum needed number but it may be a good idea to help it by assigning the result of a left shift to a variable.

HISTORY

Forp first appeared in 9front in March, 2018.

fortune, theo, troll - sample lines from a file

SYNOPSIS

fortune [file]
theo
troll

DESCRIPTION

Fortune prints a one-line aphorism chosen at random. If a *file* is specified, the saying is taken from that file; otherwise it is selected from /sys/games/lib/fortunes.

Troll is more specific than *fortune;* it specializes in inflammatory rhetoric.

Theo is more specific than troll; it presents insults from OpenBSD founder Theo de Raadt.

FILES

/sys/games/lib/fortunes
/sys/games/lib/fortunes.index fast lookup table, maintained automatically
/lib/theo
/lib/troll

SOURCE

/sys/src/cmd/fortune.c
/rc/bin/theo
/rc/bin/troll

HISTORY

Theo and troll first appeared in 9front (July, 2011).

AUTHORS

Some initial trolls were provided by ChrisPBS.

fplot - plot elementary function

SYNOPSIS

fplot [-c [-s size]] [-r range] functions ...

DESCRIPTION

Fplot plots elementary *functions* separated by spaces. The default output is the screen, but if the -c option is specified, the plot is written to the standard output as an r8g8b8 *image*(6). The latter image size is either 640x480 or the one specified by the -s option's argument (in the WIDTHx-HEIGHT format). The -r option accepts as argument the x and y ranges, in the format xmin:xmax ymin:ymax. By default *fplot* draws coordinate axes and tick marks; the -a option inhibits this.

Each function to be plotted may be a combination of the independent variable x, the elementary operations (+, -, *, / and %), and the functions described in sin(2) and exp(2). The exception being that x^n raises x to the nth power, log is the base 10 logarithm, and ln is the natural logarithm.

EXAMPLES

Plot the absolute value and x^3 functions to a 400x400 image(6) on standard output and view with *page*(1).

fplot -c -s 400x400 'abs(x)' 'x^3' | page

SOURCE

/sys/src/cmd/fplot.c

SEE ALSO

exp(2), sin(2), image(6), plot(1).

DIAGNOSTICS

Fplot either exits with syntax error or an empty status.

BUGS

There is no unary plus or minus.

Axes are not drawn in -c output.

HISTORY

Fplot first appeared in 9front (July, 2011).

freq - print histogram of character frequencies

SYNOPSIS

freq[-cdorx][*file*...]

DESCRIPTION

Freq reads the given files (default standard input) and prints histograms of the character frequencies. By default, *freq* counts each byte as a character; under the -r option it instead counts UTF sequences, that is, runes.

Each non-zero entry of the table is printed preceded by the byte value, in decimal, octal, hex, and Unicode character (if printable). If any options are given, the -d, -x, -o, -c flags specify a subset of value formats: decimal, hex, octal, and character, respectively.

SOURCE

/sys/src/cmd/freq.c

SEE ALSO

utf(6), *wc*(1)

fstype – determine file system type

SYNOPSIS

fstype file

DESCRIPTION

The *file* being a partition or file system image, *fstype* determines the type of a disk file system and prints it. If the type cannot be determined, then the error status is set.

Known file systems are:

9660	ISO9660 CD-ROM (see <i>dossrv</i> (4))
dos	FAT12/FAT16/FAT32 DOS (see <i>dossrv</i> (4))
paqfs	compressed <i>paqfs</i> (4)
kfs	old Plan 9 disk file system
fs	32-bit and
fs64	64-bit dump file system (see <i>fs</i> (4))
cwfs	32-bit,
cwfs64	64-bit and
cwfs64x	long file name cache worm file system (see <i>cwfs</i> (4))

hjfs hj file system (see *hjfs*(4))

SOURCE

/rc/bin/fstype

galaxy, mkgalaxy - galactic n-body simulator

SYNOPSIS

games/galaxy[options][-i][file]
games/mkgalaxy[options][-i][-f file] size

DESCRIPTION

Galaxy is an n-body simulator that uses a Barnes-Hut quad-tree to calculate gravitational interactions. Typical usage is to read a galaxy file (see *galaxy*(6)) from standard input using the -i command-line option or from a *file* using the -f option. If no file is read then the simulator starts with an empty universe.

Mouse commands

Holding mouse button 1 while dragging repositions the visible region of the galaxy. Holding mouse button 2 while dragging up or down zooms the visible region of the galaxy in or out, respectively. Mouse button 3 opens a menu with the following options:

new body

Creates a new galactic body. Holding button 1 positions the body. Holding a button 1-2 chord changes the mass/size of the body. Holding a button 1-3 chord changes the initial velocity of the body. Releasing button 1 restarts the simulator with the new body in motion. When new bodies are created, the simulator maintains the Galilean (inertial) reference frame where the center of mass of the galaxy is at rest.

speed

Prompts for a floating point value to change the speed of the simulation. E.g. a value of 2 will double the speed of the simulation and a value of 0.5 will halve the speed. Accuracy is sacrificed for greater speed.

gravity

Prompts for a floating point value to change the gravitational constant. E.g. a value of 2 will double the force exerted by gravity and a value of 0.5 will halve it.

- save Prompts for a file name to save the current galaxy as a *galaxy*(6) file.
- load Prompts for a file name to load the galaxy from the *galaxy*(6) file.
- exit Exits the simulator.

Keyboard commands

The following keys are recognized as commands:

- a Show accelerations as vectors.
- v Show velocities as vectors.
- s Show statistics such as the number of bodies being simulated, the maximum depth of the quad-tree, and the average number of calculations made per body.
- q Exit the simulator.

space

Pause and unpause the simulator.

del Exit the simulator.

Command-line options

Certain aspects of the galaxy simulator are controlled by the following options:

-G gravity

Sets the gravitational constant to *gravity*. The default value is 1.

−£ file

Reads the galaxy file *file* (see *galaxy*(6)).

-i Reads a galaxy file from standard input.

-p procs

Specifies the number of extra processes to use in order to calculate the gravitational force on each body in parallel. The default value is \$NPROC-1.

-t throttle

Causes the process that calculates forces to relinquish the processor for *throttle* milliseconds after each calculation.

$-\varepsilon$ softening

Sets the *softening* factor to prevent gravitational singularities during collisions or near-collisions. The default value is 500.

Mkgalaxy

Mkgalaxy is a utility to create galaxies for simulation. Galaxies can be assembled incrementally by reading an existing galaxy file from standard input with the -i command-line option or from a *file* with the -f option. Mkgalaxy then writes to standard output a *galaxy*(6) file with a galaxy of the given *size* together with the previously read galaxy. Galaxies generated by mkgalaxy have characteristics determined by the following options:

-d distance

Distance determines the spacing between bodies. The default value is 100.

−s size

Bodies have the given *size*. The default value is 25.

-v velocity

Bodies have the given *velocity* in a random direction. The default value is 0.

-av angular velocity

Bodies have the given *angular velocity* relative to the center of mass of the new galaxy being generated. The default value is 0.

-gv x, y

The entire galaxy being generated is given the directional velocity determined by the vector (x,y). The default value is (0, 0).

-o x,y

The entire galaxy being generated is offset by the vector (x,y). The default value is (0, 0).

-sq The galaxy being generated is a square. Without this option, the galaxy will be circular.

The arguments to the -d, -s, -v, and -av arguments have the form s or $s\pm r$ where s and r are double-precision floating point numbers. S is the base value and r if given determines a range in which the value will vary randomly from the base.

EXAMPLES

Two rotating circles destroy each other:

```
games/mkgalaxy -av 100 -d 60±50 -v 10 2000 |
games/mkgalaxy -i -av -70 -d 80±50 -v 10 -o 6000,2000 -gv -80,40 3000 |
games/galaxy -i
```

Cool patterns made by a square galaxy:

games/mkgalaxy -sq -av 20 5000 | games/galaxy -i

SOURCE

/sys/src/games/galaxy

SEE ALSO

J. Barnes & P. Hut (December 1986). "A hierarchical O(N log N) force-calculation algorithm". *Nature*. 324 (4): 446-449.

galaxy(6)

HISTORY

Galaxy and mkgalaxy first appeared in 9front (Feb, 2017).

4s, 5s, blabs, catclock, doom, festoon, geigerstats, glendy, juggle, life, mandel, mahjongg, memo, midi, mole, packet, sokoban, sudoku - time wasters

SYNOPSIS

```
games/4s
games/5s
games/blabs[-i][-k k-floor][-n track-length][-w track-width][-x gravity-x][-y
gravity-y]
games/catclock
games/doom
games/festoon[-pet][sentences[percent-invented-nouns]]
games/geigerstats[-d dev][-v vol]
games/glendy
games/juggle [-d delay][-h hands][ start] pattern
games/life[-3][-o][-d delay][-r rules][-b] startfile
games/mandel
games/mahjongg[-c][-f][-b background][-t tileset][-l layout]
games/memo[-h]
games/midi[-c][midifile]
games/mole
games/packet [-n nnode] [-o speed-offset] [-d decay] [-b speed-bonus] [-r regen-
rate ] [ -t thick-factor ] [ -T display-threshold ]
games/sokoban[level]
games/sudoku
```

DESCRIPTION

There are a few games in /bin/games:

- 4s, 5s Try to fill complete rows using 4-square or 5-square tiles. Move tiles left or right by moving the mouse. Rotate tiles with buttons 1 and 3. Drop tiles for more points with button 2 or the space bar. Keys a and j move left, s and k rotate left, d and l rotate right, f and ; move right. z, p and Esc toggle suspend/resume. q, Del and control-D quit.
- doom This is a port of id Software's DOOM I and II engine. In DOOM, players assume the role of a space marine, who became popularly known as "Doomguy", fighting their way through hordes of invading demons from Hell. Game data (WAD-files) for doom are not part of the distribution, but free WAD-files, like the shareware version, can be obtained on the net.
- festoon Generate an official-looking but utterly nonsensical bureaucratic report as pic | eqn | tbl | troff -mm input. Options -p, -e and -t add gibberish diagrams, equations and tables.
- glendy Don't let the rabbit escape.
- juggle Display the juggling *pattern* using the optional initial *start* pattern. The number of hands involved (default 2) can be specified with -h, and *delay* can be used to speed up or slow down the action (default is 20). Try the pattern 33333344133333 or 333353505151512333333 or YWUSQOMKIGECA (see http://seehuhn.de/jong/theory.html).
- life Play the game of Life, given an initial position. There is a library of interesting initial positions; the library is consulted if *startfile* cannot be found. The -3 and -0 options select between rules known as 34-life and lineosc, while -0 allows specifying the rules explicitly as an argument. The -d option allows specifying the delay in milliseconds between steps, and -b reverses the color scheme.
- mahjongg Remove all tiles from the board. Click on tiles with the same face that are not blocked by others. A blocked tile is one that is partially or fully covered on top or has neighbouring tiles to the left and right. The game finishes when either all tiles are gone or there are no more moves left. The arguments are for changing

background (-b), tile (-t) and layout (-1) images; -c selects a true-color buffer image, for use with drawterm or in case selecting a tile obscures it completely; -f causes mahjongg to indicate non-blocked tiles on mouse-over. The N key will generate a new level, R restarts the current one. Q and Del quit, H gives a hint, either trying to match the currently selected tile, or if no tile is selected finding out the first available tile. U and Bksp undo the last move, C tries to solve the level.

- memo Remove all tiles from the board. At first, pictures of various Bell Labs employees, Lucent Technologies' logo, and Glenda will appear. Memorize the sequence, then click to hide them and begin. Use the mouse to select two tiles. If they are the same, the tiles will disappear, otherwise the tiles will flip back and you will get a chance to try again. Button 3 generates a menu allowing you to restart, switch between easy and hard modes, and exit. The -h option sets the game to hard mode. Once the game has been completed, a message pops up with how long it took to win. Use the button 3 menu to choose a mode, or click to play again.
- mole A molecular dynamics simulation based on the Lennard-Jones potential. r restarts the simulation. f redraws the screen. R reverses the simulation. q and Del quit the simulation.
- sokoban Guide Glenda through a room full of walls, pebbles and holes to put the pebbles in. Your goal is to arrange all pebbles into holes by pushing them around, but you can only push a pebble if there is no wall or another pebble blocking the way. Arrow keys move Glenda up-down-left-right. N and P keys switch between the next and previous levels, R restarts the current level. Del and Q quit. Button 3 invokes a menu to restart the current level, load different level sets, and en- and disable animation of multi-step moves. Button 2 lets you change between levels. Button 1 lets you do multi-step moves and pushes, by clicking it on the destination where you want Glenda to go. Glenda will only move if it can reach the destination. For a multi-step push the pebble must be next to Glenda, the destination must be on the same row or column, and there must be a free place next to the destination where the pebble can be pushed to. Otherwise, if possible, Glenda will walk to the destination without pushing the pebble. *Sokoban* accepts a level file as its argument.
- sudoku Sudoku is a puzzle game from Japan. The goal of the game is to fill the numbers 1 to 9 in all squares of the 9x9 board following a few simple rules: no digit should repeat on the same row and column, and no digit should repeat in the same 3x3 boxes outlined with thicker lines. The board is initially filled with a partial solution which can be used for inferring digits for the empty squares. The top row of the board contains the digits 1 through 9, clicking on one of those digits selects that number for placement on the board, clicking it again will deselect that digit. Clicking on an empty square will then affix the square with the selected digit or, if no digit is selected empty the square.

Button 3 presents a menu with the following options:

New	autogenerate a new, random board
Check	mark in red any digits not placed according to the rules
Solve	present the board's solution
Clear	clear the board to its starting (or last loaded) state
Save	save the current board to /tmp/sudoku-save
Load	load the last saved board from /tmp/sudoku-save
Print	print the current board and solution in a format suitable for addition in the <i>sudoku</i> library to /tmp/sudoku-board
Offline	pretty-print the board for off-line solving to /tmp/sudoku-print
Exit	quit the game
Button 2 pr	esents a list of <i>sudoku</i> boards of varying degrees of difficulty from

110

/sys/games/lib/sudoku/boards.

Pressing the Q key quits sudoku.

FILES

/sys/games/lib/[45]scores score files of 4s and 5s /sys/games/lib/life/* interesting starting positions /sys/games/lib/mahjongg/* image sprites, levels and backgrounds used by mahjongg /lib/face/* tiles for memo /sys/games/lib/sokoban/* image sprites and levels used by sokoban /sys/games/lib/sudoku/* images and boards used by sudoku \$home/lib/doom/* /sys/lib/doom/* /sys/games/lib/doom/* doom WAD-files.

SOURCE

/sys/src/games

BUGS

In 4s and 5s, mouse warping (when the game is resumed, and when a new tile appears) does not happen when the mouse cursor is outside the game window. Those who prefer to use the keyboard without the mouse cursor blocking the view (or being warped all the time) may consider this a feature.

HISTORY

Doom first appeared in 9front (May, 2011). *Packet* first appeared in 9front (August, 2011).

grap - pic preprocessor for drawing graphs

SYNOPSIS

grap [file ...]

DESCRIPTION

Grap is a pic(1) preprocessor for drawing graphs on a typesetter. Graphs are surrounded by the *troff* 'commands' .G1 and .G2. Data are scaled and plotted, with tick marks supplied automatically. Commands exist to modify the frame, add labels, override the default ticks, change the plotting style, define coordinate ranges and transformations, and include data from files. In addition, *grap* provides the same loops, conditionals, and macro processing that *pic* does.

frame ht *e* wid *e* top dotted ...: Set the frame around the graph to specified ht and wid; default is 2 by 3 (inches). The line *styles* (dotted, dashed, invis, solid (default)) of the *sides* (top, bot, left, right) of the frame can be set independently.

label *side* "a label" "as a set of strings" *adjust*: Place label on specified side; default side is bottom. *adjust* is up (or down left right) *expr* to shift default position; width *expr* sets the width explicitly.

ticks side in at optname expr, expr, ...: Put ticks on side at expr, ..., and label with "expr". If any expr is followed by "...", label tick with "...", and turn off all automatic labels. If "..." contains %f's, they will be interpreted as printf formatting instructions for the tick value. Ticks point in or out (default out). Tick iterator: instead of at ..., use from expr to expr by op expr where op is optionally +-*/ for additive or multiplicative steps. by can be omitted, to give steps of size 1. If no ticks are requested, they are supplied automatically; suppress this with ticks off. Automatic ticks normally leave a margin of 7% on each side; set this to anything by margin = expr.

grid side linedesc at optname expr, expr, ...: Draw grids perpendicular to side in style linedesc at expr, Iterators and labels work as with ticks.

coord *optname* x *min, max* y *min, max* $\log x \log y$: Set range of coords and optional log scaling on either or both. This overrides computation of data range. Default value of *optname* is current coordinate system (each coord defines a new coordinate system).

plot "*str*" at *point*; "*str*" at *point*: Put *str* at *point*. Text position can be qualified with rjust, ljust, above, below after "...".

line from *point* to *point linedesc*: Draw line from here to there. arrow works in place of line.

next optname at point linedesc: Continue plot of data in optname to point; default is current.

draw *optname linedesc* ...: Set mode for next: use this style from now on, and plot "..." at each point (if given).

new *optname linedesc* ...: Set mode for next, but disconnect from previous.

A list of numbers $x \ y1 \ y2 \ y3 \ ...$ is treated as plot bullet at x,y1; plot bullet at x,y2; etc., or as next at x,y1 etc., if draw is specified. Abscissae of 1,2,3,... are provided if there is only one input number per line.

A point *optname expr, expr* maps the point to the named coordinate system. A *linedesc* is one of dot dash invis solid optionally followed by an expression.

define *name* {*whatever*}: Define a macro. There are macros already defined for standard plotting symbols like bullet, circle, star, plus, etc., in /sys/lib/grap.defines, which is included if it exists.

var = expr: Evaluate an expression. Operators are + - * and /. Functions are log and exp (both base 10), sin, cos, sqrt; rand returns random number on [0,1); max(e,e), min(e,e), int(e).

print expr; print "...": As a debugging aid, print expr or string on the standard error.

copy "file name": Include this file right here.

copy thru *macro*: Pass rest of input (until .G2) through *macro*, treating each field (non-blank, or "...") as an argument. *macro* can be the name of a macro previously defined, or the body of one in place, like /plot \$1 at \$2,\$3/.

copy thru macro until "string": Stop copy when input is string (left-justified).

pic *remainder of line*: Copy to output with leading blanks removed.

graph *Name pic-position*: Start a new frame, place it at specified position, e.g., graph Thing2 with .sw at Thing1.se + (0.1,0). *Name* must be capitalized to keep *pic* happy.


. anything at beginning of line: Copied verbatim.

sh %*anything* %: Pass everything between the %'s to the shell; as with macros, % may be any character and *anything* may include newlines.

anything: A comment, which is discarded.

Order is mostly irrelevant; no category is mandatory. Any arguments on the .G1 line are placed on the generated .PS line for *pic*.

EXAMPLES



FILES

/sys/lib/grap.defines definitions of standard plotting characters, e.g., bullet

SOURCE

/sys/src/cmd/grap

SEE ALSO

pic(1), *troff*(1)

J. L. Bentley and B. W. Kernighan, "GRAP—A Language for Typesetting Graphs", Unix Research System Programmer's Manual, Tenth Edition, Volume 2.

graph - draw a graph

SYNOPSIS

graph [option ...]

DESCRIPTION

Graph with no options takes pairs of numbers from the standard input as abscissas (x-values) and ordinates (y-values) of a graph. Successive points are connected by straight lines. The graph is encoded on the standard output for display by plot(1) filters.

If an ordinate is followed by a nonnumeric string, that string is printed as a label beginning on the point. Labels may be surrounded with quotes " " in which case they may be empty or contain blanks and numbers; labels never contain newlines.

The following options are recognized, each as a separate argument.

- -a Supply abscissas automatically; no x-values appear in the input. Spacing is given by the next argument (default 1). A second optional argument is the starting point for automatic abscissas (default 0, or 1 with a log scale in x, or the lower limit given by -x).
- -b Break (disconnect) the graph after each label in the input.
- -c Character string given by next argument is default label for each point.
- -g Next argument is grid style, 0 no grid, 1 frame with ticks, 2 full grid (default).
- -1 Next argument is a legend to title the graph. Grid ranges are automatically printed as part of the title unless a -s option is present.
- -m Next argument is mode (style) of connecting lines: 0 disconnected, 1 connected. Some devices give distinguishable line styles for other small integers. Mode -1 (default) begins with style 1 and rotates styles for successive curves under option -0.
- -o (Overlay.) The ordinates for *n* superposed curves appear in the input with each abscissa value. The next argument is *n*.
- -p Next argument is one or more of the characters bcgkmrwy, choosing pen colors by their initial letter, as in *plot*(6). Successive curves will cycle through the colors in the given order.
- -s Save screen; no new page for this graph.
- -x 1 If 1 is present, x-axis is logarithmic. Next 1 (or 2) arguments are lower (and upper) x limits. Third argument, if present, is grid spacing on x axis. Normally these quantities are determined automatically.
- -y 1 Similarly for y.
- -e Make automatically determined *x* and *y* scales equal.
- -h Next argument is fraction of space for height.
- -w Similarly for width.
- -r Next argument is fraction of space to move right before plotting.
- -u Similarly to move up before plotting.
- -t Transpose horizontal and vertical axes. (Option a now applies to the vertical axis.)

If a specified lower limit exceeds the upper limit, the axis is reversed.

SOURCE

/sys/src/cmd/graph

SEE ALSO

plot(1), grap(1)

BUGS

Segments that run out of bounds are dropped, not windowed. Logarithmic axes may not be reversed. Option -e actually makes automatic limits, rather than automatic scaling, equal.

grep, g - search a file for a pattern

SYNOPSIS

```
grep[-bchillnsv][-e] pattern | -f patternfile[file ...]
```

g[flags]pattern[file...]

DESCRIPTION

Grep searches the input *files* (standard input default) for lines that match the *pattern*, a regular expression as defined in regexp(6) with the addition of a newline character as an alternative (substitute for |) with lowest precedence. Normally, each line matching the pattern is 'selected', and each selected line is copied to the standard output. The options are

- -c Print only a count of matching lines.
- -h Do not print file name tags (headers) with output lines.
- -e The following argument is taken as a *pattern*. This option makes it easy to specify patterns that might confuse argument parsing, such as -n.
- -i Ignore alphabetic case distinctions. The implementation folds into lower case all letters in the pattern and input before interpretation. Matched lines are printed in their original form.
- -1 (ell) Print the names of files with selected lines; don't print the lines.
- -L Print the names of files with no selected lines; the converse of -1.
- -n Mark each printed line with its line number counted in its file.
- -s Produce no output, but return status.
- -v Reverse: print lines that do not match the pattern.
- -f The pattern argument is the name of a file containing regular expressions one per line.
- -b Don't buffer the output: write each output line as soon as it is discovered.

Output lines are tagged by file name when there is more than one input file. (To force this tagging, include /dev/null as a file name argument.)

Care should be taken when using the shell metacharacters $*[\land]()=\$ and newline in *pattern*; it is safest to enclose the entire expression in single quotes '...'. An expression starting with '*' will treat the rest of the expression as literal characters.

G invokes *grep* with -n (plus aditional flags, if provided) and forces tagging of output lines by file name. If no files are listed, it recursively searches the current directory for all files matching *.b *.c *.C *.h *.l *.m *.asm *.cc *.cs *.lx *.cgi *.pl *.py *.tex *.ms *.java *.xy *.go *.goc *.cpp

The recursive search can be suppressed by passing g the -n flag.

SOURCE

```
/sys/src/cmd/grep
/rc/bin/g
```

SEE ALSO

ed(1), awk(1), sed(1), sam(1), regexp(6)

DIAGNOSTICS

Exit status is null if any lines are selected, or non-null when no lines are selected or an error occurs.

gs - Aladdin Ghostscript (PostScript and PDF language interpreter)

SYNOPSIS

gs [options] [files] ...

DESCRIPTION

Ghostscript is a programming language similar to Adobe Systems' PostScript and PDF languages, which are in turn similar to Forth. *Gs* reads *files* in sequence and executes them as Ghostscript programs. After doing this, it reads further input from the standard input. If the *file* – is named, however, it represents the standard input, which is read in order and not after the files on the command line. Each line is interpreted separately. The 'quit' command, or end-of-file, exits the interpreter.

The interpreter recognizes several switches described below, which may appear anywhere in the command line and apply to all files thereafter.

The -h or -? options give help and list the available devices; the default is plan9, which produces compressed image files suitable for viewing with page(1) (but note that page(1) will invoke *gs* automatically; see its manual).

Ghostscript may be built with multiple output devices. Ghostscript normally opens the first one and directs output to it. To use device xyz as the initial output device, include the switch

-sDEVICE=xyz in the command line. This switch must precede the first PostScript file and only its first invocation has any effect. Output devices can also be selected by the word selectdevice in the input language, or by setting the environment variable GS_DEVICE. The order of precedence for these alternatives, highest to lowest, is:

selectdevice
(command line)
GS_DEVICE
plan9

Normally, output goes directly to a scratch file. To send the output to a series of files foo1.xyz, foo2.xyz, etc., use the switch

-sOutputFile=foo%d.xyz

The %d may be any *printf* (see fprintf(2)) format specification. Each file will receive one page of output. If the file name begins with a pipe character, the output will be sent as standard input to the following pipeline. For example,

-sOutputFile=|lp

Specifying the file – will send the files to standard output; this also requires enabling the -q option.

Initialization files

When looking for the initialization files $(gs_*.ps)$, the files related to fonts, or the file for the run operator, Ghostscript first looks for the file (if it doesn't start with a slash) in the current directory, then in these directories in the following order:

- 1. Any directories specified by -I switches in the command line (see below);
- 2. Any directories specified by the GS_LIB environment variable;
- The directories /sys/lib/ghostscript, /sys/lib/ghostscript/font, and /sys/lib/postscript/font.

The GS_LIB or -I parameters may be a single directory or a colon-separated list.

Options

-- filename arg1 ...

Take the next argument as a file name as usual, but take all remaining arguments (even if they have the syntactic form of switches) and define the name ARGUMENTS in userdict (not systemdict) as an array of those strings, *before* running the file. When Ghostscript finishes executing the file, it exits back to the shell.

–Dname=token

–d name=token

Define a name in systemdict with the given definition. The token must be exactly one token (as defined by the 'token' operator) and must not contain any white space.

–D*name*

–d name

Define a name in systemdict with value=null.

-Sname=string

-sname=string

Define a name in systemdict with a given string as value. This is different from -d. For example, -dname=35 is equivalent to the program fragment

/name 35 def
whereas -sname=35 is equivalent to
/name (35) def

-q Quiet startup: suppress normal startup messages, and also do the equivalent of -dQUIET.

-gnumber1xnumber2

Equivalent to -dDEVICEWIDTH = number1 and -dDEVICEHEIGHT = number2. This is for the benefit of devices, such as windows, that allow width and height to be specified.

-rnumber

-rnumber1xnumber2

Equivalent to -dDEVICEXRESOLUTION = number1 and -dDEVICEYRESOLUTION = number2. This is for the benefit of devices, such as printers, that support multiple X and Y resolutions. If only one number is given, it is used for both X and Y resolutions.

–I directories

Adds the designated list of directories at the head of the search path for library files.

Note that gs_init.ps makes systemdict read-only, so the values of names defined with -D/d/S/s cannot be changed (although, of course, they can be superseded by definitions in userdict or other dictionaries.)

Special names

-dBATCH

Exit after the last file has been processed. This is equivalent to listing *quit.ps* at the end of the list of files.

-dDISKFONTS

Causes individual character outlines to be loaded from the disk the first time they are encountered. (Normally Ghostscript loads all the character outlines when it loads a font.) This may allow loading more fonts into RAM, at the expense of slower rendering.

-dNOCACHE

Disables character caching. Only useful for debugging.

-dNOBIND

Disables the 'bind' operator. Only useful for debugging.

-dNODISPLAY

Suppresses the normal initialization of the output device. This may be useful when debugging.

-dNOPAUSE

Disables the prompt and pause at the end of each page. This may be desirable for applications where another program (e.g. page(1)) is 'driving' Ghostscript.

-dSAFER

Disables the deletefile and renamefile operators, and the ability to open files in any mode other than read-only. This may be desirable for spoolers or other sensitive environments. Files in the /fd directory may still be opened for writing.

-dWRITESYSTEMDICT

Leaves systemdict writable. This is necessary when running special utility programs such as font2c and pcharstr, which must bypass normal PostScript access protection.

-sDEVICE=*device* Selects an alternate initial output device, as described above.

-sOutputFile=filename

Selects an alternate output file (or pipe) for the initial output device, as described above.

FILES

/sys/lib/ghostscript/*

Startup-files, utilities, examples, and basic font definitions.

/sys/lib/ghostscript/fonts/* Additional font definitions.

SOURCE

/sys/src/cmd/gs

SEE ALSO

page(1), ps2pdf(1)

The Ghostscript document files in doc and man subdirectories of the source directory.

BUGS

The treatment of standard input is non-standard.

gview – interactive graph viewer

SYNOPSIS

gview[-mp][-l logfile][files]

DESCRIPTION

Gview reads polygonal lines or a polygonal line drawing from an ASCII input file (which defaults to standard input), and views it interactively, with commands to zoom in and out, perform simple editing operations, and display information about points and polylines. (Multiple input files are allowed if you want to overlay several line drawings.) The editing commands can change the color and thickness of the polylines, delete (or undelete) some of them, and optionally rotate and move them. It is also possible to generate an output file that reflects these changes and is in the same format as the input.

Since the move and rotate commands are undesirable when just viewing a graph, they are only enabled if *gview* is invoked with the -m option.

The -p option plots only the vertices of the polygons.

Clicking on a polyline with button 1 displays the coordinates and a *t* value that tells how far along the polyline. (t=0 at the first vertex, t=1 at the first vertex, t=1.5 halfway between the second and third vertices, etc.) The -1 option generates a log file that lists all points selected in this manner.

The most important interactive operations are to *zoom in* by sweeping out a rectangle, or to *zoom out* so that everything currently being displayed shrinks to fit in the swept-out rectangle. Other options on the button 3 menu are *unzoom* which restores the coordinate system to the default state where everything fits on the screen, *recenter* which takes a point and makes it the center of the window, and *square up* which makes the horizontal and vertical scale factors equal.

To take a graph of a function where some part is almost linear and see how it deviates from a straight line, select two points on this part of the graph (i.e., select one with button 1 and then select the other) and then use the *slant* command on the button 3 menu. This slants the coordinate system so that the line between the two selected points appears horizontal (but vertical still means positive *y*). Then the *zoom in* command can be used to accentuate deviations from horizontal. There is also an *unslant* command that undoes all of this and goes back to an unslanted coordinate system.

There is a *recolor* command on button 3 that lets you select a color and change everything to have that color, and a similar command on button 2 that only affects the selected polyline. If the input file uses the Multi(...) feature explained below, either flavor of *recolor* allows you to type a digit in lieu of selecting a color.

The *thick* or *thin* command on button 2 changes the thickness of the selected polyline and there is also an undo command for such edits. Finally, button 3 has commands to *read* a new input file and display it on top of everything else, *restack* the drawing order (in case lines of different color are drawn on top of each other), *write* everything into an output file, or *exit* the program.

Each polyline in an input or output file is a space-delimited x y coordinate pair on a line by itself, and the polyline is a sequence of such vertices followed by a label. The label could be just a blank line or it could be a string in double quotes, or virtually any text that does not contain spaces and is on a line by itself. The label at the end of the last polyline is optional. It is not legal to have two consecutive labels, since that would denote a zero-vertex polyline and each polyline must have at least one vertex. (One-vertex polylines are useful for scatter plots.) Under the -1 option, a newline causes the selected polyline's label to appear in the log file (where it could be seen by invoking tail -f in another window).

If the label after a polyline contains the word Thick or a color name (Red, Pink, Dkred, Orange, Yellow, Dkyellow, Green, Dkgreen, Cyan, Blue, Ltblue, Magenta, Violet, Gray, Black, White), whichever color name comes first will be used to color the polyline. Alternatively, labels can contain Multi followed by single-letter versions of these names: (R, P, r, O, Y, y, G, g, C, B, b, M, V, A, K, W, each optionally preceded by T). Then *recolor* followed by a nonzero digit *n* selects the *n*th alternative for each polyline.

EXAMPLE

To see a graph of the function y = sin(x)/x generate input with an awk script and pipe it into gview: awk 'BEGIN{for(x=.1;x<500;x+=.1)print x,sin(x)/x}' | gview

SOURCE

/sys/src/cmd/gview.c

SEE ALSO

awk(1), *tail*(1)

BUGS

The user interface for the *slant* command is counter-intuitive. Perhaps it would be better to have a scheme for sweeping out a parallelogram.

The -p option makes the interactive point selection feature behave strangely, and is unnecessary since extra blank lines in the input achieve essentially the same effect.

gzip, gunzip, bzip2, bunzip2, compress, uncompress, zip, unzip - compress and expand data

SYNOPSIS

```
gzip [-cvD[1-9]] [file ...]
gunzip [-ctTvD] [file ...]
bzip2 [-cvD[1-9]] [file ...]
bunzip2 [-cvD] [file ...]
compress [ -cv ] [ file ...]
uncompress [ -cv ] [ file ...]
zip [-avD[1-9]] [-f zipfile] file [...]
unzip [-cistTvD] [-f zipfile] [file ...]
```

DESCRIPTION

Gzip encodes files with a hybrid Lempel-Ziv 1977 and Huffman compression algorithm known as deflate. Most of the time, the resulting file is smaller, and will never be much bigger. Output files are named by taking the last path element of each file argument and appending .gz; if the resulting name ends with .tar.gz, it is converted to .tgz instead. *Gunzip* reverses the process. Its output files are named by taking the last path element of each file argument of each file argument, converting .tgz to .tar.gz, and stripping any .gz; the resulting name must be different from the original name.

Bzip2 and *bunzip2* are similar in interface to *gzip* and *gunzip*, but use a modified Burrows-Wheeler block sorting compression algorithm. The default suffix for output files is .bz2, with .tar.bz2 becoming .tbz. *Bunzip2* recognizes the extension .tbz2 as a synonym for .tbz.

Compress and *uncompress* are similar in interface to *gzip* and *gunzip*, but use the Lempel-Ziv-Welch compression algorithm. The default suffix for output files is .Z. *Compress* is one of the oldest widespread Unix compression programs.

Zip encodes the named files and places the results into the archive *zipfile*, or the standard output if no file is given. *Unzip* extracts files from an archive created by *zip*. If no files are named as arguments, all of files in the archive are extracted. A directory's name implies all recursively contained files and subdirectories. *Zip* is the *de facto* standard for compression on Microsoft operating systems.

None of these programs removes the original files. If the process fails, the faulty output files are removed.

The options are:

- -a Automaticialy creates directories as needed, needed for zip files created by broken implementations which omit directories.
- -c Write to standard output rather than creating an output file.
- -i Convert all archive file names to lower case.
- -s Streaming mode. Looks at the file data adjacent to each compressed file rather than seeking in the central file directory. This is the mode used by *unzip* if no *zipfile* is specified. If -s is given, -T is ignored.
- -t List matching files in the archive rather than extracting them.
- -T Set the output time to that specified in the archive.
- -1.. -9 Sets the compression level. -1 is tuned for speed, -9 for minimal output size. The best compromise is -6, the default.
- -v Produce more descriptive output. With -t, adds the uncompressed size in bytes and the modification time to the output. Without -t, prints the names of files on standard error as they are compressed or decompressed.
- -D Produce debugging output.

SOURCE

/sys/src/cmd/gzip /sys/src/cmd/bzip2 /sys/src/cmd/compress

SEE ALSO

tar(1) "A Technique for High Performance Data Compression", Terry A. Welch, *IEEE Computer*, vol. 17, no. 6 (June 1984), pp. 8–19.

BUGS

Unzip can only extract files which are uncompressed or compressed with the deflate compression scheme. Recent zip files fall into this category. Very recent zip files may have tables of contents that *unzip* cannot read. Such files are still readable by invoking *unzip* with the -s option.

hg - Mercurial source code management system

SYNOPSIS

hg [globaloptions] command [commandoptions] [arguments]

DESCRIPTION

The *hg* command provides a command line interface to the Mercurial system.

COMMAND ELEMENTS

files ...

indicates one or more filename or relative path filenames; see *FILE PATTERNS* for information on pattern matching

path

indicates a path on the local machine

revision

indicates a changeset which can be specified as a changeset revision number, a tag, or a unique substring of the changeset hash value

repository path

either the pathname of a local repository or the URI of a remote repository. There are two available URI protocols, http:// which is fast and the static-http:// protocol which is much slower but does not require a special server on the web host.

OPTIONS

-R, --repository

repository root directory or symbolic path name

--cwd

change working directory

-y, --noninteractive

do not prompt, assume yes for any required answers

-q, --quiet

suppress output

-v, --verbose

enable additional output

--config

set/override config option

--debug

enable debugging output

--debugger

start debugger

--encoding

set the charset encoding (default: UTF-8)

--encodingmode

set the charset encoding mode (default: strict)

--Isprof

print improved command execution profile

--traceback

print traceback on exception

--time

time how long the command takes

--profile

print command execution profile

--version

output version information and exit

-h, --help

display help and exit

COMMANDS

add [OPTION] ... [FILE] ...

Schedule files to be version controlled and added to the repository.

The files will be added to the repository at the next commit. To undo an add before that, see hg revert.

If no names are given, add all files in the repository.

options:

-I, --include include names matching the given patterns

-X, --exclude exclude names matching the given patterns

-n, --dry-run do not perform actions, just print output

addremove [OPTION]... [FILE]...

Add all new files and remove all missing files from the repository.

New files are ignored if they match any of the patterns in .hgignore. As with add, these changes take effect at the next commit.

Use the -s option to detect renamed files. With a parameter > 0, this compares every removed file with every added file and records those similar enough as renames. This option takes a percentage between 0 (disabled) and 100 (files must be identical) as its parameter. Detecting renamed files this way can be expensive.

options:

-s, --similarity guess renamed files by similarity (0<=s<=100)
 -l, --include include names matching the given patterns
 -X, --exclude exclude names matching the given patterns
 -n, --dry-run do not perform actions, just print output

annotate [-r REV] [-f] [-a] [-u] [-d] [-n] [-c] [-l] FILE...

List changes in files, showing the revision id responsible for each line

This command is useful to discover who did a change or when a change took place.

Without the -a option, annotate will avoid processing files it detects as binary. With -a, annotate will generate an annotation anyway, probably with undesirable results.

options:

- -r, --rev annotate the specified revision
- -f, --follow follow file copies and renames
- -a, --text treat all files as text
- -u, --user list the author (long with -v)
- -d, --date list the date (short with -q)
- -n, --number list the revision number (default)
- -c, --changeset list the changeset
- -l, --line-number show line number at the first appearance
- -I, --include include names matching the given patterns
- -X, --exclude exclude names matching the given patterns

aliases: blame

archive [OPTION]... DEST

By default, the revision used is the parent of the working directory; use "-r" to specify a different revision.

To specify the type of archive to create, use "-t". Valid types are:

"files" (default): a directory full of files "tar": tar archive, uncompressed "tbz2": tar archive, compressed using bzip2 "tgz": tar archive, compressed using gzip "uzip": zip archive, uncompressed "zip": zip archive, compressed using deflate

The exact name of the destination archive or directory is given using a format string; see "hg help export" for details.

Each member added to an archive file has a directory prefix prepended. Use "-p" to specify a format string for the prefix. The default is the basename of the archive, with suffixes removed.

options:

--no-decode do not pass files through decoders
-p, --prefix directory prefix for files in archive
-r, --rev revision to distribute
-t, --type type of distribution to create
-l, --include include names matching the given patterns
-X, --exclude exclude names matching the given patterns

backout [OPTION] ... [-r] REV

Commit the backed out changes as a new changeset. The new changeset is a child of the backed out changeset.

If you back out a changeset other than the tip, a new head is created. This head will be the new tip and you should merge this backout changeset with another head (current one by default).

The --merge option remembers the parent of the working directory before starting the backout, then merges the new head with that changeset afterwards. This saves you from doing the merge by hand. The result of this merge is not committed, as for a normal merge.

See 'hg help dates' for a list of formats valid for -d/--date.

options:

--merge merge with old dirstate parent after backout

--parent parent to choose when backing out merge

-r, --rev revision to backout

-I, --include include names matching the given patterns

-X, --exclude exclude names matching the given patterns

-m, --message use <text> as commit message

-l, --logfile read commit message from <file>

-d, --date record datecode as commit date

-u, --user record user as committer

bisect [-gbsr] [REV]

This command helps to find changesets which introduce problems. To use, mark the earliest changeset you know exhibits the problem as bad, then mark the latest changeset which is free from the problem as good. Bisect will update your working directory to a revision for testing. Once you have performed tests, mark the working directory as bad or good and bisect will

either update to another candidate changeset or announce that it has found the bad revision.

options:

-r, --reset reset bisect state -g, --good mark changeset good -b, --bad mark changeset bad -s, --skip skip testing changeset -U, --noupdate do not update to target

branch [-f] [NAME]

With no argument, show the current branch name. With one argument, set the working directory branch name (the branch does not exist in the repository until the next commit).

Unless --force is specified, branch will not let you set a branch name that shadows an existing branch.

Use the command 'hg update' to switch to an existing branch.

options:

-f, --force set branch name even if it shadows an existing branch

branches [-a]

List the repository's named branches, indicating which ones are inactive. If active is specified, only show active branches.

A branch is considered active if it contains repository heads.

Use the command 'hg update' to switch to an existing branch.

options:

-a, --active show only branches that have unmerged heads

bundle [-f] [-a] [-r REV]... [--base REV]... FILE [DEST]

Generate a compressed changegroup file collecting changesets not found in the other repository.

If no destination repository is specified the destination is assumed to have all the nodes specified by one or more --base parameters. To create a bundle containing all changesets, use --all (or --base null).

The bundle file can then be transferred using conventional means and applied to another repository with the unbundle or pull command. This is useful when direct push and pull are not available or when exporting an entire repository is undesirable.

Applying bundles preserves all changeset contents including permissions, copy/rename information, and revision history.

options:

-f, --force run even when remote repository is unrelated

-r, --rev a changeset up to which you would like to bundle

--base a base changeset to specify instead of a destination

-a, --all bundle all changesets in the repository

-e, --ssh specify ssh command to use

--remotecmd specify hg command to run on the remote side

cat [OPTION] ... FILE ...

Print the specified files as they were at the given revision. If no revision is given, the parent of the working directory is used, or tip if no revision is checked out.

Output may be to a file, in which case the name of the file is

given using a format string. The formatting rules are the same as for the export command, with the following additions:

%s basename of file being printed

%d dirname of file being printed, or '.' if in repo root

%p root-relative path name of file being printed

options:

-o, --output print output to file with formatted name

-r, --rev print the given revision

--decode apply any matching decode filter

-I, --include include names matching the given patterns

-X, --exclude exclude names matching the given patterns

clone [OPTION]... SOURCE [DEST]

Create a copy of an existing repository in a new directory.

If no destination directory name is specified, it defaults to the basename of the source.

The location of the source is added to the new repository's

For efficiency, hardlinks are used for cloning whenever the source and destination are on the same filesystem (note this applies only to the repository data, not to the checked out files). Some filesystems, such as AFS, implement hardlinking incorrectly, but do not report errors. In these cases, use the --pull option to avoid hardlinking.

You can safely clone repositories and checked out files using full hardlinks with

\$ cp -al REPO REPOCLONE

which is the fastest way to clone. However, the operation is not atomic (making sure REPO is not modified during the operation is up to you) and you have to make sure your editor breaks hardlinks (Emacs and most Linux Kernel tools do so).

If you use the -r option to clone up to a specific revision, no subsequent revisions will be present in the cloned repository. This option implies --pull, even on local repositories.

If the -U option is used, the new clone will contain only a repository (.hg) and no working copy (the working copy parent is the null revision).

See pull for valid source format details.

It is possible to specify an ssh:// URL as the destination, but no Look at the help text for the pull command for important details about ssh:// URLs.

options:

-U, --noupdate the clone will only contain a repository (no working copy)

-r, --rev a changeset you would like to have after cloning --pull use pull protocol to copy metadata

--uncompressed use uncompressed transfer (fast over LAN)

-e, --ssh specify ssh command to use

--remotecmd specify hg command to run on the remote side

commit [OPTION]... [FILE]... Commit changes to the given files into the repository.

> If a list of files is omitted, all changes reported by "hg status" will be committed.

If you are committing the result of a merge, do not provide any file names or -I/-X filters.

If no commit message is specified, the configured editor is started to enter a message.

See 'hg help dates' for a list of formats valid for -d/--date.

options:

-A, --addremove mark new/missing files as added/removed before committing

-I, --include include names matching the given patterns

-X, --exclude exclude names matching the given patterns

-m, --message use <text> as commit message

-l, --logfile read commit message from <file>

-d, --date record datecode as commit date

-u. --user record user as committer

aliases: ci

copy [OPTION] ... [SOURCE] ... DEST

Mark dest as having copies of source files. If dest is a directory, copies are put in that directory. If dest is a file, there can only be one source.

By default, this command copies the contents of files as they stand in the working directory. If invoked with --after, the operation is recorded, but no copying is performed.

This command takes effect in the next commit. To undo a copy before that, see hg revert.

options:

-A, --after record a copy that has already occurred -f, --force forcibly copy over an existing managed file

-I, --include include names matching the given patterns

-X, --exclude exclude names matching the given patterns

-n, --dry-run do not perform actions, just print output

aliases: cp

diff [OPTION]... [-r REV1 [-r REV2]] [FILE]...

Show differences between revisions for the specified files.

Differences between files are shown using the unified diff format.

NOTE: diff may generate unexpected results for merges, as it will default to comparing against the working directory's first parent changeset if no revisions are specified.

When two revision arguments are given, then changes are shown between those revisions. If only one revision is specified then that revision is compared to the working directory, and, when no revisions are specified, the working directory files are compared to its parent.

Without the -a option, diff will avoid generating diffs of files it detects as binary. With -a, diff will generate a diff anyway, probably with undesirable results.

options:

-r,rev	revision
-a,text	treat all files as text
-p,show-functi	on show which function each change is in
-g,git	use git extended diff format
nodates	don't include dates in diff headers
, 3	pace ignore white space when comparing lines
-b,ignore-spac	e-change ignore changes in the amount of white
	space
-B,ignore-blanl	k-lines ignore changes whose lines are all
	blank
–U, ––unified	number of lines of context to show
-I,include	include names matching the given
	patterns
-X,exclude	exclude names matching the given
	patterns

export [OPTION]... [-o OUTFILESPEC] REV...

Print the changeset header and diffs for one or more revisions.

The information shown in the changeset header is: author, changeset hash, parent(s) and commit comment.

NOTE: export may generate unexpected diff output for merge changesets, as it will compare the merge changeset against its first parent only.

Output may be to a file, in which case the name of the file is given using a format string. The formatting rules are as follows:

- %% literal "%" character
- %H changeset hash (40 bytes of hexadecimal)
- %N number of patches being generated
- %R changeset revision number
- %b basename of the exporting repository
- %h short-form changeset hash (12 bytes of hexadecimal)
- %n zero-padded sequence number, starting at 1
- %r zero-padded changeset revision number

Without the -a option, export will avoid generating diffs of files it detects as binary. With -a, export will generate a diff anyway, probably with undesirable results.

With the --switch-parent option, the diff will be against the second parent. It can be useful to review a merge.

options:

-o, --output print output to file with formatted name

-a, --text treat all files as text

-g, --git use git extended diff format

--nodates don't include dates in diff headers

--switch-parent diff against the second parent

grep [OPTION]... PATTERN [FILE]...

Search revisions of files for a regular expression.

This command behaves differently than Unix grep. It only accepts Python/Perl regexps. It searches repository history, not the

working directory. It always prints the revision number in which a match appears.

By default, grep only prints output for the first revision of a file in which it finds a match. To get it to print every revision that contains a change in match status ("-" for a match that becomes a non-match, or "+" for a non-match that becomes a match), use the --all flag.

options:	
–0, ––print0	end fields with NUL
all	print all revisions that match
-f,follow	follow changeset history, or file
	history across copies and renames
-i,ignore-case	e ignore case when matching
-l,files-with-r	matches print only filenames and revs that match
-n,line-numb	er print matching line numbers
-r,rev	search in given revision range
-u,user	list the author (long with -v)
-d,date	list the date (short with -q)
-I,include	include names matching the given
	patterns
-X,exclude	exclude names matching the given
	patterns

heads [-r REV] [REV]...

With no arguments, show all repository head changesets.

If branch or revisions names are given this will show the heads of the specified branches or the branches those revisions are tagged with.

Repository "heads" are changesets that don't have child changesets. They are where development generally takes place and are the usual targets for update and merge operations.

Branch heads are changesets that have a given branch tag, but have no child changesets with that tag. They are usually where development on the given branch takes place.

options:

-r, --rev show only heads which are descendants of rev
 -style display using template map file
 -template display with template

help [COMMAND]

With no arguments, print a list of commands and short help.

Given a command name, print help for that command.

Given an extension name, print help for that extension, and the commands it provides.

identify [-nibt] [-r REV] [SOURCE]

With no revision, print a summary of the current state of the repo.

With a path, do a lookup in another repository.

This summary identifies the repository state using one or two parent hash identifiers, followed by a "+" if there are uncommitted changes in the working directory, a list of tags for this revision and a branch

name for non-default branches.

options:

- -r, --rev identify the specified rev
 -n, --num show local revision number
 -i, --id show global revision id
 -b, --branch show branch
- -t, --tags show tags

aliases: id

import [OPTION]... PATCH...

Import a list of patches and commit them individually.

If there are outstanding changes in the working directory, import will abort unless given the -f flag.

You can import a patch straight from a mail message. Even patches as attachments work (body part must be type text/plain or text/x-patch to be used). From and Subject headers of email message are used as default committer and commit message. All text/plain body parts before first diff are added to commit message.

If the imported patch was generated by hg export, user and description from patch override values from message headers and body. Values given on command line with -m and -u override these.

If --exact is specified, import will set the working directory to the parent of each patch before applying it, and will abort if the resulting changeset has a different ID than the one recorded in the patch. This may happen due to character set problems or other deficiencies in the text patch format.

To read a patch from standard input, use patch name "-". See 'hg help dates' for a list of formats valid for -d/--date.

options:

options.		
-p,strip directory strip option for patch. This has the		
same meaning as the corresponding patch option		
(default: 1)		
-b,base base path		
-f,force skip check for outstanding uncommitted changes		
no-commit don't commit, just update the working directory		
exact apply patch to the nodes from which it was		
generated		
import-branch Use any branch information in patch (implied by		
––exact)		
-m,message		
-I,logfile read commit message from <file></file>		
-d,date record datecode as commit date		

-u, --user record user as committer

aliases: patch

incoming [-p] [-n] [-M] [-f] [-r REV]... [--bundle FILENAME] [SOURCE]

Show new changesets found in the specified path/URL or the default pull location. These are the changesets that would be pulled if a pull was requested.

For remote repository, using --bundle avoids downloading the changesets twice if the incoming is followed by a pull.

See pull for valid source format details.

options:

- -f, --force run even when remote repository is unrelated
- -n, --newest-first show newest record first
- --bundle file to store the bundles into
- -r, --rev a specific revision up to which you would like
 - to pull
- -p, --patch show patch -I, --limit limit number of char
- -I, --limit limit number of changes displayed -M, --no-merges do not show merges
- --style display using template map file
- --template display with template
- -e, --ssh specify ssh command to use
- --remotecmd specify hg command to run on the remote side

aliases: in

init [-e CMD] [--remotecmd CMD] [DEST]

Initialize a new repository in the given directory. If the given directory does not exist, it is created.

If no directory is given, the current directory is used.

It is possible to specify an ssh:// URL as the destination. Look at the help text for the pull command for important details about ssh:// URLs.

options:

-e, --ssh specify ssh command to use

--remotecmd specify hg command to run on the remote side

locate [OPTION]... [PATTERN]...

Print all files under Mercurial control whose names match the given patterns.

This command searches the entire repository by default. To search just the current directory and its subdirectories, use "--include .".

If no patterns are given to match, this command prints all file names.

If you want to feed the output of this command into the "xargs" command, use the "-0" option to both this command and "xargs". This will avoid the problem of "xargs" treating single filenames that contain white space as multiple filenames.

options:

-r, --rev search the repository as it stood at rev

-0, --print0 end filenames with NUL, for use with xargs

-f, --fullpath print complete paths from the filesystem root

-I, --include include names matching the given patterns

-X, --exclude exclude names matching the given patterns

log [OPTION]... [FILE]

Print the revision history of the specified files or the entire project.

File history is shown without following rename or copy history of files. Use -f/--follow with a file name to follow history across renames and copies. --follow without a file name will only show ancestors or descendants of the starting revision. --follow-first

only follows the first parent of merge revisions.

If no revision range is specified, the default is tip:0 unless --follow is set, in which case the working directory parent is used as the starting revision.

See 'hg help dates' for a list of formats valid for -d/--date.

By default this command outputs: changeset id and hash, tags, non-trivial parents, user, date and time, and a summary for each commit. When the -v/--verbose switch is used, the list of changed files and full commit message is shown.

NOTE: log -p may generate unexpected diff output for merge changesets, as it will compare the merge changeset against its first parent only. Also, the files: list will only reflect files that are different from BOTH parents.

options:

- -f, --follow follow changeset history, or file history across copies and renames
- --follow-first only follow the first parent of merge changesets

-d, --date show revs matching date spec

-C, --copies show copied files

-k, --keyword do case-insensitive search for a keyword

-r, --rev show the specified revision or range

--removed include revs where files were removed

-m, --only-merges show only merges

-b, --only-branch show only changesets within the given named branch

-P, --prune do not display revision or any of its ancestors

-p, --patch show patch

-l, --limit limit number of changes displayed

-M, --no-merges do not show merges

--style display using template map file

--template display with template

-I, --include include names matching the given patterns

-X, --exclude exclude names matching the given patterns

aliases: history

manifest [-r REV]

Print a list of version controlled files for the given revision. If no revision is given, the parent of the working directory is used, or tip if no revision is checked out.

The manifest is the list of files being version controlled. If no revision is given then the first parent of the working directory is used.

With -v flag, print file permissions, symlink and executable bits. With --debug flag, print file revision hashes.

options:

-r, --rev revision to display

merge [-f] [[-r] REV]

Merge the contents of the current working directory and the requested revision. Files that changed between either parent are marked as changed for the next commit and a commit must be performed before any further updates are allowed.

If no revision is specified, the working directory's parent is a

head revision, and the repository contains exactly one other head, the other head is merged with by default. Otherwise, an explicit revision to merge with must be provided.

options:

-f, --force force a merge with outstanding changes

-r, --rev revision to merge

outgoing [-M] [-p] [-n] [-f] [-r REV]... [DEST]

Show changesets not found in the specified destination repository or the default push location. These are the changesets that would be pushed if a push was requested.

See pull for valid destination format details.

options: run even when remote repository is unrelated -f, --force -r, --rev a specific revision up to which you would like to push -n, --newest-first show newest record first -p, --patch show patch -l, --limit limit number of changes displayed -M, --no-merges do not show merges display using template map file --style --template -e, --ssh display with template specify ssh command to use specify hg command to run on the remote side --remotecmd

aliases: out

parents [-r REV] [FILE]

Print the working directory's parent revisions. If a revision is given via --rev, the parent of that revision will be printed. If a file argument is given, revision in which the file was last changed (before the working directory revision or the argument to --rev if given) is printed.

options:

-r, --rev show parents from the specified rev

--style display using template map file

--template display with template

paths [NAME]

Show definition of symbolic path name NAME. If no name is given, show definition of available names.

Path names are defined in the [paths] section of /etc/mercurial/hgrc and \$HOME/.hgrc. If run inside a repository, .hg/hgrc is used, too.

pull [-u] [-f] [-r REV]... [-e CMD] [--remotecmd CMD] [SOURCE] Pull changes from a remote repository to a local one.

> This finds all changes from the repository at the specified path or URL and adds them to the local repository. By default, this does not update the copy of the project in the working directory.

Valid URLs are of the form:

local/filesystem/path (or file://local/filesystem/path)
http://[user@]host[:port]/[path]
https://[user@]host[:port]/[path]
ssh://[user@]host[:port]/[path]
static-http://host[:port]/[path]

Paths in the local filesystem can either point to Mercurial

repositories or to bundle files (as created by 'hg bundle' or 'hg incoming --bundle'). The static-http:// protocol, albeit slow, allows access to a Mercurial repository where you simply use a web server to publish the .hg directory as static content.

An optional identifier after # indicates a particular branch, tag, or changeset to pull.

Some notes about using SSH with Mercurial:

- SSH requires an accessible shell account on the destination machine and a copy of hg in the remote path or specified with as remotecmd.
- path is relative to the remote user's home directory by default.
- Use an extra slash at the start of a path to specify an absolute path: ssh://example.com//tmp/repository
- Mercurial doesn't use its own compression via SSH; the right thing to do is to configure it in your ~/.ssh/config, e.g.:

Host *.mylocalnetwork.example.com

Compression no

Host *

Compression yes

Alternatively specify "ssh -C" as your ssh command in your hgrc or with the --ssh command line option.

options:

-u, --update update to new tip if changesets were pulled

- -f, --force run even when remote repository is unrelated
- -r, --rev a specific revision up to which you would like to pull
- -e, --ssh specify ssh command to use

--remotecmd specify hg command to run on the remote side

push [-f] [-r REV]... [-e CMD] [--remotecmd CMD] [DEST] Push changes from the local repository to the given destination.

> This is the symmetrical operation for pull. It helps to move changes from the current repository to a different one. If the destination is local this is identical to a pull in that directory from the current one.

By default, push will refuse to run if it detects the result would increase the number of remote heads. This generally indicates the client has forgotten to pull and merge before pushing.

Valid URLs are of the form:

local/filesystem/path (or file://local/filesystem/path)
ssh://[user@]host[:port]/[path]
http://[user@]host[:port]/[path]
https://[user@]host[:port]/[path]

An optional identifier after # indicates a particular branch, tag, or changeset to push. If -r is used, the named changeset and all its ancestors will be pushed to the remote repository.

Look at the help text for the pull command for important details about ssh:// URLs.

Pushing to http:// and https:// URLs is only possible, if this feature is explicitly enabled on the remote Mercurial server.

options:

-f, --force force push

-r, --rev a specific revision up to which you would like to push

-e, --ssh specify ssh command to use

--remotecmd specify hg command to run on the remote side

recover

Recover from an interrupted commit or pull.

This command tries to fix the repository status after an interrupted operation. It should only be necessary when Mercurial suggests it.

remove [OPTION]... FILE...

Schedule the indicated files for removal from the repository.

This only removes files from the current branch, not from the entire project history. -A can be used to remove only files that have already been deleted, -f can be used to force deletion, and -Af can be used to remove files from the next revision without deleting them.

The following table details the behavior of remove for different file states (columns) and option combinations (rows). The file states are Added, Clean, Modified and Missing (as reported by hg status). The actions are Warn, Remove (from branch) and Delete (from disk).

ACM! noneWRDWR -fRRDRDR -AWWWR -AFRRR

This command schedules the files to be removed at the next commit. To undo a remove before that, see hg revert.

options:

-A, --after record delete for missing files

-f, --force remove (and delete) file even if added or modified

-I, --include include names matching the given patterns

-X, --exclude exclude names matching the given patterns

aliases: rm

rename [OPTION] ... SOURCE ... DEST

Mark dest as copies of sources; mark sources for deletion. If dest is a directory, copies are put in that directory. If dest is a file, there can only be one source.

By default, this command copies the contents of files as they stand in the working directory. If invoked with --after, the operation is recorded, but no copying is performed.

This command takes effect in the next commit. To undo a rename before that, see hg revert.

options:

-A, --after record a rename that has already occurred

-f, --force forcibly copy over an existing managed file

-I, --include include names matching the given patterns

-X, --exclude exclude names matching the given patterns

-n, --dry-run do not perform actions, just print output

aliases: mv

revert [OPTION]... [-r REV] [NAME]...

(use update -r to check out earlier revisions, revert does not change the working dir parents)

With no revision specified, revert the named files or directories to the contents they had in the parent of the working directory. This restores the contents of the affected files to an unmodified state and unschedules adds, removes, copies, and renames. If the working directory has two parents, you must explicitly specify the revision to revert to.

Using the -r option, revert the given files or directories to their contents as of a specific revision. This can be helpful to "roll back" some or all of an earlier change. See 'hg help dates' for a list of formats valid for -d/--date.

Revert modifies the working directory. It does not commit any changes, or change the parent of the working directory. If you revert to a revision other than the parent of the working directory, the reverted files will thus appear modified afterwards.

If a file has been deleted, it is restored. If the executable mode of a file was changed, it is reset.

If names are given, all files matching the names are reverted. If no arguments are given, no files are reverted.

Modified files are saved with a .orig suffix before reverting. To disable these backups, use --no-backup.

options:

-a, --all revert all changes when no arguments given

-d, --date tipmost revision matching date

-r, --rev revision to revert to

--no-backup do not save backup copies of files

-I, --include include names matching the given patterns

-X, --exclude exclude names matching the given patterns

-n, --dry-run do not perform actions, just print output

rollback

This command should be used with care. There is only one level of rollback, and there is no way to undo a rollback. It will also restore the dirstate at the time of the last transaction, losing any dirstate changes since that time.

Transactions are used to encapsulate the effects of all commands that create new changesets or propagate existing changesets into a repository. For example, the following commands are transactional, and their effects can be rolled back:

commit import pull push (with this repository as destination) unbundle

This command is not intended for use on public repositories. Once changes are visible for pull by other users, rolling a transaction back locally is ineffective (someone else may already have pulled the changes). Furthermore, a race is possible with readers of the repository; for example an in-progress pull from the repository may fail if a rollback is performed.

root

Print the root directory of the current repository.

serve [OPTION] ...

Start a local HTTP repository browser and pull server.

By default, the server logs accesses to stdout and errors to stderr. Use the "-A" and "-E" options to log to files.

options:

-A, --accesslog name of access log file to write to -d, --daemon run server in background --daemon-pipefds used internally by daemon mode -E, --errorlog name of error log file to write to -p, --port port to listen on (default: 8000) -a, --address address to listen on (default: all interfaces) --prefix prefix path to serve from (default: server root) name to show in web pages (default: working dir) -n, --name --webdir-conf name of the webdir config file (serve more than one repo) --pid-file name of file to write process ID to for remote clients --stdio -t, --templates web templates to use template style to use --style use IPv6 in addition to IPv4 -6, --ipv6 SSL certificate file --certificate

showconfig [-u] [NAME]...

With no args, print names and values of all config items.

With one arg of the form section.name, print just the value of that config item.

With multiple args, print names and values of all config items with matching section names.

options:

-u, --untrusted show untrusted configuration options

aliases: debugconfig

status [OPTION] ... [FILE] ...

Show status of files in the repository. If names are given, only files that match are shown. Files that are clean or ignored or source of a copy/move operation, are not listed unless -c (clean), -i (ignored), -C (copies) or -A is given. Unless options described with "show only ..." are given, the options -mardu are used.

Option -q/--quiet hides untracked (unknown and ignored) files unless explicitly requested with -u/--unknown or -i/-ignored.

NOTE: status may appear to disagree with diff if permissions have changed or a merge has occurred. The standard diff format does not report permission changes and diff only reports changes relative to one merge parent.

If one revision is given, it is used as the base revision. If two revisions are given, the difference between them is shown.

The codes used to show the status of files are:

M = modified

- A = added
- $R\,=\,removed$
- C = clean

! = deleted, but still tracked

- ? = not tracked
- I = ignored
- = the previous added file was copied from here

options:

show status of all files -A, --all -m, --modified show only modified files -a, --added show only added files -r, --removed show only removed files -d, --deleted show only deleted (but tracked) files show only files without changes -c. --clean -u, --unknown show only unknown (not tracked) files -i, --ignored show only ignored files -n, --no-status hide status prefix -C, --copies show source of copied files -0, --print0 end filenames with NUL, for use with xargs show difference from revision --rev -I, --include include names matching the given patterns -X, --exclude exclude names matching the given patterns

aliases: st

```
tag [-I] [-m TEXT] [-d DATE] [-u USER] [-r REV] NAME...
Name a particular revision using <name>.
```

Tags are used to name particular revisions of the repository and are very useful to compare different revisions, to go back to significant earlier versions or to mark branch points as releases, etc.

If no revision is given, the parent of the working directory is used, or tip if no revision is checked out.

To facilitate version control, distribution, and merging of tags, they are stored as a file named ".hgtags" which is managed similarly to other project files and can be hand-edited if necessary. The file '.hg/localtags' is used for local tags (not shared among repositories).

See 'hg help dates' for a list of formats valid for -d/--date.

options:

-f,force	replace existing tag	
-I,Iocal	make the tag local	
-r,rev	revision to tag	
remove	remove a tag	
-m,message use <text> as commit message</text>		
-d,date	record datecode as commit date	
-u,user	record user as committer	

tags

List the repository tags.

This lists both regular and local tags. When the -v/--verbose switch is used, a third column "local" is printed for local tags.

tip [-p]

The tip revision (usually just called the tip) is the most recently added changeset in the repository, the most recently changed head.

If you have just made a commit, that commit will be the tip. If you have just pulled changes from another repository, the tip of that repository becomes the current tip. The "tip" tag is special and cannot be renamed or assigned to a different changeset.

options:

-p, --patch show patch

--style display using template map file

--template display with template

unbundle [-u] FILE...

Apply one or more compressed changegroup files generated by the bundle command.

options:

-u, --update update to new tip if changesets were unbundled

update [-C] [-d DATE] [[-r] REV]

Update the working directory to the specified revision, or the tip of the current branch if none is specified.

If the requested revision is a descendant of the working directory, any outstanding changes in the working directory will be merged into the result. If it is not directly descended but is on the same named branch, update aborts with a suggestion to use merge or update -C instead.

If the requested revision is on a different named branch and the working directory is clean, update quietly switches branches.

If you want to update just one file to an older revision, use revert.

See 'hg help dates' for a list of formats valid for --date.

options:

-C, --clean overwrite locally modified files -d, --date tipmost revision matching date -r, --rev revision

aliases: up checkout co

verify

Verify the integrity of the current repository.

This will perform an extensive check of the repository's integrity, validating the hashes and checksums of each entry in the changelog, manifest, and tracked files, as well as the integrity of their crosslinks and indices.

version

output version and copyright information

DATE FORMATS

Some commands allow the user to specify a date: backout, commit, import, tag: Specify the commit date. log, revert, update: Select revision(s) by date.

Many date formats are valid. Here are some examples:

"Wed Dec 6 13:18:29 2006" (local timezone assumed) "Dec 6 13:18 -0600" (year assumed, time offset provided) "Dec 6 13:18 UTC" (UTC and GMT are aliases for +0000) "Dec 6" (midnight) "13:18" (today assumed) "3:39" (3:39AM assumed) "3:39pm" (15:39) "2006-12-6 13:18:29" (ISO 8601 format) "2006-12-6 13:18" "2006-12-6" "12-6" "12/6" (Dec 6 2006)

Lastly, there is Mercurial's internal format:

"1165432709 0" (Wed Dec 6 13:18:29 2006 UTC)

This is the internal representation format for dates. unixtime is the number of seconds since the epoch (1970-01-01 00:00 UTC). offset is the offset of the local timezone, in seconds west of UTC (negative if the timezone is east of UTC).

The log command also accepts date ranges:

"<{date}" - on or before a given date
">{date}" - on or after a given date
"{date} to {date}" - a date range, inclusive
"-{days}" - within a given number of days of today

FILE PATTERNS

Mercurial accepts several notations for identifying one or more files at a time.

By default, Mercurial treats filenames as shell-style extended glob patterns.

Alternate pattern notations must be specified explicitly.

To use a plain path name without any pattern matching, start a name with "path:". These path names must match completely, from the root of the current repository.

To use an extended glob, start a name with "glob:". Globs are rooted at the current directory; a glob such as "*.c" will match files ending in ".c" in the current directory only.

The supported glob syntax extensions are "**" to match any string across path separators, and "{a,b}" to mean "a or b".

To use a Perl/Python regular expression, start a name with "re:". Regexp pattern matching is anchored at the root of the repository.

Plain examples:

path:foo/bar a name bar in a directory named foo in the root of the repository path:path:name a file or directory named "path:name"

Glob examples:

glob:*.c	any name ending in ".c" in the current directory
*.c	any name ending in ".c" in the current directory
**.C	any name ending in ".c" in the current directory, or
	any subdirectory
foo/*.c	any name ending in ".c" in the directory foo
foo/**.c	any name ending in ".c" in the directory foo, or any
	subdirectory

Regexp examples:

re:.*\.c\$ any name ending in ".c", anywhere in the repository

ENVIRONMENT VARIABLES

НG

Path to the hg executable, automatically passed when running hooks, extensions or external tools. If unset or empty, an executable named hg (with com/exe/bat/cmd extension on Windows) is searched.

HGEDITOR

This is the name of the editor to use when committing. See EDITOR.

(deprecated, use .hgrc)

HGENCODING

This overrides the default locale setting detected by Mercurial. This setting is used to convert data including usernames, changeset descriptions, tag names, and branches. This setting can be overridden with the --encoding command-line option.

HGENCODINGMODE

This sets Mercurial's behavior for handling unknown characters while transcoding user inputs. The default is "strict", which causes Mercurial to abort if it can't translate a character. Other settings include "replace", which replaces unknown characters, and "ignore", which drops them. This setting can be overridden with the --encodingmode command-line option.

HGMERGE

An executable to use for resolving merge conflicts. The program will be executed with three arguments: local file, remote file, ancestor file.

(deprecated, use .hgrc)

HGRCPATH

A list of files or directories to search for hgrc files. Item separator is ":" on Unix, ";" on Windows. If HGRCPATH is not set, platform default search path is used. If empty, only .hg/hgrc of current repository is read.

For each element in path, if a directory, all entries in directory ending with ".rc" are added to path. Else, element itself is added to path.

HGUSER

This is the string used for the author of a commit.

(deprecated, use .hgrc)

EMAIL

If HGUSER is not set, this will be used as the author for a commit.

LOGNAME

If neither HGUSER nor EMAIL is set, LOGNAME will be used (with *@hostname* appended) as the author value for a commit.

VISUAL

This is the name of the editor to use when committing. See EDITOR.

EDITOR

Sometimes Mercurial needs to open a text file in an editor for a user to modify, for example

when writing commit messages. The editor it uses is determined by looking at the environment variables HGEDITOR, VISUAL and EDITOR, in that order. The first non-empty one is chosen. If all of them are empty, the editor defaults to *vi*.

PYTHONPATH

This is used by Python to find imported modules and may need to be set appropriately if Mercurial is not installed system-wide.

SPECIFYING SINGLE REVISIONS

Mercurial accepts several notations for identifying individual revisions.

A plain integer is treated as a revision number. Negative integers are treated as offsets from the tip, with -1 denoting the tip.

A 40-digit hexadecimal string is treated as a unique revision identifier.

A hexadecimal string less than 40 characters long is treated as a unique revision identifier, and referred to as a short-form identifier. A short-form identifier is only valid if it is the prefix of one full-length identifier.

Any other string is treated as a tag name, which is a symbolic name associated with a revision identifier. Tag names may not contain the ":" character.

The reserved name "tip" is a special tag that always identifies the most recent revision.

The reserved name "null" indicates the null revision. This is the revision of an empty repository, and the parent of revision 0.

The reserved name "." indicates the working directory parent. If no working directory is checked out, it is equivalent to null. If an uncommitted merge is in progress, "." is the revision of the first parent.

SPECIFYING MULTIPLE REVISIONS

When Mercurial accepts more than one revision, they may be specified individually, or provided as a continuous range, separated by the ":" character.

The syntax of range notation is [BEGIN]:[END], where BEGIN and END are revision identifiers. Both BEGIN and END are optional. If BEGIN is not specified, it defaults to revision number 0. If END is not specified, it defaults to the tip. The range ":" thus means "all revisions".

If BEGIN is greater than END, revisions are treated in reverse order.

A range acts as a closed interval. This means that a range of 3:5 gives 3, 4 and 5. Similarly, a range of 4:2 gives 4, 3, and 2.

FILES

This file contains regular expressions (one per line) that describe file names that should be ignored by hg. For details, see hgignore(5).

This file contains changeset hash values and text tag names (one of each separated by spaces) that correspond to tagged versions of the repository contents.

/etc/mercurial/hgrc, \$HOME/.hgrc, .hg/hgrc

This file contains defaults and configuration. Values in .hg/hgrc override those in \$HOME/.hgrc, and these override settings made in the global /etc/mercurial/hgrc configuration. See hgrc(5) for details of the contents and format of these files.

Some commands (e.g. revert) produce backup files ending in .orig, if the .orig file already exists and is not tracked by Mercurial, it will be overwritten.

BUGS

Probably lots, please post them to the mailing list (See Resources below) when you find them.

SEE ALSO

hgignore(8), hgrc(8).

AUTHOR

Written by Matt Mackall <mpm@selenic.com>

RESOURCES

Main Web Site[1]

Source code repository[2]

Mailing list[3]

COPYING

Copyright (C) 2005-2007 Matt Mackall. Free use of this software is granted under the terms of the GNU General Public License (GPL).

NOTES

- 1. Main Web Site http://selenic.com/mercurial
- 2. Source code repository http://selenic.com/hg
- 3. Mailing list http://selenic.com/mailman/listinfo/mercurial

hget, hpost, webpaste, urlencode - retrieve, post to a web page corresponding to a url

SYNOPSIS

hget[-1 | -o file][-p body | -P][-r header][-m method][-b baseurl]url

 $\begin{array}{l} hpost [-1] [-g \ action \ | \ -p \ action \ | \ -m \ action \] [\ -r \ header \] [\ -u \] \ url \ [\ name:value \ | \ name@file \] \ ... \end{array}$

webpaste [file]

urlencode [-d] [file]

DESCRIPTION

Hget retrieves the web page specified by the URL *url* and writes it, absent the -1 and -0 options, to standard output.

The *url* can be a relative path like .../index.html if a absolute *baseurl* was specified with the -b option.

If *url* is of type HTTP and the -p or -P options are specified, then a HTTP POST is performed. With -p the data to be posted is provided by the *body* argument as a string or alternatively with -P read from standard input.

The -1 option causes *hget* and *hpost* to print the location URL from the transaction response instead of retrieving the body data. This is useful for HTTP POST transactions that redirect to a URL containing the posted data so we wont refetch the data we just uploaded to the site.

The -o option is used to keep a local file in sync with a web page. If the web page has been modified later than the file, it is copied into the file. If the file is up to date but incomplete, *hget* will fetch the missing bytes.

Option -r sends an arbitrary HTTP *header*. The -r flag can be repeated to send multiple headers.

Option –m overrides the HTTP method used for the request.

Hpost retrieves the web page specified by the URL *url*, parses its HTML for form data, then prints rc(1) commands to submit the forms with default field values. If an *action* URL is provided with the -g, -p or -m flags, then *hget* is invoked to execute the transaction submitting the form data.

The -g and -p flags set the form method to GET and POST, respectively. The -m flag sets the form method to POST and its enctype to multipart/form-data. In all cases, the target relative form action URL is set to *action*.

The -u flag sets the target URL to *url*. As the *url* parameter is always required, the -u flag can be omitted when *url* follows directly after the last option if any.

The remaining arguments of the form name:value are interpreted as text form field names and values to be submitted. An argument of the form name@file is interpreted as a file upload, with the information following the @ symbol treated as the file name. For multipart/form-data uploads (see -m flag), the file has to be seekable as *file*(1) is invoked to determine its mime type.

Webpaste uploads the contents either of its standard input or *file* to the pastebin website http://okturing.com and then prints a URL where the contents may be retrieved.

Urlencode is a helper program to URL encode and decode files. The -d flag, instead of encode, decodes URL encoded file. If no *file* is given, standard input is read. The resulting data is written to standard output.

EXAMPLES

Download a file from the web.

% hget http://9front.org/img/nix-on.jpg >/tmp/nix-on.jpg

Retrieve the commands needed to submit a form, which may then be edited and sent.

% hpost http://p.intma.in hpost -u http://p.intma.in -p paste.cgi text:

Manually specify fields to be sent to a given url.

% hpost -u http://p.intma.in -p paste.cgi text:'test post' Upload a file, print the resulting URL

% hpost -l http://i.intma.in file@/tmp/screen.png | rc Upload the output of ns(1) to http://okturing.com

% ns | webpaste

SOURCE

/rc/bin/hget
/rc/bin/hpost
/rc/bin/webpaste
/sys/src/cmd/urlencode.c

SEE ALSO

webfs(4), ftpfs(4), file(1)

DIAGNOSTICS

Hget, *hpost* and *webpaste* require *webfs*(4) service mounted on /mnt/web to work.

HISTORY

Hget first appeared in Plan 9 from Bell Labs. It was rewritten as an *rc* script for 9front (January, 2012). *Hpost* and *urlencode* first appeared in 9front (October, 2012). *Webpaste* first appeared in 9front (September, 2013).

history - print file names from the dump

SYNOPSIS

history [-Dabcemnw] [-fuv] [-d dumpfilesystem] [-s yyyymmdd] files ...

DESCRIPTION

History prints the names, dates, and sizes, and modifier of all versions of the named *files*, looking backwards in time, stored in the dump file system. If the file exists in the main tree, the first line of output will be its current state. For example,

history /adm/users

produces

```
May 14 15:29:18 EDT 2001 /adm/users 10083 [adm]
May 14 15:29:18 EDT 2001 /n/dump/2001/0515/adm/users 10083 [adm]
May 11 17:26:24 EDT 2001 /n/dump/2001/0514/adm/users 10481 [adm]
May 10 16:40:51 EDT 2001 /n/dump/2001/0511/adm/users 10476 [adm]
```

When presented with a path of the form /n/fs/path, *history* will use *fsdump* as the name of the dump file system, and will print a history of *path*.

The -v option enables verbose debugging printout.

The -D option causes diff(1) to be run for each adjacent pair of dump files. The options -abcemnw are passed through to diff; the little-used diff option -f is replaced by the functionality described below, and the -r option is disallowed.

The -u option causes times to be printed in GMT (UT) rather than local time.

The -d option selects some other dump file system such as */n/bootesdump*.

The -f option forces the search to continue even when the file in question does not exist (useful for files that only exist intermittently).

Finally, the -s option sets the starting (most recent) date for the output.

EXAMPLES

Check how often a user has been logged in.

history /usr/ches/tmp

FILES

/n/dump

SOURCE

/sys/src/cmd/history.c

SEE ALSO

fs(4) yesterday(1)

hoc - interactive floating point language

SYNOPSIS

hoc [-e expression] [file ...]

DESCRIPTION

Hoc interprets a simple language for floating point arithmetic, at about the level of BASIC, with C-like syntax and functions.

The named *files* are read and interpreted in order. If no *file* is given or if *file* is -hoc interprets the standard input. The -e option allows input to *hoc* to be specified on the command line, to be treated as if it appeared in a file.

Hoc input consists of *expressions* and *statements*. Expressions are evaluated and their results printed. Statements, typically assignments and function or procedure definitions, produce no output unless they explicitly call *print*.

Variable names have the usual syntax, including _; the name _ by itself contains the value of the last expression evaluated. The variables E, PI, PHI, GAMMA and DEG are predefined; the last is 59.25..., degrees per radian.

Expressions are formed with these C-like operators, listed by decreasing precedence.

```
    exponentiation
! - ++ --
* / %
+ -
> >= < <= == !=
&&
|
|
= += -= *= /= %=</pre>
```

Built in functions are abs, acos, asin, atan (one argument), cos, cosh, exp, int, log, log10, sin, sinh, sqrt, tan, and tanh. The function read(x) reads a value into the variable x and returns 0 at EOF; the statement print prints a list of expressions that may include string constants such as "hello\n".

Control flow statements are if-else, while, and for, with braces for grouping. Newline ends a statement. Backslash-newline is equivalent to a space.

Functions and procedures are introduced by the words func and proc; return is used to return with a value from a function.

EXAMPLES

```
func gcd(a, b) {
    temp = abs(a) % abs(b)
    if(temp == 0) return abs(b)
    return gcd(b, temp)
}
for(i=1; i<12; i++) print gcd(i,12)</pre>
```

SOURCE

/sys/src/cmd/hoc

SEE ALSO

bc(1), dc(1)

B. W. Kernighan and R. Pike, The Unix Programming Environment, Prentice-Hall, 1984

BUGS

Error recovery is imperfect within function and procedure definitions.

hold – simple text editor

SYNOPSIS

hold file

DESCRIPTION

Hold sets hold mode on the *rio*(1) window where it was launched. The contents of the named file is printed above the live editing area and the newly entered text is saved in the named file upon exit.

SOURCE

/rc/bin/hold

SEE ALSO

emacs(1), rio(1)

HISTORY

Hold first appeared in 9front (May, 2011).

htmlroff - HTML formatting and typesetting

SYNOPSIS

htmlroff[-iuv][-m name][-r aN][file ...]

DESCRIPTION

Htmlroff accepts *troff*(1) input in the named *files* and formats it as HTML for viewing in a web browser.

If no *file* argument is given, *htmlroff* reads the standard input. An argument consisting of a single minus (-) is taken to be a file name corresponding to the standard input. The options are:

-i Read standard input after the input files are exhausted.

-m*name*

Process the macro file /sys/lib/tmac/tmac. name before the input files.

-raN Set register *a* (one character name) to *N*.

- -u Generate UTF output. By default, *htmlroff* converts Unicode runes into the corresponding HTML entity sequences (α, , and so on). *Htmlroff* invokes *tcs*(1) for the conversion.
- -v Generate debugging output and warnings about suspicious input.

Most *troff* input files, especially those using the ms(6) macros, can be used unaltered. In general, the macro file tmac.html should be processed after processing other standard macro files, as in htmlroff -ms -mhtml.

Htmlroff(6) describes the changes to the input language.

Mhtml(6) describes the new macros.

EXAMPLES

Format the Plan 9 web page:

cd /usr/web/plan9
htmlroff -mhtml index.tr >index.html

Format a paper:

cd /sys/doc pic auth.ms | tbl | eqn | htmlroff –ms –mhtml >auth.html

FILES

/sys/lib/troff/font/devutf/utfmap

Mapping from *troff* two-character names like \backslash (*a to Unicode characters like α .

SOURCE

/sys/src/cmd/htmlroff

SEE ALSO

tcs(1), troff(1), htmlroff(6), mhtml(6)

idiff - interactive diff

SYNOPSIS

idiff[-bw]file1 file2

DESCRIPTION

ldiff interactively merges *file1* and *file2* onto standard output. Wherever *file1* and *file2* differ, *idiff* displays the differences in the style of "diff -n" on standard error and prompts the user to select a chunk. Valid responses are:

- < Use the chunk from *file1*.
- > Use the chunk from *file2*.
- = Use the diff output itself.

q<, q>, q=

Use the given response for all future questions.

! cmd Execute cmd and prompt again.

ldiff invokes diff(1) to compare the files. The -b and -w flags, if passed, are passed to *diff*.

FILES

/tmp/idiff.*

SOURCE

/sys/src/cmd/idiff.c

SEE ALSO

diff(1)

Kernighan and Pike, The Unix Programming Environment, Prentice-Hall, 1984.

io – access PC I/O registers

SYNOPSIS

io [-WLMErw] address [value]

DESCRIPTION

io accesses PC I/O space. The operation to be performed is selected with -r or -w for reading or writing, respectively. The default operation size is a byte. C style notation for integers (e.g. 0x42 or 023) is accepted for the *address* and *value* parameters.

- -W Perform a word (16 bit) operation.
- -L Perform a long / double word (32 bit) operation.
- -M Access a 64 bit wide machine specific register (MSR).
- -E Access embedded controller space.

SOURCE

/sys/src/cmd/io.c

SEE ALSO

seg(1), *arch*(3)

HISTORY

Io first appeared in 9front (April, 2011).

ircrc – internet relay chat client

SYNOPSIS

ircrc[-p port][-P server password][-r realname][-t target][-n nick][-T][server]

DESCRIPTION

Ircrc is an IRC client. Messages are sent from standard input and received from standard output. The default server is irc.freenode.net. The arguments bitlbee and oftc are expanded to im.bitlbee.org and irc.oftc.net, respectively. The options are:

–p port

Change the default port (6667).

-P server password

Specify a password for the remote server.

–r realname

Change the default name (<nil>).

-t target

Set and join the target channel. If multiple channels are specified, only the last one will be set as *target*. Messages are sent to *target* unless they are commands.

–n nick

Change the default nickname (\$user).

-T

Use tls through *tlssrv*(8).

Commands

Ircrc commands begin with a slash. Unrecognized commands result in an error message and send nothing to the server. The commands are:

/! cmd

Send the output of the shell command *cmd* to the current target.

- /M MODE command.
- /N NOTICE command.
- /T TOPIC command.
- /W WHOIS command.
- /a AWAY command.
- /j JOIN command.
- /l LIST command.
- /m PRIVMSG command.
- /n NICK command.
- /p PART command.

```
/q cmd
```

Send the raw IRC command *cmd* to the server.

/t target

Set target. If target is more than one channel, any messages are sent to all of them.

- /u USERS command.
- /w WHO command.
- /x QUIT command. Control-D also sends this command.

See RFC 1459 and RFC 2812 for detailed information about IRC commands.

EXAMPLES

Default usage:

% ircrc Join irc.oftc.net as a different user: % ircrc -r glenda -n glenda irc.oftc.net Join two channels on login: % ircrc -t '#cat-v,#plan9' SOURCE

/rc/bin/ircrc

SEE ALSO

http://tools.ietf.org/html/rfc1459
http://tools.ietf.org/html/rfc2812

BUGS

Some fonts do not support the nickname delimiters.

If the connection is lost, *ircrc* waits for input before exiting.

join – relational database operator

SYNOPSIS

join [options] file1 file2

DESCRIPTION

Join forms, on the standard output, a join of the two relations specified by the lines of *file1* and *file2*. If one of the file names is -, the standard input is used.

File1 and *file2* must be sorted in increasing ASCII collating sequence on the fields on which they are to be joined, normally the first in each line.

There is one line in the output for each pair of lines in *file1* and *file2* that have identical join fields. The output line normally consists of the common field, then the rest of the line from *file1*, then the rest of the line from *file2*.

Input fields are normally separated spaces or tabs; output fields by space. In this case, multiple separators count as one, and leading separators are discarded.

The following options are recognized, with POSIX syntax.

- -a n In addition to the normal output, produce a line for each unpairable line in file n, where n is 1 or 2.
- -v n Like -a, omitting output for paired lines.
- -e *s* Replace empty output fields by string *s*.
- -1 m
- -2 m Join on the *m*th field of *file1* or *file2*.
- -j*n m*

Archaic equivalent for -n m.

–o fields

Each output line comprises the designated fields. The comma-separated field designators are either 0, meaning the join field, or have the form n.m, where n is a file number and m is a field number. Archaic usage allows separate arguments for field designators.

-tc Use character c as the only separator (tab character) on input and output. Every appearance of c in a line is significant.

EXAMPLES

sort -t: +1 /adm/users | join -t: -1 2 -a 1 -e "" - bdays Add birthdays to the /adm/users file, leaving unknown birthdays empty. The layout of /adm/users is given in users(6); bdays contains sorted lines like ken:Feb 4, 1953.

tr : ' </adm/users | sort -k 3 3 >temp join -1 3 -2 3 -0 1.1,2.1 temp temp | awk '1 < 2'Print all pairs of users with identical userids.

SOURCE

/sys/src/cmd/join.c

SEE ALSO

sort(1), *comm*(1), *awk*(1)

BUGS

With default field separation, the collating sequence is that of sort -b - ky, y; with -t, the sequence is that of sort -tx - ky, y.

One of the files must be randomly accessible.

jpg, gif, png, tif, ppm, bmp, v210, yuv, ico, tga, tojpg, togeordi, togif, toppm, topng, totif, toico - view and convert pictures

SYNOPSIS

```
jpg[-39cdefFkJrtvy][file...]
gif[-39cdektv][file...]
png [ -39cdektv ] [ file ... ]
tif [-39cdektv][file...]
ppm [-39cdektv] [ file ... ]
bmp [ -39cdektv ] [ file ... ]
v210 [-39cdektv] [ file ... ]
tga [ -39cdektv ] [ file ... ]
yuv [ -39cdektv ] [ file ... ]
tojpg [-c comment] [-ks] [file]
togeordi [-c comment][-k][file]
togif [-c comment] [-1 loopcount] [-d msec] [-t transindex] [file ... [-d msec] file ... |
-E1
toppm [ -c comment ] [ -r ] [ file ]
topng [-c comment] [-g gamma] [ file ]
totif[-c comment][-3bgGhklLptvyY][file]
ico[-c][file]
toico[file...]
```

DESCRIPTION

These programs read, display, and write image files in public formats. *Jpg*, *gif*, *png*, *tif*, *ppm*, *bmp*, *tga*, *v210*, and *yuv* read files in the corresponding formats and, by default, display them in the current window; options cause them instead to convert the images to Plan 9 image format and write them to standard output. *Tojpg*, *togif*, *toppm*, *topng*, and *totif* read Plan 9 images files, convert them to JPEG, GIF, PPM, PNG, or TIFF and write them to standard output.

The default behavior of *jpg*, *gif*, *png*, *tif*, *ppm*, *bmp*, *tga*, *v210*, and *yuv* is to display the *file*, or standard input if no file is named. Once a file is displayed, typing a character causes the program to display the next image. Typing a q, DEL, or control-D exits the program. For a more user-friendly interface, use *page*(1), which invokes these programs to convert the images to standard format, displays them, and offers scrolling, panning, and menu-driven navigation among the files.

These programs share many options:

- -e Disable Floyd-Steinberg error diffusion, which is used to improve the appearance of images on color-mapped displays, typically with 8 bits per pixel. Primarily useful for debugging; if the display has true RGB color, the image will be displayed in full glory.
- -k Convert and display the image as a black and white (really grey-scale) image.
- -v Convert the image to an RGBV color-mapped image, even if the display has true RGB color.
- -d Suppress display of the image; this is set automatically by any of the following options:
- -c Convert the image to a Plan 9 representation, as defined by *image*(6), and write it to standard output.
- -9 Like -c, but produce an uncompressed image. This saves processing time, particularly when the output is being piped to another program such as page(1), since it avoids compression and decompression.
- -t Convert the image, if it is in color, to a true color RGB image.
- -3 Like -t, but force the image to RGB even if it is originally grey-scale.

Jpg has two extra options used to process the output of the LML video card:

-f Merge two adjacent images, which represent the two fields of a video picture, into a single image.

-F The input is a motion JPEG file, with multiple images representing frames of the movie. Sets -f.

The *tojpg*, *togif*, *toppm* and *topng* programs go the other way: they convert from Plan 9 images to JPEG, GIF, PPM, PNG, and TIFF and have no display capability. They all accept an option -c to set the comment field of the resulting file. The -r option makes *toppm* output raw PPM. The default is to output plain PPM. The -k option makes *tojpg* output grey-scale images, and the -s option makes it output scratched JPEG images. *Togeordi* is an *rc*(1) script that invokes tojpg -s. *Totif* accepts many options. Choosing Huffman, T4, or T6 compression forces the image to GREY1.

- -3 Convert the image to a true color RGB image.
- -b Convert the image to a GREY1 black and white image.
- -g Use T4 one-dimensional compression.
- -G Use T4 two-dimensional compression.
- -h Use Huffman compression.
- -k Convert the image to a GREY8 grey-scale image.
- -1 Use LZW compression.
- -L Use LZW compression with horizontal differencing. Some TIFF decoders may not support horizontal differencing applied to images of depths less than eight.
- -p Use Packbits compression.
- -t Use T6 compression.
- -v Convert the image to an RGBV color-mapped image.
- -y Convert the image to a GREY2 grey-scale image. *Totif* will then convert it to GREY4 before encoding because TIFF does not support depths of two.
- -Y Convert the image to a GREY4 grey-scale image.

If there is only one input picture, *togif* converts the image to GIF format. If there are many *files*, though, it will assemble them into an animated GIF file. The options control this process:

-1loopcount

By default, the animation will loop forever; *loopcount* specifies how many times to loop. A value of zero means loop forever and a negative value means to stop after playing the sequence once.

```
–d msec
```

By default, the images are displayed as fast as they can be rendered. This option specifies the time, in milliseconds, to pause while displaying the next named *file*.

-E Specifying this option instead of a list of files will read the frames from a pipe on fd 0. Each frame is terminated with EOF. End of the animation is specified by an extra EOF.

Gif translates files that contain a 'transparency' index by attaching an alpha channel to the converted image.

Ico displays or converts a Windows icon (.ico) file. If no file is specified, *ico* reads from standard input. Icon files contain sets of icons represented by an image and a mask. The -c option causes *ico* to convert the first icon in the set and write it to standard output in compressed Plan 9 image format. Otherwise, the whole icon set is displayed. Clicking the right button pops up a menu that lets you write any icon's image as a Plan 9 image (*widthxheight.image*), write any icon's mask as a Plan 9 image (*widthxheight.mask*), or exit. Selecting one of the write menu items yields a sight cursor. Move the sight over the icon and right click again to write.

Toico takes a list of Plan 9 image files (or standard input) and creates a single icon file. The masks in the icon file will be the white space in the image. The icon file is written to standard output.

SOURCE

/sys/src/cmd/jpg /rc/bin/togeordi

SEE ALSO

page(1), image(6).

http://www.w3.org/Graphics/JPEG/jfif3.pdf http://www.w3.org/Graphics/JPEG/itu-t81.pdf http://en.wikibooks.org/wiki/JPEG_-_Idea_and_Practice http://en.wikipedia.org/wiki/JPEG http://www.w3.org/Graphics/GIF/spec-gif89a.txt http://www.w3.org/TR/2003/REC-PNG-20031110 http://partners.adobe.com/public/developer/en/tiff/TIFF6.pdf http://netpbm.sourceforge.net/doc/ppm.html http://en.wikipedia.org/wiki/Windows_bitmap http://en.wikipedia.org/wiki/Yuv

BUGS

Writing an animated GIF using *togif* is a clumsy undertaking.

HISTORY

Tojpg first appeared in 9front (May, 2013). Tif and totif first appeared in 9front (July, 2013).

kbmap - show a list of available keyboard maps and switch between them.

SYNOPSIS

kbmap [file...]

DESCRIPTION

Kbmap shows a single column consisting of the names of keyboard maps for different alphabets available on the system. With no arguments kbmap will look for files in /sys/lib/kbmap.

Clicking the right mouse button will highlight the entry and force the keyboard mapping defined in the corresponding file to become current for the system; typing 'q' quits.

Kbmap requires that the file /dev/kbmap served by *kbdfs*(8) exists and is writable.

SOURCE

/sys/src/cmd/kbmap.c

SEE ALSO

kbdfs(8)

BUGS

Not all keyboards map the entire set of characters, so one has to switch back to the default map before changing to another.

kill, slay, broke, dontkill - print commands to kill processes

SYNOPSIS

kill name ...

slay *name* ...

broke [user]

dontkill regexp

DESCRIPTION

Kill prints commands that will cause all processes called *name* and owned by the current user to be terminated. Use the send command of rio(1), or pipe the output of *kill* into rc(1) to execute the commands.

Kill suggests sending a kill note to the process; the same message delivered to the process's ctl file (see *proc*(3)) is a surer, if heavy handed, kill, but is necessary if the offending process is ignoring notes. The *slay* command prints commands to do this.

Broke prints commands that will cause all processes in the *Broken* state and owned by *user* (by default, the current user) to go away. When a process dies because of an error caught by the system, it may linger in the *Broken* state to allow examination with a debugger. Executing the commands printed by *broke* lets the system reclaim the resources used by the broken processes.

Dontkill flags processes matching the program name *regexp* as not to be killed in the event of memory exhaustion. This is usually run from termrc and cpurc (see *cpurc*(8)) to protect important system processes from getting killed.

SOURCE

/rc/bin/kill /rc/bin/broke /rc/bin/dontkill

SEE ALSO

ps(1), stop(1), notify(2), proc(3)

ktrace – interpret kernel stack dumps

SYNOPSIS

ktrace [-i] kernel pc sp [link]

DESCRIPTION

Ktrace translates a hexadecimal kernel stack dump into a sequence of acid(1) commands to show the points in the call trace. The *kernel* argument should be the path of the kernel being debugged, and *pc* and *sp* are the PC and SP values given in the stack dump. For MIPS kernels, the contents of the *link* register must also be supplied.

A stack trace consists of a *ktrace* command followed by a series of lines containing fields of the form *location=contents*:

ktrace /kernel/path 80105bc1 8048e174 8048e114=80105ac6 8048e120=80140bb4 8048e134=8010031c 8048e16c=80137e45 8048e170=80105bc1 8048e178=80137e62

. . .

The trace can be edited to provide the correct kernel path and then pasted into a shell window. If the -i option is present, *ktrace* instead prompts for the contents of the memory locations in which it is interested; this is useful when the stack trace is on a screen rather than in a machine readable form.

SOURCE

/sys/src/cmd/ktrace.c

SEE ALSO

acid(1), rdbfs(4)

BUGS

When examining a kernel trace resulting from an interrupt on top of other interrupts, only the topmost call trace is printed.

leak, kmem, umem - help find memory leaks

SYNOPSIS

leak [-abcds] [-f binary] [-r res] [-x width] pid ...

kmem [kernel]

umem pid [textfile]

DESCRIPTION

Leak examines the named processes, which should be sharing their data and bss segments, for memory leaks. It uses a mark and sweep-style algorithm to determine which allocated blocks are no longer reachable from the set of root pointers. The set of root pointers is created by looking through the shared bss segment as well as each process's registers.

Unless directed otherwise, *leak* prints, for each block, a line with seven space-separated fields: the string block, the address of the block, the size of the block, the first two words of the block, and the function names represented by the first two words of the block. Usually, the first two words of the block contain the malloc and realloc tags (see *malloc*(2)), useful for finding who allocated the leaked blocks.

If the -s or the -c option is given, *leak* will instead present a sequence of acid(1) commands that show each leaky allocation site. With -s a comment appears next to each command to indicate how many lost blocks were allocated at that point in the program. With -c the comments are extended to indicate also the total number of bytes lost at that point in the program, and an additional comment line gives the overall total number of bytes.

If the -a option is given, *leak* will print information as decribed above, but for all allocated blocks, not only leaked ones. If the -d option is given, *leak* will print information as decribed above, but for all free blocks, i.e. those freed, or those that are not yet in use (fragmentation?). The -a and -d options can be combined.

If the -b option is given, *leak* will print a Plan 9 image file graphically summarizing the memory arenas. In the image, each pixel represents *res* (default 8) bytes. The color code is:

- dark blue Completely allocated.
- bright blue Contains malloc headers.
- *bright red* Contains malloc headers for leaked memory.
- dark red Contains leaked memory.
- *yellow* Completely free
- *white* Padding to fill out the image. The bright pixels representing headers help in counting the number of blocks. Magnifying the images with *lens*(1) is often useful.

If given a name rather than a list of process ids, *leak* echoes back a command-line with process ids of every process with that name.

The -f option specifies a binary to go on the *acid*(1) command-line used to inspect the processes, and is only necessary when inspecting processes started from stripped binaries.

Umem prints a summary of all allocated blocks in the process with id *pid*. Each line of the summary gives the count and total size of blocks allocated at an allocation point. The list is sorted by count in decreasing order. *Umem* prints summarizes all allocations, not just memory leaks, but it is faster and requires less memory than *leak*.

Kmem is like umem but prints a summary for the running kernel.

EXAMPLES

List lost blocks in 8.out. This depends on the fact that there is only one instance of 8.out running; if there were more, the output of leak -s 8.out would need editing before sending to the shell.

% leak -s 8.out leak -s 229 230 % leak -s 8.out | rc

```
src(0x0000bf1b); // 64
src(0x000016f5); // 7
src(0x0000a988); // 7
%
```

View the memory usage graphic for the window system.

% leak -b rio | rc | page

List the top allocation points in the kernel, first by count and then by total size:

% kmem | sed 10q % kmem | sort -nr +1 | sed 10q

SOURCE

```
/sys/lib/acid/leak
/sys/src/cmd/aux/acidleak.c
/rc/bin/leak
/rc/bin/kmem
/rc/bin/umem
```

SEE ALSO

getcallerpc(2), setmalloctag in malloc(2)

BUGS

Leak and *kmem* depend on the internal structure of the libc pool memory allocator (see *pool*(2)). Since the ANSI/POSIX environment uses a different allocator, *leak* will not work on APE programs.

Leak is not speedy, and acidleak can consume more memory than the process(es) being examined.

These commands require /sys/src/libc/port/pool.acid to be present and generated from pool.c.

lens – interactive screen magnifier

SYNOPSIS

lens

DESCRIPTION

Lens presents a magnified view in its window of an arbitrary area on the screen. The default magnification is 4 (showing each pixel as a 4×4 pixel block in *lens*'s window). This may be changed by typing a digit on the keyboard (with 0 standing for 10), or by using the + and - keys to increase or decrease the magnification by one unit. The lower limit is $\times 1$; the upper $\times 16$.

The interface to indicate what area to magnify is dictated by the mouse multiplexing rules of *rio*(1). Start by pressing mouse button 1 in the *lens* window and dragging, with the button pressed, to the center of the area to magnify. *Lens* will update the display as the mouse moves. Releasing the button freezes the *lens* display. The magnified view is static—a snapshot, not a movie—but typing a space or . key in the *lens* window will refresh the display, as will changing the magnification.

To make counting pixels easier, typing a g toggles whether a checkerboard grid is imposed on the magnified area.

Button 3 brings up a menu of actions.

SOURCE

/sys/src/cmd/lens.c

BUGS

There should be an easier way to indicate what to magnify.

lex - generator of lexical analysis programs

SYNOPSIS

lex[-tvn9][*file*...]

DESCRIPTION

Lex generates programs to be used in simple lexical analysis of text. The input *files* (standard input default) contain regular expressions to be searched for and actions written in C to be executed when expressions are found.

A C source program, lex.yy.c is generated. This program, when run, copies unrecognized portions of the input to the output, and executes the associated C action for each regular expression that is recognized.

The options have the following meanings.

- -t Place the result on the standard output instead of in file lex.yy.c.
- -v Print a one-line summary of statistics of the generated analyzer.
- -n Opposite of -v; -n is default.
- -9 Adds code to be able to compile through the native C compilers.

EXAMPLES

This program converts upper case to lower, removes blanks at the end of lines, and replaces multiple blanks by single blanks.

%%

```
[A-Z] putchar(yytext[0]+'a'-'A');
[ ]+$
[ ]+ putchar(' ');
```

FILES

lex.yy.c output
/sys/lib/lex/ncform template

SEE ALSO

yacc(1), sed(1)

M. E. Lesk and E. Schmidt, 'LEX—Lexical Analyzer Generator', *Unix Research System Programmer's Manual,* Tenth Edition, Volume 2.

SOURCE

/sys/src/cmd/lex

BUGS

Cannot handle UTF.

The asteroid to kill this dinosaur is still in orbit.

lock - run a command under lock

SYNOPSIS

lock [-w] lockfile [command [argument ...]]

DESCRIPTION

Lock runs command (default rc) with arguments while holding lockfile open and (over)writing at least one byte each minute to keep the exclusive-access lock alive. If lockfile doesn't already have the exclusive-access bit set in its mode, the exclusive-access bits are set in its mode and qid.type.

Under -w, *lock* waits for exclusive access to *lockfile* instead of just trying once.

Lock sets /env/prompt to contain the name of the lock file.

EXAMPLES

Build a *replica*(1) database while preventing collisions with other occurrences.

cd /sys/lib/dist
lock scan.lock replica/scan \$dist/sources.replica

SOURCE

/sys/src/cmd/lock.c

/

SEE ALSO *intro*(5), *stat*(5)

look - find lines in a sorted list

SYNOPSIS

look[-dfnixtc][string][file]

DESCRIPTION

Look consults a sorted *file* and prints all lines that begin with *string*. It uses binary search.

The following options are recognized. Options dfnt affect comparisons as in *sort*(1).

- -i Interactive. There is no *string* argument; instead *look* takes lines from the standard input as strings to be looked up.
- -x Exact. Print only lines of the file whose key matches *string* exactly.
- -d 'Directory' order: only letters, digits, tabs and blanks participate in comparisons.
- -f Fold. Upper case letters compare equal to lower case.
- -n Numeric comparison with initial string of digits, optional minus sign, and optional decimal point.
- -t[c] Character c terminates the sort key in the *file*. By default, tab terminates the key. If c is missing the entire line comprises the key.

If no *file* is specified, /lib/words is assumed, with collating sequence df.

FILES

/lib/words

SOURCE

/sys/src/cmd/look.c

SEE ALSO

sort(1), grep(1)

DIAGNOSTICS

The exit status is "not found" if no match is found, and "no dictionary" if *file* or the default dictionary cannot be opened.

lp – printer output

SYNOPSIS

lp [option ...] [file ...]

DESCRIPTION

Lp is a generalized output printing service. It can be used to queue files for printing, check a queue, or kill jobs in a queue. The options are:

- -d dest Select the destination printer. If dest is ?, list the currently available printers. In the absence of -d, the destination is taken from the environment variable LPDEST. Destination stdout is the standard output. Destination safari is /dev/lpt1data line printer port on a 386 machine, assumed to be connected to a PostScript printer. Destinations hpdeskjet and bjc2401 are also /dev/lpt1data but assumed to be connected to an HP Deskjet 670 or Canon BJC-240. Lp can print to any printer supported by Ghostscript using syntax gs!device where device is a Ghostscript output device. See gs(1) and the canonbjc2401 entry in /sys/lib/lp/devices.
- -k Kill the job(s) given as subsequent arguments, instead of file names, for the given destination.
- -p proc The given processor is invoked. The default processor is generic, which tries to do the right thing for regular text, HTML, or troff(1) output. If no processing is desired noproc may be specified.
- -q Print the queue for the given destination. For some devices, include printer status.
- -R Stops and restarts the printer daemon. If the printer is wedged, it is often useful to cycle the power on the printer before running this command.

The remaining options may be used to affect the output at a given device. These options may not be applicable to all devices.

- -c *n* Print *n* copies.
- -f font Set the font (default CW.11).
- -H Suppress printing of header page.
- -i n Select paper input tray. n may be a number 0-9, the word man for the manual feed slot, and/or simplex or duplex to get single or double sided output. Multiple input tray options may be specified if they are separated by commas.
- -1 n Set the number of lines per page to n.
- -L Print pages in landscape mode (i.e. turned 90 degrees).
- -m v Set magnification to v.
- -n *n* Print *n* logical pages per physical page.
- -o *list* Print only pages whose page numbers appear in the comma-separated *list* of numbers and ranges. A range n-m means pages n through m; a range -n means from the beginning to page n; a range n-m means from page n to the end.
- $-\mathbf{r}$ Reverse the order of page printing.
- -x v Set the horizontal offset of the print image, measured in inches.
- -y v Set the vertical offset of the print image, measured in inches.

EXAMPLES

eqn paper | troff -ms | lp -dsafari

Typeset and print a paper containing equations.

- pr -1100 file | lp -1100 -fCW.8
 - Print a file in a small font at 100 lines per page.

SOURCE

/rc/bin/lp
/sys/src/cmd/lp

SEE ALSO

ln(8)

P. Glick, "A Guide to the Lp Printer Spooler".

BUGS

Not all options work with all output devices. Any user can kill any job.

ls, lc - list contents of directory

SYNOPSIS

ls[-dlmnpqrstuFQT] name ...

lc[-dlmnqrstuQT] name ...

DESCRIPTION

For each directory argument, *Is* lists the contents of the directory; for each file argument, *Is* repeats its name and any other information requested. When no argument is given, the current directory is listed. By default, the output is sorted alphabetically by name.

Lc is the same as ls, but sets the -p and -F options and pipes the output through mc(1).

There are a number of options:

- -d If argument is a directory, list it, not its contents.
- -1 List in long format, giving mode (see below), file system type (e.g., for devices, the # code letter that names it; see *intro*(3)), the instance or subdevice number, owner, group, size in bytes, and time of last modification for each file.
- -m List the name of the user who most recently modified the file.
- -n Don't sort the listing.
- -p Print only the final path element of each file name.
- -q List the *qid* (see *stat*(2)) of each file; the printed fields are in the order path, version, and type.
- $-\mathbf{r}$ Reverse the order of sort.
- -s Give size in Kbytes for each entry.
- -t Sort by time modified (latest first) instead of by name.
- -u Under -t sort by time of last access; under -1 print time of last access.
- -F Add the character / after all directory names and the character * after all executable files.
- -T Print the character t before each file if it has the temporary flag set, and otherwise.
- -Q By default, printed file names are quoted if they contain characters special to rc(1). The -Q flag disables this behavior.

The mode printed under the -1 option contains 11 characters, interpreted as follows: the first character is

- d if the entry is a directory;
- a if the entry is an append-only file;
- if the entry is a plain file.

The next letter is 1 if the file is exclusive access (one writer or reader at a time).

The last 9 characters are interpreted as three sets of three bits each. The first set refers to owner permissions; the next to permissions to others in the same user-group; and the last to all others. Within each set the three characters indicate permission respectively to read, to write, or to execute the file as a program. For a directory, 'execute' permission is interpreted to mean permission to search the directory for a specified file. The permissions are indicated as follows:

- r if the file is readable;
- w if the file is writable;
- x if the file is executable;
- if none of the above permissions is granted.

SOURCE

/sys/src/cmd/ls.c /rc/bin/lc

SEE ALSO

stat(2), *mc*(1)

mail, go.fishing - mail and mailboxes

SYNOPSIS

mail [arg ...]

go.fishing

DESCRIPTION

Mail is a shell script that invokes *nedmail*(1), the mail reader, when no recipients appear on the command line and *marshal*(1), the mail preparer, otherwise. All command line options are passed through. See the man pages for those two commands for more details.

Incoming mail for a user username is put in the file /mail/box/username/mbox unless either the file /mail/box/username/forward or /mail/box/username/pipeto exists. The mailbox must have append-only and exclusive-access mode (see chmod(1)). A user must create his or her own mailbox using the -c option of *nedmail*(1). Mailboxes are created writable (append-only) but not readable by others.

If the file /mail/box/username/forward exists and is readable by everyone, incoming mail will be forwarded to the addresses contained in the first line of the file. The file may contain multiple addresses. Forwarding loops are caught and resolved by local delivery.

If the file /mail/box/username/pipeto exists and is readable and executable by everyone, it will be run for each incoming message for the user. The message will be piped to it rather than appended to his/her mail box. The file is run as user none. Its two arguments are the destination address (e.g., local!gremlin) and the user's mail box path (e.g., /mail/box/gremlin/mbox)

Auto-answer

To use mail as an answering machine while you are away, run go.fishing, which will create /mail/box/\$user/gone.fishing as a flag for pipeto processing, and truncate /mail/box/\$user/gone.addrs. Any existing file that pipeto uses /mail/lib/pipeto.lib will invoke the gone.fishing machinery when it calls spool or spool-tagged-spam.

If /mail/box/\$user/gone.msg exists, it will be sent (just once) to everyone who sends you mail that lists your address in a To or Cc header; if not, /mail/lib/gone.msg will be sent. Upon your return, remove /mail/box/\$user/gone.fishing to stop automatic responses.

FILES

<pre>/sys/log/mail /mail/box/* /mail/box/*/mbox /mail/box/*/forward /mail/box/*/pipeto /mail/box/*/L.reading /mail/box/*/L.mbox /lib/face/48x48x? /mail/lib/pipeto.lib /mail/lib/pipeto.lib /mail/lib/gone.msg /mail/lib/gone.fishing /mail/lib/gone.fishing</pre>	mail log file mail directories mailbox files forwarding address(es) mail filter mutual exclusion lock for multiple mbox readers mutual exclusion lock for altering mbox directories of icons for seemail helper functions for pipeto files default vacation message auto-responder as <i>pipeto</i> script flag to active gone processing
/mail/box/\$user/gone.addrs	list of senders answered by gone.fishing

SOURCE

/rc/bin/mail /rc/bin/go.fishing

SEE ALSO

aliasmail(8), faces(1), filter(1), marshal(1), mlmgr(1), nedmail(1), qer(8), rewrite(6), send(8), smtp(8), upasfs(4)

man, lookman, sig - print or find pages of this manual

SYNOPSIS

man [-bnpPStw] [section ...] title ...

lookman key ...

sig function ...

DESCRIPTION

Man locates and prints pages of this manual named *title* in the specified *sections*. *Title* is given in lower case. Each *section* is a number; pages marked (2S), for example, belong to chapter 2. If no *section* is specified, pages in all sections are printed. Any name from the NAME section at the top of the page will serve as a *title*.

The options are:

- -n (Default) Print the pages on the standard output using *nroff*.
- -b Print the pages using *nroff* and send them to *plumber*(4) for display in the editor.
- -p Run *proof*(1) on the specified man pages.
- -P Run *page*(1) on the specified man pages.
- -S Do not search the manual indices for the names. Only print pages whose file names match the names.
- -t Run *troff*(1) and send its output to standard output.
- -w Print the names of the man page source files.

Lookman prints the names of all manual sections that contain all of the *key* words given on the command line.

Sig prints the signature (i.e. C definition) of the *functions* given on the command line.

FILES

/sys/man/?/*

troff source for manual; this page is /sys/man/1/man

/sys/man/?/INDEX

indices searched to find pages corresponding to titles

/sys/lib/man/secindex command to make an index for a given section

/sys/lib/man/lookman/index index for lookman

SOURCE

/rc/bin/man /rc/bin/lookman

SEE ALSO

page(1), proof(1)

BUGS

The manual was intended to be typeset; some detail is sacrificed on text terminals.

There is no automatic mechanism to keep the indices up to date.

Except for special cases, man doesn't recognize things that should be run through tbl and/or eqn.

marshal – formatting and sending mail

SYNOPSIS

```
upas/marshal [-[aA] attachment][-C copyaddr][-B copyaddr][-Fr#xn][-S saveto]
[-p[es]][-R reply-msg][-s subject][-t mime-type][-8 | mailaddr ...]
```

DESCRIPTION

Marshal builds a mail message from standard input and passes it, if the body is non-empty, for transmission or delivery to /mail/box/username/pipefrom if it exists, otherwise to /bin/upas/send. The message format is both RFC 822 and MIME conformant, so marshal adds any required headers not already in the message, prefixed by the contents of /mail/box/username/headers. This allows the addition of personal headers like From: lines with a full name or a different return address. Command line options direct marshal to add a subject line and append attachments. The arguments to marshal are the addresses of the recipients.

When running in a rio(1) window, *marshal* automatically puts the window into hold mode (see rio(1)); this means that the message can be edited freely, because nothing will be sent to *marshal* until the ESC key is hit to exit hold mode.

The options are:

- -a file directs marshal to append file as a mime attachment. Unless explicitly specified by the -t option, the type of the attachment is determined by running the file(1) command.
- -Afile is like -a but the message disposition is marked as *inline* directing any mail reader to display the attachment (if it can) when the mail message is read.
- -Ccopyaddr or -Bcopyaddr adds a Cc: or Bcc: header with copyaddr and also adds copyaddr as a recipient.
- -F file the message
- -S saveto file the message into the saveto mailbox.
- -n intentionally no standard input
- -#xr are all passed as command line options to the *send* that *marshal* invokes.
- -Rreplymsg tells marshal what message this one is in reply to. Replymsg is an upasfs(4) directory containing the message. Marshal uses any message id in this message in its In-Reply-To field. It also passes the directory to /mail/box/username/pipefrom in the replymsg environment variable. Thus, pipefrom can alter the message to somehow match the reply to the message it is replying to.
- -s *subject* adds a Subject: header line to the message if one does not already exist.
- -t *type* sets the content type for the attachments from all subsequent –a and –A options.
- -ps pgp sign the message
- -pe pgp encrypt the message
- -8 reads recipients (To: Cc: and Bcc:) from RFC 822 header of the message

Marshal also expands any user mail aliases contained in /mail/box/username/names. The format of the alias file is the same as that for system aliases, see *aliasmail*(8).

Marshal uses the login name as the reply address. This can be overriden using the environment variable upasname. Its value will become both the envelope and From: mailbox name. For example:

```
upasname=natasha@kremvax.com mail boris@squirrel.com
```

Marshal interprets file attachment headers Attach: and Include: as if the -A or -a options would have been given.

FILES

/mail/box/*/dead.letter

SOURCE

/sys/src/cmd/upas/marshal

SEE ALSO aliasmail(8), faces(1), filter(1), mail(1), mlmgr(1), nedmail(1), qer(8), rewrite(6), send(8), smtp(8), upasfs(4)

mc – multicolumn print

SYNOPSIS

mc [−] [−N] [file ...]

DESCRIPTION

Mc splits the input into as many columns as will fit in N print positions. If run in a rio(1) or acme(1) window, the default N is the number of blanks that will fit across the window; otherwise the default N is 80. Under option – each input line ending in a colon : is printed separately.

SOURCE

/sys/src/cmd/mc.c

SEE ALSO

rio(1), *acme*(1), *acme*(4), *pr*(1), *lc* in *ls*(1)

mines - minesweeper

SYNOPSIS

games/mines[-aeqg]

DESCRIPTION

Mines is an implementation of the game Minesweeper. The game is played on a rectangular grid. A certain number of mines is hidden beneath some of the tiles. Left clicking on a tile uncovers it. If a mine is revealed, the player loses. Otherwise, a number is shown that indicates the number of mines in the 8 adjacent tiles. The player wins once they have uncovered all tiles free from mines.

Right clicking marks a square, cycling through the flag marker indicating a mine and the query marker with no specific meaning (provided solely for the player's convenience). Middle clicking will uncover all adjacent squares, if it is safe to do so (assuming the flag markers are set correctly).

The number at the top left indicates the number of mines remaining that are not marked by flags. The number in the top right indicates the number of seconds elapsed. The smiley face can be clicked to restart the game.

The n key restarts the game. The b, a and e keys restart the game and set the difficulty to beginner, advanced and expert, respectively. The q and DEL keys quit the game.

There are a number of options:

- -a Start at advanced difficulty.
- -e Start at expert difficulty.
- -q Disable the query marker.
- -g It's a secret to everybody.

SOURCE

/sys/src/games/mines

HISTORY

Mines was written in 2001 by Antonin Vecera for Plan 9 Third Edition. It was added to 9 front in May 2011. The -g option was added by 9 front in February 2018.

LICENSE

Mines is licensed under the GNU General Public License, Version 2, reproduced in the file /lib/legal/gpl.

mix - MIX assembler and emulator

SYNOPSIS

games/mix[-g][file...]

DESCRIPTION

Mix is an assembler and emulator for Donald Knuth's fictitious MIX architecture. The command assembles the named MIXAL files into memory and then presents a command prompt to control an emulated MIX machine. The -g option causes the emulator immediately to run a complete assembled MIX program and exits when the emulator halts.

The following commands are accepted:

addr[(a:b)]

Print the value at *addr*. An optional field specification is given by (*a:b*).

a [< file]

Start the MIXAL assembler. The assembler will begin assembling at the address after the last assembled instruction. If no file is given, the assembler will accept instructions from the console.

b addr

Set or unset a breakpoint at *addr*.

Resets the MIX machine to a fresh state by clearing all memory and registers.

d addr

С

Disassemble the instruction at *addr*.

o addr

Print the alphanumeric MIX word at *addr*.

o(addr, d)

Print *d* alphanumeric mix words starting at *addr*.

r*[(a:b)]

Print the value in register r^* where * is one of a, x, ax, j, or 1–6. An optional field specification is given by (*a:b*).

- s Step through one instruction of the emulated MIX machine.
- g Start the emulated MIX machine at the instruction specified by the END pseudoinstruction.
- x Quit the emulator/assembler.

The *addr* field of the above instructions must be an integer between 0 and 3999 inclusive. A number-sign (#) or an asterisk (*) at the beginning of a line starts a comment which extends to the end of the line.

SOURCE

/sys/src/games/mix

SEE ALSO

Donald Knuth, "The Art of Computer Programming", Volume 1. Section 1.3

/sys/src/games/mix/examples

BUGS

As opposed to Knuth's specification, the ALF pseudo-instruction takes as argument five MIX characters surrounded by quotation marks. Unresolved forward references are assembled to 0 instead of to a location determined by the END psuedo-instruction.

The magnetic tapes and drum units are not implemented.

Comments are handled as described above and not exactly as Knuth specifies.

mk, membername - maintain (make) related files

SYNOPSIS

mk [-f mkfile] ... [option ...] [target ...]

membername aggregate ...

DESCRIPTION

Mk uses the dependency rules specified in *mkfile* to control the update (usually by compilation) of *targets* (usually files) from the source files upon which they depend. The *mkfile* (default mkfile) contains a *rule* for each target that identifies the files and other targets upon which it depends and an *rc*(1) script, a *recipe*, to update the target. The script is run if the target does not exist or if it is older than any of the files it depends on. *Mkfile* may also contain *meta-rules* that define actions for updating implicit targets. If no *target* is specified, the target of the first rule (not meta-rule) in *mkfile* is updated.

The environment variable \$NPROC determines how many targets may be updated simultaneously; Plan 9 sets \$NPROC automatically to the number of CPUs on the current machine.

Options are:

-a	Assume all targets to be out of date. Thus, everything is updated.
-d[egp]	Produce debugging output (p is for parsing, g for graph building, e for execution).
-е	Explain why each target is made.
-i	Force any missing intermediate targets to be made.
$-\mathbf{k}$	Do as much work as possible in the face of errors.
-n	Print, but do not execute, the commands needed to update the targets.
-s	Make the command line arguments sequentially rather than in parallel.
-t	Touch (update the modified date of) file targets, without executing any recipes.
–wtarget1	, target2,
-	Pretend the modify time for each <i>target</i> is the current time; useful in conjunction w

Pretend the modify time for each *target* is the current time; useful in conjunction with -n to learn what updates would be triggered by modifying the *targets*.

The *rc*(1) script *membername* extracts member names (see 'Aggregates' below) from its arguments.

The mkfile

A *mkfile* consists of *assignments* (described under 'Environment') and *rules*. A rule contains *targets* and a *tail*. A target is a literal string and is normally a file name. The tail contains zero or more *prerequisites* and an optional *recipe*, which is an rc script. Each line of the recipe must begin with white space. A rule takes the form

target: prereq1 prereq2
 rc recipe using prereq1, prereq2 to build target

When the recipe is executed, the first character on every line is elided.

After the colon on the target line, a rule may specify *attributes*, described below.

A *meta-rule* has a target of the form A%B where A and B are (possibly empty) strings. A meta-rule acts as a rule for any potential target whose name matches A%B with % replaced by an arbitrary string, called the *stem*. In interpreting a meta-rule, the stem is substituted for all occurrences of % in the prerequisite names. In the recipe of a meta-rule, the environment variable *stem* contains the string matched by the %. For example, a meta-rule to compile a C program using 2c(1) might be:

%: %.c 2c \$stem.c 2l -o \$stem \$stem.2

Meta-rules may contain an ampersand & rather than a percent sign %. A % matches a maximal length string of any characters; an & matches a maximal length string of any characters except period or slash.

The text of the *mkfile* is processed as follows. Lines beginning with < followed by a file name are replaced by the contents of the named file. Lines beginning with <| followed by a file name are

replaced by the output of the execution of the named file. Blank lines and comments, which run from unquoted # characters to the following newline, are deleted. The character sequence backslash-newline is deleted, so long lines in *mkfile* may be folded. Non-recipe lines are processed by substituting for '{*command*} the output of the *command* when run by *rc*. References to variables are replaced by the variables' values. Special characters may be quoted using single quotes ' as in *rc*(1).

Assignments and rules are distinguished by the first unquoted occurrence of : (rule) or = (assignment).

A later rule may modify or override an existing rule under the following conditions:

- If the targets of the rules exactly match and one rule contains only a prerequisite clause and no recipe, the clause is added to the prerequisites of the other rule. If either or both targets are virtual, the recipe is always executed.
- If the targets of the rules match exactly and the prerequisites do not match and both rules contain recipes, *mk* reports an "ambiguous recipe" error.
- If the target and prerequisites of both rules match exactly, the second rule overrides the first.

Environment

Rules may make use of rc environment variables. A legal reference of the form \$OBJ is expanded as in rc(1). A reference of the form ${nme: A\%B = C\%D}$, where A, B, C, D are (possibly empty) strings, has the value formed by expanding \$name and substituting C for A and D for B in each word in \$name that matches pattern A%B.

Variables can be set by assignments of the form

var=[attr=]value

Blanks in the *value* break it into words, as in *rc* but without the surrounding parentheses. Such variables are exported to the environment of recipes as they are executed, unless U, the only legal attribute *attr*, is present. The initial value of a variable is taken from (in increasing order of precedence) the default values below, *mk's* environment, the *mkfiles*, and any command line assignment as an argument to *mk*. A variable assignment argument overrides the first (but not any subsequent) assignment to that variable.

The variable MKFLAGS contains all the option arguments (arguments starting with – or containing =) and MKARGS contains all the targets in the call to mk.

It is recommended that mkfiles start with

</\$objtype/mkfile

to set CC, LD, AS, O, YACC, and MK to values appropriate to the target architecture (see the examples below).

Execution

During execution, *mk* determines which targets must be updated, and in what order, to build the *names* specified on the command line. It then runs the associated recipes.

A target is considered up to date if it has no prerequisites or if all its prerequisites are up to date and it is newer than all its prerequisites. Once the recipe for a target has executed, the target is considered up to date.

The date stamp used to determine if a target is up to date is computed differently for different types of targets. If a target is *virtual* (the target of a rule with the V attribute), its date stamp is initially zero; when the target is updated the date stamp is set to the most recent date stamp of its prerequisites. Otherwise, if a target does not exist as a file, its date stamp is set to the most recent date stamp of its prerequisites, or zero if it has no prerequisites. Otherwise, the target is the name of a file and the target's date stamp is always that file's modification date. The date stamp is computed when the target is needed in the execution of a rule; it is not a static value.

Nonexistent targets that have prerequisites and are themselves prerequisites are treated specially. Such a target *t* is given the date stamp of its most recent prerequisite and if this causes all the targets which have *t* as a prerequisite to be up to date, *t* is considered up to date. Otherwise, *t* is made in the normal fashion. The -i flag overrides this special treatment.

Files may be made in any order that respects the preceding restrictions.

A recipe is executed by supplying the recipe as standard input to the command /bin/rc -e -I

(the -e is omitted if the E attribute is set). The environment is augmented by the following variables:

\$alltarget

all the targets of this rule.

\$newprereq

the prerequisites that caused this rule to execute.

\$newmember

the prerequisites that are members of an aggregate that caused this rule to execute. When the prerequisites of a rule are members of an aggregate, *snewprereq* contains the name of the aggregate and out of date members, while *snewmember* contains only the name of the members.

proc the process slot for this recipe. It satisfies $0 \le proc < PROC$.

\$pid the process id for the *mk* executing the recipe.

- **\$prereq** all the prerequisites for this rule.
- \$stem if this is a meta-rule, \$stem is the string that matched % or &. Otherwise, it is empty. For regular expression meta-rules (see below), the variables stem0, ..., stem9 are set to the corresponding subexpressions.

\$target the targets for this rule that need to be remade.

These variables are available only during the execution of a recipe, not while evaluating the *mkfile*.

Unless the rule has the Q attribute, the recipe is printed prior to execution with recognizable environment variables expanded. Commands returning nonempty status (see *intro*(1)) cause mk to terminate.

Recipes and backquoted rc commands in places such as assignments execute in a copy of mk's environment; changes they make to environment variables are not visible from mk.

Variable substitution in a rule is done when the rule is read; variable substitution in the recipe is done when the recipe is executed. For example:

```
bar=a.c
foo: $bar
    $CC -o foo $bar
bar=b.c
```

will compile b.c into foo, if a.c is newer than foo.

Aggregates

Names of the form a(b) refer to member b of the aggregate a. Currently, the only aggregates supported are ar(1) archives.

Attributes

The colon separating the target from the prerequisites may be immediately followed by *attributes* and another colon. The attributes are:

- D If the recipe exits with a non-null status, the target is deleted.
- E Continue execution if the recipe draws errors.
- N If there is no recipe, the target has its time updated.
- n The rule is a meta-rule that cannot be a target of a virtual rule. Only files match the pattern in the target.
- P The characters after the P until the terminating : are taken as a program name. It will be invoked as rc c prog 'arg1' 'arg2' and should return a null exit status if and only if arg1 is up to date with respect to arg2. Date stamps are still propagated in the normal way.

- Q The recipe is not printed prior to execution.
- R The rule is a meta-rule using regular expressions. In the rule, % has no special meaning. The target is interpreted as a regular expression as defined in regexp(6). The prerequisites may contain references to subexpressions in form n, as in the substitute command of sam(1).
- U The targets are considered to have been updated even if the recipe did not do so.
- V The targets of this rule are marked as virtual. They are distinct from files of the same name.

EXAMPLES

A simple mkfile to compile a program:

```
</$objtype/mkfile
prog: a.$0 b.$0 c.$0
$LD $LDFLAGS -0 $target $prereq
```

%.\$0:%.c

\$CC \$CFLAGS \$stem.c

Override flag settings in the mkfile:

% mk target 'CFLAGS=-S -w'

Maintain a library:

```
libc.a(%.$0):N: %.$0
libc.a: libc.a(abs.$0) libc.a(access.$0) libc.a(alarm.$0) ...
ar r libc.a $newmember
```

String expression variables to derive names from a master list:

NAMES=alloc arc bquote builtins expand main match mk var word OBJ=\${NAMES:%=%.\$0}

Regular expression meta-rules:

([^/]*)/(.*)\.\$0:R: \1/\2.c
 cd \$stem1; \$CC \$CFLAGS \$stem2.c

A correct way to deal with yacc(1) grammars. The file lex.c includes the file x.tab.h rather than y.tab.h in order to reflect changes in content, not just modification time.

```
lex.$0: x.tab.h
x.tab.h: y.tab.h
    cmp -s x.tab.h y.tab.h || cp y.tab.h x.tab.h
y.tab.c y.tab.h: gram.y
    $YACC -d gram.y
```

The above example could also use the P attribute for the x.tab.h rule:

```
x.tab.h:Pcmp -s: y.tab.h
      cp y.tab.h x.tab.h
```

SOURCE

/sys/src/cmd/mk

SEE ALSO

rc(1), *regexp*(6)

A. Hume, "Mk: a Successor to Make".

Andrew G. Hume and Bob Flandrena, "Maintaining Files on Plan 9 with Mk".

BUGS

Identical recipes for regular expression meta-rules only have one target.

Seemingly appropriate input like CFLAGS=-DHZ=60 is parsed as an erroneous attribute; correct it by inserting a space after the first =.

The recipes printed by mk before being passed to rc for execution are sometimes erroneously expanded for printing. Don't trust what's printed; rely on what rc does.

mkdir - make a directory

SYNOPSIS

mkdir[-p][-m mode] dirname ...

DESCRIPTION

Mkdir creates the specified directories. It requires write permission in the parent directory.

If the -p flag is given, *mkdir* creates any necessary parent directories and does not complain if the target directory already exists.

The -m flag sets the permissions to be used when creating the directory. The default is 0777.

SEE ALSO

rm(1) *cd* in *rc*(1)

SOURCE

/sys/src/cmd/mkdir.c

DIAGNOSTICS

Mkdir returns null exit status if all directories were successfully made. Otherwise it prints a diagnostic and returns "error" status.

ml, mlmgr, mlowner - unmoderated mailing lists

SYNOPSIS

upas/mlmgr -c listname

upas/mlmgr -ar listname address

upas/ml [-r replyto-address] addressfile listname

upas/mlowner addressfile listname

DESCRIPTION

Mlmgr creates and updates unmoderated mailing lists. The -c option creates mail directories for both *listname* and *listname*-owner, each containing a pipeto file. Messages mailed to *listname* are sent to all members of the mailing list. Any Reply-to: and Precedence: fields are removed from the messages and new ones are added directing replies to *listname* and specifying bulk precedence. The envelope address for error replies is set to /dev/null.

The mailing list membership is the file /mail/box/listname/address-list. This file is an add/remove log. Each line represents a single address. Lines beginning with a hash (#) are comments. Lines beginning with an exclamation point (!) are removals. All other lines are additions.

Addition and removal entries can be appended using the -a and -r options to *mlmgr*. However, they are normally appended as a consequence of user requests.

To be added or removed from the list, a user may send a message to *listname*-owner containing a key word in the header or body. The key words are:

subscribe - add my From: address to the list

remove - remove my From: address from the list

unsubscribe - remove my From: address from the list

Addition and removal events cause notification messages to be sent to the added/removed address. In the case of addition, the message describes how to be removed.

MI and *mlowner* are the programs that receive messages for *listname* and *listname*-owner respectively. Appropriate calls to them are inserted in the pipeto files created by *mlmgr*.

MI's -r option sets the Reply-to: field in the mail sent out by *ml*.

FILES

/mail/box/ <i><listname></listname></i>	list's mailbox directory
/mail/box/ <i><listname></listname></i> —owner	owner's mailbox directory
/mail/box/ <listname>/address-list</listname>	log of mailing list deletions and additions

SOURCE

/sys/src/cmd/upas/ml

SEE ALSO

aliasmail(8), faces(1), filter(1), mail(1), marshal(1), nedmail(1), qer(8), rewrite(6), send(8), smtp(8), upasfs(4)

mothra - retrieve and display World-Wide Web files

SYNOPSIS

mothra[-dvak][-m mtpt][url]

DESCRIPTION

Mothra uses *webfs*(4) to retrieve and display files from the World–Wide Web, by name or through hypertext links. Web names, called URLs, have a peculiar syntax:

http://9front.org/ https://code.9front.org/hg/plan9front/ http://cat-v.org/

The part up to the first colon gives the protocol for retrieving the file. http:, Hyper-Text Transfer Protocol, is the usual way of accessing web files.

// begins the Internet address of the server where the file resides. The address may contain a colon and a TCP port number, which overrides the default port number for the service. Next comes a file name. Finally, the file name may be followed by # and a string giving a label within the file where the display should begin.

Mothra starts with the *url* given on the command line, defaulting to the environment variable \$url.

There are a number of options:

- -a Alt display. Starts in alt display mode, see menu commands table below.
- -k Kill images. Don't fetch/display images.
- -m Specify the *webfs*(4) mountpoint with -m *mtpt*. The default is /mnt/web.
- -v Verbose mode. Causes HTML errors to be printed on file-descriptor 2.
- -d Enables debug mode.

The display contains the last message from *mothra*, a box where typed commands appear, a scrollable list of previously visited files, the title and URL of the current file, and the scrollable text of the current file.

Button 1 selects and displays a file, either from the list of previously visited pages or from a link (indicated by underlined text or a boxed image) in the current file. Button 2 shows the URL of a file, but does not retrieve or display it. Button 3 pops up a menu of commands:

alt display Collapse or expand the navigation boxes at the top of the browser window.

moth	mode	Enter moth mode and switch to the moth cursor. If the HREF of an image link is different from the URL of the image itself, a link to the HREF will be printed on the right side of the image. Clicking an image or link with mouse button 1 prompts the user to save a copy of the file in the current directory. Clicking mouse button 2 sets the target as the current URL. Clicking the moth mode
		5
		menu option again exits moth mode.

- snarf Copy the current entry text or selected page text to snarf buffer. If nothing is selected, the current URL is copied.
- paste Paste the snarf buffer to the current text entry.
- plumb Plumb the current URL.
- search Search for a regular expression in the current page.
- save hit Save the current URL to the hit list.
- hit list Retrieve and display the hit list.
- exit Ask for confirmation and quit.

The typed commands are:

а	Toggle alt display.
g url	Go to the page with the given URL.
jп	Jump to page <i>n</i> from the list of previously viewed pages.
k	Toggle killing of images.

m	Enter or exit moth mode.
r	Reload the current page.
s file	Save the current page in the given <i>file.</i>
W file	Capture a screenshot of the entire browser window in the given <i>file</i> .
w file	Capture a screenshot of the content area in the given <i>file</i> .
q	Quit.

When *mothra* retrieves a direct link to a file that is not an HTML document (for example a GIF or JPEG image), it will start up an appropriate viewer, for example page (see *page*(1)) for most image files.

FILES

\$home/lib/mothra/hit.html the hit list

SOURCE

/sys/src/cmd/mothra

SEE ALSO

webfs(4)

BUGS

Files are saved in the form received, not in the form suggested by the name in an s command. A directory index saved from moth mode may be written in the local directory as a file named index. Sanitizing remote file names for the local file system is imperfect.

Mothra is distributed in a preliminary state; it has more than its share of bugs. Note that *mothra*, like the other Guardian Monsters, has no particular concern for humanity.

HISTORY

Mothra first appeared in Plan 9 from Bell Labs (1995). It was later modified for inclusion in 9front (September, 2011).

mpc - extended precision arithmetic code generator

SYNOPSIS

mpc [file ...]

DESCRIPTION

Mpc generates C functions from a simple language that operates on extended precision integers using the mp(2) library.

LANGUAGE

The language consists of a series of function definitions of the form:

```
name ( parameter list ) { statements }
```

All variables and parameters are extended precision integers and are passed by reference. Statements are separated by semicolon and the following statemens are defined:

```
name = expression
```

```
if (condition) { statements } else if (condition) { statements } else { statements }
```

while (condition) { statements }

break

name (parameter list)

mod (modulus) { statements }

There is no distinction between input and output parameters, but conventionally, the outputs are put at the end of the *parameter list* and the language allows one to write

F(X, Y, Z) as Y, Z = F(X)

Expressions are composed out of the following arithmetic operations:

+	addition.
-	subtraction.
*	multiplication.
/	division, or multiplicative inverse when enclosed in mod block.
%	division remainder.
٨	exponentiation.
>> constant	right shift by a constant.
<< constant	left shift by a constant.
condition? a : b	pick a when condition is true, otherwise b when false.

Conditions can use the following operations:

==	equality.
! =	inequality.
>	bigger than.
<	smaller than.
! condition	negation.

SOURCE

/sys/src/cmd/mpc.y

SEE ALSO

mp(2)

ms2html, html2ms - convert between troff's ms macros and html

SYNOPSIS

ms2html [-q][-b basename][-d delims][-t title]
html2ms

DESCRIPTION

Ms2html converts the *ms*(6) source on standard input into HTML and prints it to standard output. If the source contains *tbl*(1) or *eqn* input, you must first pipe the text through those preprocessors. Postscript images, equations, and tables will be converted to gif files. If the document has a .TL entry, its contents will be used as the title; otherwise *ms2html* will look for a ._T macro, unknown to *ms*(6), and take its value. Options are:

q suppresses warnings about malformed input;

b sets the HTML base name to *basename*;

- d sets the *eqn*(1) delimiters to *delim*;
- t sets the HTML title to *title*.

Html2ms reads HTML from standard input and converts it to *ms*(6) source on standard output. The document is expected to be UTF encoded so a preprocessor like *uhtml*(1) should be used to normalize the HTML.

SOURCE

/sys/src/cmd/ms2html.c
/sys/src/cmd/html2ms.c

SEE ALSO

htmlroff(1), ms(6), uhtml(1)

BUGS

Ms2html doesn't understand a number of troff commands. It does handle macros and defined strings.

mtime - print file modification time

SYNOPSIS

mtime file ...

DESCRIPTION

Mtime prints the modification time (in seconds since the epoch) and name of each file.

SOURCE

/sys/src/cmd/mtime.c

SEE ALSO

du(1), seconds(1)

mug – convert an image to a face icon

SYNOPSIS

mug [file]

DESCRIPTION

Mug reads a Plan 9 *image*(6) from *file* (or standard input if there is no *file*) and displays a working version of the icon a gray ramp, and a larger image (the 'crop box'), all derived from *file*. Selecting Write from the button-3 menu will write the icon in *face*(6) format to standard output.

Imagine a 3x3 grid on the crop box. You can move an edge or corner of the box by putting the mouse in the corresponding section of the grid and dragging. Dragging in the middle box in the grid translates the crop box. The mouse cursor changes to tell you where you are.

The bar in the gray ramp controls the map from picture gray levels to the output levels. The values along the bar are mapped to 0 through 255 in the output. You can move the bar vertically by grabbing the midsection or adjust the width by grabbing an endpoint.

The current icon is shown in the bottom left corner, surrounded by eight small empty boxes. You can save the settings as they are by dragging the current icon into one of the other boxes. You can restore the settings by dragging an icon from one of the periphery boxes into the middle.

EXAMPLES

Convert a JPEG image into a face icon.

jpg -c plus.jpg | mug >plus.1

SEE ALSO

faces(1), jpg(1), face(6), image(6)

mus – MUS to MIDI converter

SYNOPSIS

games/mus[musfile]

DESCRIPTION

The MUS format is a simplified MIDI music format used in doom and several related games.

Mus decodes MIDI music encoded in MUS format, either from musfile or from standard input, and produces a MIDI format file on standard output.

SEE ALSO

games(1)

SOURCE

/sys/src/games/mus.c

HISTORY

Mus first appeared in 9front (September, 2015).

nedmail - reading mail

SYNOPSIS

upas/nedmail[-nr][-f mailfile][-s mailfile]

upas/nedmail -c *dir*

DESCRIPTION

Nedmail edits a mailbox. The default mailbox is /mail/box/username/mbox. The -f command line option specifies an alternate mailbox. Unrooted path names are interpreted relative to /mail/box/username. If the mailfile argument is omitted, the name defaults to stored.

The options are:

−c dir	Create a mailbox. If <i>dir</i> is specified, the new mailbox is created in /mail/box/ <i>username/dir/</i> mbox. Otherwise, the default mailbox is created.
-r	Reverse: show messages in first-in, first-out order; the default is last-in, first-out.
-n	Make the message numbers the same as the file names in the mail box directory. This implies the $-r$ option.
−£ mailfile	Read messages from the specified file (see above) instead of the default mailbox.
−s mailfile	Read a single message file <i>mailfile</i> , as produced by <i>fs</i> , and treat it as an entire mailbox. This is provided for use in plumbing rules; see <i>faces</i> (1).

Nedmail starts by reading the mail box, printing out the number of messages, and then prompting for commands from standard input. Commands, as in ed(1), are of the form '[*range*] command [*arguments*]'. The command is applied to each message in the (optional) range.

The address range can be:

address	to indicate a single message header
address , address	to indicate a range of contiguous message headers
g/expression/ g%expression%	to indicate all messages whose headers match the regular <i>expression</i> . to indicate all messages whose contents match the regular <i>expression</i> .

The addresses can be:

number	to indicate a particular message
address . number	to indicate a subpart of a particular message
/ expression /	to indicate the next message whose header matches expression
%expression%	to indicate the next message whose contents match expression
empty or .	to indicate the current message
–address	to indicate backwards search or movement

Since messages in MIME are hierarchical structures, in *nedmail* all the subparts are individually addressable. For example if message 2 contains 3 attachments, the attachments are numbered 2.1, 2.2, and 2.3.

The commands are:

a args	Reply to all addresses in the To:, From:, and Cc: header lines. <i>Marshal</i> is used to format the reply and any arguments the user specifies are added to the command line to <i>marshal</i> before the recipient. The possibility of making a fool of yourself is very high with this command.
A args	Like a but with the message appended to the reply.
b	Print the headers for the next ten messages.
d	Mark message to be deleted upon exiting <i>nedmail</i> .
f	Append the message to the file /mail/box/username/sendername where sendername is the account name of the sender.
h	Print the disposition, size in characters, reception time, sender, and subject of the message.
Н	Print the MIME structure of the message.

help	Print a summary of the commands.		
m person	Forward the message as a mime attachment to the named <i>persons</i> .		
M person	Like m but allow the user to type in text to be included with the forwarded mes-		
	sage.		
р	Print message. An interrupt stops the printing.		
r args	Reply to the sender of the message. <i>Marshal</i> is used to format the reply. If any		
-	optional args are specified, they are added to the command line to marshal		
	before the recipient's address.		
R args	Like ${f r}$ but with the original message included as an attachment.		
rf	Like r but append the message and the reply to the file		
	/mail/box/username/sendername where sendername is the account name		
	of the sender.		
Rf	Like R but append the message and the reply to the file		
	/mail/box/username/sendername where sendername is the account name		
	of the sender.		
s mfile	Append the message to the specified mailbox. If <i>mfile</i> doesn't start with a '/', it		
is interpreted relative to the directory in which the mailbox resides. If <i>mfile</i> is a			
	directory then the destination is a file in that directry. If the MIME header speci- fies a file name, that one is used. Otherwise, one is generated using <i>mktemp</i> (2)		
	and the string att.XXXXXXXXXXX.		
q	Put undeleted mail back in the mailbox and stop.		
EOT (control-D)	Same as q.		
w file	Same as \dot{s} with the mail header line(s) stripped. This can be used to save binary		
	mail bodies.		
u	Remove mark for deletion.		
Х	Exit, without changing the mailbox file.		
У	Synchronize with the mail box. Any deleted messages are purged and any new		
	messages read. This is equivalent to quiting nedmail and restarting.		
command	Run the <i>command</i> with the message body as standard input.		
command	Run the <i>command</i> with the whole message as standard input.		
! command	Escape to the shell to do <i>command</i> .		
=	Print the number of the current message.		
Here's an examp	le of a mail session that looks at a summary of the mail messages, saves away an		

html file added as an attachment to a message and then deletes the message:

```
% mail
```

```
7 messages
  ,h
2
       2129
               07/22 12:30
                             noone@madeup.net "Add Up To 2000 free miles"
1
    Η
2
               07/22 11:43
        504
                             jmk
З
               07/20 09:05
    Η
        784
                             presotto
                                           "You don't call, you don't write..."
4
        822
               07/11 09:23
                             xxx@yyy.net
5
               07/06 16:55
        193
                             presotto
6
        529
               06/01 19:42
                             jmk
7
        798
               09/02 2000
                             howard
: 1H
1
        multipart/mixed
                                     2129
                                             from=noone@madeup.net
1.1
          text/plain
                                     115
          text/html
                                     1705
                                             filename=northwest.htm
1.2
: 1.2w /tmp/northwest.html
!saved in /tmp/northwest.html
1.2: d
1: q
!1 message deleted
%
```

Notice that the delete of message 1.2 deleted the entire message and not just the attachment.

FILES

/mail/box/*

mail directories

194

<pre>/mail/box/*/mbox /mail/box/*/forward /mail/box/*/pipeto /mail/box/*/L.reading /mail/box/*/L.mbox</pre>	mailbox files forwarding address(es) mail filter mutual exclusion lock for multiple mbox readers mutual exclusion lock for altering mbox
/mail/box/*/L.mbox	mutual exclusion lock for altering mbox
	•

SOURCE

/sys/src/cmd/upas/ned

SEE ALSO

mail(1), aliasmail(8), filter(1), marshal(1), mlmgr(1), nedmail(1), upasfs(4), smtp(8), faces(1), rewrite(6)

netstat - summarize network connections

SYNOPSIS

```
netstat[-in][-p proto][netmtpt]
```

DESCRIPTION

Netstat prints information about network mounted at *netmtpt*, default /net. For *IP* connections, *netstat* reports the protocol, connection number, user, connection state, local port, remote port and remote address.

The options are:

- Instead of the usual listing, print one line per network interface. Each line gives the device, MTU, local address, mask, remote address, packets in, packets out, errors in, and errors out for this interface.
- -n By default, *netstat* looks up port numbers and addresses in the network databases to print symbolic names if possible. This option disables such translation.
- -p Show only connections with the given protocol.

FILES

/net/*/*

SOURCE

/sys/src/cmd/netstat.c

SEE ALSO

ipconfig(8)

news – print news items

SYNOPSIS

news [-a] [-n] [*item* ...]

DESCRIPTION

When invoked without options, this simple local news service prints files that have appeared in /lib/news since last reading, most recent first, with each preceded by an appropriate header. The time of reading is recorded. The options are

- -a Print all items, regardless of currency. The recorded time is not changed.
- -n Report the names of the current items without printing their contents, and without changing the recorded time.

Other arguments select particular news items.

To post a news item, create a file in /lib/news.

You may arrange to receive news automatically by registering your mail address in /sys/lib/subscribers. A daemon mails recent news to all addresses on the list.

Empty news items, and news items named core or dead.letter are ignored.

FILES

/lib/news/*	articles
<pre>\$HOME/lib/newstime</pre>	modify time is time news was last read
/sys/lib/subscribers	who gets news mailed to them

SOURCE

/sys/src/cmd/news.c

newt - network news transport protocol (NNTP) client

SYNOPSIS

newt [-f newsgroup] [-m mountpoint] [-p maxposts]

DESCRIPTION

Newt provides an interactive, text-based interface to NNTP articles served by nntpfs(4).

There are a number of options:

- -f Load the specified newsgroup. Default is alt.test.
- -m Directory where *nntpfs* is mounted. Default is /mnt/news.
- -p Number of posts to display, up to and including the most recent post. Default is 30.

Newt starts by reading the list of messages in the *newsgroup*, printing out the number of messages, and then prompting for commands. The prompt itself represents the name of the group followed by the message number in the form of a file system path, relative to the *mountpoint*.

Commands, as in ed(1), are of the form '[*range*] *command* [*arguments*]'. The command is applied to each message in the (optional) range.

The address range can be:

address to indicate a single message header.

address, *address* to indicate a range of contiguous message headers.

The addresses can be:

number to indicate a particular message.

The commands are:

number

Print message *number*.

- b Print the headers for the next ten messages.
- e Enter a new message, honoring the environment variable *editor*. Default is *hold*(1).
- g newsgroup

Change to the specified *newsgroup*. The name of a group may be provided in dotted (*alt.test*) or path (*alt/test*) format.

h Print the disposition, date, sender and subject line of the message. These lines are suitable for selecting and sending to the prompt, in order to print messages either singly or in aggregate.

help Print a summary of the available commands.

k [newsgroup]

Without an argument, k walks the directories under the current group and prints commands suitable for changing to each available sub-group. When provided with an argument, it instead walks the directories under the group specified by the argument.

kf regexp

Greps \$home/lib/newsgroups for *regexp* and prints commands suitable for changing to each match.

- p Print the current message with minimal headers.
- P Print the raw message with full headers.
- q Quit.
- r Reply to the current message.
- y Synchronize message list with the server.

| command

Run the *command* with the message body as standard input.

| | command

Run the *command* with the whole message as standard input.

! command

Escape to the shell to do command.

" Print the current message in quoted form, suitable for reply.

The environment variables \$editor and \$pager are honored.

FILES

\$home/lib/newsgroups list of newsgroups, one per line

SOURCE

/rc/bin/newt

SEE ALSO

nntpfs(4)

BUGS

The list of available newsgroups offered by a given server may be quite large. This complicates walking the list over a slow Internet connection, and renders searching in real-time all but infeasible. Grepping a pre-generated newsgroups file is a compromise.

HISTORY

Newt first appeared in 9front (April, 2014).

nietzsche – print out Nietzsche quote

SYNOPSIS

nietzsche[numbers]

DESCRIPTION

Nietzsche cites "Human, all too human" by Friedrich Nietzsche. It prints the aphorisms with the numbers given as arguments, or a random one, if no argument is supplied.

FILES

/lib/human

SOURCE

/rc/bin/nietzsche

HISTORY

Nietzsche first appeared in 9front (July, 2011).

gb, gba, nes, snes – emulators

SYNOPSIS

games/gb [-acd] [-C ...] [-x scale] romfile
games/gba [-a] [-b biosfile] [-s savetype] [-x scale] romfile
games/nes [-aos] [-x scale] romfile
games/snes [-ahms] [-x scale] romfile

DESCRIPTION

Gb, gba, nes and *snes* are emulators for the Nintendo Game Boy and Game Boy Color (GB and GBC), Nintendo Game Boy Advance (GBA), Nintendo Entertainment System (NES), and Super Nintendo Entertainment System (SNES). They execute the romfile given as an argument. The **z**, **x**, **a**, **s**, **q**, **w**, return and shift keys correspond to B, A, Y, X, L1, L2, Start and Select, respectively. Other keys:

- F1 Pause the emulator. If already paused it will step one video frame.
- F5 Save the current state in **gb.save** / **gba.save** / **nes.save** / **snes.save**.
- F6 Load the current state from **gb.save** / **gba.save** / **nes.save** / **snes.save**.
- F12 Toggle the emulator's speedometer. It shows in the upper left, off-viewport corner, the ratio between the expected and observed time it took to draw 60 frames.
- t Toggle tracing of the emulator.
- ' It uncaps the 60fps frame rate and lets emulation go as fast as possible.
- Esc Pause the emulator.
- Del Exit the emulator.

Command line options:

- -a Enable audio output.
- -x Scale the screen to a given factor regardless of the window's size.

gb options:

- -c Run GBC roms in GBC mode and DMG (GB) roms in GBC's DMG compatibility mode.
- -d Run GB roms in DMG mode. GBC-only roms will not run in this mode; others will run only in black & white.
- -Cnnnnn,nnnnn,nnnnn,nnnnn
 - Select a color palette. Has no effect on roms in color mode. The syntax is of the form -C ffffff,aaaaaa,555555,000000 (using HTML style rrggbb notation).

gba options:

- -b Location of the GBA BIOS file (required to operate the emulator). Default is /sys/games/lib/gbabios.bin.
- -s Save format used by the original game. Valid formats are: eeprom4, eeprom64, sram256, flash512, flash1024. The number corresponds to the size, in kilobits, of the save file. By default, the emulator attempts to automatically detect the save format, but does not always succeed.

nes options:

- -o Hide the top and bottom eight pixels (overscan area), like a real television would.
- -s Save contents of battery backed SRAM (used by some games for savegames) as a file (*gb* and *snes* automatically detect if this is needed).

snes options:

- -h Override HiROM/LoROM detection: -h sets LoROM, -hh sets HiROM.
- -m Enable mouse emulation using system mouse. Mouse button 1 (left button) engages the SNES left mouse button. Mouse button 3 (right button) engages the SNES right mouse button. Holding down mouse button 2 (middle button) disengages the SNES mouse entirely so that the Plan 9 cursor offset can be adjusted to align with the SNES cursor.

SOURCE

```
/sys/src/games/gb
/sys/src/games/gba
/sys/src/games/nes
/sys/src/games/snes
```

BUGS

You bet! SRAM saving on the NES only functions when the -s option is used. The SNES horizontal hires mode is supported only with -2 scaling. All emulators assume a North American (i.e. NTSC) system. PAL games (and in some cases Japanese games) are not supported.

HISTORY

Gb first appeared in 9front (April, 2012). *Gba* first appeared in 9front (September, 2014). *Nes* first appeared in 9front (February, 2014). *Snes* first appeared in 9front (March, 2014).

nm - name list (symbol table)

SYNOPSIS

nm[-aghnsTu]*file...*

DESCRIPTION

Nm prints the name list of each executable or object *file* in the argument list. If the *file* is an archive (see ar(1)), the name list of each file in the archive is printed. If more than one file is given in the argument list, the name of each file is printed at the beginning of each line.

Each symbol name is preceded by its hexadecimal value (blanks if undefined) and one of the letters

- U undefined symbol
- T text segment symbol
- t static text segment symbol
- L leaf function text segment symbol
- 1 static leaf function text segment symbol
- D data segment symbol
- d static data segment symbol
- B bss segment symbol
- b static bss segment symbol
- a automatic (local) variable symbol
- p function parameter symbol
- z source file name
- Z source file line offset
- f source file name components

The output is sorted alphabetically.

Options are:

- -a Print all symbols; normally only user-defined text, data, and bss segment symbols are printed.
- -g Print only global (T, L, D, B) symbols.
- -h Do not print file name headers with output lines.
- -n Sort according to the address of the symbols.
- -s Don't sort; print in symbol-table order.
- -T Prefix each line with the symbol's type signature.
- -u Print only undefined symbols.

SOURCE

/sys/src/cmd/nm.c

SEE ALSO

ar(1), *2l*(1), *db*(1), *acid*(1), *a.out*(6)

ns - display name space

SYNOPSIS

ns [–r] [*pid*]

DESCRIPTION

Ns prints a representation of the file name space of the process with the named *pid*, or by default itself. The output is in the form of an rc(1) script that could, in principle, recreate the name space. The output is produced by reading and reformatting the contents of /proc/pid/ns.

By default, *ns* rewrites the names of network data files to represent the network address that data file is connected to, for example replacing /net/tcp/82/data with tcp!123.122.121.9. The -r flag suppresses this rewriting.

FILES

/proc/*/ns

SOURCE

/sys/src/cmd/ns.c

SEE ALSO

ps(1), *proc*(3), *namespace*(4), *namespace*(6)

BUGS

The names of files printed by *ns* will be inaccurate if a file or directory it includes has been renamed.

The name of this tool is reminiscent of National Socialism and NeXTSTEP, it's hard to decide which one is worse.

opl3 - OPL3 chip emulator

SYNOPSIS

opl3 [-n rate] [file]

DESCRIPTION

Opl3 is an emulator of a single Yamaha 262 chip, also known as OPL3.

The emulated chip is programmed by a stream of commands either from *file* or from standard in. It then synthesizes a number of stereo 16 bit little-endian samples for a sampling rate of 44.1 kHz, and writes them to standard out.

Commands are 5 bytes wide, in little-endian byte order:

register[2] value[1] delay[2]

Each command specifies a *value* to be written to an OPL3 chip *register*, modifying its internal state.

The *delay* field provides timing. It is a multiple of a command period, during which the OPL3 chip may be sampled before processing the next command. The period itself is the inverse of the command rate, 44100 Hz by default. This rate can be set using the -n parameter.

SOURCE

/sys/src/games/opl3

SEE ALSO

audio(3)

HISTORY

Opl3 first appeared in 9front (July, 2018), based on *ymf262.c* from the Multiple Arcade Machine Emulator (MAME).

os - interface to host OS commands (drawterm only)

SYNOPSIS

os [-b] [-m mountpoint] [-d dir] [-n] [-N level] cmd [arg...]

DESCRIPTION

Os uses a cmd(3) device to execute a command, cmd, on a host system. If the -m option is given, os uses the device at *mountpoint*, otherwise it is assumed to be at /mnt/term/cmd.

The -d option causes the command to run in directory *dir*; an error results and the command will not run if *dir* does not exist or is inaccessible. The standard output and standard error of the command appear on the standard output and standard error streams of the *os* command itself. *Os* copies the standard input to the remote command's standard input; redirect *os*'s input to /dev/null if there is no input to the command. *Os* terminates when *cmd* does, and its exit status reflects the status of *cmd* (if available).

If the *os* command is killed or exits (eg, for lack of input and output), the host's own process control operations are used to (attempt to) kill *cmd*, if it is still running. The -b (background) option suppresses that behaviour.

The -n option causes *cmd* to run with less than normal priority ('nice'). The -N option sets low priority to a particular *level* from 1 to 3.

FILES

/mnt/term/cmd/clone

SOURCE

/sys/src/cmd/os.c

SEE ALSO

rcpu(1), *cmd*(3)

DIAGNOSTICS

The exit status of *os* reflects any error that occurs when starting *cmd* and, if it starts successfully, the status of *os* is the exit status of *cmd*.

p - paginate

SYNOPSIS

p [– number] [file ...]

DESCRIPTION

P copies its standard input, or the named files if given, to its standard output, stopping at the end of every 22nd line, and between files, to wait for a newline from the user. The option sets the *number* of lines on a page.

While waiting for a newline, *p* interprets the commands:

- ! Pass the rest of the line to the shell as a command.
- q Quit.

SOURCE

/sys/src/cmd/p.c

page - view FAX, image, graphic, PostScript, PDF, and typesetter output files

SYNOPSIS

page [-iRw] [-p ppi] [-j addr] [file...]

DESCRIPTION

Page is a general purpose document viewer. It can be used to display the individual pages of a PostScript, PDF, or *troff*(1) device independent output file. *Troff* output is simply converted to PostScript in order to be viewed. It can also be used to view any number of graphics files (such as a FAX page, a Plan 9 *image*(6) file, an Inferno bitmap file, or other common format). *Page* displays these in sequence. In the absence of named files, *page* reads one from standard input.

By default, *page* runs in the window in which it is started and leaves the window unchanged. The -R option causes *page* to grow the window if necessary to display the page being viewed. The -w option causes *page* to create a new window for itself. The newly created window will grow as under the -R option.

The -p option sets the resolution for PostScript and PDF files, in pixels per inch. The default is 100 ppi.

When viewing images with *page*, it listens to the image plumbing channel (see *plumber*(4)) for more images to display. The -i option causes *page* to not load any graphics files nor to read from standard input but rather to listen for ones to load from the plumbing channel.

The -j option with a page address *addr* jumps to the specified page on startup.

Pressing and holding button 1 permits panning about the page.

Button 2 raises a menu of operations on the current image or the entire set. The image transformations are non-destructive and are valid only for the currently displayed image. They are lost as soon as another image is displayed. The button 2 menu operations are:

Orig size

Urig size		
Restores the image to the original. All modifications are lost.		
Zoom controls magnification.		
Fit Resizes the image so that it fits in the current window.		
Rotate 90		
Rotates the image 90 degrees clockwise		
Upside down		
Toggles whether images are displayed upside-down.		
Next Displays the next page.		
Prev Displays the previous page.		
Snarf Writes the current page address to the snarf buffer.		
Zerox Displays the current image in a new page window. Useful for selecting important pages		
from large documents.		
Write Asks for a filename and writes the current image as Plan 9 bitmap.		
Ext Shows the current image using external <i>jpg</i> (1) program in a separate window. This is		
mostly useful for animated gifs.		
Button 3 raises a menu of the pages to be selected for viewing in any order.		
Typing a q or control-D exits the program.		
To go to a specific page, one can type its number followed by enter. Typing left arrow or back-		

space displays the previous page. Typing right arrow, space, or enter displays the next page. The up and down arrow pan up and down one half screen height, changing pages when panning off the top or bottom of the page.

Page calls gs(1) to draw each page of PostScript and PDF *files*. It also calls a variety of conversion programs, such as those described in jpg(1), to convert the various raster graphics formats into Inferno bitmap files. Pages are converted "on the fly," as needed.

EXAMPLES

page /sys/src/cmd/gs/examples/tiger.eps Display a color PostScript file.

```
page /usr/inferno/icons/*.bit
Browse the Inferno bitmap library.
page -j /sys/doc/troff.ps!7 /sys/doc/troff.ps
Jump to page 7 in the troff manual.
man -t page | page -w
```

Preview this manual in a new window.

SEE ALSO

gs(1), jpg(1), troff(1)

SOURCE

/sys/src/cmd/page.c

BUGS

The interface to the plumber is experimental.

HISTORY

Page first appeared in Plan 9 from Bell Labs. It was rewritten from scratch for 9front (September, 2011).

paint - create image files by drawing with a mouse or other pointing device

SYNOPSIS

paint [file]

DESCRIPTION

Paint displays a canvas upon which can be drawn lines using the mouse holding down buttons 1 or 2 for foreground or background color. The canvas may be moved with button 3. Colors and brush sizes may be selected by clicking on the palette at the bottom of the screen with buttons 1 or 2. Clicking button 3 on the palette allows changing a color by entering its hex value.

If the optional *file* argument is specified, then it is read and used as the canvas. *Paint* only recognizes Plan 9 bitmap format (see *image*(6)).

A number of immediate keyboard commands are recognized:

- u Undos the previous action.
- c Clears the canvas with the background color.
- 1-9 Select brush size.
- f Select flood fill brush.
- + Doubles magnification.
- Halves magnification.

esc Centers the canvas and resets magnification.

Hitting any other key on the keyboard shows a command prompt where the following commands may be entered:

- rfile Reads the canvas from file.
- wfile Writes the canvas to file.
- <command

Executes *command* and reads the canvas from its standard output.

>command

Executes *command* and writes the canvas to its standard input.

| command

Transforms the canvas by piping it thru command.

q Quits the program.

SOURCE

/sys/src/cmd/paint.c

SEE ALSO

resample(1), rotate(1), crop(1), jpg(1), page(1), image(6)

HISTORY

Paint first appeared in 9front (October, 2011).

passwd, netkey - change or verify user password

SYNOPSIS

passwd [-1] [username[@domain]]

netkey

DESCRIPTION

Passwd changes the invoker's Plan 9 password and/or APOP secret. The Plan 9 password is used to login to a terminal while the APOP secret is used for a number of external services: POP3, IMAP, and VPN access. The optional argument specifies the user name and authentication domain to use if different than the one associated with the machine *passwd* is run on.

The program first prompts for the old Plan 9 password in the specified domain to establish identity. It then prompts for changes to the password and the secret. New passwords and secrets must be typed twice, to forestall mistakes. New passwords must be sufficiently hard to guess. They may be of any length greater than seven characters.

By default, passwd requires the auth server to support dp9ik(6). The -1 flag forces passwd to authenticate using p9sk1(6).

Netkey prompts for a password to encrypt network challenges. It is a substitute for a SecureNet box. It may only be run on a terminal.

SOURCE

/sys/src/cmd/auth/passwd.c
/sys/src/cmd/auth/netkey.c

SEE ALSO

readnvram in authsrv(2), encrypt(2), cons(3), auth(8), securenet(8)

Robert Morris and Ken Thompson, "UNIX Password Security," AT&T Bell Laboratories Technical Journal Vol 63 (1984), pp. 1649-1672

BUGS

Now that *cpu* connections are always encrypted, the only good reason to require that these commands be run only on terminals is concern that the CPU server might be subverted.

patch - simple patch creation and tracking system

SYNOPSIS

patch/create name email files ... [< description]</pre>

patch/list[name...]

patch/diff name

patch/apply name

patch/undo name

patch/note name[< note]</pre>

DESCRIPTION

These scripts are a simple patch submission and tracking system used to propose additions or changes to Plan 9. There is no guarantee that any patch will be accepted, nor that it will be accepted verbatim. Each patch has a *name* (lowercase letters, numbers, dash, dot, and underscore only) and is stored in /n/sources/patch/name.

Patch/create creates a new patch consisting of the changes to the listed files from the distribution, reading a description of the patch from standard input: please provide an explanation of what the change is supposed to do, some context, and a rationale for the change. Test data or pointers to same to verify that the fix works are also welcome. When sending a patch, follow these guidelines:

- Before preparing the patch, run *replica/pull* and base your patch on current distribution source code.
- If this is a bug fix, explain the bug clearly. Don't assume the bug is obvious from the fix.
- If this is a new feature, explain it clearly. Don't assume it is obvious from the change.
- Make the new code look as much like the old code as possible: don't make gratuitous changes, and do follow the style of the old code. See *style*(6) for the canonical Plan 9 coding style.
- If your patch changes externally-visible behaviour, update the manual page.

The *email* address, if not –, will be sent notification messages when the patch is applied, rejected, or commented on. If rejected, the e-mail will contain a note explaining why and probably listing suggested changes and encouraging you to resubmit.

Patch/list displays information about the named patches, or all currently pending patches if none are specified.

Patch/diff shows a patch as diffs between the original source files and the patched source files.

Patch/apply applies the patch to the current source tree. It is intended to be run by the Plan 9 developers with pie as their root file system. If the source has changed since the patch was created, *apply* will report the conflict and not change any files. Before changing any files, *patch/apply* makes backup copies of the current source tree's files. The backups are stored in the patch directory.

Patch/undo will copy the backups saved by *patch/apply* back into the source tree. It will not restore a backup if the file being replaced is not byte-identical to the one created by *patch/apply*.

EXAMPLES

Propose a change to *pwd*, which you have modified locally:

```
% patch/create pwd-errors user@host.dom /sys/src/cmd/pwd.c
Fix pwd to print errors to fd 2 rather than 1.
^D
%
```

Then the developers at Bell Labs run

```
patch/diff pwd-errors
```

to inspect the change (possibly viewing /n/sources/patch/pwd-errors/pwd.c to see the larger context). To make the change, they run

patch/apply pwd-errors

Otherwise they run

```
% patch/note pwd-errors
Pwd should definitely print errors to fd 1 because ...
^D
%
```

to add a note to the /n/sources/pwd-errors/notes file.

FILES

/n/sources/patch

SOURCE

/rc/bin/patch

SEE ALSO

diff(1)
http://plan9.bell-labs.com/wiki/plan9/How_to_contribute

pc – programmer's calculator

SYNOPSIS

pc [–n]

DESCRIPTION

Pc is an arbitrary precision integer calculator with a special emphasis on supporting two's complement bit operations and working with different number bases.

Pc reads input statements which are either expressions or control statements. Multiple statements in one line can be separated by semicolons. *Pc* prints the value of all expressions that are not terminated by a semicolon.

Pc can be run non-interactively by using the -n switch. In this case no input prompt is printed.

Expressions can use the C-like operators

+ - * ** (exponentiation)

/ % (Euclidean division, by default)

& | ^ ~ ! << >>

&& || (returning the second argument, if appropriate)

< >= < <= == !=

The \$ operator performs sign extension. n\$x truncates x to n bits and sign extends. If n is omitted, it is inferred from the highest set bit (the result is always ≤ 0 in this case).

Variables can be defined using =. The builtin variable @ always refers to the last printed result.

Numbers can use the prefixes 0b (binary), 0 (octal), 0d (decimal) and 0x (hexadecimal). _ in numbers can be added for readability and is ignored.

Builtin functions

bin(n)	Display <i>n</i> in binary.
oct(n)	Display <i>n</i> in octal.
dec(n)	Display <i>n</i> in decimal.
hex(n)	Display <i>n</i> in hexadecimal.
pb(n, b)	Display n in base b (currently must be one of 0, 2, 8, 10, 16; 0 uses the
	defined output base).
abs(n)	Absolute value of <i>n</i> .
round(n,m)	n rounded to the nearest multiple of m. Numbers exactly halfway between
	are rounded to the next even multiple.
floor(n,m)	<i>n</i> rounded down to the next multiple of <i>m</i> .
ceil(n,m)	<i>n</i> rounded up to the next multiple of <i>m</i> .
trunc(n,m)	<i>n</i> truncated to <i>m</i> bits.
xtend(n,m)	<i>n</i> truncated to <i>m</i> bits, with the highest bit interpreted as a sign bit.
rev(n,m)	<i>n</i> truncated to <i>m</i> bits, with the order of bits reversed.
ubits(n)	The minimum number of bits required to represent <i>n</i> as an unsigned number.
sbits(n)	The minimum number of bits required to represent <i>n</i> as an signed number.
nsa(n)	The number of bits set in <i>n</i> .
$cat(a_0, n_0,, a_N, n_N)$	Truncate each of the <i>a_i</i> arguments to <i>n_i</i> bits and concatenate their binary rep-
	resentation.
gcd(n,m)	The greatest common divisor of <i>n</i> and <i>m</i> .
clog(a,b)	The ceiling of the logarithm of <i>a</i> with respect to base <i>b</i> . <i>b</i> can be omitted, in
	which case it defaults to 2.
minv(n,m)	The inverse of <i>n</i> mod <i>m</i> .
rand(n)	A random number satisfying $0 \le rand(n) < n$.
_	

Control statements

Control statements are always evaluated with default input base 10.

n If $n \neq 0$, insert _ in all printed numbers, every *n* digits.

- < *n* Set the default input base to *n* (default 10). The input base can always be overriden by the base prefixes defined above.
- > *n* Set the output base to *n*. If n = 0 (default), print each number in the base it was input in.
- / 0 Use Euclidean division (default). a / b is rounded towards $\pm \infty$ (opposite sign as b). a % b is always non-negative.
- / 1 Use truncating division (same as C). a / b is rounded towards zero. a % b can be negative.
- '1 Enable numbering bits (disable with 0). If the base is a power of two, print the number of the corresponding bit above each digit.

SOURCE

/sys/src/cmd/pc.y

SEE ALSO

bc(1), *hoc*(1)

BUGS

With the input base set to 16, terms such as ABC are ambiguous. They are interpreted as numbers only if there is no function or variable of the same name. To force interpretation as a number, use the 0x prefix.

Arbitrary bases should be supported, but are not supported by the mp(2) string functions.

HISTORY

Pc first appeared in 9front (August, 2016).

pcc – APE C compiler driver

SYNOPSIS

pcc [option ...] [name ...]

DESCRIPTION

Pcc compiles and loads C programs, using APE (ANSI C/POSIX) include files and libraries. Named files ending with .c are preprocessed with cpp(1), then compiled with one of the compilers described in 2c(1), as specified by the environment variable objtype. The object files are then loaded using one of the loaders described in 2l(1). The options are:

- -o *out* Place loader output in file *out* instead of the default 2.out, v.out, etc.
- -P Omit the compilation and loading phases; leave the result of preprocessing *name*.cin *name*.i.
- -E Like -P, but send the result to standard output.
- -c Omit the loading phase.
- -p Insert profiling code into the executable output.
- -w Print compiler warning messages.
- -1*lib* Include / *\$objtype*/lib/ape/lib*lib*. a as a library during the linking phase.
- -B Don't complain about functions used without ANSI function prototypes.
- -V Enable void* conversion warnings, as in 2c(1).
- -v Echo the preprocessing, compiling, and loading commands before they are executed.

–Dname=def

- -Dname Define the name to the preprocessor, as if by #define. If no definition is given, the name is defined as 1.
- -Uname Undefine the *name* to the preprocessor, as if by #undef.
- -I dir #include files whose names do not begin with / are always sought first in the directory of the *file* argument, then in directories named in -I options, then in /\$objtype/include/ape.
- -N Don't optimize compiled code.
- -S Print an assembly language version of the object code on standard output.
- -a Instead of compiling, print on standard output acid functions (see *acid*(1)) for examining structures declared in the source files.
- -aa Like -a except that functions for structures declared in included header files are omitted.
- -F Enable vararg type checking as described in *2c*(1). This is of limited use without the appropriate #pragma definitions.

The APE environment contains all of the include files and library routines specified in the ANSI C standard (X3.159–1989), as well as those specified in the IEEE Portable Operating System Interface standard (POSIX, 1003.1–1990, ISO 9945–1). In order to access the POSIX routines, source programs should define the preprocessor constant _POSIX_SOURCE.

FILES

/sys/include/ape	directory for machine-independent #include files.
/\$objtype/include/ape	directory for machine-dependent #include files.
/\$objtype/lib/ape/libap.a	ANSI C/POSIX library.

SEE ALSO

cpp(1), *2c*(1), *2a*(1), *2l*(1), *mk*(1), *nm*(1), *acid*(1), *db*(1), *prof*(1)

Howard Trickey, "APE — The ANSI/POSIX Environment"

SOURCE

/sys/src/cmd/pcc.c

BUGS

The locale manipulation functions are minimal. Signal functions and terminal characteristic handlers are only minimally implemented. *Link* always fails, because Plan 9 doesn't support multiple links to a file. The functions related to setting effective user and group ids cannot be implemented because the concept doesn't exist in Plan 9.

pic - troff preprocessor for drawing pictures

SYNOPSIS

pic [files]

DESCRIPTION

Pic is a *troff*(1) preprocessor for drawing figures on a typesetter. *Pic* code is contained between . PS and . PE lines:

. PS optional-width optional-height element-list . PE

or in a file mentioned in a . PS line:

.PS <file

If *optional-width* is present, the picture is made that many inches wide, regardless of any dimensions used internally. The height is scaled in the same proportion unless *optional-height* is present. If . PF is used instead of . PE, the typesetting position after printing is restored to what it was upon entry.

An *element-list* is a list of elements:

```
primitive attribute-list
placename : element
placename : position
var = expr
direction
{ element-list }
[ element-list ]
for var = expr to expr by expr do { anything }
if expr then { anything } else { anything }
copy file, copy thru macro, copy file thru macro
sh { commandline }
print expr
reset optional var-list
troff-command
```

Elements are separated by newlines or semicolons; a long element may be continued by ending the line with a backslash. Comments are introduced by a # and terminated by a newline. Variable names begin with a lower case letter; place names begin with upper case. Place and variable names retain their values from one picture to the next.

After each primitive the current position moves in the current direction (up,down, left,right (default)) by the size of the primitive. The current position and direction are saved upon entry to a $\{...\}$ block and restored upon exit. Elements within a block enclosed in [...] are treated as a unit; the dimensions are determined by the extreme points of the contained objects. Names, variables, and direction of motion within a block are local to that block.

Troff-command is any line that begins with a period. Such a line is assumed to make sense in the context where it appears; generally, this means only size and font changes.

The *primitive* objects are:

box circle ellipse arc line arrow spline move text-list arrow is a synonym for line ->.

An *attribute-list* is a sequence of zero or more attributes; each attribute consists of a keyword, perhaps followed by a value.

h(eigh)t <i>expr</i>	wid(th) <i>expr</i>
rad(ius) <i>expr</i>	diam(eter) <i>expr</i>
up opt–expr	down <i>opt–expr</i>
right opt-expr	left opt-expr
from position	to position

at position	with <i>corner</i>
by <i>expr, expr</i>	then
dotted <i>opt-expr</i>	dashed opt-expr
chop <i>opt–expr</i>	-> <- <->
invis	same
fill opt–expr	
text–list	expr
dotted opt-expr chop opt-expr invis fill opt-expr	dashed <i>opt-expr</i> -> <- <-> same

Missing attributes and values are filled in from defaults. Not all attributes make sense for all primitives; irrelevant ones are silently ignored. The attribute at causes the geometrical center to be put at the specified place; with causes the position on the object to be put at the specified place. For lines, splines and arcs, height and width refer to arrowhead size. A bare *expr* implies motion in the current direction.

Text is normally an attribute of some primitive; by default it is placed at the geometrical center of the object. Stand-alone text is also permitted. A text list is a list of text items: *text-item*:

```
"..." positioning ...
sprintf("format", expr, ...) positioning ...
positioning:
```

center ljust rjust above below If there are multiple text items for some primitive, they are arranged vertically and centered except as qualified. Positioning requests apply to each item independently. Text items may contain *troff* commands for size and font changes, local motions, etc., but make sure that these are balanced so that the entering state is restored before exiting.

A position is ultimately an *x*,*y* coordinate pair, but it may be specified in other ways.

position:

```
expr, expr
place ± expr, expr
place ± ( expr, expr )
( position, position ) x from one, y the other
expr [of the way] between position and position
expr < position, position >
( position )
```

place:

placename optional-corner corner of placename nth primitive optional-corner corner of nth primitive Here

An *optional-corner* is one of the eight compass points or the center or the start or end of a primitive.

optional-corner:

```
.n .e .w .s .ne .se .nw .sw .c .start .end

corner:

top bot left right start end

Each object in a picture has an ordinal number; nth refers to this.
```

nth:

*n*th, *n*th last

The built-in variables and their default values are:

```
boxwid 0.75
                       boxht 0.5
circlerad 0.25
                       arcrad 0.25
ellipsewid 0.75
                       ellipseht 0.5
linewid 0.5
                       lineht 0.5
movewid 0.5
                       moveht 0.5
textwid 0
                       textht 0
arrowwid 0.05
                       arrowht 0.1
dashwid 0.1
                       arrowhead 2
scale 1
```

These may be changed at any time, and the new values remain in force from picture to picture

until changed again or reset by a reset statement. Variables changed within [and] revert to their previous value upon exit from the block. Dimensions are divided by scale during output.

Expressions in *pic* are evaluated in floating point. All numbers representing dimensions are taken to be in inches.

```
expr:
    expr op expr
    - expr
    ! expr
    ( expr )
    variable
    number
    place .x place .y place .ht place .wid place .rad
    sin(expr) cos(expr) atan2(expr,expr) log(expr) exp(expr)
    sqrt(expr) max(expr,expr) min(expr,expr) int(expr) rand()
op:
```

The define and undef statements are not part of the grammar.

define name { replacement text }

undef *name*

Occurrences of \$1, \$2, etc., in the replacement text will be replaced by the corresponding arguments if *name* is invoked as

name(arg1, arg2, ...)

Non-existent arguments are replaced by null strings. Replacement text may contain newlines. The undef statement removes the definition of a macro.

SOURCE

/sys/src/cmd/pic

SEE ALSO

grap(1), doctype(1), troff(1)

B. W. Kernighan, "PIC—a Graphics Language for Typesetting", Unix Research System Programmer's Manual, Tenth Edition, Volume 2

pipefile - attach filter to file in name space

SYNOPSIS

pipefile[-d][-r command][-w command] file

DESCRIPTION

Pipefile uses *bind*(2) to attach a pair of pipes to *file*, using them to interpose filter *commands* between the true file and the simulated file that subsequently appears in the name space. Option -r interposes a filter that will affect the data delivered to programs that read from *file*; -w interposes a filter that will affect the data written by programs to *file*. At least one *command* must be specified; *pipefile* will insert a *cat*(1) process in the other direction.

After *pipefile* has been run, the filters are established for programs that subsequently open the *file*; programs already using the *file* are unaffected.

Pipefile opens the *file* twice, once for each direction. If the *file* is a single-use device, such as /dev/mouse, use the -d flag to specify that the file is to be opened once, in ORDWR mode.

EXAMPLES

Simulate an old terminal:

% pipefile -w 'tr a-z A-Z' /dev/cons % rc -i </dev/cons >/dev/cons >[2=1] % echo hello HELLO %

Really simulate an old terminal:

```
% pipefile -r 'tr A-Z a-z' -w 'tr a-z A-Z' /dev/cons
% rc -i </dev/cons >/dev/cons >[2=1]
% DATE
THU OCT 12 10:13:45 EDT 2000
%
```

SOURCE

```
/sys/src/cmd/pipefile.c
```

SEE ALSO

mouse(8)

BUGS

The I/O model of *pipefile* is peculiar; it doesn't work well on plain files. It is really intended for use with continuous devices such as */dev/cons* and */dev/mouse*. *Pipefile* should be rewritten to be a user-level file system.

If the program using the file managed by *pipefile* exits, the filter will see EOF and exit, and the file will be unusable until the name space is repaired.

play - simple audio player

SYNOPSIS

play [-o file] [file | url ...]

DESCRIPTION

Play is a simple audio player that understands a number of audio and playlist formats.

If no *file* or *url* arguments are given, standard input is used. The file type is determined using the file(1) command and a matching *audio*(1) decoder is applied.

By default, raw audio data is written to /dev/audio unless changed with the -o option.

SOURCE

/rc/bin/play

SEE ALSO

audio(1), hget(1)

HISTORY

Play first appeared in 9front (January, 2012).

plot - graphics filter

SYNOPSIS

plot [*file* ...]

DESCRIPTION

Plot interprets plotting instructions (see *plot*(6)) from the *files* or standard input, drawing the results on the screen. Plot persists until a newline is typed. Various options may be interspersed with the *file* arguments; they take effect at the given point in processing. Options are:

- -d Double buffer: accumulate the plot off-screen and write to the screen all at once when an erase command is encountered or at end of file.
- -e Erase the screen.
- -c *col* Set the foreground color (see *plot*(6) for color names).
- -f fill Set the background color.
- -g grade Set the quality factor for arcs. Higher grades give better quality.
- -p *col* Set the pen color.
- -w Pause until a newline is typed on standard input.
- -C Close the current plot.

SOURCE

/sys/src/cmd/plot

SEE ALSO

plot(6)

plumb - send message to plumber

SYNOPSIS

plumb [-p plumbfile] [-a attributes] [-s source] [-d destination] [-t type] [-w directory] -i | data...

DESCRIPTION

The *plumb* command formats and sends a plumbing message whose data is, by default, the concatenation of the argument strings separated by blanks. The options are:

- -p write the message to *plumbfile* (default /mnt/plumb/send).
- -a set the attr field of the message (default is empty).
- -s set the src field of the message (default is plumb).
- -d set the dst field of the message (default is empty).
- -t set the type field of the message (default is text).
- -w set the wdir field of the message (default is the current working directory of *plumb*).
- -i take the data from standard input rather than the argument strings. If an action= attribute is not otherwise specified, *plumb* will add an action=showdata attribute to the message.

FILES

/usr/\$user/lib/plumbing default rules file
/mnt/plumb mount point for plumber(4).

SOURCE

/sys/src/cmd/plumb

SEE ALSO

plumb(2), plumber(4), plumb(6)

pr – print file

SYNOPSIS

pr [option ...] [file ...]

DESCRIPTION

Pr produces a printed listing of one or more *files* on its standard output. The output is separated into pages headed by a date, the name of the file or a specified header, and the page number. With no file arguments, *pr* prints its standard input.

Options apply to all following files but may be reset between files:

- -*n* Produce *n*-column output.
- +n Begin printing with page n.
- -b Balance columns on last page, in case of multi-column output.
- -d Double space.
- -en Set the tab stops for input text every *n* spaces.
- -h Take the next argument as a page header (*file* by default).
- -in Replace sequences of blanks in the output by tabs, using tab stops set every *n* spaces.
- -f Use form feeds to separate pages.
- -1n Take the length of the page to be *n* lines instead of the default 66.
- -m Print all *files* simultaneously, each in one column.
- -nm Number the lines of each *file*. The numeric argument *m*, default 5, sets the width of the line-number field.
- -on Offset the left margin *n* character positions.
- -p Pad each file printed to an even number of pages, if necessary. For two-sided printers, this will ensure each file will start a new page.
- -sc Separate columns by the single character c instead of aligning them with white space. A missing c is taken to be a tab.
- -t Do not print the 5-line header or the 5-line trailer normally supplied for each page.
- -wn For multi-column output, take the width of the page to be *n* characters instead of the default 72.

SOURCE

/sys/src/cmd/pr.c

SEE ALSO

 $cat(1), \ lp(1)$

prof, tprof, kprof - display profiling data

SYNOPSIS

prof [-dr] [program] [profile]

tprof pid

kprof kernel kpdata

DESCRIPTION

Prof interprets files produced automatically by programs loaded using the -p option of 2l(1) or other loader. The symbol table in the named program file (2.out etc., according to \$objtype, by default) is read and correlated with the profile file (prof.out by default). For each symbol, the percentage of time (in seconds) spent executing between that symbol and the next is printed (in decreasing order), together with the time spent there and the number of times that routine was called.

Under option -d, *prof* prints the dynamic call graph of the target program, annotating the calls with the time spent in each routine and those it calls, recursively. The output is indented two spaces for each call, and is formatted as

symbol:time/ncall

where *symbol* is the entry point of the call, *time* is in milliseconds, and *ncall* is the number of times that entry point was called at that point in the call graph. If *ncall* is one, the /ncall is elided. Normally recursive calls are compressed to keep the output brief; option -r prints the full call graph.

The size of the buffer in *program* used to hold the profiling data, by default 2000 entries, may be controlled by setting the environment variable profsize before running *program*. If the buffer fills, subsequent function calls may not be recorded.

The profiling code provided by the linker initializes itself to profile the current pid, producing a file called prof. *pid*. If a process forks, only the parent will continue to be profiled. Forked children can cause themselves to be profile by calling

prof(fn, arg, entries, what)

which causes the function fn(arg) to be profiled. When fn returns prof. *pid* is produced for the current process pid.

The environment variable proftype can be set to one of user, kernel, elapsed, or sample, to profile time measured spent in user mode, time spent in user+kernel mode, or elapsed time, using the cycle counter, or the time in user mode using the kernel's HZ clock. The cycle counter is currently only available on modern PCs and on the PowerPC. Default profiling measures user time, using the cycle counter if it is available.

Tprof is similar to *prof*, but is intended for profiling multiprocess programs. It uses the /proc/*pid*/profile file to collect instruction frequency counts for the text image associated with the process, for all processes that share that text. It must be run while the program is still active, since the data is stored with the running program. To enable *tprof* profiling for a given process,

echo profile > /proc/pid/ctl

and then, after the program has run for a while, execute

tprof pid

Since the data collected for *tprof* is based on interrupt-time sampling of the program counter, *tprof* has no -d or -r options.

Kprof is similar to *prof*, but presents the data accumulated by the kernel profiling device, kprof(3). The symbol table file, that of the operating system kernel, and the data file, typically /dev/kpdata, must be provided. *Kprof* has no options and cannot present dynamic data.

SOURCE

/sys/src/cmd/prof.c

/sys/src/cmd/kprof.c

SEE ALSO 21(1), exec(2), kprof(3)

proof – troff output interpreter

SYNOPSIS

proof [-m mag] [-/ nview] [-F dir] [-d] [file]

DESCRIPTION

Proof reads *troff*(1) intermediate language from *file* or standard input and simulates the resulting pages on the screen.

After a page of text is displayed, *proof* pauses for a command from the keyboard. The typed commands are:

newline Go on to next page of text.

- Go back to the previous page.
- q Quit.
- pn Print page n. An out-of-bounds page number means the end nearer to that number; a missing number means the current page; a signed number means an offset to the current page.
- *n* Same as p*n*.
- c Clear the screen, then wait for another command.

mmag Change the magnification at which the output is printed. Normally it is printed with magnification .9; mag=.5 shrinks it to half size; mag=2 doubles the size.

- x *val* Move everything *val* screen pixels to the right (left, if *val* is negative).
- y *val* Move everything *val* screen pixels down (up, if *val* is negative).
- */ nview* Split the window into *nview* pieces. The current page goes into the rightmost, bottommost piece, and previous pages are shown in the other pieces.
- -F *dir* Use *dir* for fonts instead of /lib/font/bit.
- d Toggle the debug flag.

These commands are also available, under slightly different form, from a menu on button 3. The pan menu item allows arbitrary positioning of the page: after selecting pan, press the mouse button again and hold it down while moving the page to the desired location. The page will be redisplayed in its entirety when the button is released. Mouse button 1 also pans, without the need for selecting from a menu.

The m, x, y, F, /, and d commands are also available as command line options.

FILES

/lib/font/bit/* fonts
/lib/font/bit/MAP how to convert troff output fonts and character names into screen
fonts and character numbers

SOURCE

/sys/src/cmd/proof

SEE ALSO

lp(1), *gs*(1), *page*(1) J. F. Ossanna and B. W. Kernighan, "Troff User's Manual"

ps, psu, pstree – process status

SYNOPSIS

ps[-apnr]

psu[-apnr][*user*]

pstree

DESCRIPTION

Ps prints information about processes. *Psu* prints only information about processes started by *user* (default *suser*).

For each process reported, the user, process id, user time, system time, size, state, and command name are printed. State is one of the following:

Moribund	Process has exited and is about to have its resources reclaimed.

Ready on the queue of processes ready to be run.

Scheding about to be run.

Running running.

Queueing waiting on a queue for a resource.

Wakeme waiting for I/O or some other kernel event to wake it up.

Broken dead of unnatural causes; lingering so that it can be examined.

Stopped stopped.

Stopwait waiting for another process to stop.

Fault servicing a page fault.

Idle waiting for something to do (kernel processes only).

New being created.

Pageout paging out some other process.

Syscall performing the named system call.

no *resource* waiting for more of a critical *resource*.

The -n flag causes *ps* to print, after the process id, the note group to which the process belongs.

The -r flag causes *ps* to print, before the user time, the elapsed real time for the process.

The -p flag causes *ps* to print, after the system time, the baseline and current priorities of each process.

The -a flag causes *ps* to print the arguments for the process. Newlines in arguments will be translated to spaces for display.

Pstree prints the processes as a tree in a two colum layout where the first colum being the process id and second column the program name and arguments indented and prefixed with line drawing runes to reflect the nesting in the hierarchy.

FILES

/proc/*/status

SOURCE

/sys/src/cmd/ps.c /rc/bin/psu /sys/src/cmd/pstree.c

SEE ALSO

acid(1), db(1), kill(1), ns(1), proc(3)

HISTORY

Pstree first appeared in 9front (June, 2011).

ps2pdf, pdf2ps - convert between PostScript and PDF

SYNOPSIS

ps2pdf [gs-options] [input-file [output-file]]

pdf2ps [gs-options] [input-file [output-file]]

DESCRIPTION

Ps2pdf and *pdf2ps* convert from PostScript to PDF and back by invoking *gs*(1). If *output-file* is not specified, they write to standard output. If neither *input-file* nor *output-file* is not specified, they read from standard input and write to standard output.

The *gs-options* are passed to Ghostscript unaltered. The most useful option to *ps2pdf* is -dCompatibilityLevel=*level*, which sets the version of PDF to be written. The default is 1.2; 1.3 and 1.4 are also possible. Similarly, the most useful option to *pdf2ps* is -dLanguageLevel=*level*, which sets the version of PostScript to be written. The default is 2; 1 and 3 are also possible.

Ps2pdf produces output competitive with Adobe Distiller in most cases, and it accepts all the embedded PDF-generation hints that Adobe Distiller does.

Pdf2ps produces a PostScript file containing one large bitmap per page. For a more direct and smaller translation, use Adobe Acrobat's -toPostScript command-line option.

SOURCE

/rc/bin/ps2pdf
/rc/bin/pdf2ps

SEE ALSO

gs(1)

BUGS

Gs's *pdfwrite* sometimes emits bad PDF at the default level 1.2. Adding '-dCompatibilityLevel=1.4' should cure it.

pump - copy asynchronously via a large circular buffer

SYNOPSIS

```
pump [ -b iando ] [ -d sleepms ] [ -f ofile ] [ -i ireadsize ] [ -k KB-buf ] [ -o owritesize ] [ -s start-KB ] [ file ... ]
```

DESCRIPTION

Pump copies *files* (or standard input if none) to standard output by using two processes, one reading and one writing, sharing a large circular buffer, thus permitting the reading process to get ahead of the writing process if the output device is slow (e.g., an optical disc). This in turn can keep the output device busy. The pipeline dd | dd can approximate this, but pipe buffering is limited to 64K bytes, which is fairly modest.

Options are:

- -b sets the size of *read* and *write* operations to *iando* bytes. The default size is 8 kilobytes.
- -d causes the output process to sleep for *sleepms* milliseconds initially, giving the reading process time to accumulate data in the buffer.
- -f writes *ofile* rather than standard output
- -i sets the size of *read* operations to *ireadsize* bytes.
- -k allocates a circular buffer of *KB-buf* kilobytes rather than the default 5000 kilobytes.
- -o sets the size of *write* operations to *owritesize* bytes.
- -s prevents output until *start–KB* kilobytes have been read.

EXAMPLES

Append a *venti*(8) arena to a DVD or BD quickly.

```
cdfs
```

```
venti/rdarena arena0 arena.3 |
    pump -b 65536 -k 51200 >/mnt/cd/wd/arena.3
```

SOURCE

```
/sys/src/cmd/pump.c
```

SEE ALSO

cp(1), *dd*(1), *ecp*(1), *cdfs*(4)

BUGS

Pump processes spin while waiting for the circular buffer to fill or drain.

pwd, pbd – working directory

SYNOPSIS

pwd

pbd

DESCRIPTION

Pwd prints the path name of the working (current) directory. *Pwd* is guaranteed to return the same path that was used to enter the directory. If, however, the name space has changed, or directory names have been changed, this path name may no longer be valid. (See fd2path(2) for a description of pwd's mechanism.)

Pbd prints the base name of the working (current) directory. It prints no final newline and is intended for applications such as constructing shell prompts.

SOURCE

/sys/src/cmd/pwd.c
/sys/src/cmd/pbd.c

SEE ALSO

cd in *rc*(1), *bind*(1), *intro*(2), *getwd*(2), *fd2path*(2)

python - an interpreted, interactive, object-oriented programming language

SYNOPSIS

python [-d] [-E] [-h] [-i] [-m module-name] [-0]
 [-Q argument] [-S] [-t] [-u]
 [-v] [-V] [-W argument] [-x]
 [-c command | script | -] [arguments]

DESCRIPTION

Python is an interpreted, interactive, object-oriented programming language that combines remarkable power with very clear syntax. For an introduction to programming in Python you are referred to the Python Tutorial. The Python Library Reference documents built-in and standard types, constants, functions and modules. Finally, the Python Reference Manual describes the syntax and semantics of the core language in (perhaps too) much detail. (These documents may be located via the INTERNET RESOURCES below; they may be installed on your system as well.)

Python's basic power can be extended with your own modules written in C or C++. On most systems such modules may be dynamically loaded. Python is also adaptable as an extension language for existing applications. See the internal documentation for hints.

Documentation for installed Python modules and packages can be viewed by running the pydoc program.

COMMAND LINE OPTIONS

-c command

Specify the command to execute (see next section). This terminates the option list (following options are passed as arguments to the command).

- -d Turn on parser debugging output (for wizards only, depending on compilation options).
- -E Ignore environment variables like PYTHONPATH and PYTHONHOME that modify the behavior of the interpreter.
- -h Prints the usage for the interpreter executable and exits.
- -i When a script is passed as first argument or the -c option is used, enter interactive mode after executing the script or the command. It does not read the \$PYTHONSTARTUP file. This can be useful to inspect global variables or a stack trace when a script raises an exception.
- -m module-name

Searches sys.path for the named module and runs the corresponding .py file as a script.

- -0 Turn on basic optimizations. This changes the filename extension for compiled (bytecode) files from *.pyc* to *.pyo*. Given twice, causes docstrings to be discarded.
- -Q argument

Division control; see PEP 238. The argument must be one of "old" (the default, int/int and long/long return an int or long), "new" (new division semantics, i.e. int/int and long/long returns a float), "warn" (old division semantics with a warning for int/int and long/long), or "warnall" (old division semantics with a warning for all use of the division operator). For a use of "warnall", see the Tools/scripts/fixdiv.py script.

- -S Disable the import of the module *site* and the site-dependent manipulations of *sys.path* that it entails.
- -t Issue a warning when a source file mixes tabs and spaces for indentation in a way that makes it depend on the worth of a tab expressed in spaces. Issue an error when the option is given twice.
- -u Force stdin, stdout and stderr to be totally unbuffered. On systems where it matters, also put stdin, stdout and stderr in binary mode. Note that there is internal buffering in xread-lines(), readlines() and file-object iterators ("for line in sys.stdin") which is not influenced by this option. To work around this, you will want to use "sys.stdin.readline()" inside a "while 1:" loop.

- -v Print a message each time a module is initialized, showing the place (filename or built-in module) from which it is loaded. When given twice, print a message for each file that is checked for when searching for a module. Also provides information on module cleanup at exit.
- -V Prints the Python version number of the executable and exits.
- -W argument

Warning control. Python sometimes prints warning message to *sys.stderr*. A typical warning message has the following form: *file*: *line*: *category*: By default, each warning is printed once for each source line where it occurs. This option controls how often warnings are printed. Multiple –W options may be given; when a warning matches more than one option, the action for the last matching option is performed. Invalid –W options are ignored (a warning message is printed about invalid options when the first warning is issued). Warnings can also be controlled from within a Python program using the *warnings* module.

The simplest form of *argument* is one of the following *action* strings (or a unique abbreviation): ignore to ignore all warnings; default to explicitly request the default behavior (printing each warning once per source line); all to print a warning each time it occurs (this may generate many messages if a warning is triggered repeatedly for the same source line, such as inside a loop); module to print each warning only the first time it occurs in each module; once to print each warning only the first time it occurs in the program; or error to raise an exception instead of printing a warning message.

The full form of *argument* is *action*: *message*: *category*: Here, *action* is as explained above but only applies to messages that match the remaining fields. Empty fields match all values; trailing empty fields may be omitted. The *message* field matches the start of the warning message printed; this match is case-insensitive. The *category* field matches the warning category. This must be a class name; the match test whether the actual warning category of the message is a subclass of the specified warning category. The full class name must be given. The *module* field matches the (fully-qualified) module name; this match is case-sensitive. The *line* field matches the line number, where zero matches all line numbers and is thus equivalent to an omitted line number.

-x Skip the first line of the source. This is intended for a DOS specific hack only. Warning: the line numbers in error messages will be off by one!

INTERPRETER INTERFACE

The interpreter interface resembles that of the UNIX shell: when called with standard input connected to a tty device, it prompts for commands and executes them until an EOF is read; when called with a file name argument or with a file as standard input, it reads and executes a *script* from that file; when called with -c *command*, it executes the Python statement(s) given as *command*. Here *command* may contain multiple statements separated by newlines. Leading whitespace is significant in Python statements! In non-interactive mode, the entire input is parsed before it is executed.

If available, the script name and additional arguments thereafter are passed to the script in the Python variable *sys.argv*, which is a list of strings (you must first *import sys* to be able to access it). If no script name is given, *sys.argv*[0] is an empty string; if -c is used, *sys.argv*[0] contains the string '-c'. Note that options interpreted by the Python interpreter itself are not placed in *sys.argv*.

In interactive mode, the primary prompt is '>>>'; the second prompt (which appears when a command is not complete) is '...'. The prompts can be changed by assignment to *sys.ps1* or *sys.ps2*. The interpreter quits when it reads an EOF at a prompt. When an unhandled exception occurs, a stack trace is printed and control returns to the primary prompt; in non-interactive mode, the interpreter exits after printing the stack trace. The interrupt signal raises the *KeyboardInterrupt* exception; other UNIX signals are not caught (except that SIGPIPE is sometimes ignored, in favor of the *IOError* exception). Error messages are written to stderr.

FILES AND DIRECTORIES

These are subject to difference depending on local installation conventions; \${prefix} and \${exec_prefix} are installation-dependent and should be interpreted as for GNU software; they may be the same. The default for both is */usr/local*.

\${exec_prefix}/bin/python

Recommended location of the interpreter.

\${prefix}/lib/python<version>

\${exec_prefix}/lib/python<version>

Recommended locations of the directories containing the standard modules.

\${prefix}/include/python<version>

\${exec_prefix}/include/python<version>

Recommended locations of the directories containing the include files needed for developing Python extensions and embedding the interpreter.

~/.pythonrc.py

User-specific initialization file loaded by the *user* module; not used by default or by most applications.

ENVIRONMENT VARIABLES

PYTHONHOME

Change the location of the standard Python libraries. By default, the libraries are searched in fprefix/lib/python<version> and $fexec_prefix/lib/python<version>$, where frefix and $fexec_prefix$ are installation-dependent directories, both defaulting to */usr/local*. When \$PYTHONHOME is set to a single directory, its value replaces both fprefix and $fexec_prefix$. To specify different values for these, set \$PYTHONHOME to fprefix.

PYTHONPATH

Augments the default search path for module files. The format is the same as the shell's \$PATH: one or more directory pathnames separated by colons. Non-existent directories are silently ignored. The default search path is installation dependent, but generally begins with \${prefix}/lib/python<version> (see PYTHONHOME above). The default search path is always appended to \$PYTHONPATH. If a script argument is given, the directory containing the script is inserted in the path in front of \$PYTHONPATH. The search path can be manipulated from within a Python program as the variable *sys.path*.

PYTHONSTARTUP

If this is the name of a readable file, the Python commands in that file are executed before the first prompt is displayed in interactive mode. The file is executed in the same name space where interactive commands are executed so that objects defined or imported in it can be used without qualification in the interactive session. You can also change the prompts *sys.ps1* and *sys.ps2* in this file.

PYTHONY2K

Set this to a non-empty string to cause the *time* module to require dates specified as strings to include 4-digit years, otherwise 2-digit years are converted based on rules described in the *time* module documentation.

PYTHONOPTIMIZE

If this is set to a non-empty string it is equivalent to specifying the -O option. If set to an integer, it is equivalent to specifying -O multiple times.

PYTHONDEBUG

If this is set to a non-empty string it is equivalent to specifying the -d option. If set to an integer, it is equivalent to specifying -d multiple times.

PYTHONINSPECT

If this is set to a non-empty string it is equivalent to specifying the -i option.

PYTHONUNBUFFERED

If this is set to a non-empty string it is equivalent to specifying the -u option.

PYTHONVERBOSE

If this is set to a non-empty string it is equivalent to specifying the -v option. If set to an integer, it is equivalent to specifying -v multiple times.

AUTHOR

The Python Software Foundation: http://www.python.org/psf

INTERNET RESOURCES

Main website: http://www.python.org/ Documentation: http://docs.python.org/ Community website: http://starship.python.net/ Developer resources: http://www.python.org/dev/ FTP: ftp://ftp.python.org/pub/python/ Module repository: http://www.vex.net/parnassus/ Newsgroups: comp.lang.python, comp.lang.python.announce

LICENSING

Python is distributed under an Open Source license. See the file "LICENSE" in the Python source distribution for information on terms & conditions for accessing and otherwise using Python and for a DISCLAIMER OF ALL WARRANTIES.

qr – generate QR code

SYNOPSIS

qr[-LMQHna][-v version]

DESCRIPTION

Qr generates a QR code from the data it reads on standard input. The QR code is generated as an image(6) on standard output.

The -LMQH options set the level of error correction. -L is the lowest and -H is the highest level. The default is -M.

The QR standard defines different sizes labelled version 1 to version 40. By default the smallest possible is chosen automatically. The -v option forces the use of a particular version.

By default bytes are encoded directly with no translation. Coding efficiency can be increased by reducing the set of legitimate characters using the -an options. The -n option supports only numbers and the -a option supports letters, numbers, spaces and the symbols %*+-./:. Note that all letters are converted to upper case. Both options ignore any characters they do not recognize.

SOURCE

/sys/src/cmd/qr.c

SEE ALSO

International Standard ISO/IEC 18004.

BUGS

The standard specifies the use of JIS-8 encoding in the default mode, however rumour has it that readers recognize UTF-8.

The more advanced coding features (Kanji mode, extended modes, switching modes midstream) are not supported.

ratrace - trace process system calls

SYNOPSIS

ratrace[pid] | [-c command]

DESCRIPTION

Ratrace shows the system calls executed by a process, either the one with *pid* or a fresh invocation of *command*.

Trace output is determined by the kernel, not *ratrace*. Certain fixed rules apply. The first four fields of the output are pid, text name, system call name, and the PC of the user program. Data is always printed as *pointer/"string*", where the *string* is the first 32 bytes of the data, with . replacing non-printing ASCII characters (printing characters are those between ASCII space (SP) and delete (DEL), exclusive). Return values follow an =, and include the integer return value, the *errstr* (with "" if there is no *errstr*), and the start and stop times for the system call in nanoseconds. The times are exclusive of the overhead for tracing.

FILES

/proc/pid/syscall
/proc/pid/ctl

SOURCE

/sys/src/cmd/ratrace.c

SEE ALSO

acid(1), *db*(1), *proc*(3)

BUGS

The printing of the data is too limited in length; printing . instead of something more sensible is limiting.

rc, cd, eval, exec, exit, flag, rfork, shift, wait, whatis, ., ~ - command language

SYNOPSIS

rc[-srdillxepvV][-c command][-m initial][file[arg ...]]

DESCRIPTION

Rc is the Plan 9 shell. It executes command lines read from a terminal or a file or, with the -c flag, from *rc*'s argument list.

Command Lines

A command line is a sequence of commands, separated by ampersands or semicolons (& or ;), terminated by a newline. The commands are executed in sequence from left to right. *Rc* does not wait for a command followed by & to finish executing before starting the following command. Whenever a command followed by & is executed, its process id is assigned to the *rc* variable \$apid. Whenever a command *not* followed by & exits or is terminated, the *rc* variable \$status gets the process's wait message (see *wait*(2)); it will be the null string if the command was successful.

A long command line may be continued on subsequent lines by typing a backslash (\setminus) followed by a newline. This sequence is treated as though it were a blank. Backslash is not otherwise a special character.

A number-sign (#) and any following characters up to (but not including) the next newline are ignored, except in quotation marks.

Simple Commands

A simple command is a sequence of arguments interspersed with I/O redirections. If the first argument is the name of an *rc* function or of one of *rc's* built-in commands, it is executed by *rc*. Otherwise if the name starts with a slash (/), it must be the path name of the program to be executed. Names containing no initial slash are searched for in a list of directory names stored in path. The first executable file of the given name found in a directory in path is the program to be executed. To be executable, the user must have execute permission (see *stat*(2)) and the file must be either an executable binary for the current machine's CPU type, or a shell script. Shell scripts begin with a line containing the full path name of a shell (usually /bin/rc), prefixed by #!.

The first word of a simple command cannot be a keyword unless it is quoted or otherwise disguised. The keywords are

for in while if not switch fn \sim ! @

Arguments and Variables

A number of constructions may be used where *rc's* syntax requires an argument to appear. In many cases a construction's value will be a list of arguments rather than a single string.

The simplest kind of argument is the unquoted word: a sequence of one or more characters none of which is a blank, tab, newline, or any of the following:

; & | ^ \$ = ' ' { } () < >

An unquoted word that contains any of the characters *? [is a pattern for matching against file names. The character * matches any sequence of characters, ? matches any single character, and [*class*] matches any character in the *class*. If the first character of *class* is \sim , the class is complemented. The *class* may also contain pairs of characters separated by -, standing for all characters lexically between the two. The character / must appear explicitly in a pattern, as must the first character of the path name components . and ... A pattern is replaced by a list of arguments, one for each path name matched, except that a pattern matching no names is not replaced by the empty list, but rather stands for itself. Pattern matching is done after all other operations. Thus,

x=/tmp echo $x^/*.c$

matches /tmp/*.c, rather than matching /*.c and then prefixing /tmp.

A quoted word is a sequence of characters surrounded by single quotes ('). A single quote is represented in a quoted word by a pair of quotes ('').

Each of the following is an argument.

(arguments)

The value of a sequence of arguments enclosed in parentheses is a list comprising the

members of each element of the sequence. Argument lists have no recursive structure, although their syntax may suggest it. The following are entirely equivalent:

echo hi there everybody

((echo) (hi there) everybody)

\$ argument

\$ argument (subscript)

The *argument* after the \$ is the name of a variable whose value is substituted. Multiple levels of indirection are possible, but of questionable utility. Variable values are lists of strings. If *argument* is a number n, the value is the nth element of \$*, unless \$* doesn't have n elements, in which case the value is empty. If *argument* is followed by a parenthesized list of subscripts, the value substituted is a list composed of the requested elements (origin 1). The parenthesis must follow the variable name with no spaces. Subscripts can also take the form m-n or m- to indicate a sequence of elements. Assignments to variables are described below.

\$#argument

The value is the number of elements in the named variable. A variable never assigned a value has zero elements.

\$"argument

The value is a single string containing the components of the named variable separated by spaces. A variable with zero elements yields the empty string.

' { command }

' split { command }

rc executes the *command* and reads its standard output, splitting it into a list of arguments, using characters in ifs as separators. If ifs is not otherwise set, its value is 't n'. In the second form of the command, split is used instead of ifs.

<{ command }

>{ command }

The *command* is executed asynchronously with its standard output or standard input connected to a pipe. The value of the argument is the name of a file referring to the other end of the pipe. This allows the construction of non-linear pipelines. For example, the following runs two commands old and new and uses cmp to compare their outputs

cmp <{old} <{new}</pre>

argument ^ argument

The \land operator concatenates its two operands. If the two operands have the same number of components, they are concatenated pairwise. If not, then one operand must have one component, and the other must be non-empty, and concatenation is distributive.

Free Carets

In most circumstances, *rc* will insert the \land operator automatically between words that are not separated by white space. Whenever one of \$ ' ' follows a quoted or unquoted word or an unquoted word follows a quoted word with no intervening blanks or tabs, a \land is inserted between the two. If an unquoted word immediately follows a \$ and contains a character other than an alphanumeric, underscore, or *, a \land is inserted before the first such character. Thus

cc -\$flags \$stem.c

is equivalent to

cc -^\$flags \$stem^.c

I/O Redirections

The sequence >*file* redirects the standard output file (file descriptor 1, normally the terminal) to the named *file*; >>*file* appends standard output to the file. The standard input file (file descriptor 0, also normally the terminal) may be redirected from a file by the sequence <*file*, or from an inline 'here document' by the sequence <*eof-marker*. The contents of a here document are lines of text taken from the command input stream up to a line containing nothing but the *eof-marker*, which may be either a quoted or unquoted word. If *eof-marker* is unquoted, variable names of the form \$*word* have their values substituted from *rc's* environment. If \$*word* is followed by a caret (^), the caret is deleted. If *eof-marker* is quoted, no substitution occurs. The standard input file may also be redirected from a file by the sequence <> file, which opens *file* exactly once, for reading and writing.

Redirections may be applied to a file-descriptor other than standard input or output by qualifying the redirection operator with a number in square brackets. For example, the diagnostic output (file descriptor 2) may be redirected by writing cc junk.c >[2]junk.

A file descriptor may be redirected to an already open descriptor by writing >[fd0=fd1], <>[fd0=fd1], or <[fd0=fd1]. Fd1 is a previously opened file descriptor and fd0 becomes a new copy (in the sense of dup(2)) of it. A file descriptor may be closed by writing >[fd0=] or <[fd0=].

Redirections are executed from left to right. Therefore, cc junk.c >/dev/null >[2=1] and cc junk.c >[2=1] >/dev/null have different effects: the first puts standard output in /dev/null and then puts diagnostic output in the same place, where the second directs diagnostic output to the terminal and sends standard output to /dev/null.

newconn <>/net/tcp/clone >[1=0] opens /net/tcp/clone exactly once for reading and writing and puts it on standard input and output. lpd <>[3]/net/tcp/42/data opens /net/tcp/42/data exactly once for reading and writing and puts it on file descriptor 3.

Compound Commands

A pair of commands separated by a pipe operator (|) is a command. The standard output of the left command is sent through a pipe to the standard input of the right command. The pipe operator may be decorated to use different file descriptors. |[fd] connects the output end of the pipe to file descriptor fd rather than 1. |[fd0=fd1] connects output to fd1 of the left command and input to fd0 of the right command.

A pair of commands separated by && or || is a command. In either case, the left command is executed and its exit status examined. If the operator is && the right command is executed if the left command's status is null. || causes the right command to be executed if the left command's status is non-null.

The exit status of a command may be inverted (non-null is changed to null, null is changed to non-null) by preceding it with a !.

The | operator has highest precedence, and is left-associative (i.e. binds tighter to the left than the right). ! has intermediate precedence, and && and || have the lowest precedence.

The unary @ operator, with precedence equal to !, causes its operand to be executed in a subshell.

Each of the following is a command.

if (list) command

A *list* is a sequence of commands, separated by &, ;, or newline. It is executed and if its exit status is null, the *command* is executed.

if not command

The immediately preceding command must have been if(list) command. If its condition was non-zero, the command is executed.

for(name in arguments) command

for(name) command

The *command* is executed once for each *argument* with that argument assigned to *name*. If the argument list is omitted, \$* is used.

while(list) command

The *list* is executed repeatedly until its exit status is non-null. Each time it returns null status, the *command* is executed. An empty *list* is taken to give null status.

switch(argument){list}

The *list* is searched for simple commands beginning with the word case. (The search is only at the 'top level' of the *list*. That is, cases in nested constructs are not found.) *Argument* is matched against each word following case using the pattern-matching algorithm described above, except that / and the first characters of . and . . need not be matched explicitly. When a match is found, commands in the list are executed up to the next following case command (at the top level) or the closing brace.

{ list }

Braces serve to alter the grouping of commands implied by operator priorities. The *body* is a sequence of commands separated by &, ;, or newline.

- fn name{list}
- fn *name*

The first form defines a function with the given *name*. Subsequently, whenever a command

whose first argument is *name* is encountered, the current value of the remainder of the command's argument list will be assigned to \$*, after saving its current value, and *rc* will execute the *list*. The second form removes *name*'s function definition.

fn note{list}

fn *note*

A function with a special name will be called when *rc* receives a corresponding note; see *notify*(2). The valid note names (and corresponding notes) are sighup (hangup), sigint (interrupt), sigalrm (alarm), and sigfpe (floating point trap). By default *rc* exits on receiving any signal, except when run interactively, in which case interrupts and quits normally cause *rc* to stop whatever it's doing and start reading a new command. The second form causes *rc* to handle a signal in the default manner. *Rc* recognizes an artificial note, sigexit, which occurs when *rc* is about to finish executing.

name=argument command

Any command may be preceded by a sequence of assignments interspersed with redirections. The assignments remain in effect until the end of the command, unless the command is empty (i.e. the assignments stand alone), in which case they are effective until rescinded by later assignments.

Built-in Commands

These commands are executed internally by *rc*, usually because their execution changes or depends on *rc*'s internal state.

. file ...

Execute commands from *file*. *\$** is set for the duration to the remainder of the argument list following *file*. *File* is searched for using *\$path*.

builtin command ...

Execute *command* as usual except that any function named *command* is ignored in favor of the built-in meaning.

cd [dir]

Change the current directory to *dir*. The default argument is \$home. *dir* is searched for in each of the directories mentioned in \$cdpath.

eval [*arg* ...]

The arguments are concatenated separated by spaces into a single string, read as input to *rc*, and executed.

exec [command ...]

This instance of *rc* replaces itself with the given (non-built-in) *command*.

flag f [+-]

Either set (+), clear (–), or test (neither + nor –) the flag f, where f is a single character, one of the command line flags (see Invocation, below).

exit [status]

Exit with the given exit status. If none is given, the current value of \$status is used.

rfork [nNeEsfFm]

Become a new process group using rfork(*flags*) where *flags* is composed of the bitwise OR of the rfork flags specified by the option letters (see *fork*(2)). If no *flags* are given, they default to ens. The *flags* and their meanings are: n is RFNAMEG; N is RFCNAMEG; e is RFENVG; E is RFCENVG; s is RFNOTEG; f is RFFDG; F is RFCFDG; and m is RFNOMNT.

shift [n]

Delete the first *n* (default 1) elements of \$*.

wait [*pid*]

Wait for the process with the given *pid* to exit. If no *pid* is given, all outstanding processes are waited for.

whatis name ...

Print the value of each *name* in a form suitable for input to *rc*. The output is an assignment to any variable, the definition of any function, a call to builtin for any built-in command, or the completed pathname of any executable file.

~ subject pattern ...

The *subject* is matched against each *pattern* in sequence. If it matches any pattern, \$status is set to zero. Otherwise, \$status is set to one. Patterns are the same as for file name matching, except that / and the first character of . and . . need not be matched explicitly. The *patterns* are not subjected to file name matching before the ~ command is

executed, so they need not be enclosed in quotation marks.

Environment

The *environment* is a list of strings made available to executing binaries by the env device (see *env*(3)). *Rc* creates an environment entry for each variable whose value is non-empty, and for each function. The string for a variable entry has the variable's name followed by = and its value. If the value has more than one component, these are separated by nul ($^{\circ}$ 000') characters. The string for a function is just the *rc* input that defines the function. The name of a function in the environment is the function name preceded by fn#.

When *rc* starts executing it reads variable and function definitions from its environment.

Special Variables

The following variables are set or used by rc.

- Set to rc's argument list during initialization. Whenever a . command or a function is executed, the current value is saved and \$* receives the new argument list. The saved value is restored on completion of the . or function.
- \$apid Whenever a process is started asynchronously with &, \$apid is set to its process id.
- \$home The default directory for cd.
- \$ifs The input field separators used in backquote substitutions. If ifs is not otherwise set, its value is ' t n'.
- \$path The search path used to find commands and input files for the . command. If not set in the environment, it is initialized by path=(. /bin). Its use is discouraged; instead use bind(1) to build a /bin containing what's needed.
- \$pid Set during initialization to *rc*'s process id.
- \$prompt When rc is run interactively, the first component of \$prompt is printed before reading each command. The second component is printed whenever a newline is typed and more lines are required to complete the command. If not set in the environment, it is initialized by prompt=('% ' ' ').
- \$status Set to the wait message of the last-executed program. (unless started with &). !
 and ~ also change \$status. Its value is used to control execution in &&, ||, if
 and while commands. When rc exits at end-of-file of its input or on executing an
 exit command with no argument, \$status is its exit status.

Invocation

If *rc* is started with no arguments it reads commands from standard input. Otherwise its first non-flag argument is the name of a file from which to read commands (but see -c below). Subsequent arguments become the initial value of *. *Rc* accepts the following command-line flags.

- -c string Commands are read from string.
- -s Print out exit status after any command where the status is non-null.
- -e Exit if \$status is non-null after executing a simple command.
- -i If -i is present, or *rc* is given no arguments and its standard input is a terminal, it runs interactively. Commands are prompted for using \$prompt.
- -I Makes sure *rc* is not run interactively.
- -1 If -1 is given or the first character of argument zero is -, *rc* reads commands from \$home/lib/profile, if it exists, before reading its normal input.
- -m Read commands to initialize *rc* from *initial* instead of from /rc/lib/rcmain.
- –р А по–ор.
- -d A no-op.
- -v Echo input on file descriptor 2 as it is read.
- -x Print each simple command before executing it.
- -r Print debugging information (internal form of commands as they are executed).

FILES

\$home/lib/profile the user's local rc start script

/rc/lib/rcmain System rc start script

/rc/lib/rcmain.local Site specific system rc start script

SOURCE

/sys/src/cmd/rc

SEE ALSO

Tom Duff, ''Rc - The Plan 9 Shell''.

BUGS

There should be a way to match patterns against whole lists rather than just single strings. Using ~ to check the value of \$status changes \$status.

Functions containing here documents don't work.

Free carets don't get inserted next to keywords.

rcpu, rimport, rexport, rconnect - connection to CPU server

SYNOPSIS

rcpu [-u user] [-k keypattern] [-P patternfile] [-p] [-h host] [-c cmd arg ...]

rimport [-abcCnq] [-s name] [-u user] [-k keypattern] [-p] host tree [mountpoint]

rexport [-abcCnq] [-s remotename] [-m remotemtpt] [-u user] [-k keypattern] [-P
patternfile] [-p] tree host [remotecmd arg ...]

rconnect [-u user] [-k keypattern] [-p] host remotescript localcommand arg ...

DESCRIPTION

Rcpu runs commands from rc(1) on a cpu server with the local namespace exported to the remote side under /mnt/term. The current directory, interrupt notes, standard file descriptors 0,1,2 and /dev/cons are passed to the remote side. The command to run can be passed with -c *cmd arg* ..., otherwise an interactive shell is started. The user's profile is run before the command with \$service set to cpu to allow further customization of the environment (see rc(1) for more information). The cpu server can be specified with -h *host*, otherwise it defaults to the environment variable \$cpu or is looked up from ndb(6).

Rimport mounts a remote directory *tree* from a cpu server *host* into the local namespace at *mountpoint*. When *mountpoint* is omitted, it is set the same as *tree*. When the -s *name* option is present, the service is also posted to /srv/name allowing it to be mounted in other namespaces.

Rexport is the reverse of *rimport*, exporting a local directory *tree* to the server *host* and optionally executing *remotecmd arg* on the server side after posting the service to /srv/remotename or mounting it at *remotemtpt*.

Rconnect is a helper program handling client side connection setup for the commands listed above. The rcpu protocol starts by setting up a mutual authenticated and encrypted TLS connection using tlssrv(8) followed by the client sending an rc(1) remotescript file to the server which gets executed under the authenticated user with file descriptors 0,1,2 cross connected to file descriptors 0,1 of the client side running *localcommand* over the encrypted connection.

The common options are:

```
-a -b -c -C -n -q
```

Specifies the *mount* options (see *bind*(1)) for *rimport* and *rexport*.

–P patternfile

Restricts the set of exported files (see *exportfs*(4)) for *rcpu* and *rexport*.

–u user

Remote user id to authenticate as.

-k keypattern

Use *keypattern* to select a key to authenticate to the remote side (see *auth*(2)).

-p Protect the connection against connection resets by establishing *aan*(8) tunnel.

FILES

/rc/bin/service/tcp17019

SOURCE

```
/rc/bin/rcpu
/rc/bin/rimport
/rc/bin/rexport
/rc/bin/rconnect
```

SEE ALSO

```
rc(1), cpu(1), con(1), import(4), exportfs(4), tlssrv(8), aan(8)
```

changes, pull, push, scan - client-server replica management

SYNOPSIS

```
replica/pull[-nv][-c name]... [-s name]... name[path]
replica/push[-nv] name[path]
replica/changes name[path]
replica/scan name[path]
```

DESCRIPTION

These shell scripts provide a simple log-based client-server replica management. The server keeps a log of changes made to its file system, and clients synchronize by reading the log and applying these changes locally.

These scripts are a polished interface to the low-level tools described in *replica*(8). See *replica*(8) for details on the inner workings of replica management. These tools were written primarily as the fourth edition Plan 9 distribution mechanism, but they have wider applicability. For example, they could be used to synchronize one's home directory between a laptop and a central file server.

Replicas are described by configuration files. The *name* in all the replica commands is a configuration file. Paths that do not begin with /, ./, or ../ are assumed to be relative to \$home/lib/replica. Configuration files are described below.

Replica/scan is the only one of these programs that does not need to be run on the client. It scans the server file system for changes and appends entries for those changes into the server log. Typically it is run on a machine with a fast network connection to the server file system.

Replica/pull copies changes from the server to the client, while *replica/push* copies changes from the client to the server. (Both run on the client.) If a list of *paths* is given, only changes to those paths or their children are copied. The -v flag causes *pull* or *push* to print a summary of what it is doing. Each status line is of the form

verb path serverpath mode uid gid mtime length

Verb describes the event: addition of a file (a), deletion of a file (d), a change to a file's contents (c), or a change to a file's metadata (m). *Path* is the file path on the client; *serverpath* is the file path on the server. *Mode*, *uid*, *gid*, and *mtime* are the file's metadata as in the Dir structure (see *stat*(5)). For deletion events, the metadata is that of the deleted file. For other events, the metadata is that after the event. The -n flag causes *pull* or *push* to print the summary but not actually carry out the actions.

Push and *pull* are careful to notice simultaneous changes to a file or its metadata on both client and server. Such simultaneous changes are called *conflicts*. Here, simultaneous does not mean at the same instant but merely that both changes were carried out without knowledge of the other. For example, if a client and server both make changes to a file without an intervening *push* or *pull*, the next *push* or *pull* will report an update/update conflict. If a conflict is detected, both files are left the same. The -c flag to *pull* specifies that conflicts for paths beginning with *name* should be resolved using the client's copy, while -s specifies the server's copy. The -c and -s options may be repeated.

Replica/changes prints a list of local changes made on the client that have not yet been pushed to the server. It is like *push* with the -n flag, except that it does not check for conflicts and thus does not require the server to be available.

The replica configuration file is an rc(1) script that must define the following functions and variables:

servermount

A function that mounts the server; run on both client and server.

serverupdate

A function that rescans the server for changes. Typically this command dials a CPU server known to be close to the file server and runs *replica/scan* on that well-connected machine.

serverroot

The path to the root of the replicated file system on the server, as it will be in the name

space after running servermount.

serverlog

The path to the server's change log, after running servermount.

serverproto

The path to the proto file describing the server's files, after running servermount. Only used by *scan*.

serverdb

The path to the server's file database, after running servermount. Only used by scan.

clientmount

A function to mount the client file system; run only on the client.

clientroot

The path to the root of the replicated file system on the client, after running clientmount.

clientlog

The path to the client's copy of the server log file. The client log is maintained by *pull*.

clientproto

The path to the proto file describing the client's files. Only used by *changes*. Often just a copy of \$serverproto.

clientdb

The path to the client's file database, after running clientmount.

clientexclude

A (potentially empty) list of paths to exclude from synchronization. A typical use of this is to exclude the client database and log files. These paths are relative to the root of the replicated file system.

As an example, the Plan 9 distribution replica configuration looks like:

```
fn servermount { 9fs sources; bind /n/sources/plan9 /n/dist }
fn serverupdate { status='' }
serverroot=/n/dist
s=/n/dist/dist/replica
serverlog=$s/plan9.log
serverproto=$s/plan9.proto
```

```
fn clientmount { 9fs boot }
clientroot=/n/boot
c=/n/boot/dist/replica
clientlog=$c/client/plan9.log
clientproto=$c/plan9.proto
clientdb=$c/client/plan9.db
clientexclude=(dist/replica/client)
```

(Since the Plan 9 developers run *scan* manually to update the log, the clients need not do anything to rescan the file system. Thus serverupdate simply returns successfully.)

The fourth edition Plan 9 distribution uses these tools to synchronize installations with the central server at Bell Labs. The replica configuration files and metadata are kept in /dist/replica. To update your system, make sure you are connected to the internet and run

replica/pull /dist/replica/network

If conflicts are reported (say you have made local changes to /rc/bin/cpurc and /rc/bin/termrc, but only want to keep the cpurc changes), use

replica/pull -c rc/bin/cpurc -s rc/bin/termrc /dist/replica/network to instruct *pull* to ignore the server's change to cpurc.

The script /usr/glenda/bin/rc/pull runs *pull* with the -v flag and with /dist/replica/network inserted at the right point on the command line. Logged in as glenda, one can repeat the above example with:

pull -c rc/bin/cpurc -s rc/bin/termrc

To see a list of changes made to the local file system since installation, run replica/changes /dist/replica/network (Although the script is called *network*, since *changes* is a local-only operation, the network need not be configured.)

SOURCE

/rc/bin/replica

SEE ALSO replica(8)

resample, resize – resample a picture

SYNOPSIS

resample[-x size][-y size][file]
resize[-n][-x size][-y size][file]

DESCRIPTION

Resample and *Resize* resamples its input image (default standard input) to a new size. *Resample* uses a Kaiser window which produces high quality results and *resize* uses bilinear interpolation which is faster but produces more fuzzy images. By specifying the -n option, *resize* can also use nearest neighbour interpolation which preserves the individual pixels and is appropriate for pixel art or qr(1) output.

The size of the resampled image can be specified with the -x and -y options. An unadorned value sets the number of pixels of that dimension; a suffixed percent sign specifies a percentage. If only one of -x or -y is given, the other dimension is scaled to preserve the aspect ratio of the original image. Thus, -x50% will reduce the image to half its original dimension in both x and y.

The input should be a Plan 9 image as described in *image*(6), and the output will be a compressed 24-bit r8g8b8 image. To uncompress the image or change the pixel format, use *iconv* (see *crop*(1)).

SOURCE

```
/sys/src/cmd/resample.c
/sys/src/cmd/resize.c
```

SEE ALSO

crop(1), image(6)

rio, label, window, wloc - window system

SYNOPSIS

rio[-i 'cmd'][-k 'kbdcmd'][-s][-b][-f font]

label name

```
window [ -m ] [ -r minx miny maxx maxy ] [ -dx n ] [ -dy n ] [ -minx n ] [ -miny n ] [ -maxx
n ] [ -maxy n ] [ -cd dir ] [ -hide ] [ -scroll ] [ -noscroll ] [ cmd arg ... ]
```

wloc

DESCRIPTION

Rio manages asynchronous layers of text, or windows, on a raster display. It also serves a variety of files for communicating with and controlling windows; these are discussed in section *rio*(4).

Commands

The *rio* command starts a new instance of the window system. Its -i option names a startup script, which typically contains several *window* commands generated by *wloc*. The -k option causes *rio* to run the command *kbdcmd* at startup and allow it to provide characters as keyboard input; the keyboard program described in *bitsyload*(1) is the usual choice.

The -s option initializes windows so that text scrolls; the default is not to scroll. The -b option reverses the normal color scheme for windows, painting white text on a black background. The *font* argument names a font used to display text, both in *rio*'s menus and as a default for any programs running in its windows; it also establishes the environment variable font. If -f is not given, *rio* uses the imported value of font if set; otherwise it imports the default font from the underlying graphics server, usually the terminal's operating system.

The *label* command changes a window's identifying name.

The window command creates a window. By default, it creates a shell window and sizes and places it automatically. The geometry arguments control the size (dx, dy) and placement (minx, miny, maxx, maxy); the units are pixels with the upper left corner of the screen at (0, 0). The hide option causes the window to be created off-screen. The scroll and noscroll options set the scroll mode. The cd option sets the working directory. The optional command and arguments define which program to run in the window.

By default, window uses /dev/wctl (see rio(4)) to create the window and run the command. Therefore, the window and command will be created by rio and run in a new file name space, just as if the window had been created using the interactive menu. However, the -m option uses the file server properties of rio to mount (see bind(1)) the new window's name space within the name space of the program calling window. This means, for example, that running window in a CPU window will create another window whose command runs on the terminal, where rio is running; while window -m will create another window whose command runs on the CPU server.

The *wloc* command prints the coordinates and label of each window in its instance of *rio* and is used to construct arguments for *window*.

Window control

Each window behaves as a separate terminal with at least one process associated with it. When a window is created, a new process (usually a shell; see rc(1)) is established and bound to the window as a new process group. Initially, each window acts as a simple terminal that displays character text; the standard input and output of its processes are attached to /dev/cons. Other special files, accessible to the processes running in a window, may be used to make the window a more general display. Some of these are mentioned here; the complete set is discussed in rio(4).

One window is *current*, and is indicated with a dark border and text; characters typed on the keyboard are available in the /dev/cons file of the process in the current window. Characters written on /dev/cons appear asynchronously in the associated window whether or not the window is current.

Windows are created, deleted and rearranged using the mouse. Clicking (pressing and releasing) mouse button 1 in a non-current window makes that window current and brings it in front of any windows that happen to be overlapping it. When the mouse cursor points to the background area

or is in a window that has not claimed the mouse for its own use, pressing mouse button 3 activates a menu of window operations provided by *rio*. Releasing button 3 then selects an operation. At this point, a gunsight or cross cursor indicates that an operation is pending. The button 3 menu operations are:

- New Create a window. Press button 3 where one corner of the new rectangle should appear (cross cursor), and move the mouse, while holding down button 3, to the diagonally opposite corner. Releasing button 3 creates the window, and makes it current. Very small windows may not be created.
- Resize Change the size and location of a window. First click button 3 in the window to be changed (gunsight cursor). Then sweep out a window as for the New operation. The window is made current.
- Move Move a window to another location. After pressing and holding button 3 over the window to be moved (gunsight cursor), indicate the new position by dragging the rectangle to the new location. The window is made current. Windows may be moved partially off-screen.
- Delete Delete a window. Click in the window to be deleted (gunsight cursor). Deleting a window causes a hangup note to be sent to all processes in the window's process group (see notify(2)).
- Hide Hide a window. Click in the window to be hidden (gunsight cursor); it will be moved off-screen. Each hidden window is given a menu entry in the button 3 menu according to the value of the file /dev/label, which *rio* maintains (see *rio*(4)).
- label Restore a hidden window.

Windows may also be arranged by dragging their borders. Pressing button 1 or 2 over a window's border allows one to move the corresponding edge or corner, while button 3 moves the whole window.

Text windows

Characters typed on the keyboard or written to /dev/cons collect in the window to form a long, continuous document.

There is always some *selected text*, a contiguous string marked on the screen by reversing its color. If the selected text is a null string, it is indicated by a hairline cursor between two characters. The selected text may be edited by mousing and typing. Text is selected by pointing and clicking button 1 to make a null-string selection, or by pointing, then sweeping with button 1 pressed. Text may also be selected by double-clicking: just inside a matched delimiter-pair with one of $\{[(< ", " on the left and \}]) >> "," on the right, it selects all text within the pair; at the beginning or end of a line, it selects the line; within or at the edge of an alphanumeric word, it selects the word.$

Characters typed on the keyboard replace the selected text; if this text is not empty, it is placed in a *snarf buffer* common to all windows but distinct from that of *sam*(1).

Programs access the text in the window at a single point maintained automatically by *rio*. The *output point* is the location in the text where the next character written by a program to /dev/cons will appear; afterwards, the output point is the null string beyond the new character. The output point is also the location in the text of the next character that will be read (directly from the text in the window, not from an intervening buffer) by a program from /dev/cons. When such a read will occur is, however, under control of *rio* and the user.

In general there is text in the window after the output point, usually placed there by typing but occasionally by the editing operations described below. A pending read of /dev/cons will block until the text after the output point contains a newline, whereupon the read may acquire the text, up to and including the newline. After the read, as described above, the output point will be at the beginning of the next line of text. In normal circumstances, therefore, typed text is delivered to programs a line at a time. Changes made by typing or editing before the text is read will not be seen by the program reading it. If the program in the window does not read the terminal, for example if it is a long-running computation, there may accumulate multiple lines of text after the output point; changes made to all this text will be seen when the text is eventually read. This means, for example, that one may edit out newlines in unread text to forestall the associated text being read when the program finishes computing. This behavior is very different from most systems.

Even when there are newlines in the output text, *rio* will not honor reads if the window is in *hold mode*, which is indicated by a white cursor and blue text and border. The ESC character toggles hold mode. Some programs, such as *mail*(1), automatically turn on hold mode to simplify the editing of multi-line text; type ESC when done to allow *mail* to read the text.

An EOT character (control–D) behaves exactly like newline except that it is not delivered to a program when read. Thus on an empty line an EOT serves to deliver an end–of–file indication: the read will return zero characters. Like newlines, unread EOTs may be successfully edited out of the text. The BS character (control–H) erases the character before the selected text. The ETB character (control–W) erases any nonalphanumeric characters, then the alphanumeric word just before the selected text. 'Alphanumeric' here means non–blanks and non–punctuation. The NAK character (control–U) erases the text after the output point, and not yet read by a program, but not more than one line. All these characters are typed on the keyboard and hence replace the selected text; for example, typing a BS with a word selected places the word in the snarf buffer, removes it from the screen, and erases the character before the word.

An ACK character (control-F) or Insert character triggers file name completion for the preceding string (see *complete*(2)).

Typing a left or right arrow moves the cursor one character in that direction. Typing an SOH character (control-A) moves the cursor to the beginning of the current line; an ENQ character (control-E) moves to the end. The STX character (control-B) moves the cursor to the output point.

Text may be moved vertically within the window. A scroll bar on the left of the window shows in its clear portion what fragment of the total output text is visible on the screen, and in its gray part what is above or below view; it measures characters, not lines. Mousing inside the scroll bar moves text: clicking button 1 with the mouse pointing inside the scroll bar brings the line at the top of the window to the cursor's vertical location; button 3 takes the line at the cursor to the top of the window; button 2, treating the scroll bar as a ruler, jumps to the indicated portion of the stored text. Holding a button pressed in the scroll bar will cause the text to scroll continuously until the button is released. Also, a page down or down-arrow scrolls forward half a window, and page up or up-arrow scrolls back. Typing the home key scrolls to the top of the window; typing the end key scrolls to the bottom.

The DEL character sends an interrupt note to all processes in the window's process group. Unlike the other characters, the DEL, VIEW, and up- and down-arrow keys do not affect the selected text. The left (right) arrow key moves the selection to one character before (after) the current selection.

Normally, written output to a window blocks when the text reaches the end of the screen; a button 2 menu item toggles scrolling.

Other editing operations are selected from a menu on button 2. The cut operation deletes the selected text from the screen and puts it in the snarf buffer; snarf copies the selected text to the buffer without deleting it; paste replaces the selected text with the contents of the buffer; and send copies the snarf buffer to just after the output point, adding a final newline if missing. Paste will sometimes and send will always place text after the output point; the text so placed will behave exactly as described above. Therefore when pasting text containing newlines after the output point, it may be prudent to turn on hold mode first.

The plumb menu item sends the contents of the selection (not the snarf buffer) to the *plumber*(4). If the selection is empty, it sends the white-space-delimited text containing the selection (typing cursor). A typical use of this feature is to tell the editor to find the source of an error by plumbing the file and line information in a compiler's diagnostic.

Raw text windows

Opening or manipulating certain files served by *rio* suppresses some of the services supplied to ordinary text windows. While the file /dev/mouse is open, any mouse operations are the responsibility of another program running in the window. Thus, *rio* refrains from maintaining the scroll bar, supplying text editing or menus, interpreting the VIEW key as a request to scroll, and also turns scrolling on.

The file /dev/consctl controls interpretation of keyboard input. In particular, a raw mode may be set: in a raw-input window, no typed keyboard characters are special, they are not echoed to the screen, and all are passed to a program immediately upon reading, instead of being gathered

into lines.

Graphics windows

A program that holds /dev/mouse and /dev/consctl open after putting the console in raw mode has complete control of the window: it interprets all mouse events, gets all keyboard characters, and determines what appears on the screen.

FILES

/lib/font/bit/*	font directories
/mnt/wsys	Files served by <i>rio</i> (also unioned in /dev in a window's name
	space, before the terminal's real /dev files)
/srv/rio. <i>user.pid</i>	Server end of <i>rio</i> .
/srv/riowctl. <i>user.pid</i>	Named pipe for <i>wctl</i> messages.

SOURCE

/sys/src/cmd/rio /rc/bin/label /rc/bin/window /rc/bin/wloc

SEE ALSO

rio(4), *rc*(1), *cpu*(1), *sam*(1), *mail*(1), *proof*(1), *graphics*(2), *frame*(2), *window*(2), *notify*(2), *cons*(3), *draw*(3), *mouse*(3), *keyboard*(6)

BUGS

The standard input of *window* is redirected to the newly created window, so there is no way to pipe the output of a program to the standard input of the new window. In some cases, plumb(1) can be used to work around this limitation.

rm - remove files

SYNOPSIS

rm [-fr] file ...

DESCRIPTION

Rm removes files or directories. A directory is removed only if it is empty. Removal of a file requires write permission in its directory, but neither read nor write permission on the file itself. The options are

- -f Don't report files that can't be removed.
- -r Recursively delete the entire contents of a directory and the directory itself.

SOURCE

/sys/src/cmd/rm.c

SEE ALSO

remove(2)

rotate - rotate or mirror a picture

SYNOPSIS

rotate[-r degree][-u | -1][file]

DESCRIPTION

Rotate reads its input image (default from standard input), applies the rotation or mirroring and outputs the transformed image in compressed plan9 bitmap format.

The option -r rotates the image clockwise in 90 degree steps by the *degree* argument. The options -u and -1 mirror the image upside/down or left/right.

SOURCE

/sys/src/cmd/rotate.c

SEE ALSO

crop(1), resample(1), image(6)

HISTORY

Rotate first appeared in 9front (September, 2011).

rwd, conswdir - maintain remote working directory

SYNOPSIS

rwd path

conswdir[prog]

DESCRIPTION

Rwd and *conswdir* conspire to keep *rio*(4) and *acme*(4) informed about the current directory on remote systems during login sessions. *Rio* and *acme* include this information in plumb messages sent to *plumber*(4). If the remote system's name space is mounted in the plumber's name space, the end result is that file paths printed during the session are plumbable.

Rwd informs *rio* and *acme* of directory changes. The name of the remote machine is taken from the environment variable \$remotesys. *Rwd* writes the full path to /dev/wdir; writes the last element of the path, suffixed by @*remotesys*, to /dev/label; and when run inside a *win* (see *acme*(1)) window, changes the window title to *path*/-*remotesys* using /dev/acme/ctl.

Conswdir copies standard input to standard output, looking for in-band messages about directory changes. The messages are of the form:

\033]; path\007

where 033 and 007 are ASCII escape and bell characters. Such messages are removed from the stream and not printed to standard output; for each such message *conswdir* runs *prog* (default /bin/rwd) with *path* as its only argument.

EXAMPLES

Add this plumbing rule (see *plumb*(6)) in order to run commands in the plumber's name space:

```
# have plumber run command
kind is text
data matches 'Local (.*)'
plumb to none
plumb start rc -c $1
```

Mount a Unix system in your name space and the plumber's:

```
% 9fs unix
% plumb 'Local 9fs unix'
```

(If you're using acme, execute Local 9fs unix with the middle button to mount the Unix system in acme's name space.)

Connect to the Unix system, processing in-band directory change messages:

% ssh unix | aux/conswdir

Add this shell function to your .profile on the Unix system to generate directory change messages every time a cd command is executed:

```
H='hostname | sed 's/\..*//''
_cd () {
    \cd $* &&
    case $- in
        *i*)
        __dir='pwd'
        echo /n/$H$_dir | awk '{printf("\033];%s\007", $1);}'
    esac
}
```

```
alias cd=_cd
```

The examples described so far only help for relative path names. Add this plumbing rule to handle rooted names like /usr/include/stdio.h:

remote rooted path names
type is text
wdir matches '/n/unix(/.*)?'

```
data matches '/([.a-zA-Z<sub>i</sub>-10-9_/\-]*[a-zA-Z<sub>i</sub>-10-9_/\-])('$addr')?'
arg isfile /n/unix/$1
data set $file
attr add addr=$3
plumb to edit
plumb client window $editor
```

SOURCE

```
/rc/bin/rwd
/sys/src/cmd/aux/conswdir.c
```

SEE ALSO

plumber(4), plumb(6), srv(4)

BUGS

This mechanism is clunky, but Unix and SSH make it hard to build a better one.

The escape sequence was chosen because it changes the title on xterm windows.

sam, B, sam.save, samterm - screen editor with structural regular expressions

SYNOPSIS

sam [option ...] [files]

sam —r *machine*

sam.save

B [–nnnn] *file …*

DESCRIPTION

Sam is a multi-file editor. It modifies a local copy of an external file. The copy is here called a *file*. The files are listed in a menu available through mouse button 3 or the n command. Each file has an associated name, usually the name of the external file from which it was read, and a 'modified' bit that indicates whether the editor's file agrees with the external file. The external file is not read into the editor's file until it first becomes the current file—that to which editing commands apply—whereupon its menu entry is printed. The options are

- -a Autoindent. In this mode, when a newline character is typed in the terminal interface, *samterm* copies leading white space on the current line to the new line.
- -i Indent with spaces. In this mode, when a tab character is typed in the terminal interface, *samterm* will insert spaces until the next tabstop. Backspace will delete spaces until the previous tabstop or another character is encountered.
- -d Do not 'download' the terminal part of *sam*. Editing will be done with the command language only, as in *ed*(1).
- -r *machine* Run the host part remotely on the specified machine, the terminal part locally.
- -s path Start the host part from the specified file on the remote host. Only meaningful with the -r option.
- -t *path* Start the terminal part from the specified file. Useful for debugging.

Regular expressions

Regular expressions are as in regexp(6) with the addition of n to represent newlines. A regular expression may never contain a literal newline character. The empty regular expression stands for the last complete expression encountered. A regular expression in *sam* matches the longest leftmost substring formally matched by the expression. Searching in the reverse direction is equivalent to searching backwards with the catenation operations reversed in the expression.

Addresses

An address identifies a substring in a file. In the following, 'character n' means the null string after the n-th character in the file, with 1 the first character in the file. 'Line n' means the n-th match, starting at the beginning of the file, of the regular expression .*\n?. All files always have a current substring, called dot, that is the default address.

Simple Addresses

- #n The empty string after character n; #0 is the beginning of the file.
- *n* Line *n*; 0 is the beginning of the file.

/ regexp /

?regexp?

The substring that matches the regular expression, found by looking toward the end (/) or beginning (?) of the file, and if necessary continuing the search from the other end to the starting point of the search. The matched substring may straddle the starting point. When entering a pattern containing a literal question mark for a backward search, the question mark should be specified as a member of a class.

- 0 The string before the first full line. This is not necessarily the null string; see + and below.
- \$ The null string at the end of the file.
- . Dot.
- ' The mark in the file (see the k command below).

"regexp"

Preceding a simple address (default .), refers to the address evaluated in the unique file whose menu line matches the regular expression.

Compound Addresses

In the following, *a1* and *a2* are addresses.

- a1+a2 The address a2 evaluated starting at the end of a1.
- a1-a2 The address a2 evaluated looking in the reverse direction starting at the beginning of a1.
- *a1*, *a2* The substring from the beginning of *a1* to the end of *a2*. If *a1* is missing, 0 is substituted. If *a2* is missing, \$\$ is substituted.
- *a1*; *a2* Like *a1*, *a2*, but with *a2* evaluated at the end of, and dot set to, *a1*.

The operators + and - are high precedence, while , and ; are low precedence.

In both + and - forms, if a^2 is a line or character address with a missing number, the number defaults to 1. If a^1 is missing, . is substituted. If both a^1 and a^2 are present and distinguishable, + may be elided. a^2 may be a regular expression; if it is delimited by ?'s, the effect of the + or - is reversed.

It is an error for a compound address to represent a malformed substring. Some useful idioms: a1+-(a1-+) selects the line containing the end (beginning) of a1. 0/regexp/ locates the first match of the expression in the file. (The form 0; // sets dot unnecessarily.) ./regexp/// finds the second following occurrence of the expression, and ., /regexp/ extends dot.

Commands

In the following, text demarcated by slashes represents text delimited by any printable character except alphanumerics. Any number of trailing delimiters may be elided, with multiple elisions then representing null strings, but the first delimiter must always be present. In any delimited text, newline may not appear literally; n may be typed for newline; and / quotes the delimiter, here /. Backslash is otherwise interpreted literally, except in s commands.

Most commands may be prefixed by an address to indicate their range of operation. Those that may not are marked with a * below. If a command takes an address and none is supplied, dot is used. The sole exception is the w command, which defaults to 0, \$. In the description, 'range' is used to represent whatever address is supplied. Many commands set the value of dot as a side effect. If so, it is always set to the 'result' of the change: the empty string for a deletion, the new text for an insertion, etc. (but see the s and e commands).

Text commands

a/text/

or

а

lines of text

Insert the text into the file after the range. Set dot.

С

- i Same as a, but c replaces the text, while i inserts *before* the range.
- d Delete the text in the range. Set dot.
- s/regexp/text/

Substitute *text* for the first match to the regular expression in the range. Set dot to the modified range. In *text* the character & stands for the string that matched the expression. Backslash behaves as usual unless followed by a digit: $\ d$ stands for the string that matched the subexpression begun by the *d*-th left parenthesis. If *s* is followed immediately by a number *n*, as in s2/x/y/, the *n*-th match in the range is substituted. If the command is followed by a g, as in s/x/y/g, all matches in the range are substituted.

m *a1*

t *a1* Move (m) or copy (t) the range to after *a1*. Set dot.

Display commands

- p Print the text in the range. Set dot.
- = Print the line address and character address of the range.

=# Print just the character address of the range.

File commands

* b file-list

Set the current file to the first file named in the list that *sam* also has in its menu. The list may be expressed *<Plan 9 command* in which case the file names are taken as words (in the shell sense) generated by the Plan 9 command.

* B file-list

Same as b, except that file names not in the menu are entered there, and all file names in the list are examined.

- * n Print a menu of files. The format is:
 - ' or blank indicating the file is modified or clean,
 - or + indicating the file is unread or has been read (in the terminal, * means more than one window is open),
 - . or blank indicating the current file,

a blank,

and the file name.

* D file-list

Delete the named files from the menu. If no files are named, the current file is deleted. It is an error to D a modified file, but a subsequent D will delete such a file.

I/O Commands

* e filename

Replace the file by the contents of the named external file. Set dot to the beginning of the file.

r filename

Replace the text in the range by the contents of the named external file. Set dot.

w filename

Write the range (default 0, \$) to the named external file.

* f filename

Set the file name and print the resulting menu entry.

If the file name is absent from any of these, the current file name is used. e always sets the file name; r and w do so if the file has no name.

< Plan 9–command

Replace the range by the standard output of the Plan 9 command.

> Plan 9–command

Send the range to the standard input of the Plan 9 command.

∧ Plan 9–command

Send the standard output of the Plan 9 command to the command window.

| Plan 9–command

Send the range to the standard input, and replace it by the standard output, of the Plan 9 command.

_ Plan 9–command

Send the range to the standard input, and send the standard output of the Plan 9 command to the command window.

* ! Plan 9–command

Run the Plan 9 command.

* cd *directory*

Change working directory. If no directory is specified, \$home is used.

In any of <, >, \land , _, | or !, if the *Plan 9 command* is omitted the last *Plan 9 command* (of any type) is substituted. If *sam* is *downloaded* (using the mouse and raster display, i.e. not using option -d), ! sets standard input to /dev/null, and otherwise unassigned output (stdout for ! and >, stderr for all) is placed in /tmp/sam.err and the first few lines are printed.

Sam sets two environmental variables depending on the current file. *\$%* is set to the file name. *\$%dot* is set to a list consisting of three values that define the dot.

Loops and Conditionals

x/regexp/ command

For each match of the regular expression in the range, run the command with dot set to the match. Set dot to the last match. If the regular expression and its slashes are omitted,

/.*n/ is assumed. Null string matches potentially occur before every character of the range and at the end of the range.

y/regexp/ command

Like x, but run the command for each substring that lies before, between, or after the matches that would be generated by x. There is no default regular expression. Null substrings potentially occur before every character in the range.

* X/regexp/ command

For each file whose menu entry matches the regular expression, make that the current file and run the command. If the expression is omitted, the command is run in every file.

* Y/regexp/ command

Same as X, but for files that do not match the regular expression, and the expression is required.

g/regexp/ command

v/regexp/ command

If the range contains (g) or does not contain (v) a match for the expression, set dot to the range and run the command.

These may be nested arbitrarily deeply, but only one instance of either X or Y may appear in a single command. An empty command in an x or y defaults to p; an empty command in X or Y defaults to f. g and v do not have defaults.

Miscellany

- * q Quit. It is an error to quit with modified files, but a second q will succeed.
- * u *n* Undo the last *n* (default 1) top-level commands that changed the contents or name of the current file, and any other file whose most recent change was simultaneous with the current file's change. Successive u's move further back in time. The only commands for which u is ineffective are cd, u, q, w and D. If *n* is negative, u 'redoes,' undoing the undo, going forwards in time again.
- (empty) If the range is explicit, set dot to the range. If *sam* is downloaded, the resulting dot is selected on the screen; otherwise it is printed. If no address is specified (the command is a newline) dot is extended in either direction to line boundaries and printed. If dot is thereby unchanged, it is set to .+1 and printed.

Grouping and multiple changes

Commands may be grouped by enclosing them in braces {}. Commands within the braces must appear on separate lines (no backslashes are required between commands). Semantically, an opening brace is like a command: it takes an (optional) address and sets dot for each sub-command. Commands within the braces are executed sequentially, but changes made by one command are not visible to other commands (see the next paragraph). Braces may be nested arbitrarily.

When a command makes a number of changes to a file, as in x/re/c/text/, the addresses of all changes to the file are computed in the original file. If the changes are in sequence, they are applied to the file. Successive insertions at the same address are catenated into a single insertion composed of the several insertions in the order applied.

The terminal

What follows refers to behavior of *sam* when downloaded, that is, when operating as a display editor on a raster display. This is the default behavior; invoking *sam* with the -d (no download) option provides access to the command language only.

Each file may have zero or more windows open. Each window is equivalent and is updated simultaneously with changes in other windows on the same file. Each window has an independent value of dot, indicated by a highlighted substring on the display. Dot may be in a region not within the window. There is usually a 'current window', marked with a dark border, to which typed text and editing commands apply. Text may be typed and edited as in rio(1); also the escape key (ESC) selects (sets dot to) text typed since the last mouse button hit.

Ctrl+b switches to the command window and moves to the end of the text. Ctrl+g switches from to the last focused window. If the focused window is a text window, ctrl+g switches to the next zeroxed instance of that window.

The button 3 menu controls window operations. The top of the menu provides the following operators, each of which uses one or more *rio*-like cursors to prompt for selection of a window or sweeping of a rectangle. 'Sweeping' a null rectangle gets a large window, disjoint from the command window or the whole screen, depending on where the null rectangle is.

newCreate a new, empty file.zeroxCreate a copy of an existing window.resizeAs in *rio*.closeDelete the window. In the last window of a file, close is equivalent to a D for the file.writeEquivalent to a w for the file.

Below these operators is a list of available files, starting with $\sim sam \sim$, the command window. Selecting a file from the list makes the most recently used window on that file current, unless it is already current, in which case selections cycle through the open windows. If no windows are open on the file, the user is prompted to open one. Files other than $\sim sam \sim$ are marked with one of the characters -+* according as zero, one, or more windows are open on the file. A further mark . appears on the file in the current window and a single quote, ', on a file modified since last write.

The command window, created automatically when sam starts, is an ordinary window except that text typed to it is interpreted as commands for the editor rather than passive text, and text printed by editor commands appears in it. The behavior is like *rio*, with an 'output point' that separates commands being typed from previous output. Commands typed in the command window apply to the current open file—the file in the most recently current window.

Manipulating text

Button 1 changes selection, much like *rio*. Pointing to a non-current window with button 1 makes it current; within the current window, button 1 selects text, thus setting dot. Double-clicking selects text to the boundaries of words, lines, quoted strings or bracketed strings, depending on the text at the click.

Button 2 provides a menu of editing commands:

- cut Delete dot and save the deleted text in the snarf buffer.
- paste Replace the text in dot by the contents of the snarf buffer.
- snarf Save the text in dot in the snarf buffer.
- plumb Send the text in the selection as a plumb message. If the selection is empty, the white-space-delimited block of text is sent as a plumb message with a click attribute defining where the selection lies (see *plumb*(6)).
- look Search forward for the next occurrence of the literal text in dot. If dot is the null string, the text in the snarf buffer is used. The snarf buffer is unaffected.
- <ri>> Exchange snarf buffers with *rio*.
- / regexp Search forward for the next match of the last regular expression typed in a command. (Not in command window.)
- send Send the text in dot, or the snarf buffer if dot is the null string, as if it were typed to the command window. Saves the sent text in the snarf buffer. (Command window only.)

External communication

Sam listens to the edit plumb port. If plumbing is not active, on invocation sam creates a named pipe /srv/sam. user which acts as an additional source of commands. Characters written to the named pipe are treated as if they had been typed in the command window.

B is a shell-level command that causes an instance of *sam* running on the same terminal to load the named *files*. *B* uses either plumbing or the named pipe, whichever service is available. If plumbing is not enabled, the option allows a line number to be specified for the initial position to display in the last named file (plumbing provides a more general mechanism for this ability).

Abnormal termination

If *sam* terminates other than by a q command (by hangup, deleting its window, etc.), modified files are saved in an executable file, \$home/sam.save. This program, when executed, asks whether to write each file back to a external file. The answer y causes writing; anything else skips the file.

FILES

\$home/sam.save
\$home/sam.err

/sys/lib/samsave the program called to unpack \$home/sam.save.

SOURCE

/sys/src/cmd/sam source for sam itself
/sys/src/cmd/samterm source for the separate terminal part
/rc/bin/B

SEE ALSO

ed(1), sed(1), grep(1), rio(1), regexp(6).

Rob Pike, "The text editor sam".

seconds - convert human-readable date (and time) to seconds since epoch

SYNOPSIS

seconds date ...

DESCRIPTION

Seconds prints the number of seconds since 1 Jan 1970 corresponding to one or more humanreadable *dates*. Each *date* must be *one* argument; it will usually be necessary to enclose it in quotes.

Seconds accepts a somewhat wider range of input than just output from date(1). The main requirement is that the date must be fully specified, with a day of month, month and year in any order. The month must be an English name (or abbreviation), not a number, and the year must contain 4 digits. Unambiguous time-zone names are understood (i.e., not IST) or time zones may be written as $\pm hhmm$. Case is ignored.

EXAMPLES

Print the names of all files under . modified since the start of 23 May 2011.

```
du -ta | awk '$1 >= '^'{seconds '23 may 2011'}^' {print $2}'
```

SOURCE

/sys/src/cmd/seconds.c

SEE ALSO

date(1), *du*(1), *mtime*(1), *ctime*(2)

BUGS

All-numeric dates, popular in the USA, are simply ambiguous, more so if the year is truncated to 2 digits.

aescbc, ipso, secstore - secstore commands

SYNOPSIS

```
auth/secstore [-cinv][-(g|G) getfile][-p putfile][-r rmfile][-s server][-u user
]
```

auth/aescbc -e [-in] <cleartext >ciphertext auth/aescbc -d [-in] <ciphertext >cleartext ipso [-a -e -l -f -s] [file ...]

DESCRIPTION

Secstore authenticates to a secure-store server using a password and optionally a hardware token, then saves or retrieves a file. This is intended to be a credentials store (public/private keypairs, passwords, and other secrets) for a factotum.

Option -c prompts for a password change.

Option -g retrieves a file to the local directory; option -G writes it to standard output instead. Specifying *getfile* of . will send to standard output a list of remote files with dates, lengths and SHA1 hashes.

Option -i says that the password should be read from standard input instead of from /dev/cons.

Option -n says that the password should be read from NVRAM (see *authsrv*(2)) instead of from /dev/cons.

Option -p stores a file on the secstore.

Option -r removes a file from the secstore.

Option -s sets the dial string of the *secstore*(8) server. The default is contained in the secstore environment variable. If the -s option is absent and secstore is empty, *secstore*(1) will attempt to dial tcp!suth!secstore.

Option –u access the secure-store files belonging to *user*.

Option -v produces more verbose output, in particular providing a few bits of feedback to help the user detect mistyping.

For example, to add a secret to the file read by *factotum*(4) at startup, open a new window, type

```
% ramfs -p; cd /tmp
% auth/secstore -g factotum
secstore password:
% echo 'key proto=apop dom=x.com user=ehg !password=hi' >> factotum
% auth/secstore -p factotum
secstore password:
% read -m factotum > /mnt/factotum/ctl
```

and delete the window. The first line creates an ephemeral memory-resident workspace, invisible to others and automatically removed when the window is deleted. The next three commands fetch the persistent copy of the secrets, append a new secret, and save the updated file back to secstore. The final command loads the new secret into the running factorum.

The *ipso* command packages this sequence into a convenient script to simplify editing of *files* stored on a secure store. It copies the named *files* into a local *ramfs*(4) and invokes *acme*(1) on them. When the editor exits, *ipso* prompts the user to confirm copying modifed or newly created files back to *secstore*. If no *file* is mentioned, *ipso* grabs all the user's files from *secstore* for editing.

By default, *ipso* will edit the *secstore* files and, if one of them is named factotum, flush current keys from factotum and load the new ones from the file. If the -e, -f, or -1 options are given, *ipso* will just perform only the requested operations, i.e., edit, flush, and/or load.

The -s option of *ipso* invokes *sam*(1) as the editor insted of acme; the -a option provides a similar service for files encrypted by *aescbc* (*q.v.*). With the -a option, the full rooted pathname of the

file must be specified and all files must be encrypted with the same key. Also with -a, newly created files are ignored.

Aescbc encrypts (under -e) and decrypts (under -d) using AES (Rijndael) in cipher block chaining (CBC) mode. Options i and n are as per secstore, except that i reads from file descriptor 3.

SOURCE

/rc/bin/ipso
/sys/src/cmd/auth/secstore

SEE ALSO

factotum(4), secstore(8)

DIAGNOSTICS

Secstore sets error status on failure but will not print an error message when reading NVRAM or dialing the secstore server fails unless the -v flag is specified.

BUGS

There is deliberately no backup of files on the secstore, so -r (or a disk crash) is irrevocable. You are advised to store important secrets in a second location.

When using *ipso*, secrets will appear as plain text in the editor window, so use the command in private.

sed - stream editor

SYNOPSIS

sed [-n] [-g] [-u] [-e script] [-f sfile] [file ...]

DESCRIPTION

Sed copies the named *files* (standard input default) to the standard output, edited according to a script of commands. The -f option causes the script to be taken from file *sfile*; these options accumulate. If there is just one -e option and no -f's, the option -e may be omitted. The -n option suppresses the default output; -g causes all substitutions to be global, as if suffixed g. If -u is specified, sed flushes its output buffers before reading in further input.

A script consists of editing commands, one per line, of the following form:

[address [, address]] function [argument ...] [;]

In normal operation *sed* cyclically copies a line of input into a *pattern space* (unless there is something left after a D command), applies in sequence all commands whose *addresses* select that pattern space, and at the end of the script copies the pattern space to the standard output (except under -n) and deletes the pattern space.

An *address* is either a decimal number that counts input lines cumulatively across files, a that addresses the last line of input, or a context address, */regular-expression/*, in the style of *regexp*(6), with the added convention that n matches a newline embedded in the pattern space.

A command line with no addresses selects every pattern space.

A command line with one address selects each pattern space that matches the address.

A command line with two addresses selects the inclusive range from the first pattern space that matches the first address through the next pattern space that matches the second. (If the second address is a number less than or equal to the line number first selected, only one line is selected.) Thereafter the process is repeated, looking again for the first address.

Editing commands can be applied to non-selected pattern spaces by use of the negation function ! (below).

An argument denoted *text* consists of one or more lines, all but the last of which end with \setminus to hide the newline. Backslashes in text are treated like backslashes in the replacement string of an s command, and may be used to protect initial blanks and tabs against the stripping that is done on every script line.

An argument denoted *rfile* or *wfile* must terminate the command line and must be preceded by exactly one blank. Each *wfile* is created before processing begins. There can be at most 120 distinct *wfile* arguments.

a∖	
text	Append. Place <i>text</i> on the output before reading the next input line.
b <i>label</i>	Branch to the : command bearing the <i>label</i> . If <i>label</i> is empty, branch to the end of the script.
c\	
text	Change. Delete the pattern space. With 0 or 1 address or at the end of a 2-address range, place <i>text</i> on the output. Start the next cycle.
d	Delete the pattern space. Start the next cycle.
D	Delete the initial segment of the pattern space through the first newline. Start the next cycle.
g	Replace the contents of the pattern space by the contents of the hold space.
G	Append the contents of the hold space to the pattern space.
h	Replace the contents of the hold space by the contents of the pattern space.

H	Append the contents of t	the pattern space	to the hold space.
---	--------------------------	-------------------	--------------------

- i\ *text* Insert. Place *text* on the standard output.
- n Copy the pattern space to the standard output. Replace the pattern space with the next line of input.
- N Append the next line of input to the pattern space with an embedded newline. (The current line number changes.)
- p Print. Copy the pattern space to the standard output.
- P Copy the initial segment of the pattern space through the first newline to the standard output.
- q Quit. Branch to the end of the script. Do not start a new cycle.
- *r rfile* Read the contents of *rfile*. Place them on the output before reading the next input line.
- s/regular-expression/replacement/flags

Substitute the *replacement* string for instances of the *regular-expression* in the pattern space. Any character may be used instead of /. For a fuller description see *regexp*(6). *Flags* is zero or more of

- g Global. Substitute for all non-overlapping instances of the *regular expression* rather than just the first one.
- p Print the pattern space if a replacement was made.
- w wfile

Write. Append the pattern space to *wfile* if a replacement was made.

An ampersand & appearing in the replacement is replaced by the string matching the regular expression. The characters n, where *n* is a digit, are replaced by the text matched by the *n*-th regular subexpression enclosed between (and). When nested parenthesized subexpressions are present, *n* is determined by counting occurrences of (starting from the left.

t *label* Test. Branch to the : command bearing the *label* if any substitutions have been made since the most recent reading of an input line or execution of a t. If *label* is empty, branch to the end of the script.

wfile

w

- Write. Append the pattern space to *wfile*.
- x Exchange the contents of the pattern and hold spaces.
- y/string1/string2/

Transform. Replace all occurrences of characters in *string1* with the corresponding character in *string2*. The lengths of *string1* and *string2* must be equal.

- *! function* Don't. Apply the *function* (or group, if *function* is {) only to lines *not* selected by the address(es).
- # Comment. Ignore the rest of the line.
- : *label* This command does nothing; it bears a *label* for b and t commands to branch to.
- = Place the current line number on the standard output as a line.
- { Execute the following commands through a matching } only when the pattern space is selected.

An empty command is ignored.

EXAMPLES

sed 10q file

Print the first 10 lines of the file.

sed '/^\$/d'

Delete empty lines from standard input.

sed 's/UNIX/& system/g' Replace every instance of UNIX by UNIX system.			
/^\$/d	drop trailing blanks drop empty lines replace blanks by newlines		
/g /^\$/d' chapter* Print the files chapter1, chapter2, etc. one word to a line.			
nroff —ms manuscript sed ' \${			
-	if last line of file is empty, print it		
//N /^\n\$/D' Delete all but	if current line is empty, append next line if two lines are empty, delete the first one of each group of empty lines from a formatted manuscript.		

SOURCE

/sys/src/cmd/sed.c

SEE ALSO

ed(1), grep(1), awk(1), lex(1), sam(1), regexp(6)L. E. McMahon, 'SED — A Non-interactive Text Editor', Unix Research System Programmer's Manual, Volume 2.

BUGS

If input is from a pipe, buffering may consume characters beyond a line on which a q command is executed.

-u does not work as expected if \$ addressing is used.

seg – access a named segment

SYNOPSIS

seg [-WLrw] segment segment-size offset [value]

DESCRIPTION

seg accesses a named segment as provided by e.g. certain drivers. The operation to be performed is selected with -r and -w for reading and writing, respectively. The default operation size is a byte. C style notation for integers (e.g. 0x42 or 023) is accepted for the *segment-size*, *offset* and *value* parameters.

-W Perform a word (16 bit) operation

-L Perform a long / double word (32 bit) operation.

SOURCE

/sys/src/cmd/seg.c

SEE ALSO

io(1)

BUGS

No check of the *segment-size* and *offset* parameters is performed whatsoever. Odd values may cause the front to fall off.

HISTORY

Seg first appeared in 9front (April, 2011).

md – emulator

SYNOPSIS

games/md [-a] [-x scale] romfile

DESCRIPTION

Md is an emulator for the Sega Megadrive/Genesis. It executes the romfile given as an argument. The z, x, c, return and shift keys correspond to A, B, C, Start and Select, respectively. Other keys:

- F1 Pause the emulator. If already paused it will step one video frame.
- F12 Toggle the emulator's speedometer. It shows in the upper left, off-viewport corner, the ratio between the expected and observed time it took to draw 60 frames.
- t Toggle tracing of the emulator.
- ' It uncaps the 60fps frame rate and lets emulation go as fast as possible.
- Esc Pause the emulator.

Del Exit the emulator.

Command line options:

- -a Enable audio output.
- -x Scale the screen to a given factor regardless of the window's size.

SOURCE

/sys/src/games/md

BUGS

Probably!

HISTORY

Md first appeared in 9front (November, 2014).

seq - print sequences of numbers

SYNOPSIS

seq[-w][-fformat][first[incr]] last

DESCRIPTION

Seq prints a sequence of numbers, one per line, from *first* (default 1) to as near *last* as possible, in increments of *incr* (default 1). The loop is:

for(val = min; val <= max; val += incr) print val;</pre>

The numbers are interpreted as floating point.

Normally integer values are printed as decimal integers. The options are

- -f format Use the print(2)-style format print for printing each (floating point) number. The default is %g.
- -w Equalize the widths of all numbers by padding with leading zeros as necessary. Not effective with option -f, nor with numbers in exponential notation.

EXAMPLES

seq 0 .05 .1 Print 0 0.05 0.1 (on separate lines).

seq -w 0 .05 .1 Print 0.00 0.05 0.10.

SOURCE

/sys/src/cmd/seq.c

BUGS

Option -w always surveys every value in advance. Thus seq -w 1000000000 is a painful way to get an 'infinite' sequence.

size - print size of executable files

SYNOPSIS

size[file...]

DESCRIPTION

Size prints the size of the segments for each of the argument executable files (default <code>v.out</code>). The format is

textsizet + datasized + bsssizeb = total

where the numbers are in bytes.

SOURCE

/sys/src/cmd/size.c

SEE ALSO

a.out(6)

sleep - suspend execution for an interval

SYNOPSIS

sleep time

DESCRIPTION

Sleep suspends execution for *time* seconds. *Time* may be floating-point.

EXAMPLES

Execute a command 100 seconds hence.

{sleep 100; command}&

Repeat a command every 30 seconds.

while (){
 command
 sleep 30
}

SOURCE

/sys/src/cmd/sleep.c

SEE ALSO

sleep(2)

sort - sort and/or merge files

SYNOPSIS

sort [-cmuMbdfinrwtx][+pos1 [-pos2] ...] ... [-k pos1 [,pos2]] ... [-o output] [-T dir ...] [option ...] [file ...]

DESCRIPTION

Sort sorts lines of all the *files* together and writes the result on the standard output. If no input files are named, the standard input is sorted.

The default sort key is an entire line. Default ordering is lexicographic by runes. The ordering is affected globally by the following options, one or more of which may appear.

- -M Compare as months. The first three non-white space characters of the field are folded to upper case and compared so that JAN precedes FEB, etc. Invalid fields compare low to JAN.
- -b Ignore leading white space (spaces and tabs) in field comparisons.
- -d 'Phone directory' order: only letters, accented letters, digits and white space are significant in comparisons.
- -f Fold lower case letters onto upper case. Accented characters are folded to their nonaccented upper case form.
- -i Ignore characters outside the ASCII range 040-0176 in non-numeric comparisons.
- -w Like -i, but ignore only tabs and spaces.
- -n An initial numeric string, consisting of optional white space, optional plus or minus sign, and zero or more digits with optional decimal point, is sorted by arithmetic value.
- -g Numbers, like -n but with optional e-style exponents, are sorted by value.
- -r Reverse the sense of comparisons.
- -tx 'Tab character' separating fields is x.

The notation +pos1 - pos2 restricts a sort key to a field beginning at pos1 and ending just before pos2. Pos1 and pos2 each have the form $m \cdot n$, optionally followed by one or more of the flags Mbdfginr, where m tells a number of fields to skip from the beginning of the line and n tells a number of characters to skip further. If any flags are present they override all the global ordering options for this key. A missing $\cdot n$ means $\cdot 0$; a missing -pos2 means the end of the line. Under the -tx option, fields are strings separated by x; otherwise fields are non-empty strings separated by white space. White space before a field is part of the field, except under option -b. A b flag may be attached independently to pos1 and pos2.

The notation -k pos1[, pos2] is how POSIX sort defines fields: pos1 and pos2 have the same format but different meanings. The value of *m* is origin 1 instead of origin 0 and a missing . *n* in pos2 is the end of the field.

When there are multiple sort keys, later keys are compared only after all earlier keys compare equal. Lines that otherwise compare equal are ordered with all bytes significant.

These option arguments are also understood:

- -c Check that the single input file is sorted according to the ordering rules; give no output unless the file is out of sort.
- -m Merge; assume the input files are already sorted.
- -u Suppress all but one in each set of equal lines. Ignored bytes and bytes outside keys do not participate in this comparison.
- -o The next argument is the name of an output file to use instead of the standard output. This file may be the same as one of the inputs.

-T *dir* Put temporary files in *dir* rather than in /tmp.

EXAMPLES

sort -u +0f +0 list

Print in alphabetical order all the unique spellings in a list of words where capitalized words differ from uncapitalized.

sort -t: +1 /adm/users Print the users file sorted by user name (the second colon-separated field). sort -umM dates

Print the first instance of each month in an already sorted file. Options –um with just one input file make the choice of a unique representative from a set of equal lines predictable.

grep -n '^' input | sort -t: +1f +0n | sed 's/[0-9]*://'
A stable sort: input lines that compare equal will come out in their original order.

FILES

/tmp/sort.<pid>.<ordinal>

SOURCE

/sys/src/cmd/sort.c

SEE ALSO

uniq(1), look(1)

DIAGNOSTICS

Sort comments and exits with non-null status for various trouble conditions and for disorder discovered under option -c.

BUGS

An external null character can be confused with an internally generated end-of-field character. The result can make a sub-field not sort less than a longer field.

Some of the options, e.g. -i and -M, are hopelessly provincial.

spell, sprog – find spelling errors

SYNOPSIS

spell [options] ... [file] ...

aux/sprog [options] [-f file]

DESCRIPTION

Spell looks up words from the named *files* (standard input default) in a spelling list and places possible misspellings—words not sanctioned there—on the standard output.

Spell ignores constructs of troff(1) and its standard preprocessors. It understands these options:

- -b Check British spelling.
- -v Print all words not literally in the spelling list, with derivations.
- -x Print on standard error, marked with =, every stem as it is looked up in the spelling list, along with its affix classes.

As a matter of policy, *spell* does not admit multiple spellings of the same word. Variants that follow general rules are preferred over those that don't, even when the unruly spelling is more common. Thus, in American usage, 'modelled', 'sizeable', and 'judgment' are rejected in favor of 'modeled', 'sizable', and 'judgement'. Agglutinated variants are shunned: 'crewmember' and 'backyard' cede to 'crew member' and 'back yard' (noun) or 'back-yard' (adjective).

FILES

/sys/lib/amspell American spelling list
/sys/lib/brspell British spelling list
/bin/aux/sprog The actual spelling checker. It expects one word per line on standard
input, and takes the same arguments as spell.

SOURCE

/rc/bin/spell the script
/sys/src/cmd/spell source for sprog

SEE ALSO

deroff(1)

BUGS

The heuristics of *deroff*(1) used to excise formatting information are imperfect.

The spelling list's coverage is uneven; in particular biology, medicine, and chemistry, and perforce proper names, not to mention languages other than English, are covered very lightly.

spin - verification tool for models of concurrent systems

SYNOPSIS

```
spin -a [ -m ] [ -Pcpp ] file
spin [ -bglmprsv ] [ -nN ] [ -Pcpp ] file
spin -c [ -t ] [ -Pcpp ] file
spin -d [ -Pcpp ] file
spin -f ltl
spin -F file
spin -i [ -bglmprsv ] [ -nN ] [ -Pcpp ] file
spin -t[N] [ -Pcpp ] file
spin -t[N] [ -bglmprsv ] [ -jN ] [ -Pcpp ] file
spin -V
```

DESCRIPTION

Spin is a tool for analyzing the logical consistency of asynchronous systems, specifically distributed software and communication protocols. A verification model of the system is first specified in a guarded command language called *Promela*. This specification language, described in the reference, allows for the modeling of dynamic creation of asynchronous processes, nondeterministic case selection, loops, gotos, local and global variables. It also allows for a concise specification of logical correctness requirements, including, but not restricted to, requirements expressed in linear temporal logic.

Given a Promela model stored in *file*, *spin* can perform interactive, guided, or random simulations of the system's execution. It can also generate a C program that performs an exhaustive or approximate verification of the correctness requirements for the system.

- -a Generate a verifier (model checker) for the specification. The output is written into a set of C files, named pan.[cbhmt], that can be compiled (pcc pan.c) to produce an executable verifier. The online *spin* manuals (see below) contain the details on compilation and use of the verifiers.
- -c Produce an ASCII approximation of a message sequence chart for a random or guided (when combined with -t) simulation run. See also option -M.
- -d Produce symbol table information for the model specified in *file*. For each Promela object this information includes the type, name and number of elements (if declared as an array), the initial value (if a data object) or size (if a message channel), the scope (global or local), and whether the object is declared as a variable or as a parameter. For message channels, the data types of the message fields are listed. For structure variables, the third field defines the name of the structure declaration that contains the variable.
- -f *ltl* Translate the LTL formula *ltl* into a *never* claim.

This option reads a formula in LTL syntax from the second argument and translates it into Promela syntax (a *never* claim, which is Promela's equivalent of a Büchi Automaton). The LTL operators are written: [] (always), <> (eventually), and U (strong until). There is no X (next) operator, to secure compatibility with the partial order reduction rules that are applied during the verification process. If the formula contains spaces, it should be quoted to form a single argument to the *spin* command.

-F file

Translate the LTL formula stored in *file* into a *never* claim.

This behaves identically to option -f but will read the formula from the *file* instead of from the command line. The file should contain the formula as the first line. Any text that follows this first line is ignored, so it can be used to store comments or annotation on the formula. (On some systems the quoting conventions of the shell complicate the use of option -f. Option -F is meant to solve those problems.)

- -i Perform an interactive simulation, prompting the user at every execution step that requires a nondeterministic choice to be made. The simulation proceeds without user intervention when execution is deterministic.
- -M Produce a message sequence chart in Postscript form for a random simulation or a guided simulation (when combined with -t), for the model in *file*, and write the result into *file.ps*. See also option -c.
- -m Changes the semantics of send events. Ordinarily, a send action will be (blocked) if the target message buffer is full. With this option a message sent to a full buffer is lost.
- -nN Set the seed for a random simulation to the integer value *N*. There is no space between the -n and the integer *N*.
- -t Perform a guided simulation, following the error trail that was produces by an earlier verification run, see the online manuals for the details on verification.
- -V Prints the *spin* version number and exits.

With only a filename as an argument and no options, *spin* performs a random simulation of the model specified in the file (standard input is the default if the filename is omitted). If option -i is added, the simulation is *interactive*, or if option -t is added, the simulation is *guided*.

The simulation normally does not generate output, except what is generated explicitly by the user within the model with *printf* statements, and some details about the final state that is reached after the simulation completes. The group of options -bglmprsv sets the desired level of information that the user wants about a random, guided, or interactive simulation run. Every line of output normally contains a reference to the source line in the specification that generated it.

- -b Suppress the execution of *printf* statements within the model.
- -g Show at each time step the current value of global variables.
- -1 In combination with option -p, show the current value of local variables of the process.
- -p Show at each simulation step which process changed state, and what source statement was executed.
- -r Show all message-receive events, giving the name and number of the receiving process and the corresponding the source line number. For each message parameter, show the message type and the message channel number and name.
- -s Show all message-send events.
- -v Verbose mode, add some more detail, and generate more hints and warnings about the model.

SOURCE

/sys/src/cmd/spin

SEE ALSO

- http://spinroot.com: GettingStarted.pdf, Roadmap.pdf, Manual.pdf, WhatsNew.pdf, Exercises.pdf
- G.J. Holzmann, Design and Validation of Computer Protocols, Prentice Hall, 1991.

-, 'Design and validation of protocols: a tutorial,' *Computer Networks and ISDN Systems*, Vol. 25, No. 9, 1993, pp. 981-1017.

-, 'The model checker Spin,' *IEEE Trans. on SE*, Vol, 23, No. 5, May 1997.

split - split a file into pieces

SYNOPSIS

split [option ...] [file]

DESCRIPTION

Split reads *file* (standard input by default) and writes it in pieces of 1000 lines per output file. The names of the output files are xaa, xab, and so on to xzz. The options are

- -n *n* Split into *n*-line pieces.
- -1 n Synonym for -n n, a nod to Unix's syntax.
- -e expression

File divisions occur at each line that matches a regular *expression*; see regexp(6). Multiple –e options may appear. If a subexpression of *expression* is contained in parentheses (...), the output file name is the portion of the line which matches the subexpression.

−f stem

Use *stem* instead of x in output file names.

-s suffix

Append *suffix* to names identified under -e.

- -x Exclude the matched input line from the output file.
- -i Ignore case in option -e; force output file names (excluding the suffix) to lower case.

SOURCE

/sys/src/cmd/split.c

SEE ALSO

sed(1), awk(1), grep(1), regexp(6)

spred – sprite editor

SYNOPSIS

spred

DESCRIPTION

Spred is an editor for small images using a limited palette. It uses a window system mimicking *sam*(1). There is a command window which uses a command language described below. There is also an arbitrary number of palette and sprite windows. Each open sprite file has an associated palette file.

A left click on a color in a palette window selects that color. Colors in different palettes can be selected indepedently. A left click on a pixel in a sprite window sets that pixel to the selected color.

A right click brings up the global menu to create windows etc. It also lists all currently open files, including those that are not open in any window. A middle click brings up the menu for the local window, if applicable. Available commands there are:

pal The *pal* command sets the palette for the current sprite window. The palette is selected with a middle click.

The command language is a very stripped down version of rc(1), currently only supporting "simple" commands consisting of a name and an arbitrary number of arguments separated by spaces. Quoting works just like with rc(1). Available commands are:

q Quits the program. If any files have unsaved changes, it will fail on the first attempt to quit.

pal file

spr file

Open a palette (*pal*) or sprite (*spr*) file named *file*. If the file does not exist it is created.

w *file* Write the currently selected file to *file*. If *file* is not specified, the name specified to the command opening the file is used.

size sz

Sets the size of the current file to sz. Sz should be of the form n for palettes or n^*m for sprites where n and m are integers.

set 0xrrggbb

Sets the currently selected color to the rgb color (*rr,gg,bb*) where *rr, gg* and *bb* are in hexadecimal notation.

zoom n

Sets the current zoom factor to *n*.

SOURCE

/sys/src/cmd/spred

SEE ALSO

sam(1)

src, Bfn - find source code for executable

SYNOPSIS

src[-n][-s symbol] file ...

Bfn fn

DESCRIPTION

Src examines the named *files* to find the corresponding source code, which is then sent to the editor using B (see sam(1)). If *file* is an rc(1) script, the source is the file itself. If *file* is an executable, the source is defined to be the single file containing the definition of main and *src* will point the editor at the line that begins the definition. *Src* uses db(1) to extract the symbol table information that identifies the source.

Src looks for each *file* in the current directory, in /bin, and in the subdirectories of /bin, in that order.

The -n flag causes src to print the file name but not send it to the editor. The -s flag identifies a *symbol* other than main to locate.

Bfn finds the definition of all C functions named *fn* by searching the .c files in the current directory. It prints the file name and line number of each match found and submits the match to the plumber(4) if it is unique. *Fn* can be a regexp(6).

EXAMPLES

Find the source to the main routine in /bin/ed:

src ed

Find the source for strcmp:

src -s strcmp rc

SOURCE

/rc/bin/src

SEE ALSO

db(1), plumb(1), sam(1).

BUGS

Bfn requires the source code to follow style(6).

ssam - stream interface to sam

SYNOPSIS

ssam [-n][-e script][-f sfile][file ...]

DESCRIPTION

Ssam copies the named *files* (standard input default) to the standard output, edited by a script of *sam* commands (q.v.). When the script starts, the entire input is selected. The -f option causes the script to be taken from file *sfile*. If there is a -e option and no -f, the flag -e may be omitted. The -n option suppresses the default output.

EXAMPLES

- ssam -n ,10p file Print first 10 lines of file.
- ssam 'y/[a-zA-Z]+/c/n/'*.msPrint one word per line.
- ssam 's/\n\n+/\n/g' Delete empty lines from standard input.
- ssam 's/UNIX/& system/g'
 Replace every instance of UNIX by UNIX system.
- ssam 'y/[a-zA-Z]+/ c/n/' | grep . Count frequency of words read from standard input.

SOURCE

/rc/bin/ssam

SEE ALSO

sed(1), *sam*(1), *regexp*(6)

Rob Pike, "The text editor sam".

BUGS

Ssam consumes all of standard input before running the script.

ssh – secure shell remote login client

SYNOPSIS

```
ssh[-d][-R][-r][-t thumbfile ][-T tries ][-u user ][-h][user@]host [-W remote!port][cmd args ...]
```

DESCRIPTION

Ssh starts a remote shell or *cmd* on the computer *host* logged in as *user*. The input file descriptor is forwarded to the remote side and output and error descriptors are forwarded to the local side.

The connection is authenticated and encrypted using the SSH2 protocol. The user authenticates itself to the host using his RSA key pair (stored in factotum) or plaintext passwords. To authenticate the host to the user, the hosts RSA public key is hashed and compared to the entries in $\home/lib/sshthumbs$ file (see *thumbprint*(6)). The *thumbfile* location can be changed with the -t option.

When *cmd* is specified, it is concatenated with the list of quoted *args* and run on the remote side. No pseudo terminal will be requested. A *cmd* beginning with # is interpreted as a subsystem name such as sftp (see *sshfs*(4)).

Without *cmd*, a shell is started on the remote side. In that case and when the TERM environment variable is set (such as when started under a terminal emulator like vt(1)), a pseudo terminal will be requested for the shell. This can be disabled with the -R option. A pseudo-terminal can be requested in all cases with the -r option.

With the -W option, instead of executing a command remotely, makes the server dial a tcp connection to *remote!port* which the client relays on standard input and output. For handling multiple connections transparently to programs, see *sshnet*(4).

The -d option enables debug output.

FILES

\$home/lib/sshthumbs the user's thumbfile of known host fingerprints

SOURCE

/sys/src/cmd/ssh.c

BUGS

If *keyboard-interactive* authentication fails, by default it is retried three times. The number of *tries* can be changed with -T. Setting it to zero disables keyboard-interactive authentication.

SEE ALSO

vt(1), rsa(8), thumbprint(6), factotum(4), sshfs(4), sshnet(4)

stop, start - print commands to stop and start processes

SYNOPSIS

stop name

start name

DESCRIPTION

Stop prints commands that will cause all processes called *name* and owned by the current user to be stopped. The processes can then be debugged when they are in a consistent state.

Start prints commands that will cause all stopped processes called *name* and owned by the current user to be started again.

Use the send command of *rio*(1), or pipe into *rc*(1) to execute the commands.

SOURCE

/rc/bin/stop /rc/bin/start

SEE ALSO

ps(1), kill(1), proc(3)

strings – extract printable strings

SYNOPSIS

strings[-m min][file ...]

DESCRIPTION

Strings finds and prints strings containing *min* (default 6) or more consecutive printable UTFencoded characters in a (typically) binary file, default standard input. Printable characters are taken to be ASCII characters from blank through tilde (hexadecimal 20 through 7E), inclusive, and all other characters above A0. Strings reports the decimal offset within the file at which the string starts and the text of the string.

SOURCE

/sys/src/cmd/strings.c

SEE ALSO

nm(1)

strip - remove symbols from binary files

SYNOPSIS

strip file ...

strip -o ofile file

DESCRIPTION

Strip removes symbol table segments from executable files, rewriting the files in place. Stripping a file requires write permission of the file and the directory it is in.

If the -o flag is given, the single input file *file* is stripped and the result written to *ofile*. *File* is unchanged.

SOURCE

/sys/src/cmd/strip.c

SEE ALSO

a.out(6)

sum, md5sum, sha1sum - sum and count blocks in a file

SYNOPSIS

sum [-5r] [file ...]

md5sum[*file*...]

sha1sum [-2 *bits*] [*file* ...]

DESCRIPTION

By default, *sum* calculates and prints a 32-bit hexadecimal checksum, a byte count, and the name of each *file*. The checksum is also a function of the input length. If no *files* are given, the standard input is summed. Other summing algorithms are available. The options are

- -r Sum with the algorithm of System V's sum -r and print the length (in 1K blocks) of the input.
- -5 Sum with System V's default algorithm and print the length (in 512-byte blocks) of the input.

Sum is typically used to look for bad spots, to validate a file communicated over some transmission line or as a quick way to determine if two files on different machines might be the same.

Md5sum computes the 32 hex digit RSA Data Security, Inc. MD5 Message-Digest Algorithm described in RFC1321.

Sha1sum computes the 40 hex digit National Institute of Standards and Technology (NIST) SHA1 secure hash algorithm described in FIPS PUB 180–1, by default. Given the 2 option, it instead computes the *bits*-bit NIST SHA2 secure hash algorithm described in FIPS PUB 180–2 and prints the hash in hex. Currently supported values of *bits* are 224, 256, 384, and 512.

SOURCE

/sys/src/cmd/sum.c
/sys/src/cmd/md5sum.c
/sys/src/cmd/sha1sum.c

SEE ALSO

cmp(1), wc(1), sechash(2)

syscall - test a system call

SYNOPSIS

syscall [-os] entry [arg ...]

DESCRIPTION

Syscall invokes the system call *entry* with the given arguments. The return value is printed. If an error occured, the error string is also printed.

For convenience, *write*(2) and *read*(2) are included in *entries*, even though they are not strictly syscalls.

Syscall arguments are integer constants, strings, or the literal buf. The literal buf refers to a writable 1 megabyte buffer. Strings and buf are passed as pointers. Integers are passed as values.

The -o option prints contents of the 1MB buffer. For *errstr*(2) and *fd2path*(2), the buffer is treated as a 0-terminated string. For other calls, the number of bytes printed is determined by the system call's return value.

The -s option is similar, but interprets the data as a *stat*(5) message and formats it to standard output.

EXAMPLES

Write a string to standard output:

syscall write 1 hello 5

Print information about the file connected to standard input:

syscall -s fstat 0 buf 1024

SOURCE

/sys/src/cmd/syscall

SEE ALSO

Section 2 of this manual.

DIAGNOSTICS

If *entry* is not known to *syscall*, the exit status is unknown. If the system call succeeds, the exit status is null; otherwise the exit status is the string that *errstr*(2) returns.

sysinfo, sysupdate - report information about, update the system

SYNOPSIS

sysinfo[-e e-mail][-p]
sysupdate[-i]

DESCRIPTION

Sysinfo executes a number of commands that report information about the hardware and software configuration of the running system, concatenating the output to stdout.

posted website The -p flag causes the output to be at а archive, http://sysinfo.9front.org, which in turn forwards the message to a mailing list, 9front-sysinfo@9front.org. A URL pointing to the archived output is returned. The -e flag causes a reply-to e-mail address to be included in the message (the e-mail address is not divulged to the mailing list). These flags are useful for reporting new installs to the development team.

Sysupdate updates the local mercurial repository by executing the following commands:

bind -ac /dist/plan9front /
hg -v pull -u

If the -i flag is included, the command hg incoming is prepended.

SOURCE

/rc/bin/sysinfo
/rc/bin/sysupdate

SEE ALSO

intro(3), plan9.ini(8), hg(1)

HISTORY

Sysinfo first appeared in 9front (May, 2012). Sysupdate first appeared in 9front (February, 2012).

tail - deliver the last part of a file

SYNOPSIS

tail [+-number[lbc][rf]] [file]

tail [-fr][-n nlines][-c nbytes][file]

DESCRIPTION

Tail copies the named file to the standard output beginning at a designated place. If no file is named, the standard input is copied.

Copying begins at position +*number* measured from the beginning, or –*number* from the end of the input. *Number* is counted in lines, 1K blocks or bytes, according to the appended flag 1, b, or c. Default is -101 (ten ell).

The further flag r causes tail to print lines from the end of the file in reverse order; f (follow) causes *tail*, after printing to the end, to keep watch and print further data as it appears.

The second syntax is that promulgated by POSIX, where the *numbers* rather than the options are signed.

EXAMPLES

tail file

Print the last 10 lines of a file.

tail +0f file

Print a file, and continue to watch data accumulate as it grows.

sed 10q file

Print the first 10 lines of a file.

SOURCE

/sys/src/cmd/tail.c

BUGS

Tails relative to the end of the file are treasured up in a buffer, and thus are limited in length.

According to custom, option +*number* counts lines from 1, and counts blocks and bytes from 0. *Tail* is ignorant of UTF.

tap - follow the pipes of a process

SYNOPSIS

tap[*pid...*]

DESCRIPTION

Tap walks the file descriptors of a process looking for pipes (see pipe(3)) and then finds the processes on the other end of these pipes repeating the process recursively. The result is a tree of alternating process and filedescriptor nodes that make up the process pipeline.

SOURCE

/rc/bin/tap

SEE ALSO

ps(1), *pipe*(3), *proc*(3).

HISTORY

Tap first appeared in 9front (March, 2012).

tar, dircp - archiver

SYNOPSIS

tar key [file ...]

dircp fromdir todir

DESCRIPTION

Tar saves and restores file trees. It is most often used to transport a tree of files from one system to another. The *key* is a string that contains at most one function letter plus optional modifiers. Other arguments to the command are names of files or directories to be dumped or restored. A directory name implies all the contained files and subdirectories (recursively).

The function is one of the following letters:

- c Create a new archive with the given files as contents.
- r The named files are appended to the archive.
- t List all occurrences of each *file* in the archive, or of all files if there are no *file* arguments.
- x Extract the named files from the archive. If a file is a directory, the directory is extracted recursively. Modes are restored if possible. If no file argument is given, extract the entire archive. If the archive contains multiple entries for a file, the latest one wins.

The modifiers are:

- f Use the next argument as the name of the archive instead of the default standard input (for keys x and t) or standard output (for keys c and r).
- g Use the next (numeric) argument as the group id for files in the output archive.
- i Ignore errors encountered when reading. Errors writing either produce a corrupt archive or indicate deeper file system problems.
- k (keep) Modifies the behavior of x not to extract files which already exist.
- m Do not set the modification time on extracted files. This is the default behavior; the flag exists only for compatibility with other tars.
- p Create archive in POSIX ustar format, which raises the maximum pathname length from 100 to 256 bytes. Ustar archives are recognised automatically by *tar* when reading archives. This is the default behavior; the flag exists only for backwards compatibility with older versions of tar.
- P Do not generate the POSIX ustar format.
- R When extracting, respect leading slash on file names. By default, files are always extracted relative to the current directory.
- s When extracting, attempt to resynchronise after not finding a tape header block where expected.
- T Modifies the behavior of x to set the modified time, mode and, for POSIX archives and filesystem permitting, the user and group of each file to that specified in the archive.
- u Use the next (numeric) argument as the user id for files in the output archive. This is only useful when moving files to a non-Plan 9 system.
- $v \,$ (verbose) Print the name of each file as it is processed. With t, give more details about the archive entries.
- Z Operate on compressed *tar* archives. The type of compression is inferred from the file name extension: *gzip*(1) for .tar.gz and .tgz; *bzip2* (see *gzip*(1)) for .tar.bz, .tbz, .tar.bz2, and .tbz2; *compress* for .tar.Z and .tz. If no extension matches, *gzip* is used. The z flag is unnecessary (but allowed) when using the t and x verbs on archives with recognized extensions.

EXAMPLES

Tar can be used to copy hierarchies thus:

```
@{cd fromdir && tar c .} | @{cd todir && tar xT}
```

Dircp does this.

SOURCE

```
/sys/src/cmd/tar.c
/rc/bin/dircp
```

SEE ALSO

ar(1), bundle(1), tapefs(4), mkfs(8)

BUGS

There is no way to ask for any but the last occurrence of a file.

File path names are limited to 100 characters (256 when using ustar format).

The *tar* format allows specification of links and symbolic links, concepts foreign to Plan 9: they are ignored.

The r key (append) cannot be used on compressed archives.

The $\ensuremath{\mathrm{T}}$ key (write metadata) won't work for non-empty directories.

Tar, thus *dircp*, doesn't record Plan-9-specific metadata such as append-only and exclusive-open permission bits, so they aren't copied.

tbl - format tables for nroff or troff

SYNOPSIS

tbl [*file ...*]

DESCRIPTION

Tbl is a preprocessor for formatting tables for *nroff* or *troff*(1). The input *files* are copied to the standard output, except for segments of the form

.TS options ; format . data .T& format . dataTE

which describe tables and are replaced by *troff* requests to lay out the tables. If no arguments are given, *tbl* reads the standard input.

The (optional) options line is terminated by a semicolon and contains one or more of

center	center the table; default is left-adjust
expand	make table as wide as current line length
box	
doublebox	enclose the table in a box or double box
allbox	enclose every item in a box
tab(x)	use <i>x</i> to separate input items; default is tab
linesize(<i>n</i>)	set rules in <i>n</i> -point type
<pre>delim(xy)</pre>	recognize x and y as $eqn(1)$ delimiters

Each line, except the last, of the obligatory *format* describes one row of the table. The last line describes all rows until the next . T&, where the format changes, or the end of the table at . TE. A format is specified by key letters, one per column, either upper or lower case:

- L Left justify: the default for columns without format keys.
- R Right justify.
- C Center.
- N Numeric: align at decimal point (inferred for integers) or at &.
- S Span: extend previous column across this one.
- A Alphabetic: left-aligned within column, widest item centered, indented relative to L rows.
- Vertical span: continue item from previous row into this row.
- Draw a horizontal rule in this column.
- = Draw a double horizontal rule in this column.

Key letters may be followed by modifiers, also either case:

- Draw vertical rule between columns.
- Draw a double vertical rule between columns.
- *n* Gap between column is *n* ens wide. Default is 3.
- Ffont Use specified font. B and I mean FB and FI.
- T Begin vertically-spanned item at top row of range; default is vertical centering (with \wedge).
- Pn Use point size n.
- Vn Use *n*-point vertical spacing in text block; signed *n* means relative change.
- W(n) Column width as a *troff* width specification. Parens are optional if *n* is a simple integer.
- E Equalize the widths of all columns marked E.

Each line of *data* becomes one row of the table; tabs separate items. Lines beginning with . are *troff* requests. Certain special data items are recognized:

- _ Draw a horizontal rule in this column.
- Draw a double horizontal rule in this column. A data line consisting of a single _ or
 = draws the rule across the whole table.
- _ Draw a rule only as wide as the contents of the column.
- Rx Repeat character *x* across the column.
- \land Span the previous item in this column down into this row.
- T{ The item is a text block to be separately formatted by *troff* and placed in the table. The block continues to the next line beginning with T}. The remainder of the data line follows at that point.

When it is used in a pipeline with *eqn*, the *tbl* command should be first, to minimize the volume of data passed through pipes.

EXAMPLES

Let <tab> represent a tab (which should be typed as a genuine tab).

.TS

CSS			
CCS			
ССС	Household 1	Populatio	n
lnn.	Town	Households	
Household Population		Number	Size
Town <tab>Households</tab>	Bedminster	789	3.26
<tab>Number<tab>Size</tab></tab>	Bernards Twp.	3087	3.74
Bedminster <tab>789<tab>3.26</tab></tab>	Bernardsville	2018	3.30
Bernards Twp. <tab>3087<tab>3.74</tab></tab>			
Bernardsville <tab>2018<tab>3.30</tab></tab>			
.TE			

SOURCE

/sys/src/cmd/tbl

SEE ALSO

troff(1), eqn(1), doctype(1)

M. E. Lesk and L. L. Cherry, "TBL—a Program to Format Tables", Unix Research System Programmer's Manual, Tenth Edition, Volume 2.

tcs – translate character sets

SYNOPSIS

tcs[-slcv][-f *ics*][-t *ocs*][*file* ...]

DESCRIPTION

Tcs interprets the named *file(s)* (standard input default) as a stream of characters from the *ics* character set or format, converts them to runes, and then converts them into a stream of characters from the *ocs* character set or format on the standard output. The default value for *ics* and *ocs* is utf, the UTF encoding described in *utf*(6). The -1 option lists the character sets known to *tcs*. Processing continues in the face of conversion errors (the -s option prevents reporting of these errors). The -c option forces the output to contain only correctly converted characters; otherwise, Runeerror (0xFFFD) characters will be substituted for UTF encoding errors and unknown characters.

The -v option generates various diagnostic and summary information on standard error, or makes the -1 output more verbose.

Tcs recognizes an ever changing list of character sets. In particular, it supports a variety of Russian and Japanese encodings. Some of the supported encodings are

utf	The Plan 9 UTF encoding, known by ISO as UTF-8
utf1	The deprecated original UTF encoding from ISO 10646
ascii	7-bit ASCII
8859-1	Latin-1 (Central European)
8859-2	Latin-2 (Czech Slovak)
8859-3	Latin-3 (Dutch Turkish)
8859-4	Latin-4 (Scandinavian)
8859-5	Part 5 (Cyrillic)
8859-6	Part 6 (Arabic)
8859-7	Part 7 (Greek)
8859-8	Part 8 (Hebrew)
8859-9	Latin-5 (Finnish Portuguese)
html	Unicode as encoded by HTML
koi8	KOI-8 (GOST 19769-74)
jis-kanji	ISO 2022–JP
ujis	EUC–JX: JIS 0208
ms-kanji	Microsoft, or Shift-JIS
jis	(from only) guesses between ISO 2022–JP, EUC or Shift–Jis
gb	Chinese national standard (GB2312-80)
big5	Big 5 (HKU version)
unicode	Unicode Standard 1.0
tis	Thai character set plus ASCII (TIS 620–1986)
msdos	IBM PC: CP 437
atari	Atari-ST character set

EXAMPLES

tcs -f 8859-1

Convert 8859-1 (Latin-1) characters into UTF format.

tcs -s -f jis

Convert characters encoded in one of several shift JIS encodings into UTF format. Unknown Kanji will be converted into 0xFFFD characters.

tcs -t html

Convert UTF into character set-independent HTML.

tcs -lv

Print an up to date list of the supported character sets.

SOURCE

/sys/src/cmd/tcs

SEE ALSO

ascii(1), rune(2), utf(6).

tee – pipe fitting

SYNOPSIS

tee[−i][−a]*files*

DESCRIPTION

Tee transcribes the standard input to the standard output and makes copies in the *files*. The options are

-i Ignore interrupts.

-a Append the output to the *files* rather than rewriting them.

SOURCE

/sys/src/cmd/tee.c

tel, iwhois – look in phone book

SYNOPSIS

tel key ...

iwhois name[@domain]

DESCRIPTION

Tel looks up *key* in a private telephone book, home/lib/tel, and in the public telephone book, /lib/tel. It uses *grep* (with the -i option to ignore case differences), so the key may be any part of a name or number. Customarily, the telephone book contains names, userids, home numbers, and office numbers of users. It also contains a directory of area codes and miscellaneous people of general interest.

Iwhois looks up names in the Internet NIC's personnel database. *Name* should be a surname optionally followed by a comma and given name. A different server can be chosen by appending to the name an @ followed by the server's domain name.

FILES

/lib/areacodes	Telephone area codes database.
/lib/tel	Public telephone number database.
<pre>\$home/lib/tel</pre>	Personal telephone number database.

SOURCE

/rc/bin/tel /rc/bin/iwhois

test - set status according to condition

SYNOPSIS

test expr

DESCRIPTION

Test evaluates the expression *expr*. If the value is true the exit status is null; otherwise the exit status is non-null. If there are no arguments the exit status is non-null.

The following primitives are used to construct *expr*.

- -r *file* True if the file exists (is accessible) and is readable.
- -w *file* True if the file exists and is writable.
- -x *file* True if the file exists and has execute permission.
- -e *file* True if the file exists.
- -f file True if the file exists and is a plain file.
- -d file True if the file exists and is a directory.
- -s *file* True if the file exists and has a size greater than zero.
- -t *fildes* True if the open file whose file descriptor number is *fildes* (1 by default) is the same file as /dev/cons.
- -A *file* True if the file exists and is append-only.
- -L *file* True if the file exists and is exclusive-use.
- -T*file* True if the file exists and is temporary.
- s1 = s2 True if the strings s1 and s2 are identical.
- s1 = s2 True if the strings s1 and s2 are not identical.
- s1 True if *s1* is not the null string. (Deprecated.)
- -n s1 True if the length of string s1 is non-zero.
- $-z \ s1$ True if the length of string s1 is zero.
- n1 -eq n2 True if the integers n1 and n2 are arithmetically equal. Any of the comparisons -ne, -gt, -ge, -lt, or -le may be used in place of -eq. The (nonstandard) construct -l string, meaning the length of string, may be used in place of an integer.
- a nt b True if file a is newer than (modified after) file b.
- a ot b True if file a is older than (modified before) file b.
- f -older t True if file f is older than (modified before) time t. If t is a integer followed by the letters y(years), M(months), d(days), h(hours), m(minutes), or s(seconds), it represents current time minus the specified time. If there is no letter, it represents seconds since epoch. You can also concatenate mixed units. For example, 3d12h means three days and twelve hours ago.

These primaries may be combined with the following operators:

- ! unary negation operator
- -o binary *or* operator
- -a binary *and* operator; higher precedence than -o
- (*expr*) parentheses for grouping.

The primitives -b, -u, -g, and -s return false; they are recognized for compatibility with POSIX.

Notice that all the operators and flags are separate arguments to *test*. Notice also that parentheses and equal signs are meaningful to *rc* and must be enclosed in quotes.

EXAMPLES

Test is a dubious way to check for specific character strings: it uses a process to do what an rc(1) match or switch statement can do. The first example is not only inefficient but wrong, because *test* understands the purported string "-c" as an option.

if (test \$1 '=' "-c") echo OK # wrong!

A better way is

if (~ \$1 -c) echo OK

Test whether abc is in the current directory.

test -f abc -o -d abc

SOURCE

/sys/src/cmd/test.c

SEE ALSO

rc(1)

BUGS

Won't complain about extraneous arguments since there may be arguments left unprocessed by short-circuit evaluation of -a or -o.

thesaurus - search online thesaurus

SYNOPSIS

thesaurus word

DESCRIPTION

thesaurus searches the online thesaurus at http://thesaurus.reference.com

SOURCE

/rc/bin/thesaurus

time - time a command

SYNOPSIS

time command [arg ...]

DESCRIPTION

The *command* is executed with the given arguments; after it is complete, *time* reports on standard error the program's elapsed user time, system time, and real time, in seconds, followed by the command line.

SOURCE

/sys/src/cmd/time.c

SEE ALSO

prof(1)

timepic - troff preprocessor for drawing timing diagrams

SYNOPSIS

timepic[files]

DESCRIPTION

Timepic is a *pic*(1) and *troff*(1) preprocessor for drawing timing diagrams. *Timepic* code is contained between .TPS and .TPE lines:

.TPS width row-height statement-list .TPE

There are two types of *timepic* statements: variable definitions and signal definitions. Variables are defined with the syntax

var = expr;

where expr is an arithmetic expression involving floating-point constants and previously defined variables. Currently only basic arithmetic (+, -, * and /) is supported. Signals are defined with the syntax

name events ;

where *name* is a name that must be quoted unless it's a valid symbol. *Events* is a list consisting of the following things:

• The current time can be set using an arithmetic expression, that may be followed by a symbol interpreted as a unit. For instance if you defined $\mu s = 1000$; then $1\mu s$ and $(x+2)*3\mu s$ are both valid time expressions. Note that $x+2\mu s$ is interpreted as $(x+2)\mu s$ which may or may not be intended behaviour.

A time expression can be preceded by + to mark it as relative to the previous time. The first time is zero.

A time expression can be followed by a symbol name in square brackets. The symbol is then defined with the time.

- An expression of the form :*name* creates an 'event' at the current time, changing the value of the signal to *name*. *name* can be a symbol (which is not evaluated), a numerical constant or a string in single quotes. The values 0, 1, x and z have special meaning, unless they are quoted.
- A pipe symbol | draws a vertical dashed line at the next event.
- An expression of the form *expr*{*events*} evaluates the expression, rounded to the nearest integer, and then repeats the events the specified number of times. It is illegal if the expression evaluates to a negative number. It is also illegal to use absolute times in the events list. It is however legal to nest this construct.

EXAMPLES

```
.TPS 6 0.4
c=5;
clk +5{:1 +.5c:0 +.5c};
data :x 2.3c:DQ 4c|:x;
valid :0 2.3c:1 4c:0;
ready :0 3.6c:1 4c:0;
.TPE
```

FILES

/sys/src/cmd/timepic.c

SEE ALSO

troff(1), *pic*(1)

BUGS

Yes.

timmy - physics sandbox

SYNOPSIS

games/timmy[-s steps-per-frame]

DESCRIPTION

Timmy is a simple 2D physics sandbox.

To pick up an object click on it with mouse button 1. New objects can be created by picking up their archetypes in the gray area on the bottom (the "tray"). To place an object in the working area click at the desired position with mouse button 1; *timmy* will refuse to place the object if it would collide with an existing one. To abort the process — deleting the carried object — click anywhere with mouse button 3. Picking up an object in the working area with mouse button 3 will duplicate the object.

The following operations can be performed with the keyboard.

w Rotate carried object by 15° to the left.

e Rotate carried object by 15° to the right.

space Start or stop the simulation.

del Exit timmy.

The small circles on some objects are "hinges". Two hinges can be connected by placing them on top of each other. Their relative position will not change during the simulation; objects are however free to rotate around them. To undo a hinge, pick up either of the objects.

The -s option adjusts the speed of the simulation; only integer values are permitted. It does not compromise accuracy.

SOURCE

/sys/src/games/timmy

BUGS

Timmy's physics may occasionally appear to originate from another universe.

-s is a hack.

HISTORY

Timmy first appeared in 9front (June, 2016).

tinyurl – shrink a URL

SYNOPSIS

tinyurl URL

DESCRIPTION

Exchanges a long URL for a shorter URL utilizing the API at tinyurl.com.

SOURCE

/rc/bin

BUGS

Redesigns of the source website can break this program.

torrent – bittorrent client

SYNOPSIS

```
ip/torrent[-d][-v][-p][-m mtpt][-t tracker-url][-w webseed-url][-s][-c][
-i peer-id][-A user-agent][file]
```

DESCRIPTION

BitTorrent is a protocol for efficient file distribution over the internet. Files are split into small pieces that are then downloaded by clients in random order. As soon as a client completes a piece, it makes the piece available for others to download.

To find other clients (peers), a tracker-server is contacted.

Before files can be transmitted, a torrent-file needs to be created describing the pieces of the files and other meta-data like network addresses of the trackers.

This is done with the -c option. If provided, *torrent* reads the file given at the final *file* argument (or standard-input when omitted) and writes a torrent file to standard-output and exits. A *tracker-url* should be given with the -t option in that case. A list of trackers can be obtained on the web, see the examples below.

If the files in the torrent are also available from a url, a *webseed-url* can be passed with the -w option. If *webseed-url* ends with a slash, the filename, from the torrent, concatenated with the url forms the target url.

Without the -c option, *torrent* downloads the files that are described in the torrent-file given by the *file* argument to the current working directory. If no *file* is given, the torrent is read from standard-input.

Normally, the program exits immediately after all pieces have been completed. The -s option causes it to keep running and serve the remaining clients (also known as seeding).

Trackers use a subset of the HTTP protocol, so an alternative webfs(4) mountpoint can be given with the -m option (defaults to /mnt/web).

The -v option causes *torrent* to list the files in the torrent-file before downloading.

The -d option produces verbose debug output to standard-error.

To monitor the download progress, the -p option can be given to cause the completed and total number of pieces written as a line of text to standard-output in one second intervals.

The -i option allows you to set the 20-byte *peer-id* that is sent to trackers and peers. If less than 20 bytes, the *peer-id* will be padded on the right with random ASCII numbers. The -A option allows setting the http *user-agent* string that is used to contact the tracker. These options are useful to fool trackers that filter clients based on the *peer-id* or *user-agent*

EXAMPLES

```
Create new torrent file
```

```
ip/torrent -t http://exodus.desync.com/announce \
    -c 9atom.iso >9atom.torrent
```

```
Download the latest iso file of the distribution
```

```
cd /tmp
```

```
hget http://r-36.net/9front/9front.iso.bz2.torrent | \
    ip/torrent -pv | \
    aux/statusbar 'download...'
```

Get list of public alive trackers to choose from hget https://newtrackon.com/api/live

SOURCE

```
/sys/src/cmd/ip/torrent.c
```

SEE ALSO

hget(1), webfs(4)

HISTORY

Torrent first appeared in 9front (October, 2011).

touch - set modification date of a file

SYNOPSIS

touch [-c] [-t *time*] *file* ...

DESCRIPTION

Touch attempts to set the modification time of the *files* to *time* (by default, the current time). If a *file* does not exist, it will be created unless option -c is present.

SOURCE

/sys/src/cmd/touch.c

SEE ALSO

ls(1), *stat*(2), *chmod*(1)

BUGS

Touch will not touch directories.

tput - measure read throughput

SYNOPSIS

tput [-b *buflen*] [-p]

DESCRIPTION

Tput continuously reads standard input writing throughput statistics to standard error. The throughput value is calculated and written once per second and automatically scaled to kilo-, mega- or gigabytes.

When the -p flag is specified, *tput* will write the data read to standard output (the default is to discard the data).

A read blocksize (default is 8192) in bytes can be given with the -b *buflen* option.

EXAMPLE

tput </dev/zero</pre>

SOURCE

/sys/src/cmd/tput.c

SEE ALSO

iostats(4)

DIAGNOSTICS

Tput sets error status on read error.

HISTORY

Tput first appeared in 9front (May, 2011).

tr – translate characters

SYNOPSIS

```
tr[-cds][string1[string2]]
```

DESCRIPTION

Tr copies the standard input to the standard output with substitution or deletion of selected characters (runes). Input characters found in *string1* are mapped into the corresponding characters of *string2*. When *string2* is short it is padded to the length of *string1* by duplicating its last character. Any combination of the options -cds may be used:

- -c Complement *string1*: replace it with a lexicographically ordered list of all other characters.
- -d Delete from input all characters in *string1*.
- -s Squeeze repeated output characters that occur in *string2* to single characters.

In either string a noninitial sequence -x, where x is any character (possibly quoted), stands for a range of characters: a possibly empty sequence of codes running from the successor of the previous code up through the code for x. The character \setminus followed by 1, 2 or 3 octal digits stands for the character whose 16-bit value is given by those digits. The character sequence $\setminus x$ followed by 1, 2, 3, or 4 hexadecimal digits stands for the character whose 16-bit value is given by those digits. A \setminus followed by any other character stands for that character.

EXAMPLES

Replace all upper-case ASCII letters by lower-case.

tr A-Z a-z <mixed >lower

Create a list of all the words in file1 one per line in file2, where a word is taken to be a maximal string of alphabetics. *String2* is given as a quoted newline.

```
tr -cs A-Za-z '
' <file1 >file2
```

SOURCE

/sys/src/cmd/tr.c

SEE ALSO

sed(1)

trace - show (real-time) process behavior

SYNOPSIS

trace [-d file] [-v] [-w] [pid ...]

DESCRIPTION

Trace displays the behavior of processes running on the machine. In its window it shows a time line for each traced process. Running processes appear as colored blocks, with arrows marking important events in real-time processes (see *proc*(3)). Black up arrows mark process releases, black down arrows mark process deadlines, green down arrows mark times when a process yielded the processor before its deadline, red down arrows mark times when the process overran its allotted time.

Trace reads /proc/trace to retrieve trace events from the kernel scheduler. Trace events are binary data structures generated by the kernel scheduler. It is assumed that the reader of /proc/trace and the kernel providing it have the same byte order.

The options are:

- -d specify an alternate trace event file
- -v print events as they are read from the trace event file
- -w run in a new window rather than using the current one

Trace recognizes these keystroke commands while it is running:

- + zoom in by a factor of two
- zoom out by a factor of two
- p pause or resume
 - quit

SEE ALSO

proc(3)

q

FILES

```
/proc/trace trace event file
/sys/include/trace.h trace event data structures
```

SOURCE

/sys/src/cmd/trace.c

troff, nroff, dpost - text formatting and typesetting

SYNOPSIS

troff [option ...] [file ...]

dpost [-f] [*file* ...]

nroff[option ...][file ...]

DESCRIPTION

Troff formats text in the named *files* for printing on a typesetter, emitting a textual intermediate format called 'typesetter-independent *troff* output', understood by programs such as *proof*(1) and lp(1), but also by a *troff* post-processor named *dpost*, which emits corresponding Postscript. Under -f, *dpost* also emits Postscript font definitions as needed. Nroff does the same as *troff*, but produces output suitable for typewriter-like devices, usually without further post-processing, but see *col*(1).

If no *file* argument is present, the standard input is read. An argument consisting of a single minus (-) is taken to be a file name corresponding to the standard input. The options are:

- -olist Print pages in the comma-separated list of numbers and ranges. A range N-M means N through M; initial -M means up to M; final N- means from N to the end.
- -n*N* Number first generated page *N*.

-mname Process the macro file /sys/lib/tmac/tmac. name before the input files.

- -raN Set register *a* (one character name) to *N*.
- -i Read standard input after the input files are exhausted.
- -q Invoke the simultaneous input-output mode of the rd request.
- -N Produce output suitable for typewriter-like devices.

Typesetter devices (not -N) only

-a Send a printable textual approximation of the results to the standard output.

- -T*dest* Prepare output for typesetter *dest*:
 - -Tutf (The default.) PostScript printers with preprocessing to handle Unicode characters encoded in UTF
 - -Tpost Regular PostScript printers
 - -T202 Mergenthaler Linotron 202
- -F *dir* Take font information from directory *dir*.

Typewriter (-N) output only

- -sN Halt prior to every N pages (default N=1) to allow paper loading or changing.
- -Tname Prepare output for specified terminal. Known names include utf for the normal Plan 9 UTF encoding of the Unicode Standard character set (default), 37 for the Teletype model 37, 1p ('line-printer') for any terminal without half-line capability, 450 for the DASI-450 (Diablo Hyterm), and think (HP ThinkJet).
- -e Produce equally-spaced words in adjusted lines, using full terminal resolution.
- -h Use output tabs during horizontal spacing to speed output and reduce output character count. Tab settings are assumed to be every 8 nominal character widths.

FILES

/tmp/trtmp* temporary file /sys/lib/tmac/tmac.* standard macro files /sys/lib/troff/term/* terminal driving tables for nroff /sys/lib/troff/font/* font width tables for troff SOURCE

/sys/src/cmd/troff
/rc/bin/dpost

SEE ALSO

lp(1), *proof*(1), *page*(1), *eqn*(1), *tbl*(1), *pic*(1), *grap*(1), *doctype*(1), *ms*(6), *image*(6), *deroff*(1), *col*(1)

J. F. Ossanna and B. W. Kernighan, "Troff User's Manual"

B. W. Kernighan, "A Typesetter-Independent TROFF", CSTR #97
B. W. Kernighan, "A TROFF Tutorial", Unix Research System Programmer's Manual, Tenth Edition, Volume 2.

troff2html – convert troff output into HTML

SYNOPSIS

troff2html[-t title][file ...]

DESCRIPTION

Troff2html reads the *troff*(1) output in the named *files*, default standard input, and converts them into HTML.

Troff2html does a tolerable job with straight troff output, but it is helped by annotations, described below. Its main use is for man2html (see *httpd*(8)), which converts *man*(1) pages into HTML and depends on a specially annotated set of *man*(6) macros, invoked by troff -manhtml.

Troff output lines beginning

x X html ...

which are introduced by placing X'html ...' in the *input*, cause the rest of the line to be interpolated into the HTML produced. Several such lines are recognized specially by *troff2html*. The most important are the pair

x X html manref start cp 1 x X html manref end cp 1

which are used to create HTML hyperlinks around text of the form cp(1) pointing to /magic/man2html/1/cp.

Troff2html is new and experimental; in time, it may improve and subsume *ms2html*(1). On the one hand, because it uses the input, ms2html can handle *pic*(1), *eqn*(1), etc., which *troff2html* does not handle at all; on the other hand, ms2html understands only *ms*(6) documents and is easily confused by complex troff constructions. *Troff2html* has the reverse properties: it does not handle the preprocessors but its output is reliable and (modulo helper annotations) is independent of macro package.

SOURCE

/sys/src/cmd/troff2html

SEE ALSO

troff(1), ms2html(1), man2html in httpd(8).

BUGS

Troff and HTML have different models, and they don't mesh well in all cases. Troff's indented paragraphs are not well served in HTML, and the output of *troff2html* shows this.

troff2png, troff2gif - miscellaneous text processing tools

SYNOPSIS

troff2png[troffargs][file]
troff2gif[troffargs][file]

DESCRIPTION

Troff2png uses *troff*(1) to compile a document using the *ms*(6) macro library to a PNG image on standard output.

Troff2gif is similar but outputs GIF data.

SOURCE

/bin/troff2png /bin/troff2gif

SEE ALSO

ms(6) troff(1)

tweak - edit image files, subfont files, face files, etc.

SYNOPSIS

tweak [*file ...*]

DESCRIPTION

Tweak edits existing files holding various forms of images. To create original images, start from an existing image, subfont, etc.

Tweak reads its argument files and displays the resulting images in a vertical column. If the image is too wide to fit across the display, it is folded much like a long line of text in an *rio* window. Under each image is displayed one or two lines of text presenting its parameters. The first line shows the image's depth, the number of bits per pixel; r, the rectangle covered by the image; and the name of the file from which it was read. If the file is a subfont, a second line presents a hexadecimal 16-bit offset to be applied to character values from the subfont (typically as stored in a font file; see font(6)); and the subfont's n, height, and ascent as defined in *cachechars*(2).

By means described below, magnified views of portions of the images may be displayed. The text associated with such a view includes mag, the magnification. If the view is of a single character from a subfont, the second line of text shows the character's value (including the subfont's offset) in hexadecimal and as a character in *tweak's* default font; the character's x, top, bottom, left, and width as defined in *cachechars*(2); and iwidth, the physical width of the image in the subfont's image.

There are two methods to obtain a magnified view of a character from a subfont. The first is to click mouse button 1 over the image of the character in the subfont. The second is to select the char entry on the button 3 menu, point the resulting gunsight cursor at the desired subfont and click button 3, and then type at the text prompt at the bottom of the screen the character value, either as a multi-digit hexadecimal number or as a single rune representing the character.

To magnify a portion of other types of image files, click button 1 over the unmagnified file. The cursor will switch to a cross. Still with button 1, sweep a rectangle, as in rio, that encloses the portion of the image to be magnified. (If the file is 16×16 or smaller, *tweak* will just magnify the entire file; no sweeping is necessary.)

Pressing buttons 1 and 2 within magnified images changes pixel values. By default, button 1 sets the pixel to all zeros and button 2 sets the pixel to all ones.

Across the top of the screen is a textual display of global parameters. These values, as well as many of the textual values associated with the images, may be edited by clicking button 1 on the displayed value and typing a new value. The values along the top of the screen are:

mag Default magnification.

val(hex)

The value used to modify pixels within magnified images. The value must be in hexadecimal, optionally preceded by a tilde for bitwise negation.

but1

but 2 The pixel value written when the corresponding button is pressed over a pixel.

invert-on-copy

Whether the pixel values are inverted when a copy operation is performed.

Under button 3 is a menu holding a variety of functions. Many of these functions prompt for the image upon which to act by switching to a gunsight cursor; click button 3 over the selection, or click a different button to cancel the action.

open Read and display a file. The name of the file is typed to the prompt on the bottom line.

read Reread a file.

write

Write a file.

- copy Use the copy function, default S, to transfer a rectangle of pixels from one image to another. The program prompts with a cross cursor; sweep out a rectangle in one image or just click button 3 to select the whole image. The program will leave that rectangle in place and attach another one to the cursor. Move that rectangle to the desired place in any image and click button 3, or another button to cancel the action.
- char As described above, open a magnified view of a character image in a subfont.

pixels

Report the coordinate and value of individual pixels indicated by pressing button 3. This is a mode of operation canceled by pressing button 1 or 2.

close

Close the specified image. If the image is the unmagnified file, also close any magnified views of that file.

exit Quit tweak. The program will complain once about modified but unwritten files.

Tweak listens to the *plumber* channel imageedit for filenames as well as image data. Plumbed image data is stored as files in /tmp and is automatically cleaned when exiting *tweak*.

SOURCE

/sys/src/cmd/tweak.c

SEE ALSO

cachechars(2), image(6), font(6)

BUGS

For a program written to adjust width tables in fonts, *tweak* has been pushed unreasonably far.

uhtml - convert foreign character set HTML file to unicode

SYNOPSIS

uhtml [-p] [-c *charset*] [*file*]

DESCRIPTION

HTML comes in various character set encodings and has special forms to encode characters. To make it easier to process html, uhtml is used to normalize it to a unicode only form.

Uhtml detects the character set of the html input *file* and calls tcs(1) to convert it to utf replacing html-entity forms by ther unicode character representations except for lt gt amp quot and apos . The converted html is written to standard output. If no *file* was given, it is read from standard input. If the -p option is given, the detected character set is printed and the program exits without conversion. In case character set detection fails, the default (utf) is assumed. This default can be changed with the -c option.

SOURCE

/sys/src/cmd/uhtml.c

SEE ALSO

tcs(1)

uniq - report repeated lines in a file

SYNOPSIS

uniq[-udcs[+-*num*]][*file*]

DESCRIPTION

Uniq copies the input *file*, or the standard input, to the standard output, comparing adjacent lines. In the normal case, the second and succeeding copies of repeated lines are removed. Repeated lines must be adjacent in order to be found.

- -u Print unique lines.
- -d Print (one copy of) duplicated lines.
- -c Prefix a repetition count and a tab to each output line. Implies -u and -d.
- -s Count as a duplicate if the prefix matches the previous unique line.
- -*num* The first *num* fields together with any blanks before each are ignored. A field is defined as a string of non-space, non-tab characters separated by tabs and spaces from its neighbors.
- +num The first num characters are ignored. Fields are skipped before characters.

SOURCE

/sys/src/cmd/uniq.c

SEE ALSO

sort(1)

BUGS

Field selection and comparison should be compatible with *sort*(1).

units - conversion program

SYNOPSIS

units [-v] [file]

DESCRIPTION

Units converts quantities expressed in various standard scales to their equivalents in other scales. It works interactively in this fashion:

A quantity is specified as a multiplicative combination of units and floating point numbers. Operators have the following precedence:

add and subtract
multiply and divide
multiply
exponentiation
divide
grouping

Most familiar units, abbreviations, and metric prefixes are recognized, together with a generous leavening of exotica and a few constants of nature including:

pi,π	ratio of circumference to diameter
С	speed of light
e	charge on an electron
g	acceleration of gravity
force	same as g
mole	Avogadro's number
water	pressure head per unit height of water
au	astronomical unit

The pound is a unit of mass. Compound names are run together, e.g. lightyear. British units that differ from their US counterparts are prefixed thus: brgallon. Currency is denoted belgiumfranc, britainpound, etc.

The complete list of units can be found in /lib/units. A *file* argument to *units* specifies a file to be used instead of /lib/units. The -v flag causes *units* to print its entire database.

EXAMPLE

you have: 15 pounds force/in²
you want: atm
 * 1.02069
 / .97973

FILES

```
/lib/units
```

SOURCE

/sys/src/cmd/units.y

BUGS

Since *units* does only multiplicative scale changes, it can convert Kelvin to Rankine but not Centigrade to Fahrenheit.

Currency conversions are only as accurate as the last time someone updated the database.

uptime - show how long the system has been running

SYNOPSIS

uptime

DESCRIPTION

Uptime shows how long the system has been running. It uses the following format:

sysname up 33 days, 17:56:42

The time given accounts for the timezone.

SOURCE

/rc/bin/uptime

SEE ALSO

date(1)

vac, unvac - create, extract a vac archive on Venti

SYNOPSIS

vac [-mqsv] [-a vacfile] [-b blocksize] [-d oldvacfile] [-e exclude] [-f vacfile] [-i
name] [-h host] [-x excludefile] file ...

unvac [-Tcdtv] [-h host] vacfile [file ...]

DESCRIPTION

Vac creates an archival copy of Plan 9 file trees on Venti. It can be used to build a simple backup system. One of the unusual properties of Venti is that duplicate blocks are detected and coalesced. When *vac* is used on a file tree that shares data with an existing archive, the consumption of storage will be approximately equal to an incremental backup. This reduction in storage consumption occurs transparently to the user.

As an optimization, the -d and -q options, described below, can be used to explicitly create an archive relative to an existing archive. These options do not change the resulting archive generated by *vac*, but simply reduce the number of write operations to Venti.

The output of *vac* is the hexadecimal representation of the SHA1 fingerprint of the root of the archive, in this format:

vac:64daefaecc4df4b5cb48a368b361ef56012a4f46

The options to *vac* are:

- -a *vacfile* Specifies that vac should create or update a backup archive, inserting the files under an extra two levels of directory hierarchy named *yyyy/mmdd* (year, month, day) in the style of the dump file system (see Plan 9's *fs*(4)). If *vacfile* already exists, an additional backup day is added to the existing hierarchy, behaving as though the -d flag was specified giving the most recent backup tree in the archive. Typically, this option is used as part of a nightly backup script. This option cannot be used with -d or -f.
- -b *blocksize* Specifies the block size that data will be broken into. The units for the size can be specified by appending k to indicate kilobytes. The default is 8k. The size must be in the range of 512 bytes to 52k.
- -d *oldvacfile* Reduce the number of blocks written to Venti by comparing the files to be stored with the contents of an existing *vac* file tree whose score is stored in *oldvacfile*.
- -e exclude Do not include the file or directory specified by exclude. This option may be repeated multiple times. Exclude can be a shell pattern as accepted by rc(1), with one extension: . . . matches any sequence of characters including slashes.
- -f *vacfile* The results of *vac* are placed in *vacfile*, or the standard output if no file is given.
- -i name Include standard input as one of the input files, storing it in the archive with the specified name.
- -h host The network address of the Venti server. The default is taken from the environment variable venti. If this variable does not exist, then the default is the metaname \$venti, which can be configured via ndb(6).
- -m Expand and merge any vac archives that are found while reading the input files. This option is useful for building an archive from a collection of existing archives. Each archive is inserted into the new archive as if it had been unpacked in the directory in which it was found. Multiple archives can be unpacked in a single directory and the contents will be merged. To be detected, the archives must end in .vac. Note, an archive is inserted by simply copying the root fingerprint and does not require the archive to be unpacked.
- -q Increase the performance of the -d option by detecting unchanged files based on a match of the files name and other meta data, rather than examining the contents of the files.

- -s Print out various statistics on standard error.
- -v Produce more verbose output on standard error, including the name of the files added to the archive and the vac archives that are expanded and merged.
- -x excfile Read exclude patterns from the file excfile. Blank lines and lines beginning with # are ignored. All other lines should be of the form include pattern or exclude pattern. When considering whether to include a directory or file in the vac archive, the earliest matching pattern in the file applies. The patterns are the same syntax accepted by the -e option. This option may be repeated multiple times.

Unvac lists or extracts files stored in the vac archive *vacfile*, which can be either a vac archive string in the format given above or the name of a file containing one. If *file* arguments are given, only those files or directories will be extracted. The options are:

- -T Set the modification time on extracted files to the time listed in the archive.
- -c Write extracted files to standard output instead of creating a file.
- -d Reduce the number of blocks read from Venti by comparing the files to be stored with their counterparts in the file system. This option cannot be used with -c.
- -t Print a list of the files to standard output rather than extracting them.
- -v If extracting files, print the name of each file and directory to standard error. If listing files, print metadata in addition to the names.
- -h as per *vac*.

SOURCE

/sys/src/cmd/vac

SEE ALSO

vacfs(4), venti(8)

read, write, copy - simple Venti clients

SYNOPSIS

```
venti/read[-h host][-t type] score
venti/write[-z][-h host][-t type]
venti/copy[-fir][-t type] srchost dsthost score[type]
```

DESCRIPTION

Venti is a SHA1-addressed block storage server. See venti(6) for a full introduction.

Read reads a block with the given *score* and numeric *type* from the server *host* and prints the block to standard output. If the -h option is omitted, *read* consults the environment variable \$venti for the name of the Venti server. If the -t option is omitted, *read* will try each type, one at a time, until it finds one that works. It prints the corresponding read -t command to standard error to indicate the type of the block.

Write writes at most 56 kilobytes of data from standard input to the server host and prints the resulting score to standard output. If the -t option is omitted, write uses type 0, denoting a data block. If the -z option is given, write zero truncates the block before writing it to the server.

Copy expects *score* to be the score of a VtRoot block. It copies the entire tree of blocks reachable from the root block from the server *srchost* to the server *dsthost*.

The -f option causes *copy* to run in 'fast' mode, assuming that if a block already exists on the destination Venti server, all its children also exist and need not be checked.

The -i and -r options control *copy*'s reaction to errors reading from *srchost*. *Copy* always prints information to standard error about each read error. By default, *copy* exits after printing the first error. If the -i option is given, read errors are ignored. This is dangerous behavior because it breaks the assumption made by 'fast' mode. If the -r option is given, *copy* replaces pointers to unreadable blocks with pointers to the zero block. It writes the new root score to standard output.

SOURCE

/sys/src/cmd/venti

SEE ALSO

vac(1), venti(2), vacfs(4), venti(6), venti(8), venti-backup(8), venti-fmt(8)

BUGS

There should be programs to read and write venti files and directories.

5i, ki, vi, qi - instruction simulators

SYNOPSIS

- vi [textfile] vi pid 5i [textfile] 5i pid ki [textfile] ki pid ci [toxtfile]
- qi[textfile]
- qi pid

DESCRIPTION

Vi simulates the execution of a MIPS binary in a Plan 9 environment. It has two main uses: as a debugger and as a statistics gatherer. Programs running under *vi* execute about two hundred times slower than normal—but faster than single stepping under *db*. *5i*, *ki*, and *qi* are similar to *vi* but interpret ARM, SPARC, and PowerPC binaries. The following discussion refers to *vi* but applies to the others as well.

Vi will simulate the execution of a named *textfile*. It will also make a copy of an existing process with process id *pid* and simulate its continuation.

As a debugger vi offers more complete information than db(1). Tracing can be performed at the level of instructions, system calls, or function calls. *Vi* allows breakpoints to be triggered when specified addresses in memory are accessed. A report of instruction counts, load delay fills and distribution is produced for each run. *Vi* simulates the CPU's caches and MMU to assist the optimization of compilers and programs.

The command interface mirrors the interface to db; see db(1) for a detailed description. Data formats and addressing are compatible with db except for disassembly: vi offers only MIPS (db -mmipsco) mnemonics for machine instructions. *Ki* offers both Plan 9 and Sun SPARC formats.

Several extra commands allow extended tracing and printing of statistics:

\$t[0ics]

The *t* command controls tracing. Zero cancels all tracing options.

- i Enable instruction tracing
- c Enable call tracing
- s Enable system call tracing

\$i[itsp]

The i command prints statistics accumulated by all code run in this session.

- i Print instruction counts and frequency.
- p Print cycle profile.
- t (*Vi* only) Print TLB and cache statistics.
- s Print memory reference, working set and size statistics.

:b[arwe]

Vi allows breakpoints to be set on any memory location. These breakpoints monitor when a location is accessed, read, written, or equals a certain value. For equality the compared value is the *count* (see db(1)) supplied to the command.

SOURCE

/sys/src/cmd/vi etc.

SEE ALSO

nm(1), db(1)

BUGS

The code generated by the compilers is well supported, but some unusual instructions are unimplemented. Some Plan 9 system calls such as *rfork* cause simulated traps. The floating point simulation makes assumptions about the interpreting machine's floating point support. The floating point conversions performed by vi may cause a loss of precision.

vmx – virtual PC

SYNOPSIS

vmx [-D] [-M mem] [-c com1] [-C com2] [-n nic] [-d blockfile] [-v|-w vga] [-m bootmod] kernel [args ...]

DESCRIPTION

Vmx uses Intel VT-x through vmx(3) to simulate a virtual PC, running the specified kernel (see below for supported formats).

By default the virtual PC has 64 MB of memory. The amount of memory can be changed with the -M option, the argument of which is interpreted in bytes unless suffixed by K, M, or G to change the unit to kilobytes, megabytes or gigabytes, respectively.

Args is passed to the kernel as its command line. Boot modules can be specified with the -m argument.

-D enables debug messages.

If -v is specified, a graphics device, PS/2 keyboard and mouse are simulated. The -w flag behaves the same as -v but also creates a new window for the screen. Clicking on the screen "grabs" the mouse; pressing Ctrl and Alt simultaneously releases the grab. Valid values for the argument are

text Simulate a VGA text-mode console.

widthxheight [xchan] [@addr]

Simulate a framebuffer at address *addr* of the specified size and channel format *chan* (see *image*(6)). x*chan* and @*addr* are optional, in which case they default to x8r8g8b8 and 0xf0000000, respectively (in this mode there is no way to change the resolution and accesses to VGA registers have no effect).

vesa: modes [@addr]

(*modes* is a comma separated list of modes of the format *widthxheightxchan* with the chan optional as before.) Simulate a VESA-compatible PCI graphics adapter, initially in text mode. The guest can use VESA functions to switch the mode to one of those listed, which are assigned consecutive mode numbers starting with 0x120. The first mode is indicated as the preferred mode of the monitor.

The -c and -C options specify the targets for the COM1 and COM2 devices. The argument consists of two fields separated by a comma, which specify the file to be used for input and output, respectively. Either field can be left empty. If there is no comma in the argument, the same value is used for both fields.

A -n option adds a network card. The argument to -n specifies a physical network device (such as ether0) to use. Alternatively, a dial string such as udp!*host*!*port* can be used. It can also be prefixed by file! to interpret the argument as a file instead and it can be prefixed by hdr! to enable headers matching the binary *snoopy*(8) format. The MAC address can be specified with the ea:*nnnnnnnnn*! prefix, otherwise a random address is used.

A -d option adds a *virtio* block device (a hard disk) with the argument as a disk image.

Multiboot kernels

If the specified kernel complies with the Multiboot specification, then *args* is concatenated with spaces and passed as the *cmdline*; the *-*m modules are passed as boot modules.

Note that 9front is Multiboot compliant and interprets the first boot module as *plan9.ini*(8).

OpenBSD kernels

If the specified kernel is an OpenBSD kernel, the boot modules are ignored and the *cmdline* is interpreted as

[-asdc] [*var=value* ...]

where the options correspond to the boot options and the assignments to the boot variables, which are defined in the OpenBSD manpage *boot*(8).

Linux kernels

If the specified kernel is a Linux kernel (which must be 2.6.22 or newer and in bzImage format), *args* are concatenated with spaces and passed as the *cmdline* (see Documentation/admin-guide/kernel-parameters.txt). The first boot module is passed as the *initrd*; any further boot modules are ignored.

SOURCE

/sys/src/cmd/vmx

SEE ALSO

vmx(3), cpuid(8)

BUGS

Vmx can and will crash your kernel.

Currently only one core is supported.

The Linux vga = option is not supported, as well as many of the OpenBSD boot variables.

HISTORY

Vmx first appeared in 9front (June, 2017).

vncs, vncv - remote frame buffer server and viewer for Virtual Network Computing (VNC)

SYNOPSIS

vncs [-v][-c cert][-d : display][-g widthx height][-p pixfmt][-x net][cmd[args]]

vncs –k : *display* [–x *net*]

vncv[-cstv][-e encodings][-l charset][-k keypattern]host[:n]

DESCRIPTION

VNC is a lightweight protocol for accessing graphical applications remotely. The protocol allows one or more clients to connect to a server. While connected, clients display the frame buffer presented by the server and can send mouse events, keyboard events, and exchange snarf buffers. The server persists across viewer sessions, so that the virtual application can be accessed from various locations as its owner moves around.

VNC displays have names of the form *host*: n, where *host* is the machine's network name and n is a small integer identifier; display n is served on TCP port 5900+n.

Vncs starts a new virtual frame buffer in memory, simulating a Plan 9 terminal running *cmd args*, by default an interactive shell. As viewers connect, each is authenticated using a (rather breakable) challenge-response protocol using the user's Inferno/POP password.

The options are:

- -c *cert* start TLS on each viewer connection using the certificate in the file *cert*. The corresponding private key must be loaded into the server's *factotum*(4). When serving TLS connections, the base port is 35729 rather than 5900.
- -d : *n* run on display *n*; without this option, the server searches for an unused display.
- –g width**x**height

set the virtual frame buffer to be *widthxheight* (default 1024x768) pixels.

- -p *pixfmt* set the virtual frame buffer's internal pixel format to *pixfmt* (default r5g6b5).
- -v print verbose output to standard error.
- -x *net* announce on an alternate network interface.
- -A turn off authentication.

The command vncs -k : *n* kills the VNC server running on display *n*.

Vncv provides access to remote display *host*: *n*. It resizes its window to be the smaller of the remote frame buffer size and the local screen.

The options are:

- -c when connecting to 8-bit displays, request r4g4b4 pixels rather than r3g3b2 pixels. This takes up more bandwidth but usually gives significantly better matching to the Plan 9 color map.
- -e encodings

set the ordered list of allowed frame buffer update encodings. The default (and full) set is copyrect corre hextile rre raw. The encodings should be given as a single space-separated argument (quoted when using the shell).

−1 charset

sets the character set (see tcs(1)) used by the server to encode clipboard text. The default is utf-8.

–k keypattern

add keypattern to the pattern used to select a key from factotum(4).

- -s share the display with extant viewers; by default extant viewers are closed when a new viewer connects.
- -t start TLS on the connection.

-v print verbose output to standard error.

SOURCE

/sys/src/cmd/vnc

SEE ALSO

http://www.uk.research.att.com/vnc

BUGS

If the remote frame buffer is larger than the local screen, only the upper left corner can be accessed.

Vncv does no verification of the TLS certificate presented by the server.

Vncv supports only version 3.3 of the RFB protocol.

vt - emulate a VT-100 or VT-220 terminal

SYNOPSIS

vt[-2abcrx][-f font][-l log][cmd...]

DESCRIPTION

Vt replaces a *rio* window with a fresh instance of the program cmd (or the rc(1) shell when omited) running within an emulation of a DEC VT-100 terminal.

Options

2

а

- x change *vt* to emulate a VT-220, ANSI, or XTerm terminal respectively.
- b changes the color scheme to white text on a black background, but potentially with colors from escape sequences.
- c changes the color scheme to monochrome (no colors).
- f sets the font.
- 1 names a *log* file for the session.
- r start in raw mode.

Menus

The right button has a menu with the following entries to provide the sort of character processing expected by non-Plan 9 systems:

- 24x80 Resize the *vt* window to hold 24 rows of 80 columns.
- crnl Print a newline (linefeed) character after receiving a carriage return from the host.
- cr Do not print a newline after carriage return.
- nlcr Print a carriage return after receiving a newline from the host.
- nl Do not print a carriage return after newline.
- raw Enter raw (no echo, no interpretation) character mode for input.
- cooked Leave raw mode.

blocksel

Toggle block selection for mode for rio snarf buffer.

exit Exit vt.

The middle button has a menu with the following entries:

backup	Move the display back one screenful.
forward	Move the display forward one screenful. (These are a poor substitute for a scroll
	bar.)
reset	Display the last screenful; the same as going forward to the end.
paste	Pastes the contents of the rio snarf buffer, just as paste in the rio menu.
snarf	Copy selection to the rio snarf buffer.
plumb	Send selection to the plumber.
scroll	Make new lines visible as they appear at the bottom.
page	When the page fills, pause and wait for a character to be typed before proceeding.
	The down arrow key advances a page without sending the character to the host.

SOURCE

/sys/src/cmd/vt

BUGS

This program is used only for communicating with foreign systems, so it is not as rich an emulation as its equivalent in other environments.

Use care in setting raw and newline modes when connecting to Unix systems via *con*(1). It may also be necessary to set the emulator into raw mode.

walk - walk a path

SYNOPSIS

walk [-dftxu][-n mind, maxd][-e statfmt][name ...]

DESCRIPTION

Walk recursively descends any directory arguments, printing the name of each file on a separate line. When no arguments are given, the working directory is assumed. Non-directory arguments are checked for existence, then printed, if so.

Options are:

- -d Print only directories.
- -f Print only non-directories.
- -t Print a file only if it has the temporary flag set.
- -x Print a file only if it has any executable bits set.
- -u Unbuffered output.
- -n min,max

Set the inclusive range of depths for filtering in results. Both min and max are optional. An argument of n with no comma is equivalent to 0,n.

-e statfmt

Specify the output format. Each character in *statfmt* specifies a file attribute to display. The printed attributes are separated by spaces.

The statfmt characters are as follows:

- U owner name (uid)
- G group name (gid)
- M name of last user to modify (muid)
- a last access time (atime)
- m last modification time (mtime)
- n final path element (name)
- p path
- q qid path.version.type (see *stat*(2))
- s size in bytes
- x permissions
- D server device
- T server type (kernel device rune)

The default statfmt is simply, p.

EXAMPLES

List files in a directory, sorted by modification time.

walk -femp catpics | sort -n | sed 's/ $[\land]+ //'$

Print the size and path of files (excluding dirs) in the working directory.

```
walk -fn1 -esp
```

SOURCE

/sys/src/cmd/walk.c

SEE ALSO

ls(1), du(1)

BUGS

Statfmt character 'x' displays permissions as an integer.

Manipulating ifs is a nuisance.

File names are assumed to not contain newlines.

Correct invocation requires too much thought.

Walk first appeared in 9front (March, 2019).

wc – word count

SYNOPSIS

wc[-lwrbc][*file*...]

DESCRIPTION

Wc counts lines, words, runes, syntactically-invalid UTF codes and bytes in the named *files*, or in the standard input if no file is named. A word is a maximal string of characters delimited by spaces, tabs or newlines. The count of runes includes invalid codes.

If the optional argument is present, just the specified counts (lines, words, runes, broken UTF codes or bytes) are selected by the letters 1, w, r, b, or c. Otherwise, lines, words and bytes (-lwc) are reported.

SOURCE

/sys/src/cmd/wc.c

BUGS

The Unicode Standard has many blank characters scattered through it, but *wc* looks for only ASCII space, tab and newline.

Wc should have options to count suboptimal UTF codes and bytes that cannot occur in any UTF code.

weather - print weather report

SYNOPSIS

weather[*air*][*st*]

DESCRIPTION

Weather prints the local conditions and seven-day forecast most recently reported at the US airport with the three-letter location identifier *air*. Given a two-letter US state abbreviation *st* instead, *weather* prints a table of *air* location identifiers known for *st*.

The arguments are mutually exclusive and case-insensitive. If neither is given, *air* defaults to the value of the environment variable \$weather, or if it is unset, to the location identifier ewr, designating the Newark, NJ, airport near Bell Labs, Murray Hill.

SOURCE

/rc/bin/weather

BUGS

Weather is hopelessly provincial.

who, whois - who is using the machine

SYNOPSIS

who

whois person

DESCRIPTION

Who prints the name of everyone with a non-Exiting process on the current machine.

Whois looks in /adm/whois and /adm/users to find out more information about person.

SOURCE

/rc/bin/who /rc/bin/whois

winwatch - monitor rio windows

SYNOPSIS

winwatch[-e exclude][-f font]

DESCRIPTION

Winwatch displays the labels of all current *rio*(4) windows, refreshing the display every five seconds. Right clicking a window's label unhides, raises and gives focus to that window. Right clicking a window again hides the window. Middle clicking a window's label prompts for a new label. Typing q or DEL quits *winwatch*.

If the -e flag is given, windows matching the regular expression *exclude* are not shown.

EXAMPLE

Excluding winwatch, stats and faces from being showed.

% winwatch -e '^(winwatch|stats|faces)'

FILES

/dev/wsys/*/label

SOURCE

/sys/src/cmd/winwatch.c

SEE ALSO

rio(1), *rio*(4), *regexp*(6).

xargs - construct argument list and execute

SYNOPSIS

```
xargs [ -n number ] [ -p maxprocs ] cmd [ arg ... ]
```

DESCRIPTION

Xargs reads number (default 10) lines from standard input and runs the given cmd with those lines as arguments. This is repeated until standard input is exhausted.

Options are as follows:

- -n Set *number* as the maximum number of lines taken from standard input for each invocation.
- -p Parallel mode: run *maxprocs* invocations at once.

EXAMPLE

seq 1 9 | xargs -n 3 echo

SOURCE

/sys/src/cmd/xargs.c

HISTORY

Xargs was implemented from scratch for 9front (August, 2011).

xd - hex, octal, decimal, or ASCII dump

SYNOPSIS

xd [option ...] [– format ...] [file ...]

DESCRIPTION

Xd concatenates and dumps the *files* (standard input by default) in one or more formats. Groups of 16 bytes are printed in each of the named formats, one format per line. Each line of output is prefixed by its address (byte offset) in the input file. The first line of output for each group is zero-padded; subsequent are blank-padded.

Formats other than -c are specified by pairs of characters telling size and style, 4x by default. The sizes are

1 or b 1-byte units.

2 or w 2-byte big-endian units.

4 or 1 4-byte big-endian units.

8 or v $\,$ 8-byte big-endian units.

The styles are

- o Octal.
- x Hexadecimal.
- d Decimal.

Other options are

- -c Format as 1x but print ASCII representations or C escape sequences where possible.
- -astyle Print file addresses in the given style (and size 4).
- -u (Unbuffered) Flush the output buffer after each 16-byte sequence.
- -s Switch to little-endian units.
- -r Print repeating groups of identical 16-byte sequences as the first group followed by an asterisk.

SOURCE

/sys/src/cmd/xd.c

SEE ALSO

db(1)

BUGS

The various output formats don't line up properly in the output of *xd*.

yacc - yet another compiler-compiler

SYNOPSIS

yacc [option ...] grammar

DESCRIPTION

Yacc converts a context-free grammar and translation code into a set of tables for an LR(1) parser and translator. The grammar may be ambiguous; specified precedence rules are used to break ambiguities.

The output file, y.tab.c, must be compiled by the C compiler to produce a program yyparse. This program must be loaded with a lexical analyzer function, yylex(void) (often generated by *lex*(1)), with a main(int argc, char *argv[]) program, and with an error handling routine, yyerror(char*).

The options are

- -o *output* Direct output to the specified file instead of y.tab.c.
- -Dn
 Create file y.debug, containing diagnostic messages. To incorporate them in the parser, compile it with preprocessor symbol yydebug defined. The amount of diagnostic output from the parser is regulated by value *n*. The value 0 reports errors; 1 reports reductions; higher values (up to 4) include more information about state transitions.
- -v Create file y.output, containing a description of the parsing tables and of conflicts arising from ambiguities in the grammar.
- -d Create file y.tab.h, containing #define statements that associate yacc-assigned 'token codes' with user-declared 'token names'. Include it in source files other than y.tab.c to give access to the token codes.
- -s stem Change the prefix y of the file names y.tab.c, y.tab.h, y.debug, and y.output to stem.
- -S Write a parser that uses Stdio instead of the print routines in libc.

The specification of *yacc* itself is essentially the same as the UNIX version described in the references mentioned below. Besides the -D option, the main relevant differences are:

The interface to the C environment is by default through <libc.h> rather than <stdio.h>; the -S option reverses this.

The parser accepts UTF input text (see utf(6)), which has a couple of effects. First, the return value of yylex() no longer fits in a short; second, the starting value for non-terminals is now 0xE000 rather than 257.

The generated parser can be recursive: actions can call *yyparse*, for example to implement a sort of *#include* statement in an interpreter.

Finally, some undocumented inner workings of the parser have been changed, which may affect programs that know too much about its structure.

FILES

y.output y.tab.c y.tab.h y.debug	
y.tmp.*	temporary file
y.acts.*	temporary file
/sys/lib/yaccpar	parser prototype
/sys/lib/yaccpars	parser prototype using stdio

SOURCE

/sys/src/cmd/yacc.c

```
SEE ALSO
```

```
lex(1)
```

S. C. Johnson and R. Sethi, "Yacc: A parser generator", Unix Research System Programmer's Manual, Tenth Edition, Volume 2

B. W. Kernighan and Rob Pike, The UNIX Programming Environment, Prentice Hall, 1984

BUGS

The parser may not have full information when it writes to y.debug so that the names of the tokens returned by yylex may be missing.

yesterday, diffy - print file names from the dump

SYNOPSIS

yesterday [-abcCdDs] [-n daysago] [-date] files ...

diffy [-abcefmnrw] files ...

DESCRIPTION

Yesterday prints the names of the *files* from the most recent dump. Since dumps are done early in the morning, yesterday's files are really in today's dump. For example, if today is March 17, 1992,

yesterday /adm/users

prints

/n/dump/1992/0317/adm/users

In fact, the implementation is to select the most recent dump in the current year, so the dump selected may not be from today.

When presented with a path of the form /n/fs/path, yesterday will look for dump files of the form /n/fsdump/yyyy/hhmm/path.

By default, *yesterday* prints the names of the dump files corresponding to the named files. The first set of options changes this behavior.

- -a Run *acme*(1)'s *adiff* to compare the dump files with the named files.
- -b Bind the dump files over the named files.
- -c Copy the dump files over the named files.
- -C Copy the dump files over the named files only when they differ.
- -d Run diff to compare the dump files with the named files.
- -D Run diff -n to compare the dump files with the named files.

The *date* option selects other day's dumps, with a format of 1, 2, 4, 6, or 8 digits of the form *d*, *dd*, *mmdd*, *yymmdd*, or *yyyymmdd*.

The -n option selects the dump *daysago* prior to the current day.

The -s option selects the most recent snapshot instead of the most recent archived dump. Snapshots may occur more frequently than dumps.

Yesterday does not guarantee that the string it prints represents an existing file.

Diffy runs *diff*(1) with the given options to compare yesterday's version of each of the named files with today's.

EXAMPLES

Back up to yesterday's MIPS binary of vc:

yesterday -c /mips/bin/vc

Temporarily back up to March 1's MIPS C library to see if a program runs correctly when loaded with it:

yesterday -b -0301 /mips/lib/libc.a rm v.out mk v.out

Find what has changed in the C library since March 1:

```
yesterday -d -0301 /sys/src/libc/port/*.c
```

Find what has changed in the source tree today:

diffy -r /sys/src

FILES

/n/dump

SOURCE

/rc/bin/yesterday /rc/bin/diffy

SEE ALSO

history(1), bind(1), diff(1), fs(4).

BUGS

It's hard to use this command without singing.

Doesn't work on January 1st.

intro - introduction to library functions

SYNOPSIS

SIS
#include <u.h>
#include <libc.h>
#include <libc.h>
#include <auth.h>
#include <bio.h>
#include <draw.h>
#include <fcall.h>
#include <fcall.h>
#include <frame.h>
#include <mach.h>
#include <ndb.h>
#include <regexp.h>
#include <stdio.h>
#include <thread.h>
#Include <thread.h</th>
#Inclu

DESCRIPTION

This section describes functions in various libraries. For the most part, each library is defined by a single C include file, such as those listed above, and a single archive file containing the library proper. The name of the archive is /\$objtype/lib/libx.a, where x is the base of the include file name, stripped of a leading lib if present. For example, <draw.h> defines the contents of library /\$objtype/lib/libdraw.a, which may be abbreviated when named to the loader as -ldraw. In practice, each include file contains a #pragma that directs the loader to pick up the associated archive automatically, so it is rarely necessary to tell the loader which libraries a program needs.

The library to which a function belongs is defined by the header file that defines its interface. The 'C library', *libc*, contains most of the basic subroutines such as *strlen*. Declarations for all of these functions are in <libc.h>, which must be preceded by (*needs*) an include of <u.h>. The graphics library, *draw*, is defined by <draw.h>, which needs <libc.h> and <u.h>. The Buffered I/O library, *libbio*, is defined by <bio.h>, which needs <libc.h> and <u.h>. The ANSI C Standard I/O library, *libstdio*, is defined by <stdio.h>, which needs <u.h>. There are a few other, less commonly used libraries defined on individual pages of this section.

The include file $\langle u.h \rangle$, a prerequisite of several other include files, declares the architecturedependent and -independent types, including: *uchar*, *ushort*, *uint*, and *ulong*, the unsigned integer types; *schar*, the signed char type; *vlong* and *uvlong*, the signed and unsigned very long integral types; *Rune*, the Unicode character type; *u8int*, *u16int*, *u32int*, and *u64int*, the unsigned integral types with specific widths; *uintptr*, the unsigned integral type with the same width as a pointer; *jmp_buf*, the type of the argument to *setjmp* and *longjmp*, plus macros that define the layout of *jmp_buf* (see *setjmp*(2)); definitions of the bits in the floating-point control register as used by *getfcr*(2); and the macros va_arg and friends for accessing arguments of variadic functions (identical to the macros defined in <stdarg.h> in ANSI C).

Name space

Files are collected into a hierarchical organization called a *file tree* starting in a *directory* called the *root*. File names, also called *paths*, consist of a number of /-separated *path elements* with the slashes corresponding to directories. A path element must contain only printable characters (those outside the control spaces of ASCII and Latin-1). A path element cannot contain a slash.

When a process presents a file name to Plan 9, it is *evaluated* by the following algorithm. Start with a directory that depends on the first character of the path: / means the root of the main hierarchy, # means the separate root of a kernel device's file tree (see Section 3), and anything else means the process's current working directory. Then for each path element, look up the element in the directory, advance to that directory, do a possible translation (see below), and repeat. The last step may yield a directory or regular file. The collection of files reachable from the root is

called the *name space* of a process.

A program can use *bind* or *mount* (see *bind*(2)) to say that whenever a specified file is reached during evaluation, evaluation instead continues from a second specified file. Also, the same system calls create *union directories*, which are concatenations of ordinary directories that are searched sequentially until the desired element is found. Using *bind* and *mount* to do name space adjustment affects only the current process group (see below). Certain conventions about the layout of the name space should be preserved; see *namespace*(4).

File I/O

Files are opened for input or output by *open* or *create* (see *open*(2)). These calls return an integer called a *file descriptor* which identifies the file to subsequent I/O calls, notably *read*(2) and *write*. The system allocates the numbers by selecting the lowest unused descriptor. They are allocated dynamically; there is no visible limit to the number of file descriptors a process may have open. They may be reassigned using dup(2). File descriptors are indices into a kernel resident *file descriptor table*. Each process has an associated file descriptor table. In some cases (see *rfork* in *fork*(2)) a file descriptor table may be shared by several processes.

By convention, file descriptor 0 is the standard input, 1 is the standard output, and 2 is the standard error output. With one exception, the operating system is unaware of these conventions; it is permissible to close file 0, or even to replace it by a file open only for writing, but many programs will be confused by such chicanery. The exception is that the system prints messages about broken processes to file descriptor 2.

Files are normally read or written in sequential order. The I/O position in the file is called the *file* offset and may be set arbitrarily using the seek(2) system call.

Directories may be opened and read much like regular files. They contain an integral number of records, called *directory entries*. Each entry is a machine-independent representation of the information about an existing file in the directory, including the name, ownership, permission, access dates, and so on. The entry corresponding to an arbitrary file can be retrieved by *stat*(2) or *fstat*; *wstat* and *fwstat* write back entries, thus changing the properties of a file. An entry may be translated into a more convenient, addressable form called a Dir structure; *dirstat*, *dirfstat*, *dirwstat*, and *dirfwstat* execute the appropriate translations (see *stat*(2)).

New files are made with *create* (see *open*(2)) and deleted with *remove*(2). Directories may not directly be written; *create*, *remove*, *wstat*, and *fwstat* alter them.

The operating system kernel records the file name used to access each open file or directory. If the file is opened by a local name (one that does not begin / or #), the system makes the stored name absolute by prefixing the string associated with the current directory. Similar lexical adjustments are made for path names containing . (dot) or . . (dot-dot). By this process, the system maintains a record of the route by which each file was accessed. Although there is a possibility for error—the name is not maintained after the file is opened, so removals and renamings can confound it—this simple method usually permits the system to return, via the fd2path(2) system call and related calls such as getwd(2), a valid name that may be used to find a file again. This is also the source of the names reported in the name space listing of ns(1) or /dev/ns (see proc(3)).

Pipe(2) creates a connected pair of file descriptors, useful for bidirectional local communication.

Process execution and control

A new process is created when an existing one calls *rfork* with the RFPROC bit set, usually just by calling *fork*(2). The new (child) process starts out with copies of the address space and most other attributes of the old (parent) process. In particular, the child starts out running the same program as the parent; *exec*(2) will bring in a different one.

Each process has a unique integer process id; a set of open files, indexed by file descriptor; and a current working directory (changed by *chdir*(2)).

Each process has a set of attributes — memory, open files, name space, etc. — that may be shared or unique. Flags to *rfork* control the sharing of these attributes.

The memory of a process is divided into *segments*. Every program has at least a *text* (instruction) and *stack* segment. Most also have an initialized *data* segment and a segment of zero-filled data called *bss*. Processes may *segattach*(2) other segments for special purposes.

A process terminates by calling *exits*(2). A parent process may call *wait*(2) to wait for some child to terminate. A string of status information may be passed from *exits* to *wait*. A process can go to sleep for a specified time by calling *sleep*(2).

There is a *notification* mechanism for telling a process about events such as address faults, floating point faults, and messages from other processes. A process uses *notify*(2) to register the function to be called (the *notification handler*) when such events occur.

Multithreading

By calling *rfork* with the RFMEM bit set, a program may create several independently executing processes sharing the same memory (except for the stack segment, which is unique to each process). Where possible according to the ANSI C standard, the main C library works properly in multiprocess programs; *malloc*, *print*, and the other routines use locks (see *lock*(2)) to synchronize access to their data structures. The graphics library defined in < draw.h> is also multi-process capable; details are in *graphics*(2). In general, though, multiprocess programs should use some form of synchronization to protect shared data.

The thread library, defined in <thread.h>, provides support for multiprocess programs. It includes a data structure called a Channel that can be used to send messages between processes, and coroutine-like *threads*, which enable multiple threads of control within a single process. The threads within a process are scheduled by the library, but there is no pre-emptive scheduling within a process; thread switching occurs only at communication or synchronization points.

Most programs using the thread library comprise multiple processes communicating over channels, and within some processes, multiple threads. Since Plan 9 I/O calls may block, a system call may block all the threads in a process. Therefore, a program that shouldn't block unexpectedly will use a process to serve the I/O request, passing the result to the main processes over a channel when the request completes. For examples of this design, see *ioproc*(2) or *mouse*(2).

SEE ALSO

nm(1), *2l*(1), *2c*(1)

DIAGNOSTICS

Math functions in *libc* return special values when the function is undefined for the given arguments or when the value is not representable (see *nan*(2)).

Some of the functions in *libc* are system calls and many others employ system calls in their implementation. All system calls return integers, with -1 indicating that an error occurred; *errstr*(2) recovers a string describing the error. Some user–level library functions also use the *errstr* mechanism to report errors. Functions that may affect the value of the error string are said to "set *errstr*"; it is understood that the error string is altered only if an error occurs.

Srv, chatty9p, dirread9p, emalloc9p, erealloc9p, estrdup9p, listensrv, postmountsrv, postsharesrv, readbuf, readstr, respond, responderror, srvacquire, srvrelease, threadlistensrv, threadpost-mountsrv, threadpostsharesrv, srv - 9P file service

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <fcall.h>
#include <thread.h>
#include <9p.h>
typedef struct Srv {
   Tree* tree;
         (*attach)(Req *r);
   void
          (*auth)(Req *r);
   void
         (*open)(Req *r);
   void
    void
         (*create)(Req *r);
    void (*read)(Req *r);
   void (*write)(Req *r);
   void (*remove)(Req *r);
    void (*flush)(Req *r);
   void
         (*stat)(Req *r);
          (*wstat)(Req *r);
   void
    void
         (*walk)(Req *r);
    char* (*walk1)(Fid *fid, char *name, Qid *qid);
    char* (*clone)(Fid *oldfid, Fid *newfid);
   void (*destroyfid)(Fid *fid);
    void
         (*destroyreq)(Req *r);
   void (*start)(Srv *s);
   void (*end)(Srv *s);
   void* aux;
   int
          infd;
   int
          outfd:
   int
          srvfd;
} Srv;
void srv(Srv *s)
     postmountsrv(Srv *s, char *name, char *mtpt, int flag)
void
     postsharesrv(Srv *s, char *name, char *mtpt, char *desc)
void
     threadpostmountsrv(Srv *s, char *name, char *mtpt, int flag)
void
     threadpostsharesrv(Srv *s, char *name, char *mtpt, char *desc)
void
     listensrv(Srv *s, char *addr)
void
void threadlistensrv(Srv *s, char *addr)
void respond(Req *r, char *error)
void responderror(Req*)
void readstr(Req *r, char *src)
void readbuf(Req *r, void *src, long nsrc)
typedef int Dirgen(int n, Dir *dir, void *aux)
     dirread9p(Req *r, Dirgen *gen, void *aux)
void
void walkandclone(Req *r, char *(*walk1)(Fid *old, char *name, void *v),
          char *(*clone)(Fid *old, Fid *new, void *v), void *v)
void
     srvrelease(Srv *s)
void srvacquire(Srv *s)
```

```
void* emalloc9p(ulong n)
void* erealloc9p(void *v, ulong n)
char* estrdup9p(char *s)
extern int chatty9p;
```

DESCRIPTION

The function *srv* serves a 9P session by reading requests from $s \rightarrow infd$, dispatching them to the function pointers kept in Srv, and writing the responses to $s \rightarrow outfd$. (Typically, *postmountsrv* or *threadpostmountsrv* initializes the infd and outfd structure members. See the description below.)

Req and Fid structures are allocated one-to-one with uncompleted requests and active fids, and are described in *9pfid*(2).

The behavior of srv depends on whether there is a file tree (see 9pfile(2)) associated with the server, that is, whether the tree element is nonzero. The differences are made explicit in the discussion of the service loop below. The aux element is the client's, to do with as it pleases.

Srv does not return until the 9P conversation is finished. Since it is usually run in a separate process so that the caller can exit, the service loop has little chance to return gracefully on out of memory errors. It calls *emalloc9p*, *erealloc9p*, and *estrdup9p* to obtain its memory. The default implementations of these functions act as *malloc*, *realloc*, and *strdup* but abort the program if they run out of memory. If alternate behavior is desired, clients can link against alternate implementations of these functions.

Postmountsrv and *threadpostmountsrv* are wrappers that create a separate process in which to run *srv*. They do the following:

Initialize $s \rightarrow infd$ and $s \rightarrow outfd$ to be one end of a freshly allocated pipe, with $s \rightarrow srvfd$ initialized as the other end.

If name is non-nil, post the file descriptor $s \rightarrow srvfd$ under the name /srv/name.

Fork a child process via *rfork* (see *fork*(2)) or *procrfork* (see *thread*(2)), using the RFPROC, RFNOWAIT, RFNAMEG, RFNOTEG and RFMEM flags. This isolates the service loop from the callers namespace and from notes posted to the callers note group but shares data and bss segments.

The child process then waits for the parent to copy its file descriptor table via *rfork* using RFFDG flag. This way, the service loop will share the original file descriptor table with previously created child processes of the caller.

The child process then calls close(s - > srvfd) and then srv(s); it will exit once srv returns.

If *mtpt* is non-nil, call amount (*s*->*srvfd*, *mtpt*, *flag*, ""); otherwise, close *s*->*srvfd*.

The parent returns to the caller.

If any error occurs during this process, the entire process is terminated by calling *sysfatal* (see *perror*(2)).

Postsharesrv is similar to *Postmountsrv* but instead of mounting the service on a directory, it is put in a share (see shr(3)) where *mtpt* is the name of the share and *desc* is the name of the service channel.

Listensrv and *threadlistensrv* create a separate process to announce as *addr*. The process listens for incoming connections, creating a new process to serve each. Using these functions results in *srv* and the service functions being run in multiple processes simultaneously. The library locks its own data structures as necessary; the client may need to lock data it shares between the multiple connections.

Service functions

The functions in a Srv structure named after 9P transactions are called to satisfy requests as they arrive. If a function is provided, it *must* arrange for *respond* to be called when the request is satisfied. The only parameter of each service function is a Req* parameter (say *r*). The incoming request parameters are stored in r->*ifcall*; r->*fid* and r->*newfid* are pointers to Fid structures corresponding to the numeric fids in r->*ifcall*; similarly, r->*oldreq* is the Req structure corresponding to r->*ifcall.oldtag*. The outgoing response data should be stored in r->*ofcall*. The

one exception to this rule is that *stat* should fill in $r \rightarrow d$ rather than $r \rightarrow ofcall.stat$: the library will convert the structure into the machine-independent wire representation. Similarly, *wstat* may consult $r \rightarrow d$ rather than decoding $r \rightarrow ifcall$. *stat* itself. When a request has been handled, *respond* should be called with r and an error string. If the request was satisfied successfully, the error string should be a nil pointer. Note that it is permissible for a function to return without itself calling *respond*, as long as it has arranged for *respond* to be called at some point in the future by another proc sharing its address space, but see the discussion of *flush* below. Once *respond* has been called, the Req* as well as any pointers it once contained must be considered freed and not referenced.

Responderror calls respond with the system error string (see errstr(2)).

If the service loop detects an error in a request (e.g., an attempt to reuse an extant fid, an open of an already open fid, a read from a fid opened for write, etc.) it will reply with an error without consulting the service functions.

The service loop provided by *srv* (and indirectly by *postmountsrv* and *threadpostmountsrv*) is single-threaded. If it is expected that some requests might block, arranging for alternate processes to handle them is suggested (see *9pqueue*(2)).

Srvrelease temporarily releases the calling process from the server loop and if neccesary spawns a new process to handle 9p requests. When released, the process can do blocking work that would otherwise halt processing of 9p requests. *Srvacquire* rejoins the calling process with the server loop after a srvrelease.

The constraints on the service functions are as follows. These constraints are checked while the server executes. If a service function fails to do something it ought to have, *srv* will call *endsrv* and then abort.

- Auth If authentication is desired, the *auth* function should record that $r \rightarrow afid$ is the new authentication fid and set $r \rightarrow afid \rightarrow qid$ and *ofcall.qid*. Auth may be nil, in which case it will be treated as having responded with the error "*argv0*: *authentication not required*," where *argv0* is the program name variable as set by *ARGBEGIN* (see *arg*(2)).
- Attach The attach function should check the authentication state of *afid* if desired, and set $r \rightarrow fid \rightarrow qid$ and *ofcall.qid* to the qid of the file system root. Attach may be nil only if file trees are in use; in this case, the qid will be filled from the root of the tree, and no authentication will be done.
- *Walk* If file trees are in use, *walk* is handled internally, and *srv->walk* is never called.

If file trees are not in use, *walk* should consult $r \rightarrow ifcall$. *wname* and $r \rightarrow ifcall$. *nwname*, filling in *ofcall*. *qid* and *ofcall*. *nqid*, and also copying any necessary *aux* state from $r \rightarrow fid$ to $r \rightarrow newfid$ when the two are different. As long as *walk* sets *ofcall*. *nqid* appropriately, it can *respond* with a nil error string even when 9P demands an error (*e.g.*, in the case of a short walk); the library detects error conditions and handles them appropriately.

Because implementing the full walk message is intricate and prone to error, the helper routine walkandclone will handle the request given pointers to two functions walk1 and (optionally) clone. Clone, if non-nil, is called to signal the creation of newfid from oldfid. Typically a clone routine will copy or increment a reference count in oldfid's aux element. Walk1 should walk fid to name, initializing fid->qid to the new path's qid. Both should return nil on success or an error message on error. Walkandclone will call respond after handling the request.

Walk1, Clone

If the client provides functions $srv \rightarrow walk1$ and (optionally) $srv \rightarrow clone$, the 9P service loop will call *walkandclone* with these functions to handle the request. Unlike the *walk1* above, $srv \rightarrow walk1$ must fill in both $fid \rightarrow qid$ and *qid with the new qid on a successful walk.

Open If file trees are in use, the file metadata will be consulted on open, create, remove, and wstat to see if the requester has the appropriate permissions. If not, an error will be sent back without consulting a service function.

If not using file trees or the user has the appropriate permissions, *open* is called with $r \rightarrow ofcall$. *qid* already initialized to the one stored in the Fid structure (that is, the one

returned in the previous walk). If the qid changes, both should be updated.

Create The *create* function must fill in both $r \rightarrow fid \rightarrow qid$ and $r \rightarrow ofcall$. *qid* on success. When using file trees, *create* should allocate a new File with *createfile*; note that *createfile* may return nil (because, say, the file already exists). If the *create* function is nil, *srv* behaves as though it were a function that always responded with the error "create prohibited".

Remove

Remove should mark the file as removed, whether by calling *removefile* when using file trees, or by updating an internal data structure. In general it is not a good idea to clean up the *aux* information associated with the corresponding File at this time, to avoid memory errors if other fids have references to that file. Instead, it is suggested that *remove* simply mark the file as removed (so that further operations on it know to fail) and wait until the file tree's destroy function is called to reclaim the *aux* pointer. If not using file trees, it is prudent to take the analogous measures. If *remove* is not provided, all remove requests will draw "remove prohibited" errors.

- Read The read function must be provided; it fills $r \rightarrow ofcall$. data with at most $r \rightarrow ifcall$. count bytes of data from offset $r \rightarrow ifcall$. offset of the file. It also sets $r \rightarrow ofcall$. count to the number of bytes being returned. If using file trees, srv will handle reads of directories internally, only calling read for requests on files. Readstr and readbuf are useful for satisfying read requests on a string or buffer. Consulting the request in $r \rightarrow ifcall$, they fill $r \rightarrow ofcall$. data and set $r \rightarrow ofcall$. count; they do not call respond. Similarly, dirread9p can be used to handle directory reads in servers not using file trees. The passed gen function will be called as necessary to fill dir with information for the nth entry in the directory. The string pointers placed in dir should be fresh copies made with estrdup9p; they will be freed by dirread9p after each successful call to gen. Gen should return zero if it successfully filled dir, minus one on end of directory.
- Write The write function is similar but need not be provided. If it is not, all writes will draw "write prohibited" errors. Otherwise, write should attempt to write the $r \rightarrow ifcall . count$ bytes of $r \rightarrow ifcall . data$ to offset $r \rightarrow ifcall . offset$ of the file, setting $r \rightarrow ofcall . count$ to the number of bytes actually written. Most programs consider it an error to write less than the requested amount.
- Stat Stat should fill $r \rightarrow d$ with the stat information for $r \rightarrow fid$. If using file trees, $r \rightarrow d$ will have been initialized with the stat info from the tree, and *stat* itself may be nil.
- Wstat The wstat function consults $r \rightarrow d$ in changing the metadata for $r \rightarrow fid$ as described in stat(5). When using file trees, srv will take care to check that the request satisfies the permissions outlined in stat(5). Otherwise wstat should take care to enforce permissions where appropriate.
- Flush Servers that always call respond before returning from the service functions need not provide a flush implementation: flush is only necessary in programs that arrange for respond to be called asynchronously. Flush should cause the request r -> oldreq to be cancelled or hurried along. If oldreq is cancelled, this should be signalled by calling respond on oldreq with error string 'interrupted'. Flush must respond to r with a nil error string. Flush may respond to r before forcing a response to r -> oldreq. In this case, the library will delay sending the Rflush message until the response to r -> oldreq has been sent.

Destroyfid, destroyreq, start, and end are auxiliary functions, not called in direct response to 9P requests.

Destroyfid

When a Fid's reference count drops to zero (*i.e.*, it has been clunked and there are no outstanding requests referring to it), *destroyfid* is called to allow the program to dispose of the $fid \rightarrow aux$ pointer.

Destroyreq

Similarly, when a Req's reference count drops to zero (*i.e.*, it has been handled via *respond* and other outstanding pointers to it have been closed), *destroyreq* is called to allow the program to dispose of the r->aux pointer.

Start This gets called (from the forked service process) prior entering the 9P service loop.

End Once the 9P service loop has finished (end of file been reached on the service pipe or a bad message has been read), *end* is called (if provided) to allow any final cleanup. For example, it was used by the Palm Pilot synchronization file system (never finished) to gracefully terminate the serial conversation once the file system had been unmounted. After calling *end*, the service loop (which runs in a separate process from its caller) terminates using *_exits* (see *exits*(2)).

If the chatty9p flag is at least one, a transcript of the 9P session is printed on standard error. If the chatty9p flag is greater than one, additional unspecified debugging output is generated. By convention, servers written using this library accept the -D option to increment chatty9p.

EXAMPLES

Archfs(4), cdfs(4), nntpfs(4), snap(4), and /sys/src/lib9p/ramfs.c are good examples of simple single-threaded file servers.

In general, the File interface is appropriate for maintaining arbitrary file trees (as in *ramfs*). The File interface is best avoided when the tree structure is easily generated as necessary; this is true when the tree is highly structured (as in *cdfs* and *nntpfs*) or is maintained elsewhere.

SOURCE

/sys/src/lib9p

SEE ALSO

9pfid(2), 9pfile(2), 9pqueue(2), srv(3), shr(3), intro(5)

BUGS

The switch to 9P2000 was taken as an opportunity to tidy much of the interface; we promise to avoid such gratuitous change in the future.

Cmdbuf, parsecmd, respondcmderror, lookupcmd - control message parsing

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <fcall.h>
#include <thread.h>
#include <9p.h>
typedef struct Cmdbuf
{
            *buf;
    char
            **f:
    char
    int
            nf;
} Cmdbuf;
typedef struct Cmdtab
{
    int
            index:
    char
            * cmd;
    int
            narg;
};
Cmdbuf
            *parsecmd(char *p, int n)
Cmdtab
            *lookupcmd(Cmdbuf *cb, Cmdtab *tab, int ntab)
void
            respondemderror(Req *r, Cmdbuf *cb, char *fmt, ...)
```

DESCRIPTION

These data structures and functions provide parsing of textual control messages.

Parsecmd treats the *n* bytes at *p* (which need not be NUL-terminated) as a UTF string and splits it using *tokenize* (see *getfields*(2)). It returns a Cmdbuf structure holding pointers to each field in the message. It is the caller's responsibility to free this structure when it is no longer needed.

Lookupcmd walks through the array *ctab*, which has *ntab* entries, looking for the first Cmdtab that matches the parsed command. (If the parsed command is empty, *lookupcmd* returns nil immediately.) A Cmdtab matches the command if *cmd* is equal to cb -> f[0] or if *cmd* is *. Once a matching Cmdtab has been found, if *narg* is not zero, then the parsed command must have exactly *narg* fields (including the command string itself). If the command has the wrong number of arguments, *lookupcmd* returns nil. Otherwise, it returns a pointer to the Cmdtab entry. If *lookupcmd* does not find a matching command at all, it returns nil. Whenever *lookupcmd* returns nil, it sets the system error string.

Respondemderror responds to request r with an error of the form '*fmt*: *cmd*,' where *fmt* is the formatted string and *cmd* is a reconstruction of the parsed command. Fmt is often simply %r.

EXAMPLES

This interface is not used in any distributed 9P servers. It was lifted from the Plan 9 kernel. Almost any kernel driver (/sys/src/9/*/dev*.c) is a good example.

SOURCE

/sys/src/lib9p/parse.c

SEE ALSO

9p(2)

Fid, Fidpool, allocfidpool, freefidpool, allocfid, closefid, lookupfid, removefid, Req, Reqpool, allocreqpool, freereqpool, allocreq, closereq, lookupreq, removereq - 9P fid, request tracking

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <fcall.h>
#include <thread.h>
#include <9p.h>
typedef struct Qid
{
    uvlong path;
    ulong vers;
    uchar type;
} Qid;
typedef struct Fid
    ulong fid;
    char
          omode; /* -1 if not open */
    char
          *uid:
    Oid
          qid;
    File
          *file;
    void *aux;
} Fid:
typedef struct Req
{
    ulong tag;
    Fcall ifcall;
    Fcall ofcall;
          *oldreg:
    Req
          *aux;
    void
    Fid
           *fid;
    Fid
           *afid:
    Fid
          *newfid:
} Req;
Fidpool* allocfidpool(void (*destroy)(Fid*))
void
         freefidpool(Fidpool *p)
Fid*
         allocfid(Fidpool *p, ulong fid)
         lookupfid(Fidpool *p, ulong fid)
Fid*
Fid*
         removefid(Fidpool *p, ulong fid);
         closefid(Fid *f)
void
Reqpool* allocreqpool(void (*destroy)(Req*))
void
         freereqpool(Reqpool *p)
         allocreq(Reqpool *p, ulong tag)
lookupreq(Reqpool *p, ulong tag)
Req*
Req*
         removereq(Reqpool *p, ulong tag);
Req*
void
         closereq(Req *f)
```

DESCRIPTION

These routines provide management of Fid and Req structures from Fidpools and Reqpools. They are primarily used by the 9P server loop described in 9p(2).

Fid structures are intended to represent active fids in a 9P connection, as Chan structures do in the Plan 9 kernel. The fid element is the integer fid used in the 9P connection. Omode is the mode under which the fid was opened, or -1 if this fid has not been opened yet. Note that in

addition to the values OREAD, OWRITE, and ORDWR, omode can contain the various flags permissible in an open call. To ignore the flags, use omode&OMASK. Omode should not be changed by the client. The fid derives from a successful authentication by uid. Qid contains the qid returned in the last successful walk or create transaction involving the fid. In a file tree-based server, the Fid's file element points at a File structure (see *9pfile*(2)) corresponding to the fid. The aux member is intended for use by the client to hold information specific to a particular Fid. With the exception of aux, these elements should be treated as read-only by the client.

Allocfidpool creates a new Fidpool. Freefidpool destroys such a pool. Allocfid returns a new Fid whose fid number is fid. There must not already be an extant Fid with that number in the pool. Once a Fid has been allocated, it can be looked up by fid number using lookupfid. Fids are reference counted: both allocfid and lookupfid increment the reference count on the Fid structure before returning. When a reference to a Fid is no longer needed, closefid should be called to note the destruction of the reference. When the last reference to a Fid is removed, if destroy (supplied when creating the fid pool) is not zero, it is called with the Fid as a parameter. It should perform whatever cleanup is necessary regarding the aux element. Removefid is equivalent to lookupfid but also removes the Fid from the pool. Note that due to lingering references, the return of removefid may not mean that destroy has been called.

Allocreqpool, freereqpool, allocreq, lookupreq, closereq, and removereq are analogous but operate on Reqpools and Req structures.

SOURCE

/sys/src/lib9p

SEE ALSO

9p(2), 9pfile(2)

Tree, alloctree, freetree, File, createfile, closefile, removefile, walkfile, opendirfile, readdirfile, closedirfile, hasperm - in-memory file hierarchy

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <fcall.h>
#include <thread.h>
#include <9p.h>
typedef struct File
{
     Ref;
     Dir;
     void*aux;
} File;
typedef struct Tree
{
     File *root:
     ...
} Tree;
Tree*
         alloctree(char *uid, char *gid, ulong mode,
               void (*destroy)(File*))
void
         freetree(Tree *tree)
File*
         createfile(File *dir, char *name, char *uid,
               ulong mode, void *aux)
int
         removefile(File *file)
         closefile(File *file)
void
File*
         walkfile(File *dir, char *path)
Readdir* opendirfile(File *dir)
         readdirfile(Readdir *rdir, uchar *buf, long n, long o)
closedirfile(Readdir *rdir)
long
void
int
         hasperm(File *file, char *uid, int p)
```

DESCRIPTION

Files and Trees provide an in-memory file hierarchy intended for use in 9P file servers.

Alloctree creates a new tree of files, and *freetree* destroys it. The root of the tree (also the root element in the structure) will have mode *mode* and be owned by user *uid* and group *gid*. *Destroy* is used when freeing File structures and is described later.

Files (including directories) other than the root are created using *createfile*, which attempts to create a file named *name* in the directory *dir*. If created, the file will have owner *uid* and have a group inherited from the directory. *Mode* and the permissions of *dir* are used to calculate the permission bits for the file as described in *open*(5). It is permissible for *name* to be a slash-separated path rather than a single element.

Removefile removes a file from the file tree. The file will not be freed until the last reference to it has been removed. Directories may only be removed when empty. *Removefile* returns zero on success, -1 on error. It is correct to consider *removefile* to be *closefile* with the side effect of removing the file when possible.

Walkfile evaluates *path* relative to the directory *dir*, returning the resulting file, or zero if the named file or any intermediate element does not exist.

The File structure's aux pointer may be used by the client for per-File storage. Files are reference-counted: if not zero, *destroy* (specified in the call to *alloctree*) will be called for each file when its last reference is removed or when the tree is freed. *Destroy* should take care of any necessary cleanup related to aux. When creating new file references by copying pointers, call *incref* (see *lock*(2)) to update the reference count. To note the removal of a reference to a file, call

closefile. *Createfile* and *walkfile* return new references. *Removefile*, *closefile*, and *walkfile* (but not *createfile*) consume the passed reference.

Directories may be read, yielding a directory entry structure (see *stat*(5)) for each file in the directory. In order to allow concurrent reading of directories, clients must obtain a Readdir structure by calling *opendirfile* on a directory. Subsequent calls to *readdirfile* will each yield an integral number of machine-independent stat buffers, until end of directory. When finished, call *closedirfile* to free the Readdir.

Hasperm does simplistic permission checking; it assumes only one-user groups named by uid and returns non-zero if uid has permission p (a bitwise-or of AREAD, AWRITE and AEXEC) according to *file*->mode. 9P servers written using File trees will do standard permission checks automatically; *hasperm* may be called explicitly to do additional checks. A 9P server may link against a different *hasperm* implementation to provide more complex groups.

EXAMPLE

The following code correctly handles references when elementwise walking a path and creating a file.

SOURCE

```
/sys/src/lib9p/file.c
```

SEE ALSO

9p(2)

BUGS

The reference counting is cumbersome.

Reqqueue, reqqueuecreate, reqqueuepush, reqqueueflush - deferred processing of 9P requests

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <fcall.h>
#include <thread.h>
#include <9p.h>
struct Reqqueue
{
     ...
};
Reggueue*
            reqqueuecreate(void);
            reqqueuepush(Reqqueue *q, Req *r, void (*f)(Req *));
void
void
            reqqueueflush(Reqqueue *q, Req *r);
void
            reqqueuefree(Reqqueue *q);
```

DESCRIPTION

Reqqueue provides routines for deferred processing of 9p request in multithreaded 9p servers.

The *reqqueuecreate* function spawns a process for handling requests returning a pointer to the *Reqqueue* structure allocated.

To schedule a request to be processed on a queue, reqqueuepush is called with request r and its handler function f.

A previously submitted request can be flushed from a queue by *reqqueueflush* which will remove the request immediately if processing has not started. If processing has been started, the process will be interrupted.

Reqqueuefree frees a queue. No new requests should be send to the queue and it will be freed once all requests in it have been processed.

SOURCE

/sys/src/lib9p/queue.c

SEE ALSO

9p(2)

abort - generate a fault

SYNOPSIS

#include <u.h>
#include <libc.h>

void abort(void)

DESCRIPTION

Abort causes an access fault, causing the current process to enter the 'Broken' state. The process can then be inspected by a debugger.

SOURCE

/sys/src/libc/9sys/abort.c

abs, labs - integer absolute values

SYNOPSIS

#include <u.h>
#include <libc.h>
int abs(int a)

long labs(long a)

DESCRIPTION

Abs returns the absolute value of integer a, and labs does the same for a long.

SOURCE

/sys/src/libc/port/abs.c

SEE ALSO

floor(2) for fabs

DIAGNOSTICS

Abs and labs return the most negative integer or long when the true result is unrepresentable.

access - determine accessibility of file

SYNOPSIS

#include <u.h>
#include <libc.h>

int access(char *name, int mode)

DESCRIPTION

Access evaluates the given file name for accessibility. If mode&4 is nonzero, read permission is expected; if mode&2, write permission; if mode&1, execute permission. If mode==0, the file merely need exist. In any case all directories leading to the file must permit searches. Zero is returned if the desired access is permitted, -1 if not.

Only access for open is checked. A file may look executable, but *exec*(2) will fail unless it is in proper format.

The include file defines AEXIST=0, AEXEC=1, AWRITE=2, and AREAD=4.

SOURCE

/sys/src/libc/9sys/access.c

SEE ALSO

stat(2)

DIAGNOSTICS

Sets errstr.

BUGS

Since file permissions are checked by the server and group information is not known to the client, *access* must open the file to check permissions. (It calls *stat*(2) to check simple existence.)

addpt, subpt, mulpt, divpt, rectaddpt, rectsubpt, insetrect, canonrect, eqpt, eqrect, ptinrect, rectinrect, rectXrect, rectclip, combinerect, badrect, Dx, Dy, Pt, Rect, Rpt - arithmetic on points and rectangles

SYNOPSIS

<pre>#include <u.h> #include <libc.h> #include <libc.h></libc.h></libc.h></u.h></pre>				
Point	addpt(Point p, Point q)			
Point	<pre>subpt(Point p, Point q)</pre>			
Point	<pre>mulpt(Point p, int a)</pre>			
Point	divpt(Point p, int a)			
Rectangle	<pre>rectaddpt(Rectangle r, Point p)</pre>			
Rectangle	<pre>rectsubpt(Rectangle r, Point p)</pre>			
Rectangle	<pre>insetrect(Rectangle r, int n)</pre>			
Rectangle	<pre>canonrect(Rectangle r)</pre>			
int	eqpt(Point p, Point q)			
int	<pre>eqrect(Rectangle r, Rectangle s)</pre>			
int	<pre>ptinrect(Point p, Rectangle r)</pre>			
int	<pre>rectinrect(Rectangle r, Rectangle s)</pre>			
int	<pre>rectXrect(Rectangle r, Rectangle s)</pre>			
int	<pre>rectclip(Rectangle *rp, Rectangle b)</pre>			
void	<pre>combinerect(Rectangle *rp, Rectangle b)</pre>			
int	<pre>badrect(Rectangle r)</pre>			
int	Dx(Rectangle r)			
int	Dy(Rectangle r)			
Point	Pt(int x, int y)			
Rectangle	Rect(int x0, int y0, int x1, int y1)			
Rectangle	Rpt(Point p, Point q)			

DESCRIPTION

The functions *Pt*, *Rect* and *Rpt* construct geometrical data types from their components.

Addpt returns the Point sum of its arguments: Pt(p.x+q.x, p.y+q.y). Subpt returns the Point difference of its arguments: Pt(p.x-q.x, p.y-q.y). Mulpt returns the Point $Pt(p.x^*a, p.y^*a)$. Divpt returns the Point Pt(p.x/a, p.y/a).

Rectaddpt returns the Rectangle Rect(add(r.min, p), add(r.max, p)); rectsubpt returns the Rectangle Rpt(sub(r.min, p), sub(r.max, p)).

Insetrect returns the Rectangle Rect(r.min.x+n, r.min.y+n, r.max.x-n, r.max.y-n).

Canonrect returns a rectangle with the same extent as r, canonicalized so that min.x \leq max.x, and min.y \leq max.y.

Eqpt compares its argument Points and returns 0 if unequal, 1 if equal. *Eqrect* does the same for its argument Rectangles.

Ptinrect returns 1 if p is a point within r, and 0 otherwise.

Rectinrect returns 1 if all the pixels in *r* are also in *s*, and 0 otherwise.

RectXrect returns 1 if *r* and *s* share any point, and 0 otherwise.

Rectclip clips in place the Rectangle pointed to by rp so that it is completely contained within b. The return value is 1 if any part of *rp is within b. Otherwise, the return value is 0 and *rp is unchanged.

Combinerect overwrites rp with the smallest rectangle sufficient to cover all the pixels of rp and b.

Badrect returns 1 if *r* is zero, negative size or insanely huge rectangle. It returns 0 otherwise.

The functions Dx and Dy give the width (Δx) and height (Δy) of a Rectangle. They are implemented as macros.

SOURCE

/sys/src/libdraw

SEE ALSO

graphics(2)

setupAESstate, aesCBCencrypt, aesCBCdecrypt, aesCFBencrypt, aesCFBdecrypt, aesOFBencrypt, aes_xts_encrypt, aes_xts_decrypt, setupAESGCMstate, aesgcm_setiv, aesgcm_encrypt, aesgcm_decrypt - advanced encryption standard (rijndael)

SYNOPSIS

#include <u.h>
#include <libc.h>
#include <mp.h>
#include <libsec.h>

woid and onerwrt(ulong rk[] int Nr

void aes_encrypt(ulong rk[], int Nr, uchar pt[16], uchar ct[16])

void aes_decrypt(ulong rk[], int Nr, uchar ct[16], uchar pt[16])

void setupAESstate(AESstate *s, uchar key[], int nkey, uchar *ivec)

void aesCBCencrypt(uchar *p, int len, AESstate *s)

void aesCBCdecrypt(uchar *p, int len, AESstate *s)

void aesCFBencrypt(uchar *p, int len, AESstate *s)

void aesCFBdecrypt(uchar *p, int len, AESstate *s)

void aesOFBencrypt(uchar *p, int len, AESstate *s)

void aes_xts_encrypt(AESstate *tweak, AESstate *ecb, uvlong sector-Number, uchar *input, uchar *output, ulong len)

void aes_xts_decrypt(AESstate *tweak, AESstate *ecb, uvlong sector-Number, uchar *input, uchar *output, ulong len)

void setupAESGCMstate(AESGCMstate *s, uchar *key, int keylen, uchar *iv, int ivlen)

void aesgcm_setiv(AESGCMstate *s, uchar *iv, int ivlen)

void aesgcm_encrypt(uchar *dat, ulong ndat, uchar *aad, ulong naad, uchar tag[16], AESGCMstate *s)

int aesgcm_decrypt(uchar *dat, ulong ndat, uchar *aad, ulong naad, uchar tag[16], AESGCMstate *s)

DESCRIPTION

AES (a.k.a. Rijndael) has replaced DES as the preferred block cipher. Aes_encrypt and aes_decrypt are the block ciphers, corresponding to des(2)'s block_cipher. AesCBCencrypt and aesCBCdecrypt implement cipher-block-chaining encryption. AesCFBencrypt, aesCFBdecrypt and aesOFBencrypt implement cipher-feedback- and output-feedback-mode stream cipher encryption. Aes_xts_encrypt and aes_xts_decrypt implement the XTS-AES tweakable block cipher, per IEEE 1619-2017 (see bugs below). SetupAESstate is used to initialize the state of the above encryption modes. The expanded roundkey parameters rk and Nr of aes_encrypt and aes_decrypt are returned in AESstate.ekey and AESstate.dkey with the corresponding number of rounds in AESstate.rounds. SetupAESGCMstate, aesgcm_setiv, aesgcm_encrypt and aesgcm_decrypt implement Galois/Counter Mode (GCM) authenticated encryption with associated data (AEAD). Before encryption or decryption, a new initialization vector (nonce) has to be set with *aesgcm_setiv* or by calling setupAESGCMstate with non-zero iv and ivlen arguments. Aesgcm_decrypt returns zero when authentication and decryption where successfull and non-zero otherwise. All ciphering is performed in place. The byte keysize nkey should be 16, 24, or 32. The initialization vector ivec of AESbsize bytes should be random enough to be unlikely to be reused but does not need to be cryptographically strongly unpredictable.

SOURCE

/sys/src/libsec

SEE ALSO

aescbc in secstore(1), mp(2), blowfish(2), des(2), dsa(2), elgamal(2), rc4(2), rsa(2), sechash(2), prime(2), rand(2)

http://csrc.nist.gov/publications/fips/fips197/fips-197.pdf

BUGS

Because of the way that non-multiple-of-16 buffers are handled, *aesCBCdecrypt* must be fed buffers of the same size as the *aesCBCencrypt* calls that encrypted it.

The functions *aes_xts_encrypt* an *aes_xts_decrypt* abort on a non-multiple-of-16 length as ciphertext stealing is not implemented.

ALLOCIMAGE(2)

NAME

allocimage, allocimagemix, freeimage, nameimage, namedimage, setalpha, loadimage, cloadimage, unloadimage, readimage, writeimage, bytesperline, wordsperline – allocating, freeing, reading, writing images

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <draw.h>
Image *allocimage(Display *d, Rectangle r,
      ulong chan, int repl, ulong col)
Image *allocimagemix(Display *d, ulong one, ulong three)
      freeimage(Image *i)
int
      nameimage(Image *i, char *name, int in)
int
Image *namedimage(Display *d, char *name)
ulong setalpha(ulong color, uchar alpha)
      loadimage(Image *i, Rectangle r, uchar *data, int ndata)
int
      cloadimage(Image *i, Rectangle r, uchar *data, int ndata)
int
      unloadimage(Image *i, Rectangle r, uchar *data, int ndata)
int
Image *readimage(Display *d, int fd, int dolock)
int
      writeimage(int fd, Image *i, int dolock)
      bytesperline(Rectangle r, int d)
int
      wordsperline(Rectangle r, int d)
int
enum
{
  DOpaque
                                = 0xFFFFFFF,
  DTransparent
                                = 0 \times 00000000,
  DBlack
                                = 0 \times 000000 FF,
  DWhite
                                = 0xFFFFFFFF,
  DRed
                                = 0xFF0000FF.
  DGreen
                                = 0x00FF00FF,
  DBlue
                                = 0x0000FFFF,
  DCvan
                                = 0x00FFFFFF.
  DMagenta
                                = 0xFF00FFFF,
  DYellow
                               = 0 \times FFFF00FF,
  DPaleyellow
                               = 0xFFFFAAFF,
  DDarkyellow
                               = 0xEEE9EFF,
  DDarkgreen
                               = 0x448844FF,
  DPalegreen
                               = 0xAAFFAAFF,
  DMedgreen
                               = 0 \times 88 C C \times 8 F F,
  DDarkblue
                                = 0 \times 000055 FF,
  DPalebluegreen
                                = 0xAAFFFFFF,
  DPaleblue
                                = 0x0000BBFF,
  DBluegreen
                                = 0 \times 008888 FF
  DGreygreen
                                = 0x55AAAFF.
  DPalegreygreen
                               = 0x9EEEEFF,
  DYellowgreen
                               = 0x99994CFF,
  DMedblue
                               = 0 \times 000099 FF,
  DGreyblue
                               = 0 \times 005 DBBFF,
  DPalegreyblue
                               = 0x4993DDFF,
  DPurpleblue
                               = 0x8888CCFF,
  DNotacolor
                                = 0xFFFFF00,
```

DNofill

= DNotacolor,

};

DESCRIPTION

A new Image on Display d is allocated with allocimage; it will have the rectangle, pixel channel format, replication flag, and initial fill color given by its arguments. Convenient pixel channels like GREY1, GREY2, CMAP8, RGB16, RGB24, and RGBA32 are predefined. All the new image's pixels will have initial value *col*. If *col* is DNofill, no initialization is done. Representative useful values of color are predefined: DBlack, DWhite, DRed, and so on. Colors are specified by 32-bit numbers comprising, from most to least significant byte, 8-bit values for red, green, blue, and alpha. The values correspond to illumination, so 0 is black and 255 is white. Similarly, for alpha 0 is transparent and 255 is opaque. The *id* field will have been set to the identifying number used by /dev/draw (see *draw*(3)), and the *cache* field will be zero. If *repl* is true, the clip rectangle is set to a very large region; if false, it is set to *r*. The *depth* field will be set to the number of bits per pixel specified by the channel descriptor (see *image*(6)). *Allocimage* returns 0 if the server has run out of image memory.

Allocimagemix is used to allocate background colors. On 8-bit color-mapped displays, it returns a 2×2 replicated image with one pixel colored the color *one* and the other three with *three*. (This simulates a wider range of tones than can be represented by a single pixel value on a color-mapped display.) On true color displays, it returns a 1×1 replicated image whose pixel is the result of mixing the two colors in a one to three ratio.

Freeimage frees the resources used by its argument image.

Nameimage publishes in the server the image *i* under the given *name*. If *in* is non-zero, the image is published; otherwise *i* must be already named *name* and it is withdrawn from publication. Namedimage returns a reference to the image published under the given *name* on Display *d*. These routines permit unrelated applications sharing a display to share an image; for example they provide the mechanism behind getwindow (see graphics(2)).

The RGB values in a color are *premultiplied* by the alpha value; for example, a 50% red is 0x7F00007F not 0xFF00007F. The function *setalpha* performs the alpha computation on a given color, ignoring its initial alpha value, multiplying the components by the supplied alpha. For example, to make a 50% red color value, one could execute setalpha(DRed, 0x7F).

The remaining functions deal with moving groups of pixel values between image and user space or external files. There is a fixed format for the exchange and storage of image data (see *image*(6)).

Unloadimage reads a rectangle of pixels from image *i* into *data*, whose length is specified by *ndata*. It is an error if *ndata* is too small to accommodate the pixels.

Loadimage replaces the specified rectangle in image *i* with the *ndata* bytes of *data*.

The pixels are presented one horizontal line at a time, starting with the top-left pixel of r. In the data processed by these routines, each scan line starts with a new byte in the array, leaving the last byte of the previous line partially empty, if necessary. Pixels are packed as tightly as possible within *data*, regardless of the rectangle being extracted. Bytes are filled from most to least significant bit order, as the x coordinate increases, aligned so x=0 would appear as the leftmost pixel of its byte. Thus, for depth 1, the pixel at x offset 165 within the rectangle will be in a *data* byte at bit-position 0x04 regardless of the overall rectangle: 165 mod 8 equals 5, and 0x80 >> 5 equals 0x04.

Cloadimage does the same as *loadimage*, but for *ndata* bytes of compressed image *data* (see *image*(6)). On each call to *cloadimage*, the *data* must be at the beginning of a compressed data block, in particular, it should start with the y coordinate and data length for the block.

Loadimage, cloadimage, and unloadimage return the number of bytes copied.

Readimage creates an image from data contained in an external file (see *image*(6) for the file format); *fd* is a file descriptor obtained by opening such a file for reading. The returned image is allocated using *allocimage*. The *dolock* flag specifies whether the Display should be synchronized for multithreaded access; single-threaded programs can leave it zero.

Writeimage writes image *i* onto file descriptor *fd*, which should be open for writing. The format is as described for *readimage*.

Readimage and *writeimage* do not close *fd*.

Bytesperline and wordsperline return the number of bytes or words occupied in memory by one scan line of rectangle r in an image with d bits per pixel.

EXAMPLE

To allocate a single-pixel replicated image that may be used to paint a region red,

red = allocimage(display, Rect(0, 0, 1, 1), RGB24, 1, DRed);

SOURCE

/sys/src/libdraw

SEE ALSO

graphics(2), draw(2), draw(3), image(6)

DIAGNOSTICS

These functions return pointer 0 or integer -1 on failure, usually due to insufficient memory.

May set *errstr*.

BUGS

Depth must be a divisor or multiple of 8.

amltag, amlval, amlint, amllen, amlnew, amlinit, amlexit, amlload, amlwalk, amleval, amlenum, amltake, amldrop - ACPI machine language interpreter

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <aml.h>
int
        amltag(void *);
void*
        amlval(void *);
       amlint(void *);
uvlong
        amllen(void *);
int
void*
        amlnew(char tag, int len);
void
        amlinit(void);
void
        amlexit(void);
        amlload(uchar *data, int len);
int
void*
        amlwalk(void *dot, char *name);
        amleval(void *dot, char *fmt, ...);
int
        amlenum(void *dot, char *seg, int (*proc)(void *, void *), void *arg);
void
        amltake(void *);
void
        amldrop(void *);
void
void*
        amlroot;
        amldebug;
int
       amlintmask;
uvlong
```

DESCRIPTION

The aml library implements an interpreter for the ACPI machine language byte code.

amlinit() amlexit()

The interpreter runtime state is initialized by calling *amlinit* and frees all the resources when *amlexit* is called. The runtime state consists of objects organized in a global namespace. The name object referred to by *amlroot* is the root of that namespace.

amlload(data,len)

Amlload populates the namespace with objects parsed from the definition block of *len* byte size read from *data*. The pc kernel provides access to the ACPI tables through the /dev/acpitbls file (see *arch*(3) for further details).

```
amltag(p)
```

Objects are dynamically allocated and typed and are passed as void* pointers. The type tag of an object can be determined with the *amltag* function. The following table shows the defined tags and ther underlying type: /*

/					
*	b	uchar*	buffer	amllen()	returns number of bytes
*	S	char*			is strlen()
*	n	char*	undefined name	amllen()	is strlen()
*	i	uvlong*	integer		
*	р		package	amllen()	is # of elements
*	r	void*	region		
*	f	void*	field		
*	u	void*	bufferfield		
*	Ν	void*	name		
*	R	void*	reference		

*/

amlwalk(dot, name)

Amlwalk takes a path string (relative to *dot*) in *name* and returns the final name object of the walk; or nil if not found.

amlenum(dot, seg, proc, arg)

Amlenum recursively enumerates all child name objects of *dot* that have *seg* as name; or any name if *seg* is nil; calling *proc* for each one passing *dot*. When *proc* returns zero, enumeration will continue recursively down for the current dot.

amlval(p)

Amlval returns the value of a name, reference or field object. Calling *amlval* on any other object yields the same object.

amllen(p)

Amllen is defined for variable length objects like buffers, strings and packages. For strings, the number of characters (not including the terminating null byte) is returned. For buffers, the size of the buffer in bytes is returned. For packages (arrays), the number of elements is returned. For any other object types, the return value is undefined.

amlint(p)

Amlint returns the integer value of an object. For strings, the string is interpreted as an hexadecimal number. For buffers and buffer fields, the binary value is returned. Integers just return their value. Any other object types yield zero.

amlnew(tag,len)

Integer, buffer, string and package objects can be created with the *amlnew* function. The *tag* specific definition of the *len* parameter is the same as in *amllen* (see above).

amleval(dot,fmt,...)

Amleval evaluates the name object *dot*. For method evaluation, the *fmt* string parameter describes the arguments passed to the evaluated method. Each character in *fmt* represents a tag for an method argument taken from the variable argument list of *amleval* and passed to the method. The fmt tags I, i and s take uvlong, int and char* from the variable argument list and create object copies to be passed. The tags b, p and * take void* from the variable argument list and pass them as objects by reference (without conversion or copies). The last variable argument is a pointer to the result object location. When the last parameter is nil the result is discarded.

amltake(p) amldrop(p)

Objects returned by *amlval*, *amleval* and *amlnew* are subject to garbage collection during method evaluation unless previously maked to be excluded from collection with *amltake*. To remark an object for collection, *amldrop* needs be called. Objects stay valid as long as they are reachable from *amlroot*.

The aml library can be linked into userspace programs and the kernel which have different means of hardware access and memory constraints.

The Amlio data structure defines access to a hardware space.

```
enum {
         MemSpace
                           = 0 \times 00,
                           = 0 \times 01,
         IoSpace
         PcicfgSpace
                           = 0 \times 02,
         EbctlSpace
                           = 0 \times 03.
         SmbusSpace
                           = 0x04,
         CmosSpace
                           = 0 \times 05,
         PcibarSpace
                           = 0 \times 06.
         IpmiSpace
                           = 0 \times 07,
};
typedef struct Amlio Amlio;
struct Amlio
{
         int
                  space;
         uvlong off;
        uvlong len;
         void
                  *name;
         uchar
                  *va;
         void
                  *aux;
                  (*read)(Amlio *io, void *data, int len, int off);
         int
                  (*write)(Amlio *io, void *data, int len, int off);
         int
};
```

The members *space*, *off*, *len* and *name* are initialized by the interpreter and describe the I/O region it needs access to. For memory regions, *va* can to be set to the virtual address mapping base by the mapping function. The interpreter will call the *read* and *write* function pointers with a relative offset to the regions base offset. The *aux* pointer can be used freely by the map function to attach its own resources to the I/O region and allows it to free these resources on *amlunmapio*.

amlmapio(io) amlunmapio(io)

The interpreter calls *amImapio* with a *AmIio* data structure that is to be filled out. When finished, the interpreter calls *amIunmapio* with the same data structure to allow freeing resources.

amldelay(µs)

Amldelay is called by the interpreter with the number of microseconds to sleep.

```
amlalloc(n) amlfree(p)
```

Amlalloc and *amlfree* can be optionally defined to control dynamic memory allocation providing a way to limit or pool the memory allocated by acpi. If not provided, the library will use the functions defined in *malloc*(2) for dynamic allocation.

SOURCE

/sys/src/libaml

SEE ALSO

arch(3)

ARGBEGIN, ARGEND, ARGC, ARGF, EARGF - process option letters from argv

SYNOPSIS

```
#include <u.h>
#include <libc.h>
ARGBEGIN {
char *ARGF();
char *EARGF(code);
Rune ARGC();
} ARGEND
```

extern char *argv0;

DESCRIPTION

These macros assume the names *argc* and *argv* are in scope; see *exec*(2). *ARGBEGIN* and *ARGEND* surround code for processing program options. The code should be the cases of a C switch on option characters; it is executed once for each option character. Options end after an argument --, before an argument -, or before an argument that doesn't begin with -.

The function macro ARGC returns the current option character, as an integer.

The function macro ARGF returns the current option argument: a pointer to the rest of the option string if not empty, or the next argument in *argy* if any, or 0. ARGF must be called just once for each option argument. The macro EARGF is like ARGF but instead of returning zero runs code and, if that returns, calls *abort*(2). A typical value for *code* is usage(), as in EARGF(usage()).

After ARGBEGIN, argv0 is a copy of $\arg v[0]$ (conventionally the name of the program).

After ARGEND, argv points at a zero-terminated list of the remaining argc arguments.

EXAMPLE

This C program can take option b and option f, which requires an argument.

```
#include <u.h>
     #include <libc.h>
     void
     main(int argc, char *argv[])
     {
             char *f;
             print("%s", argv[0]);
             ARGBEGIN {
             case 'b':
                      print(" -b");
                      break;
             case 'f':
                      print(" -f(%s)", (f=ARGF())? f: "no arg");
                      break;
             default:
                      print(" badflag('%c')", ARGC());
             } ARGEND
             print(" %d args:", argc);
             while(*argv)
                      print(" '%s'", *argv++);
             print("\n");
             exits(nil);
     }
Here is the output from running the command prog -bffile1 -r -f file2 arg1
```

arg2

prog -b -f(file1) badflag('r') -f(file2) 2 args: 'arg1' 'arg2' SOURCE

```
/sys/include/libc.h
```

SEE ALSO

getflags(8)

add3, sub3, neg3, div3, mul3, eqpt3, closept3, dot3, cross3, len3, dist3, unit3, midpt3, lerp3, reflect3, nearseg3, pldist3, vdiv3, vrem3, pn2f3, ppp2f3, fff2p3, pdiv4, add4, sub4 - operations on 3-d points and planes

SYNOPSIS

#include <draw.h> #include <geometry.h> Point3 add3(Point3 a, Point3 b) Point3 sub3(Point3 a, Point3 b) Point3 neg3(Point3 a) Point3 div3(Point3 a, double b) Point3 mul3(Point3 a, double b) int eqpt3(Point3 p, Point3 q) int closept3(Point3 p, Point3 q, double eps) double dot3(Point3 p, Point3 q) Point3 cross3(Point3 p, Point3 q) double len3(Point3 p) double dist3(Point3 p, Point3 q) Point3 unit3(Point3 p) Point3 midpt3(Point3 p, Point3 q) Point3 lerp3(Point3 p, Point3 q, double alpha) Point3 reflect3(Point3 p, Point3 p0, Point3 p1) Point3 nearseg3(Point3 p0, Point3 p1, Point3 testp) double pldist3(Point3 p, Point3 p0, Point3 p1) double vdiv3(Point3 a, Point3 b) Point3 vrem3(Point3 a, Point3 b) Point3 pn2f3(Point3 p, Point3 n) Point3 ppp2f3(Point3 p0, Point3 p1, Point3 p2) Point3 fff2p3(Point3 f0, Point3 f1, Point3 f2) Point3 pdiv4(Point3 a) Point3 add4(Point3 a, Point3 b) Point3 sub4(Point3 a, Point3 b)

DESCRIPTION

These routines do arithmetic on points and planes in affine or projective 3-space. Type Point3 is

typedef struct Point3 Point3; struct Point3{ double x, y, z, w; };

Routines whose names end in 3 operate on vectors or ordinary points in affine 3-space, represented by their Euclidean (x, y, z) coordinates. (They assume w=1 in their arguments, and set w=1 in their results.)

add3 Add the coordinates of two points.

sub3 Subtract coordinates of two points.

neg3	Negate the coordinates of a point.
mul3	Multiply coordinates by a scalar.
div3	Divide coordinates by a scalar.
eqpt3	Test two points for exact equality.
closept3	Is the distance between two points smaller than <i>eps</i> ?
dot3	Dot product.
cross3	Cross product.
len3	Distance to the origin.
dist3	Distance between two points.
unit3	A unit vector parallel to <i>p</i> .
midpt3	The midpoint of line segment pq.
lerp3	Linear interpolation between <i>p</i> and <i>q</i> .
reflect3	The reflection of point p in the segment joining $p0$ and $p1$.
nearseg3	The closest point to <i>testp</i> on segment <i>p0 p1</i> .
pldist3	The distance from <i>p</i> to segment <i>p0 p1</i> .
vdiv3	Vector divide — the length of the component of a parallel to b , in units of the
	length of <i>b</i> .
vrem3	Vector remainder — the component of a perpendicular to b . Ignoring roundoff, we
	<pre>have eqpt3(add3(mul3(b, vdiv3(a, b)), vrem3(a, b)), a).</pre>

The following routines convert amongst various representations of points and planes. Planes are represented identically to points, by duality; a point p is on a plane q whenever p.x*q.x+p.y*q.y+p.z*q.z+p.w*q.w=0. Although when dealing with affine points we assume p.w=1, we can't make the same assumption for planes. The names of these routines are extra-cryptic. They contain an f (for 'face') to indicate a plane, p for a point and n for a normal vector. The number 2 abbreviates the word 'to.' The number 3 reminds us, as before, that we're dealing with affine points. Thus pn2f3 takes a point and a normal vector and returns the corresponding plane.

Name Description

pn2f3 Compute the plane passing through *p* with normal *n*.

ppp2f3 Compute the plane passing through three points.

fff2p3 Compute the intersection point of three planes.

The names of the following routines end in 4 because they operate on points in projective 4-space, represented by their homogeneous coordinates.

- pdiv4 Perspective division. Divide p.w into p's coordinates, converting to affine coordinates. If p.w is zero, the result is the same as the argument.
- add4 Add the coordinates of two points.
- sub4 Subtract the coordinates of two points.

SOURCE

/sys/src/libgeometry

SEE ALSO

matrix(2)

assert - check program invariants

SYNOPSIS

#include <u.h>

#include <libc.h>

#define assert(cond) if(cond);else _assert("cond")

void _assert(char* cond)

DESCRIPTION

Assert is a preprocessor macro that (via _*assert*) prints a message and calls *abort* when *cond* is false.

SOURCE

/sys/src/libc/port/_assert.c

atof, atoi, atol, atoll, charstod, strtod, strtol, strtoll, strtoul, strtoull - convert text to numbers

```
SYNOPSIS
     #include <u.h>
     #include <libc.h>
     double atof(char *nptr)
     int
            atoi(char *nptr)
     long
            atol(char *nptr)
     vlong atoll(char *nptr)
     double charstod(int (*f)(void *), void *a)
     double strtod(char *nptr, char **rptr)
     long
            strtol(char *nptr, char **rptr, int base)
     vlong strtoll(char *nptr, char **rptr, int base)
           strtoul(char *nptr, char **rptr, int base)
     ulong
     uvlong strtoull(char *nptr, char **rptr, int base)
```

DESCRIPTION

Atof, atoi, atol, and atoll convert a string pointed to by nptr to floating, integer, long integer, and long long integer (vlong) representation respectively. The first unrecognized character ends the string. Leading C escapes are understood, as in *strtol* with *base* zero (described below).

Atof recognizes an optional string of tabs and spaces, then an optional sign, then a string of digits optionally containing a decimal point, then an optional e or E followed by an optionally signed integer.

Atoi and *atol* recognize an optional string of tabs and spaces, then an optional sign, then a string of decimal digits.

Strtod, *strtol*, *strtoll*, *strtoul*, and *strtoull* behave similarly to *atof* and *atol* and, if *rptr* is not zero, set **rptr* to point to the input character immediately after the string converted.

Strtol, strtoll, strtoul, and *strtoull* interpret the digit string in the specified *base*, from 2 to 36, each digit being less than the base. Digits with value over 9 are represented by letters, a-z or A-Z. If *base* is 0, the input is interpreted as an integral constant in the style of C (with no suffixed type indicators): numbers are octal if they begin with 0, hexadecimal if they begin with 0x or 0X, otherwise decimal.

Charstod interprets floating point numbers in the manner of *atof*, but gets successive characters by calling (*f)(a). The last call to *f* terminates the scan, so it must have returned a character that is not a legal continuation of a number. Therefore, it may be necessary to back up the input stream one character after calling *charstod*.

SOURCE

```
/sys/src/libc/port
```

SEE ALSO

fscanf(2)

DIAGNOSTICS

Zero is returned if the beginning of the input string is not interpretable as a number; even in this case, *rptr* will be updated.

amount, newns, addns, login, noworld, procsetuser, auth_proxy, fauth_proxy, auth_allocrpc, auth_freerpc, auth_rpc, auth_getkey, amount_getkey, auth_freeAI, auth_chuid, auth_challenge, auth_response, auth_freechal, auth_respond, auth_respondAI, auth_userpasswd, auth_getuserpasswd, auth_getinfo - routines for authenticating users

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <auth.h>
          newns(char *user, char *nsfile);
int
int
          addns(char *user, char *nsfile);
          amount(int fd, char *old, int flag, char *aname);
int
          login(char *user, char *password, char *namespace);
int
int
          noworld(char *user);
int
          procsetuser(char *user);
AuthInfo* auth_proxy(int fd, AuthGetkey *getkey, char *fmt, ...);
          fauth_proxy(int fd, AuthRpc *rpc, AuthGetkey *getkey,
AuthInfo*
          char *params);
          auth_allocrpc(int afd);
AuthRpc*
void
          auth_freerpc(AuthRpc *rpc);
uint
          auth_rpc(AuthRpc *rpc, char *verb, void *a, int n);
int
          auth_getkey(char *params);
          (*amount_getkey)(char*);
int
void
          auth_freeAI(AuthInfo *ai);
int
             auth_chuid(AuthInfo *ai, char *ns);
Chalstate* auth_challenge(char *fmt, ...);
AuthInfo* auth_response(Chalstate*);
void
          auth_freechal(Chalstate*);
             auth_respond(void *chal, uint nchal, char *user, uint
int
nuser, void *resp, uint nresp, AuthGetkey *getkey, char *fmt, ...);
             auth_respondAI(void *chal, uint nchal, char *user,
int
uint nuser, void *resp, uint nresp, AuthInfo **ai, AuthGetkey *get-
key, char *fmt, ...);
AuthInfo* auth_userpasswd(char*user, char*password);
UserPasswd* auth_getuserpasswd(AuthGetkey
                                               *getkey,
                                                        char*fmt,
```

```
...);
```

AuthInfo* auth_getinfo(AuthRpc*);

DESCRIPTION

This library, in concert with *factotum*(4), is used to authenticate users. It provides the primary interface to *factotum*.

Newns builds a name space for user. It opens the file nsfile (/lib/namespace is used if nsfile is null), copies the old environment, erases the current name space, sets the environment variables user and home, and interprets the commands in nsfile. The format of nsfile is described in namespace(6).

Addns also interprets and executes the commands in *nsfile*. Unlike *newns* it applies the command to the current name space rather than starting from scratch.

Amount is like mount but performs any authentication required. It should be used instead of mount whenever the file server being mounted requires authentication. See *bind*(2) for a definition of the arguments to mount and amount.

Login changes the user id of the process to user and recreates the namespace using the file namespace (default /lib/namespace). It uses auth_userpasswd and auth_chuid.

Noworld returns 1 if the user is in the group noworld in /adm/users. Otherwise, it returns 0. *Noworld* is used by telnetd and ftpd to provide sandboxed access for some users.

Procsetuser changes the user id of the process to *user* but keeps the namespace unchanged. Only hostowner can change the user to anything other than the none user.

The following routines use the AuthInfo structure returned after a successful authentication by *factotum*(4).

```
typedef struct
{
    char *cuid; /* caller id */
    char *suid; /* server id */
    char *cap; /* capability */
    int nsecret; /* length of secret */
    uchar *secret; /* secret */
} AuthInfo;
```

The fields cuid and suid point to the authenticated ids of the client and server. Cap is a capability returned only to the server. It can be passed to the cap(3) device to change the user id of the process. Secret is an nsecret-byte shared secret that can be used by the client and server to create encryption and hashing keys for the rest of the conversation.

Auth_proxy proxies an authentication conversation between a remote server reading and writing fd and a factotum file. The factotum file used is /mnt/factotum/rpc. An sprint (see print(2)) of fmt and the variable arg list yields a key template (see factotum(4)) specifying the key to use. The template must specify at least the protocol (proto=xxx) and the role (either role=client or role=server). Auth_proxy either returns an allocated AuthInfo structure, or sets the error string and returns nil.

Fauth_proxy can be used instead of *auth_proxy* if a single connection to *factotum* will be used for multiple authentications. This is necessary, for example, for *newns* which must open the *factotum* file before wiping out the namespace. *Fauth_proxy* takes as an argument a pointer to an AuthRPC structure which contains an fd for an open connection to *factotum* in addition to storage and state information for the protocol. An AuthRPC structure is obtained by calling *auth_allocrpc* with the fd of an open *factotum* connection. It is freed using *auth_freerpc*. Individual commands can be sent to *factotum*(4) by invoking *auth_rpc*.

Both *auth_proxy* and *fauth_proxy* take a pointer to a routine, *getkey*, to invoke should *factotum* not posess a key for the authentication. If *getkey* is nil, the authentication fails. *Getkey* is called with a key template for the desired key. We have provided a generic routine, *auth_getkey*, which queries the user for the key information and passes it to *factotum*. This is the default for the global variable, *amount_getkey*, which holds a pointer to the key prompting routine used by *amount*.

Auth_chuid uses the cuid and cap fields of an AuthInfo structure to change the user id of the current process and uses *ns*, default /lib/namespace, to build it a new name space.

Auth_challenge and auth_response perform challenge/response protocols with factotum. State between the challenge and response phase are kept in the Chalstate structure:

```
struct Chalstate
{
    char *user;
    char chal[MAXCHLEN];
    int nchal;
    void *resp;
    int nresp;

/* for implementation only */
    int afd;
```

```
AuthRpc *rpc;
char userbuf[MAXNAMELEN];
int userinchal;
};
```

Auth_challenge requires a key template generated by an sprint of *fmt* and the variable arguments. It must contain the protocol (proto=xxx) and depending on the protocol, the user name (user=xxx). P9cr and vnc expect the user specified as an attribute in the key template and apop, cram, and chap expect it in the user field of the arg to *auth_response*. For all protocols, the response is returned to *auth_response* in the *resp* field of the Chalstate. *Chalstate.nresp* must be the length of the response.

Supply to *auth_respond* a challenge string and the fmt and args specifying a key, and it will use *factotum* to return the proper user and response.

Auth_respondAI is like *auth_respond* but has an additional *ai* output parameter to return an *AuthInfo* structure on success that holds protocol specific secret keys derived from the exchange. The returned *AuthInfo* structure should be freed with *auth_freeAI* by the caller.

Auth_userpasswd verifies a simple user/password pair. *Auth_getuserpasswd* retrieves a user/password pair from *factotum* if permitted:

typedef struct UserPasswd {
 char *user;
 char *passwd;
} UserPasswd;

Auth_getinfo reads an AuthInfo message from *rpc* and converts it into a structure. It is only used by the other routines in this library when communicating with *factotum*.

Auth_freeAl is used to free an AuthInfo structure returned by one of these routines. Similary *auth_freechal* frees a challenge/response state.

SOURCE

/sys/src/libauth

SEE ALSO

factotum(4), authsrv(2), bind(2)

DIAGNOSTICS

These routines set errstr.

authdial, passtokey, nvcsum, readnvram, convT2M, convM2T, convTR2M, convM2TR, convA2M, convM2A, convPR2M, convM2PR, _asgetticket, _asrequest, _asgetresp, _asrdresp, _asgetpakkey, authpak_hash, authpak_new, authpak_finish - routines for communicating with authentication servers

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <authsrv.h>
     authdial(char *netroot, char *ad);
int
void passtokey(Authkey *key, char *password)
uchar nvcsum(void *mem, int len)
     readnvram(Nvrsafe *nv, int flag);
int
int
     convT2M(Ticket *t, char *msg, int len, Authkey *key)
int
     convM2T(char *msg, int len, Ticket *t, Authkey *key)
     convA2M(Authenticator *a, char *msg, int len, Ticket *t)
int
     convM2A(char *msg, int len, Authenticator *a, Ticket *t)
int
     convTR2M(Ticketreq *tr, char *msg, int len)
int
     convM2TR(char *msg, int len, Ticketreq *tr)
int
     convPR2M(Passwordreq *pr, char *msg, int len, Ticket *t)
int
int
     convM2PR(char *msg, int len, Passwordreq *pr, Ticket *t)
int
     _asgetticket(int fd, Ticketreq *tr, char *buf, int len)
int
     _asrequest(int fd, Ticketreq *tr)
int
     _asgetresp(int fd, Ticket *t, Authenticator *a, Authkey *key)
int
     _asrdresp(int fd, char *buf, int len)
     _asgetpakkey(int fd, Ticketreq *tr, Authkey *a)
int
void authpak_hash(Authkey *k, char *u)
void authpak_new(PAKpriv *p, Authkey *k, uchar y[PAKYLEN],
                                                                 int
isclient)
     authpak_finish(PAKpriv *p, Authkey *k, uchar y[PAKYLEN])
int
```

int autipak_initsh(iAkpiiv p, Autikey k, uchai

DESCRIPTION

Authdial dials an authentication server over the network rooted at *net*, default /net. The authentication domain, *ad*, specifies which server to call. If *ad* is non-nil, the connection server cs (see *ndb*(8)) is queried for an entry which contains authdom=ad or dom=ad, the former having precedence, and which also contains an auth attribute. If it finds neither, it tries p9auth. *ad* in DNS as the authentication server. The string dialed is then *netroot*!*server*!ticket where *server* is the value of the auth attribute. If no entry is found, the error string is set to "no authentication server found" and -1 is returned. If *authdom* is nil, the string *netroot*!\$auth!*ticket* is used to make the call.

Passtokey converts *password* into a set of cryptographic keys and stores them in the *Authkey* structure *key*.

Readnvram reads authentication information into the structure:

struct Nvrsafe

{

```
char machkey[DESKEYLEN];/* was file server's authid's des key */
uchar machsum;
char authkey[DESKEYLEN];/* authid's des key from password */
uchar authsum;
```

};

```
/*
 * file server config string of device holding full configuration;
 * secstore key on non-file-servers.
*/
        config[CONFIGLEN];
char
uchar
        configsum;
        authid[ANAMELEN];/* auth userid, e.g., bootes */
char
uchar
        authidsum:
        authdom[DOMLEN]; /* auth domain, e.g., cs.bell-labs.com */
char
        authdomsum;
uchar
uchar
        aesmachkev[AESKEYLEN];
uchar
        aesmachsum:
```

On Sparc, MIPS, and SGI machines this information is in non-volatile ram, accessible in the file #r/nvram. On x86s and Alphas *readnvram* successively opens the following areas stopping with the first to succeed:

- the partition named by the \$nvram environment variable (commonly set via plan9.ini(8))

- the partition #S/sdC0/nvram
- a file called plan9.nvr in the partition #S/sdC0/9fat
- the partition #S/sd00/nvram
- a file called plan9.nvr in the partition #S/sd00/9fat
- a file called plan9.nvr on a DOS floppy in drive 0
- a file called plan9.nvr on a DOS floppy in drive 1

The *nvcsums* of the fields machkey, authid, and authdom must match their respective checksum or that field is zeroed. If *flag* is NVwrite or at least one checksum fails and *flag* is NVwriteonerr, *readnvram* will prompt for new values on #c/cons and then write them back to the storage area. If *flag* is NVwritemem, *readnvram* will write the values in **nv* back to the storage area.

ConvT2M, *convA2M*, *convTR2M*, and *convPR2M* convert tickets, authenticators, ticket requests, and password change request structures into transmittable messages. *ConvM2T*, *convM2A*, *convM2TR*, and *convM2PR* are used to convert them back. *Key* is used for encrypting the message before transmission and decrypting after reception. *ConvA2M*, *convM2A*, *convPR2M* and *convM2PR* encrypt/decrypt the message with the random ticket key.

The routine *_asgetticket* sends a ticket request *tr* returning the two encrypted tickets in *buf*. The routine *_asrequest* encodes the ticket request *tr* and sends it not waiting for a response. After sending a request, *_asgetresp* can be used to receive the response containing a ticket and an optional authenticator and decrypts the ticket and authenticator using *key*. The routine *_asrdresp* receives either a character array or an error string. On error, it sets errstr and returns -1. If successful, it returns the number of bytes received.

Authpak_hash prepares a Authkey structure for a password authenticated key exchange (see authsrv(6)) by calculating the pakhash from a user's aeskey and id u. The fuction hashes the password derived aeskey and user id together using hmac_sha256 and maps the result into two elliptic curve points PN/PM on the Ed448-goldielocks curve using elligator2.

Authpak_new generates a new elliptic curve diffie-hellman key pair for a password authenticated key exchange from a previously hashed Authkey structure k. The randomly generated private key is returned in the *PAKpriv* structure passed in p, while the pakhash encrytped public key is returned in y.

Authpak_finish completes a password authenticated key exchange, taking the other sides pakhash encrypted public key y and our private key p returning the shared secret pakkey in the Authkey structure k. The function returns zero on success or non-zero on failure (malformed public key).

The function *_asgetpakkey* establishes a new shared pakkey between the us and the authentication server for ticket encryption; using the functions above; taking a previously hashed *Authkey a* and *Ticketreq tr* and returns the shared pakkey in the *Authkey* structure. It is usually called before *_asrequest* right after *authdial* to negotiate bruteforce resistant ticket encryption for the ticket request that follows (see *authsrv*(6)). Returns zero on success, or non-zero on error

(authenticatoin server does not support the AuthPAK request or when we got a malformed public key).

SOURCE

/sys/src/libauthsrv

SEE ALSO

passwd(1), cons(3), dial(2), authsrv(6),

DIAGNOSTICS

These routines set *errstr*. Integer-valued functions return -1 on error.

avlcreate, avlinsert, avldelete, avllookup, avlnext, avlprev - Balanced binary search tree routines

```
SYNOPSIS
```

```
#include <u.h>
#include <libc.h>
#include <avl.h>
typedef struct Avl Avl;
typedef struct Avltree Avltree;
struct Avl {
        Avl *c[2];
                         /* children */
        Avl *p;
                         /* parent */
                         /* balance factor */
        schar balance;
};
struct Avltree {
        int (*cmp)(Avl*, Avl*);
        Avl *root;
};
Avltree *avlcreate(int(*cmp)(Avl*, Avl*));
        *avlinsert(Avltree *tree, Avl *new);
Avl
        *avldelete(Avltree *tree, Avl *key);
Avl
Avl
        *avllookup(Avltree *tree, Avl *key, int dir);
        *avlmin(Avltree *tree);
Avl
        *avlmax(Avltree *tree);
Avl
Avl
        *avlnext(Avl *n);
        *avlprev(Avl *n);
Avl
```

DESCRIPTION

These routines allow creation and maintenance of in-memory balanced binary search trees.

An empty tree is created by calling *avlcreate* with a comparison function as an argument. The comparison function must take two pointers to Avl structures and return an integer less than, equal to, or greater than 0 as the first is respectively less than, equal to, or greater than the second.

Avlinsert adds a new node into the tree and returns an existing node with the same key that has been removed from the tree and may be freed. Avllookup searches for a given key and returns the closest node less than the given key, equal to, or the closest node greater than the key depending on whether *dir* is less than, equal to, or greater than zero, respectively. If *dir* is zero and there is no matching key, it returns nil. Avldelete removes the node matching the key from the tree and returns it. It returns nil if no matching key is found.

Avlmin returns the minimum Avl node in the tree and avlmax returns the maximum node. Avlnext returns the next Avl node in an in-order walk of the AVL tree and avlprev returns the previous node.

EXAMPLES

Intended usage is to embed the Avl structure anonymously. For example, the following will create a key-value store with strings as keys and integers as values.

```
{
        Node *a, *b;
        a = (Node*)la;
        b = (Node*)lb;
        return strcmp(a->key, b->key);
}
int
get(Avltree *t, char *key)
{
        Node *h, n;
        n.key = key;
        h = (Node*)avllookup(t, &n);
        return h ? h->val : -1;
}
•••
        Avltree *t = avlcreate(nodecmp);
```

SOURCE

/sys/src/libavl

SEE ALSO

Donald Knuth, "The Art of Computer Programming", Volume 3. Section 6.2.3

DIAGNOSTICS Avlcreate returns nil on error.

HISTORY

This implementation was written for 9front (Dec, 2016).

binalloc, bingrow, binfree - grouped memory allocation

SYNOPSIS

DESCRIPTION

These routines provide simple grouped memory allocation and deallocation. Items allocated with *binalloc* are added to the *Bin* pointed to by *bp*. All items in a bin may be freed with one call to *binfree*; there is no way to free a single item.

Binalloc returns a pointer to a new block of at least *size* bytes. The block is suitably aligned for storage of any type of object. No two active pointers from *binalloc* will have the same value. The call binalloc(0) returns a valid pointer rather than null. If *clr* is non-zero, the allocated memory is set to 0; otherwise, the contents are undefined.

Bingrow is used to extend the size of a block of memory returned by *binalloc*. *Bp* must point to the same bin group used to allocate the original block, and *osize* must be the last size used to allocate or grow the block. A pointer to a block of at least *size* bytes is returned, with the same contents in the first *osize* locations. If *clr* is non-zero, the remaining bytes are set to 0, and are undefined otherwise. If *op* is nil, it and *osize* are ignored, and the result is the same as calling *binalloc*.

Binalloc and *bingrow* allocate large chunks of memory using *malloc*(2) and return pieces of these chunks. The chunks are *free*'d upon a call to *binfree*.

SOURCE

/sys/src/libbin

SEE ALSO

malloc(2)

DIAGNOSTICS

binalloc and *bingrow* return 0 if there is no available memory.

bind, mount, unmount - change name space

SYNOPSIS

#include <u.h>

#include <libc.h>

int bind(char *name, char *old, int flag)

int mount(int fd, int afd, char *old, int flag, char *aname)

int unmount(char *name, char *old)

DESCRIPTION

Bind and *mount* modify the file name space of the current process and other processes in its name space group (see *fork*(2)). For both calls, *old* is the name of an existing file or directory in the current name space where the modification is to be made. The name *old* is *evaluated* as described in *intro*(2), except that no translation of the final path element is done.

For *bind*, *name* is the name of another (or possibly the same) existing file or directory in the current name space. After a successful *bind* call, the file name *old* is an alias for the object originally named by *name*; if the modification doesn't hide it, *name* will also still refer to its original file. The evaluation of *new* happens at the time of the *bind*, not when the binding is later used.

The *fd* argument to *mount* is a file descriptor of an open network connection or pipe to a file server, while *afd* is a authentication file descriptor as created by *fauth*(2) and subsequently authenticated. If authentication is not required, *afd* should be -1. The *old* file must be a directory. After a successful *mount* the file tree *served* (see below) by *fd* will be visible with its root directory having name *old*.

The *flag* controls details of the modification made to the name space. In the following, *new* refers to the file as defined by *name* or the root directory served by *fd*. Either both *old* and new files must be directories, or both must not be directories. *Flag* can be one of:

- MREPL Replace the *old* file by the new one. Henceforth, an evaluation of *old* will be translated to the new file. If they are directories (for *mount*, this condition is true by definition), *old* becomes a *union directory* consisting of one directory (the new file).
- MBEFORE Both the *old* and new files must be directories. Add the constituent files of the new directory to the union directory at *old* so its contents appear first in the union. After an MBEFORE *bind* or *mount*, the new directory will be searched first when evaluating file names in the union directory.
- MAFTER Like MBEFORE but the new directory goes at the end of the union.

The flags are defined in <libc.h>. In addition, there is an MCREATE flag that can be OR'd with any of the above. When a *create* system call (see *open*(2)) attempts to create in a union directory, and the file does not exist, the elements of the union are searched in order until one is found with MCREATE set. The file is created in that directory; if that attempt fails, the *create* fails.

Finally, the MCACHE flag, valid for *mount* only, turns on caching for files made available by the mount. By default, file contents are always retrieved from the server. With caching enabled, the kernel may instead use a local cache to satisfy *read*(5) requests for files accessible through this mount point. The currency of cached data for a file is verified at each *open*(5) of the file from this client machine.

With *mount*, the file descriptor fd must be open for reading and writing and prepared to respond to 9P messages (see Section 5). After the *mount*, the file tree starting at *old* is served by a kernel *mnt*(3) device. That device will turn operations in the tree into messages on *fd*. Aname selects among different file trees on the server; the null string chooses the default tree.

The file descriptor *fd* is automatically closed by a successful *mount* call.

The effects of *bind* and *mount* can be undone by *unmount*. If *name* is zero, everything bound to or mounted upon *old* is unbound or unmounted. If *name* is not zero, it is evaluated as described above for *bind*, and the effect of binding or mounting that particular result on *old* is undone.

SOURCE

/sys/src/libc/9syscall

SEE ALSO

bind(1), intro(2), fcall(2), auth(2) (particularly amount), intro(5), mnt(3), srv(3)

DIAGNOSTICS

The return value is a positive integer (a unique sequence number) for success, -1 for failure. These routines set *errstr*.

BUGS

Mount will not return until it has successfully attached to the file server, so the process doing a *mount* cannot be the one serving.

Bopen, Bfdopen, Binit, Binits, Brdline, Brdstr, Bgetc, Bgetrune, Bgetd, Bungetc, Bungetrune, Bread, Bseek, Boffset, Bfildes, Blinelen, Bputc, Bputrune, Bprint, Bvprint, Bwrite, Bflush, Bterm, Bbuffered, Blethal, Biofn – buffered input/output

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <bio.h>
typedef struct BiobufhdrBiobufhdr;
struct Biobufhdr {
            *aux:
                    /* user data */
    void
                /* internals */
    . . .
};
Biobuf* Bopen(char *file, int mode)
Biobuf* Bfdopen(int fd, int mode)
int Binit(Biobuf *bp, int fd, int mode)
int Binits(Biobufhdr *bp, int fd, int mode, uchar *buf, int size)
int Bterm(Biobufhdr *bp)
int Bprint(Biobufhdr *bp, char *format, ...)
int Bvprint(Biobufhdr *bp, char *format, va_list arglist);
void*
        Brdline(Biobufhdr *bp, int delim)
        Brdstr(Biobufhdr *bp, int delim, int nulldelim)
char*
int Blinelen(Biobufhdr *bp)
vlong
        Boffset(Biobufhdr *bp)
int Bfildes(Biobufhdr *bp)
int Bgetc(Biobufhdr *bp)
long
        Bgetrune(Biobufhdr *bp)
int Bgetd(Biobufhdr *bp, double *d)
int Bungetc(Biobufhdr *bp)
int Bungetrune(Biobufhdr *bp)
vlong
        Bseek(Biobufhdr *bp, vlong n, int type)
int Bputc(Biobufhdr *bp, int c)
int Bputrune(Biobufhdr *bp, long c)
        Bread(Biobufhdr *bp, void *addr, long nbytes)
long
        Bwrite(Biobufhdr *bp, void *addr, long nbytes)
long
int Bflush(Biobufhdr *bp)
int Bbuffered(Biobufhdr *bp)
void
        Blethal(Biobufhdr *bp, void (*errorf)(char *))
void
        Biofn(Biobufhdr *bp, int (*iof)(Biobufhdr *, void *, long))
```

DESCRIPTION

These routines implement fast buffered I/O. I/O on different file descriptors is independent.

Bopen opens *file* for mode OREAD or creates for mode OWRITE. It calls *malloc*(2) to allocate a buffer.

Bfdopen allocates a buffer for the already-open file descriptor *fd* for mode OREAD or OWRITE. It calls *malloc*(2) to allocate a buffer.

Binit initializes a standard size buffer, type *Biobuf*, with the open file descriptor passed in by the user. *Binits* initializes a non-standard size buffer, type *Biobufhdr*, with the open file descriptor, buffer area, and buffer size passed in by the user. *Biobuf* and *Biobufhdr* are related by the declaration:

```
typedef struct Biobuf Biobuf;
struct Biobuf
{
    Biobufhdr;
    uchar b[Bungetsize+Bsize];
};
```

Arguments of types pointer to Biobuf and pointer to Biobufhdr can be used interchangeably in the following routines.

Bopen, *Binit*, or *Binits* should be called before any of the other routines on that buffer. *Bfildes* returns the integer file descriptor of the associated open file.

Bterm flushes the buffer for bp and returns Bflush's return value. If the buffer was allocated by Bopen or Bfdopen, the buffer is freed and the file is closed.

Brdline reads a string from the file associated with *bp* up to and including the first *delim* character. The delimiter character at the end of the line is not altered, thus the returned string probably won't be NUL-terminated. *Brdline* returns a pointer to the start of the line or 0 on end-of-file or read error. *Blinelen* returns the length (including the delimiter) of the most recent string returned by *Brdline*.

Brdstr returns a *malloc*(2)-allocated buffer containing the next line of input delimited by *delim*, terminated by a NUL (0) byte. Unlike *Brdline*, which returns when its buffer is full even if no delimiter has been found, *Brdstr* will return an arbitrarily long line in a single call. If *nulldelim* is set, the terminal delimiter will be overwritten with a NUL. After a successful call to *Brdstr*, the return value of *Blinelen* will be the length of the returned buffer, excluding the NUL.

Bgetc returns the next character from *bp*, or a negative value at end of file. *Bungetc* may be called immediately after *Bgetc* to allow the same character to be reread.

Bgetrune calls *Bgetc* to read the bytes of the next UTF sequence in the input stream and returns the value of the rune represented by the sequence. It returns a negative value at end of file. *Bungetrune* may be called immediately after *Bgetrune* to allow the same UTF sequence to be reread as either bytes or a rune. *Bungetc* and *Bungetrune* may back up a maximum of five bytes.

Bgetd uses *charstod* (see *atof*(2)) and *Bgetc* to read the formatted floating-point number in the input stream, skipping initial blanks and tabs. The value is stored in *d.

Bread reads *nbytes* of data from *bp* into memory starting at *addr*. The number of bytes read is returned on success and a negative value is returned if a read error occurred.

Bseek applies seek(2) to bp. It returns the new file offset. Boffset returns the file offset of the next character to be processed.

Bputc outputs the low order 8 bits of *c* on *bp*. If this causes a *write* to occur and there is an error, a negative value is returned. Otherwise, a zero is returned.

Bputrune calls Bputc to output the low order 16 bits of c as a rune in UTF format on the output stream.

Bprint is a buffered interface to *print*(2). If this causes a *write* to occur and there is an error, a negative value (Beof) is returned. Otherwise, *Bprint* returns the number of bytes written. *Bvprint* does the same except it takes as argument a va_list parameter, so it can be called within a variadic function.

Bwrite outputs *nbytes* of data starting at *addr* to *bp*. If this causes a *write* to occur and there is an error, a negative value is returned. Otherwise, the number of bytes written is returned.

Bflush causes any buffered output associated with *bp* to be written. The return is as for *Bputc*. *Bflush* is called on exit for every buffer still open for writing.

Bbuffered returns the number of bytes in the buffer. When reading, this is the number of bytes still available from the last read on the file; when writing, it is the number of bytes ready to be written.

Blethal arranges *errorf* to be called in case of an error happening on read/write. An argument of nil will have the program terminated in case of error.

If *Biofn* is called with a non-nil *iof* function, then that function is called for I/O in lieu of *read*(2) and *write*. A nil argument for *iof* restores normal behaviour.

SOURCE

/sys/src/libbio

SEE ALSO

open(2), read(2), print(2), exits(2), utf(6),

DIAGNOSTICS

Bio routines that return integers yield Beof if *bp* is not the descriptor of an open file. *Bopen* returns zero if the file cannot be opened in the given mode. All routines set *errstr* on error.

An error during read or write will call an error handler specified by *Blethal*, if any.

BUGS

Brdline returns an error on strings longer than the buffer associated with the file and also if the end-of-file is encountered before a delimiter. *Blinelen* will tell how many characters are available in these cases. In the case of a true end-of-file, *Blinelen* will return zero. At the cost of allocating a buffer, *Brdstr* sidesteps these issues.

Only the low byte of *Brdstr*'s *delim* is examined, so *delim* cannot be an arbitrary rune.

The data returned by *Brdline* may be overwritten by calls to any other *bio* routine on the same *bp*.

setupBFstate, bfCBCencrypt, bfCBCdecrypt, bfECBencrypt, bfECBdecrypt - blowfish encryption

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <mp.h>
#include <libsec.h>
void
      setupBFstate(BFstate
                              *s,
                                    uchar
                                            key[],
                                                     int
                                                           keybytes,
                uchar *ivec)
void bfCBCencrypt(uchar *data, int len, BFstate *s)
void bfCBCdecrypt(uchar *data, int len, BFstate *s)
void bfECBencrypt(uchar *data, int len, BFstate *s)
void bfECBdecrypt(uchar *data, int len, BFstate *s)
```

DESCRIPTION

Blowfish is Bruce Schneier's symmetric block cipher. It supports variable length keys from 32 to 448 bits and has a block size of 64 bits. Both CBC and ECB modes are supported.

setupBFstate takes a BFstate structure, a key of at most 56 bytes, the length of the key in bytes, and an initialization vector of 8 bytes (set to all zeroes if argument is nil). The encryption and decryption functions take a BFstate structure, a data buffer, and a length, which must be a multiple of eight bytes as padding is currently unsupported.

SOURCE

/sys/src/libsec

SEE ALSO

mp(2), aes(2), des(2), dsa(2), elgamal(2), rc4(2), rsa(2), sechash(2), prime(2), rand(2)

brk, sbrk - change memory allocation

SYNOPSIS

#include <u.h> #include <libc.h>

int

brk(void *addr)

void* sbrk(ulong incr)

DESCRIPTION

Brk sets the system's idea of the lowest bss location not used by the program (called the break) to *addr* rounded up to the next multiple of 8 bytes. Locations not less than *addr* and below the stack pointer may cause a memory violation if accessed.

In the alternate function *sbrk*, *incr* more bytes are added to the program's data space and a pointer to the start of the new area is returned. Rounding occurs as with brk.

When a program begins execution via exec the break is set at the highest location defined by the program and data storage areas. Ordinarily, therefore, only programs with growing data areas need to use brk. A call to sbrk with a zero argument returns the lowest address in the dynamic segment.

SOURCE

/sys/src/libc/9sys/sbrk.c

SEE ALSO

intro(2), malloc(2), segattach(2), segbrk(2)

DIAGNOSTICS

These functions set errstr.

The error return from *sbrk* is $(void^*)-1$.

cachechars, agefont, loadchar, Subfont, Fontchar, Font - font utilities

SYNOPSIS

DESCRIPTION

A *Font* may contain too many characters to hold in memory simultaneously. The graphics library and draw device (see *draw*(3)) cooperate to solve this problem by maintaining a cache of recently used character images. The details of this cooperation need not be known by most programs: *initdraw* and its associated *font* variable, *openfont*, *stringwidth*, *string*, and *freefont* are sufficient for most purposes. The routines described below are used internally by the graphics library to maintain the font cache.

A Subfont is a set of images for a contiguous range of characters, stored as a single image with the characters placed side-by-side on a common baseline. It is described by the following data structures.

```
typedef
struct Fontchar {
                       /* left edge of bits */
    int
             X;
                       /* first non-zero scan-line */
    uchar
             top;
                       /* last non-zero scan-line */
    uchar
             bottom:
                       /* offset of baseline */
    char
             left:
                       /* width of baseline */
             width:
    uchar
} Fontchar;
typedef
struct Subfont {
    char
             *name:
                       /* number of chars in subfont */
    short
             n;
                       /* height of image */
    uchar
             height:
                       /* top of image to baseline */
    char
             ascent;
                       /* n+1 Fontchars */
    Fontchar *info;
                       /* of font */
    Image
             *bits:
} Subfont:
```

The image fills the rectangle (0, 0, w, height), where w is the sum of the horizontal extents (of non-zero pixels) for all characters. The pixels to be displayed for character c are in the rectangle (i->x, i->top, (i+1)->x, i->bottom) where i is &subfont->info[c]. When a character is displayed at Point p in an image, the character rectangle is placed at (p.x+i->left, p.y) and the next character of the string is displayed at (p.x+i->width, p.y). The baseline of the characters is ascent rows down from the top of the subfont image. The info array has n+1 elements, one each for characters 0 to n-1 plus an additional entry so the size of the last character can be calculated. Thus the width, w, of the Image associated with a Subfont s is s->info[s->n].x.

A Font consists of an overall height and ascent and a collection of subfonts together with the ranges of runes (see utf(6)) they represent. Fonts are described by the following structures.

typedef
struct Cachefont {
 Rune min; /* value of 0th char in subfont */

```
max;
                         /* value+1 of last char in subfont */
    Rune
                         /* posn in subfont of char at min */
    int
              offset:
                         /* stored in font */
    char
              *name:
              *subfontname;/* to access subfont */
    char
} Cachefont;
typedef
struct Cacheinfo {
                         /* left edge of bits */
    ushort
              х;
                         /* width of baseline */
    uchar
              width:
                         /* offset of baseline */
    schar
              left:
    Rune
              value:
                         /* of char at this slot in cache */
    ushort
              age;
} Cacheinfo;
typedef
struct Cachesubf {
                        /* for replacement */
    ulong
              age:
                        /* font info that owns us */
    Cachefont *cf;
                         /* attached subfont */
    Subfont
              *f:
} Cachesubf;
typedef
struct Font {
              *name;
    char
    Display
              *display;
    short
              height;
                         /* max ht of image;interline space*/
                         /* top of image to baseline */
    short
              ascent:
                         /* widest so far; used in caching */
    short
              width;
                         /* number of subfonts */
    short
              nsub:
                         /* increasing counter: for LRU */
    ulong
              age;
                         /* size of cache */
    int
              ncache:
                         /* size of subfont list */
    int
              nsubf;
    Cacheinfo *cache;
    Cachesubf *subf:
                         /* as read from file */
    Cachefont **sub;
    Image
              *cacheimage;
```

} Font;

The height and ascent fields of Font are described in *graphics*(2). Sub contains nsub pointers to Cachefonts. A Cachefont connects runes min through max, inclusive, to the subfont with file name name; it corresponds to a line of the file describing the font.

The characters are taken from the subfont starting at character number offset (usually zero) in the subfont, permitting selection of parts of subfonts. Thus the image for rune r is found in position $r-\min+offset$ of the subfont.

For each font, the library, with support from the graphics server, maintains a cache of subfonts and a cache of recently used character images. The subf and cache fields are used by the library to maintain these caches. The width of a font is the maximum of the horizontal extents of the characters in the cache. String draws a string by loading the cache and emitting a sequence of cache indices to draw. Cachechars guarantees the images for the characters pointed to by *s or *r (one of these must be nil in each call) are in the cache of f. It calls loadchar to put missing characters into the cache. Cachechars translates the character string into a set of cache indices which it loads into the array c, up to a maximum of n indices or the length of the string. Cachechars returns in c the number of cache indices emitted, updates *s to point to the next character to be processed, and sets *widp to the total width of the characters processed. Cachechars may return before the end of the string if it cannot proceed without destroying active data in the caches. If it needs to load a new subfont, it will fill *sfname with the name of the subfont it needs and return -1. It can return zero if it is unable to make progress because it cannot resize the caches.

Loadchar loads a character image into the character cache. Then it tells the graphics server to copy the character into position h in the character cache. If the current font width is smaller than the horizontal extent of the character being loaded, *loadfont* clears the cache and resets it to accept characters with the bigger width, unless *noclr* is set, in which case it just returns -1. If the character does not exist in the font at all, *loadfont* returns 0; if it is unable to load the character without destroying cached information, it returns -1, updating *sfname as described above. It returns 1 to indicate success.

The age fields record when subfonts and characters have been used. The font age is increased every time the font is used (*agefont* does this). A character or subfont age is set to the font age at each use. Thus, characters or subfonts with small ages are the best candidates for replacement when the cache is full.

SOURCE

/sys/src/libdraw

SEE ALSO

graphics(2), allocimage(2), draw(2), subfont(2), image(6), font(6)

DIAGNOSTICS

All of the functions use the graphics error function (see *graphics*(2)).

setupChachastate, chacha_setblock, chacha_setiv, chacha_encrypt, chacha_encrypt2, hchacha, ccpoly_encrypt, ccpoly_decrypt - chacha encryption

SYNOPSIS

#include <u.h>
#include <libc.h>
#include <libsec.h>

void setupChachastate(Chachastate *s, uchar key[], ulong keylen, uchar *iv, ulong ivlen, int rounds)

void chacha_encrypt(uchar *data, ulong len, Chachastate *s)

void chacha_encrypt2(uchar *src, uchar *dst, ulong len, Chachastate *s)

void chacha_setblock(Chachastate *s, u64int blockno)

void chacha_setiv(Chachastate *s, uchar *iv);

void hchacha(uchar h[32], uchar *key, ulong keylen, uchar nonce[16], int rounds);

void ccpoly_encrypt(uchar *dat, ulong ndat, uchar *aad, ulong naad, uchar tag[16], Chachastate *cs);

int ccpoly_decrypt(uchar *dat, ulong ndat, uchar *aad, ulong naad, uchar tag[16], Chachastate *cs);

DESCRIPTION

Chacha is D J Berstein's symmetric stream cipher, as modified by RFC7539. It supports keys of 256 bits (128 bits is supported here for special purposes). It has an underlying block size of 64 bytes (named as constant ChachaBsize).

SetupChachastate takes a reference to a Chachastate structure, a key of keylen bytes, which should normally be ChachaKeylen, a *iv* or nonce of *ivlen* bytes (can be ChachaIVlen=12, 8 or XChachaIVlen=24; set to all zeros if the *iv* argument is nil), and the number of *rounds* (set to the default of 20 if the argument is zero). With a key length of 256 bits (32 bytes), a nonce of 96 bits (12 bytes) and 20 *rounds*, the function implements the Chacha20 encryption function of RFC7539.

Chacha_encrypt encrypts *len* bytes of *buf* in place using the Chachastate in *s*. *Len* can be any byte length. Encryption and decryption are the same operation given the same starting state *s*.

Chacha_encrypt2 is similar, but encrypts len bytes of src into dst without modifying src.

Chacha_setblock sets the Chacha block counter for the next encryption to *blockno*, allowing seeking in an encrypted stream.

Chacha_setiv sets the the initialization vector (nonce) to *iv*.

Hchacha is a key expansion function that takes a 128 or 256-bit key and a 128-bit nonce and produces a new 256-bit key.

Ccpoly_encrypt and *ccpoly_decrypt* implement authenticated encryption with associated data (AEAD) using Chacha cipher and Poly1305 message authentication code as specified in RFC7539. These routines require a *Chachastate* that has been setup with a new (per key unique) initialization vector (nonce) on each invocation. The referenced data *dat[ndat]* is in-place encrypted or decrypted. *Ccpoly_encrypt* produces a 16 byte authentication *tag*, while *ccpoly_decrypt* verifies the *tag*, returning zero on success or negative on a mismatch. The *aad[naad]* arguments refer to the additional authenticated data that is included in the *tag* calculation, but not encrypted.

SOURCE

/sys/src/libsec

SEE ALSO

mp(2), *aes*(2), *blowfish*(2), *des*(2), *dsa*(2), *elgamal*(2), *rc4*(2), *rsa*(2), *salsa*(2), *sechash*(2), *prime*(2), *rand*(2)

chdir - change working directory

SYNOPSIS

#include <u.h>
#include <libc.h>

int chdir(char *dirname)

DESCRIPTION

Chdir changes the working directory of the invoking process to *dirname*. The working directory is the starting point for evaluating file names that do not begin with / or #, as explained in *intro*(2). When Plan 9 boots, the initial process has / for its working directory.

SOURCE

/sys/src/libc/9syscall

SEE ALSO

intro(2), getwd(2)

DIAGNOSTICS

Sets errstr.

cleanname - clean a path name

SYNOPSIS

#include <u.h>
#include <libc.h>

char* cleanname(char *filename)

DESCRIPTION

Cleanname takes a *filename* and by lexical processing only returns the shortest string that names the same (possibly hypothetical) file. It eliminates multiple and trailing slashes, and it lexically interprets . and . . directory components in the name. The string is overwritten in place.

The shortest string *cleanname* can return is two bytes: the null-terminated string ".". Therefore *filename* must contain room for at least two bytes.

SOURCE

/sys/src/libc/port/cleanname.c

SEE ALSO

cleanname(1)

cmap2rgb, cmap2rgba, rgb2cmap - colors and color maps

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <libc.h>
int rgb2cmap(int red, int green, int blue)
int cmap2rgb(int col)
int cmap2rgba(int col)
```

DESCRIPTION

These routines convert between 'true color' red/green/blue triples and the Plan 9 color map. See *color*(6) for a description of RGBV, the standard color map.

Rgb2cmap takes a trio of color values, scaled from 0 (no intensity) to 255 (full intensity), and returns the index of the color in RGBV closest to that represented by those values.

Cmap2rgb decomposes the color of RGBV index *col* and returns a 24-bit integer with the low 8 bits representing the blue value, the next 8 representing green, and the next 8 representing red. *Cmap2rgba* decomposes the color of RGBV index *col* and returns a 32-bit integer with the low 8 bits representing an alpha value, defined to be 255, and the next 8 representing blue, then green, then red, as for *cmap2rgba* shifted up 8 bits. This 32-bit representation is the format used by *draw*(2) and *memdraw*(2) library routines that take colors as arguments.

SOURCE

/sys/src/libdraw

SEE ALSO

graphics(2), allocimage(2), draw(2), image(6), color(6)

complete - file name completion

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <complete.h>
typedef struct CompletionCompletion;
struct Completion{
    uchar advance;
                    /* whether forward progress has been made */
    uchar complete; /* whether the completion now represents a file or directo
                    /* the string to advance, suffixed " " or "/" for file or
    char *string;
                    /* number of files that matched */
    int nmatch;
    int nfile;
                    /* number of files returned */
    char **filename;/* their names */
};
```

Completion* complete(char *dir, char *s);

void freecompletion(Completion *c);

DESCRIPTION

The *complete* function implements file name completion. Given a directory *dir* and a string *s*, it returns an analysis of the file names in that directory that begin with the string *s*. The fields nmatch and nfile will be set to the number of files that match the prefix and filename will be filled in with their names. If the file named is a directory, a slash character will be appended to it.

If no files match the string, nmatch will be zero, but *complete* will return the full set of files in the directory, with *nfile* set to their number.

The flag advance reports whether the string *s* can be extended without changing the set of files that match. If true, string will be set to the extension; that is, the value of string may be appended to *s* by the caller to extend the embryonic file name unambiguously.

The flag complete reports whether the extended file name uniquely identifies a file. If true, string will be suffixed with a blank, or a slash and a blank, depending on whether the resulting file name identifies a plain file or a directory.

The *freecompletion* function frees a Completion structure and its contents.

In *rio*(1) and *acme*(1), file name completion is triggered by a control-F character or an Insert character.

SOURCE

```
/sys/src/libcomplete
```

SEE ALSO

rio(1), *acme*(1)

DIAGNOSTICS

The *complete* function returns a null pointer and sets *errstr* if the directory is unreadable or there is some other error.

BUGS

The behavior of file name completion should be controlled by the plumber.

Control, Controlset, activate, closecontrol, closecontrolset, controlcalled, controlwire, createbox, createboxbox, createbutton, createcolumn, createentry, createkeyboard, createlabel, createmenu, createradiobutton, createrow, createscribble, createslider, createstack, createtab, createtext, createtxbutton, ctlerror, ctlmalloc, ctlrealloc, ctlstrdup, ctlprint, deactivate, freectlfont, freectlimage, initcontrols, namectlfont, namectlimage, newcontrolset, resizecontrolset – interactive graphical controls

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <draw.h>
#include <thread.h>
#include <keyboard.h>
#include <mouse.h>
#include <control.h>
typedef struct Control Control;
typedef struct Controlset Controlset;
struct Control
{
  char
           *name;
  Rectangle rect; /* area on screen */
  Rectangle size; /* min/max Dx, Dy (not a rect) */
  Channel *event; /* chan(char*) to client */
  Channel *data; /* chan(char*) to client */
   . . .
};
struct Controlset
{
   . . .
  Channel
              *ctl;
  Channel
              *data;
   . . .
  int
        clicktotype;
   . . .
};
        initcontrols(void)
void
Controlset*newcontrolset(Image *i, Channel *kc, Channel *mc, Channel *rc)
void
        closecontrolset(Controlset *cs)
        namectlfont(Font *font, char *name)
int
        freectlfont(char *name)
int
int
        namectlimage(Image *image, char *name)
int
        freectlimage(char *name)
Control* createbox(Controlset *cs, char *name)
Control* createboxbox(Controlset *cs, char *name)
Control* createbutton(Controlset *cs, char *name)
Control* createcolumn(Controlset*, char*)
Control* createentry(Controlset *cs, char *name)
Control* createkeyboard(Controlset *cs, char *name)
Control* createlabel(Controlset *cs, char *name)
Control* createmenu(Controlset *cs, char *name)
Control* createradiobutton(Controlset *cs, char *name)
Control* createrow(Controlset*, char*)
```

```
Control*createscribble(Controlset *cs, char *name)
Control* createslider(Controlset *cs, char *name)
Control* createstack(Controlset*, char*)
Control* createtab(Controlset*, char *)
Control* createtext(Controlset *cs, char *name)
Control*createtextbutton(Controlset *cs, char *name)
        closecontrol(Control *c)
void
        ctlprint(Control*, char*, ...);
int
void
        ctlerror(char *fmt, ...)
Control* controlcalled(char *name)
        controlwire(Control *c, char *cname, Channel *ch)
void
void
        activate(Control *c)
void
        deactivate(Control *c)
void
        resizecontrolset(Controlset *cs)
void*
        ctlmalloc(uint n)
void*
        ctlrealloc(void *p, uint n)
char*
        ctlstrdup(char *s)
int
        ctldeletequits;
```

DESCRIPTION

This library provides a set of interactive controls for graphical displays: buttons, sliders, text entry boxes, and so on. It also provides aggregator Controls: boxes, columns, rows and stacks of Controls. A stack is a collection of co-located Controls, of which one is normally visible. A Controlset collects a group of Controls that share mouse and keyboard. Each Controlset has a separate thread of control that processes keyboard and mouse events as well as commands to be passed on to the Controls. Since each Controlset uses a thread, programs using the control library must be linked with the thread library, *thread*(2).

Controls are manipulated by reading and writing to the control channel, ctl, of their Controlset. Channels are defined in *thread*(2). Each Control has two output channels: Event delivers messages about actions within the control (such as a button press) and data delivers (if requested by an appropriate write to ctl) control-specific data such as the contents of a field.

The library provides a simple mechanism for automatic layout: the minimum and maximum sizes of each simple control can be specified. Boxbox, row, column and stack Controls then use these sizes to lay out their constituent Controls when called upon to do so. See the description of these grouping Controls for further details.

Message format

All messages are represented as UTF-8 text. Numbers are formatted in decimal, and strings are transmitted in the quoted form of *quote*(2).

Messages sent to a Controlset are of the form,

```
sender: destination verb [argument ... ]
```

The sender (and the colon following it) may be omitted. For example, the initial field of a text entry control called *entry* could be set by sending the message,

entry value 'Hello, world!'

to its Controlset's ctl file. This message contains the verb value and the single argument Hello, world!

To make it easy to write messages, the function *chanprint* (see *thread*(2)) can be used to print formatted text to a Controlset's channel.

The %q and %Q formats are convenient for properly quoting string arguments, as in

chanprint(e->event, "value %q", "Don't touch!");

It is wise to use %q always instead of %s when sending messages, and avoid dealing with the quoting explicitly. In the other direction, tokenize (see *getfields*(2)) parses these messages and interprets the quotes correctly.

The destination of a message can be a named control, or a set of controls identified by name or type. The command

'entry slider' show

(note the quotation) sends the 'show' command to the entry named *entry* and all controls of type *slider*. If there were a control whose name was *slider* that control would also be shown.

Note that we are still experimenting with destination names. One proposal is that a destination of the form "'name1 name2 ... type1 type2 ...' selects all controls of the named types in the control hierarchies (of columns, rows and stacks) whose names precede the types.

Messages sent by a control on its event channel are of the form

sender: event

The *sender* is the name of the control sending the message; the *event* describes the event. Its format can often be controlled by setting the Control's *format string*. For example, when the user types a newline at a text entry Control named entry, the control sends the message

entry: value 'Hello again!' on its event channel.

Initialization and Control sets

After initdraw (see *graphics*(2)) is called, the function *initcontrols* should be called to initialize the library. It calls *quotefmtinstall* to install the %q and %Q formats; see *quote*(2).

Each control is represented by a Control data structure and is associated with a Controlset that groups a set of controls sharing mouse, keyboard, and display. Most applications will need only one Controlset; only those with multiple windows or unusual configurations will need more than one. The function *newcontrolset* creates a Controlset. Its arguments are the image (usually a window) on which its controls will appear, typically the screen variable in the draw library, and three channels: kc, a channel of Runes from the keyboard; mc, a channel of Mouse structures from the mouse; and rc, a channel of int that indicates when the window has been resized. Any of the channels may be nil, in which case *newcontrolset* will call initkeyboard and/or initmouse (see *keyboard*(2) and *mouse*(2)) to initialize the keyboard and mouse and connect them to the control set. The mouse and resize channels must both be nil or both be non-nil.

The function *closecontrolset* frees all the controls in the control set and tears down all the associated threads. It does not close the mouse and keyboard.

The public elements of a Controlset are the flag clicktotype, and the *ctl* and *data* channels.

Clicktotype is zero by default. If it is set to non-zero, the controls in the set will acquire 'focus' by the click-to-type paradigm. Otherwise, focus is always given to the control under the mouse.

Commands for controls are sent through the Controlset's *ctl* channel. One special command is recognized by the Controlset itself: Sending the string sync to the *ctl* channel causes that string to be echoed to the Controlset's *data* channel when all commands up to the *sync* command have been processed. The string is allocated and must be freed (see *malloc*(2)). Synchronization is necessary between sending a command, for example, to resize all controls, and using their *rect* fields.

The function *resizecontrolset* must be provided by the user. When the associated window is resized, the library will call *resizecontrolset* with the affected Controlset; the function should reconnect to and redraw the window.

If all windows are organized in a hierachy of *boxboxes*, *columns*, *rows* and *stacks*, and minimum and maximum sizes have already been supplied, only the top control needs to be resized (see the *rect* command below).

Fonts and images

Fonts and images must be given names so they may be referenced in messages. The functions *namectlfont* and *namectlimage* associate a (unique) name with the specified font or image. The association is removed by *freectlfont* and *freectlimage*. The font or image is not freed by these

functions, however.

The function *initcontrols* establishes name bindings for all the colors mentioned in <draw.h>, such as black, white, red, yellow, etc., as well as masks transparent and opaque. It also sets the name font to refer to the default font variable set up by initdraw.

Creation

Each type of control has an associated creation function: *createbutton*, *createentry*, etc., whose arguments are the Controlset to attach it to and a globally unique name for it. A control may be destroyed by calling *closecontrol*.

The function *controlcalled* returns a pointer to the Control with the given *name*, or nil if no such control exists.

Configuration

After a control is created, it must be configured using the control-specific commands documented below. Commands are sent to the ctl channel of the Controlset. Multiple commands may be sent in a single message; newline characters separate commands. For an example, see the implementation of *resizecontrolset* in the EXAMPLES section. Note that newline is a separator, not a terminator; the final command does not need a newline.

Messages sent to the *ctl* channel are delivered to all controls that match the *destination* field. This field is a set of names separated by spaces, tabs or newlines. A control matches the destination if its name or its type is among the set.

The recipient of a message ignores the initial *sender*: field of the message, if present, making it possible to send messages generated on an event channel directly to another control's ctl channel.

Activation

When they are created, controls are disabled: they do not respond to user input. Not all controls need to be responsive; for example, labels are static and a text display might show a log of messages but not be useful to edit. But buttons, entry boxes, and other text displays should be active.

To enable a control, call the *activate* function, which specifies that the Control *c* should respond to mouse and keyboard events; *deactivate* turns it off again.

Controls can be either *revealed* (default) or *hidden*. When a control is hidden, it will not receive mouse or keyboard events and state changes or *show* commands will be ignored until the control is once again *revealed*. Control hiding is particularly useful when different controls are overlayed, revealing only the 'top' one.

The function *controlwire* permits rearrangement of the channels associated with a Control. The channel *cname* (one of "data" or "event") of Control *c* is reassigned to the channel *ch*. There are several uses for this operation: one may reassign all the event channels to a single channel, in effect multiplexing all the events onto a single channel; or connect the event channel of a slider to the ctl channel for delivery to a text display (after setting the format for the slider's messages to name the destination control and the appropriate syntax for the rest of the command) to let the slider act as a scroll bar for the text without rerouting the messages explicitly.

Controls

The following sections document the individual controls in alphabetical order. The layout of each section is a brief description of the control's behavior, followed by the messages it sends on event, followed by the messages it accepts via the ctl channel. The event messages are triggered *only* by mouse or keyboard action; messages to the ctl file do not cause events to be generated.

All controls accept the following messages:

rect minx miny maxx maxy

Set the bounding rectangle for the control on the display. The syntax generated by the R print format of the draw library is also acceptable for the coordinates.

size [$min\Delta x min\Delta y max\Delta x max\Delta y$]

Set the minimum and maximum size for automatic layout in *columns*, *rows* and *stacks*. Without its four arguments, this command is ignored by primitive controls and used by grouping controls to calculate their minimum and maximum sizes by examining those of their constituent members. If all primitive controls have been assigned a size, a

single size request addressed to the top of a layout hierarchy will assign sizes to all grouping Controls.

- hide Disable drawing of the control and ignore mouse and keyboard events until the control is once again revealed. Grouping Controls (*column*, *row*, and *stack*) pass the request down to their constituent Controls.
- reveal This is the opposite of hide: the Control is displayed and mouse and keyboard operations resume. Grouping Controls (*column, row,* and *stack*) pass the request down to their constituent Controls. The reveal command for *stacks* takes an optional argument naming the Control to be revealed; all other Controls will be hidden.
- show Display the Control on its screen if not hidden. Some actions will also cause the Controls to show themselves automatically (but never when the control is hidden). Grouping Controls (*column, row,* and *stack*) pass the request down to their constituent Controls.

Many messages are common between multiple Controls. Such messages are described in detail here to avoid repetition. In the individual descriptions, only the syntax is presented.

- align *n* Specify the alignment of (some part of) the Control's display within its rectangle. For textual controls, the alignment specifies where the text should appear. For multiline text, the alignment refers to each line within its box, and only the horizontal part is honored. For other Controls, the alignment affects the appearance of the display in a reasonable way. The valid alignments are words with obvious interpretations: upperleft, uppercenter, upperright, centerleft, center, centerright, lowerleft, lowercenter, and lowerright.
- border *n* Inset the Control (or separate constituent Controls in *boxbox*, *column* and *row* Controls after the next *rect* command) within its rectangle by *n* pixels, default zero.

bordercolor name

Paint the border of the control with the named color, default black.

- focus *n* The Control now has (if *n* is non-zero) or does not have (if *n* is zero) focus. Most Controls ignore the message; there are plans to make them react.
- format *fmt* Set the format of 'value' messages sent on the event channel. By default, the format is "%q: value %q" for string-valued Controls, "%q: value %d" for integer-valued Control s such as buttons, and "%q: value 0x%x" for the keyboard and scribble Controls. The %q prints the name of the Control; the rest the value. Any supplied format string must be type-equivalent to the default for that Control.

image name
light name

Many controls set a background image or color for display. The image message sets the image. The mask and light images together specify how the Control shows it is enabled: the light is printed through the mask when the state is 'on' or 'pressed'. Otherwise, the image appears unmodified. The default image is white; mask opaque; light yellow.

font name

textcolor name

- These commands set the font and color for displaying text. The defaults are the default font set up by the draw library, and black.
- value *v* Set the value of the Control. Textual images accept an arbitrary string; others an integral value.

Box

A box is a trivial control that does nothing more than pass keyboard, mouse, and focus messages back on its event channel. Keyboard characters are sent in the format

boxname: key 0xnn

where *nn* is the hexadecimal value of the character. Mouse messages are sent in the format

boxname: mouse [x y] but msec

where x, y, but, and msec are the various fields of the Mouse structure. The focus message is just

boxname: focus n

where *n* is 0 if the box has lost focus, 1 if it has acquired it.

The box displays within its rectangle an image, under mask, with specified alignment. The control messages it accepts are:

align *a* Controls the placement of the image in the rectangle (unimplemented).

```
border b
bordercolor name
focus n
hide
image name
rect minx miny maxx maxy
reveal
show
size min\Delta x min\Delta y max\Delta x max\Delta y
```

Boxbox

A boxbox allows a set of controls ("boxes") to be displayed in rows and columns within the rectangle of the *boxbox*. The maximum of the minimum heights of the constituent controls determines the number of rows to be displayed. The number of columns is the minimum that allows all Controls to be displayed. This aggregator works well for collections of buttons, labels, or textbuttons that all have a fixed height.

add *name* ... adds the named control to the box of controls. The display order is determined by the order of adding. The first named control is top left, the second goes below it, etc. It is possible to add one control to multiple grouping controls but the layout of the result will be quite unpredictable.

	a of s but the hayout of the result will be quite unpredictable.				
border <i>width</i>					
bordercolor <i>color</i>					
hide	This command is passed on to the member controls.				
image color	Background color displayed between member controls.				
reveal	This command is passed on to the member controls.				
separation width					
	Set the separation between member controls to <i>n</i> pixels.				
rect minx miny maxx maxy					
,	The member controls are layed out within the given rectangle according to the minimum and maximum sizes given. If the rectangle is not large enough for the minimum a fatal error is currently generated. If the controls at their maximum size are not big enough to fit, they are top-left justified at their maximum size in the space given. Otherwise, controls will get their minimum size and be enlarged proportional to the extra size given by the maximum until they fit given rectangle. The members are separated by borders of the width established by <i>borderwidth</i> .				
remove name	Remove the named control from the box.				
show	This command is passed on to the member controls. Show also (re)displays background and borders.				

size $min\Delta x min\Delta y max\Delta x max\Delta y$

Button

A button is a simple control that toggles its state when mouse button 1 is pressed on its rectangle. Each state change triggers an event message:

buttonname: value n

where n encodes the mouse buttons used to make the selection.

The button displays an image (which may of course be a simple color) and illuminates in the standard way when it is 'on'. The control messages it accepts are:

align *a* Controls the placement of the image in the rectangle (unimplemented).

border b bordercolor name focus n format fmt hide image name light name mask name rect minx miny maxx maxy reveal show size min $\Delta x \min \Delta y \max \Delta x \max \Delta y$ value n Set the button to 'on' (if n is non-zero) or 'off' (if n is zero).

Column

A column is a grouping control which lays out its members vertically, from top to bottom. Currently, columns ignore mouse and keyboard events, but there are plans to allow dragging the borders (when they have non-zero width) between constituent members.

add name ...
 adds the named control to the column of controls. The vertical order is determined by the order of adding. The first named control goes at the top. It is possible to add one control to multiple grouping controls but the layout of the result will be quite unpredictable.
 border width
 Set the border between members to the width given.

bordercolor color

hide

image color Background color displayed between member controls.

reveal

separation width

Set the separation between member controls to *n* pixels.

show These three commands are passed on to the member controls. Show also (re)displays the borders between members.

rect minx miny maxx maxy

The member controls are layed out within the given rectangle according to the minimum and maximum sizes given. If the rectangle is not large enough for the minimum a fatal error is currently generated. However, see the example at the end of this man page. If the controls at their maximum size are not big enough to fit, they are centered at their maximum size in the space given. Otherwise, controls will get their minimum size and be enlarged proportional to the extra size given by the maximum until they fit given rectangle. The members are separated by borders of the width established by *borderwidth*.

remove *name* Remove the named control from the column.

size [$min\Delta x min\Delta y max\Delta x max\Delta y$]

Without arguments, this command computes the minimum and maximum size of a column by adding the minimum and maximum heights to set $min\Delta y$ and $max\Delta y$, and it finds the largest minimum and maximum widths to set $min\Delta y$ and $max\Delta y$. When called with arguments, it simply sets the minimum and maximum sizes to those given.

Entry

The entry control manages a single line of editable text. When the user hits a carriage return anywhere in the text, the control generates the event message,

entryname: value s

with *s* the complete text of the entry box.

The cursor can be moved by clicking button 1; at the moment, there is no way to select characters, only a typing position. Some control characters have special actions: control-H (backspace) deletes the character before the cursor; control-U clears the line; and control-V pastes the snarf buffer at the typing position. Most important, carriage return sends the text to the event channel.

To enter passwords and other secret text without displaying the contents, set the font to one in which all characters are the same. The easiest way to do this is to make a font containing only one

character, at position 0 (NUL), since that position is used to render all characters not otherwise defined in the font (see *draw*(2)). The file /lib/font/bit/lucm/passwd.9.font defines such a font.

The control messages the entry control accepts are:

align *a* Controls the placement of the text in the rectangle.

border b

bordercolor name

- data After receiving this message, the entry will send its value to its data channel as an unadorned, unquoted string.
- focus n When it receives focus, the entry box displays a typing cursor. When it does not have focus, the cursor is not displayed.

```
font name
format fmt
hide
image name
rect minx miny maxx maxy
reveal
show
size min\Delta x min\Delta y max\Delta x max\Delta y
textcolor name
value s Set the string displayed in the entry box.
```

Keyboard

The keyboard control implements a simulated keyboard useful on palmtop devices. Keystrokes, generated by mouse button 1 on the simulated keys, are sent as event messages:

keyboardname: value 0xnn

where *nn* is the hexadecimal Unicode value of the character. Shift, control, and caps lock are handled by the keyboard control itself; shift and control affect only the next regular keystroke. The Alt key is unimplemented; it will become equivalent to the standard Plan 9 key for synthesizing non-ASCII characters.

There are two special keys, Scrib and Menu, which return values 0x10000 and 0x10001.

The image, mask, light rules are used to indicate that a key is pressed, but to aid clumsy fingers the keystroke is not generated until the key is released, so it is possible to slide the pointer to a different key to correct for bad aim.

The control messages the keyboard accepts are:

```
border b
bordercolor name
focus n
font namel name?
       Sets the font for the keys. If only one font is named, it is used for all keys. If two are
       named, the second is used for key caps with special names such as Shift and Enter.
       (Good
                       choices
                                         on
                                                      the
                                                                    Bitsv
                                                                                   are
       /lib/font/bit/lucidasans/boldlatin1.6.font
                                                                for
                                                                     the
                                                                            first
                                                                                  and
       /lib/font/bit/lucidasans/unicode.6.font for the second argument.) If
       neither is specified, both will be set to the default global font.
format fmt
hide
image name
light name
mask name
rect minx miny maxx maxy
reveal
show
size minx miny maxx maxy
```

Label

A label is like a textbutton (q.v.) that does not react, but whose value is the text it displays. The

control messages it accepts are:

align a Controls the placement of the image in the rectangle. border b bordercolor name focus n font name hide image *name* rect minx miny maxx maxy reveal show size minx miny maxx maxy textcolor *name* value s The value is a string that can be modified only by sending this message to the ctlfile.

Menu

A menu is a pop-up window containing a set of textual selections. When a selection is made, it removes itself from the screen and reports the selection by value:

menuname: value n

If no selection is made, no message is reported. Because it creates a window, programs using a menu must have their screen variable (see *graphics*(2) and *window*(2)) set up to be refreshed properly. The easiest way to do this is to call getwindow with refresh argument Refbackup (see *graphics*(2)); most programs use Refnone.

The control messages accepted by a menu are:

	The control messages accepted by a menu are.			
	add <i>text</i> align <i>a</i> border <i>b</i>	Add a line of <i>text</i> to the end of the menu. Controls the left-right placement of the text in its rectangle.		
	bordercolor name			
	focus n			
	font <i>name</i>			
	format <i>fmt</i>			
	, hide			
	image name			
	rect minx miny maxx maxy			
	reveal			
	size minx miny maxx maxy			
	Only the origin of the rectangle is significant; menus calculate the appropriate size			
	selectcolor name			
		Set the color in which to highlight selected lines; default yellow.		
	selecttex	tcolor name		
		Set the color in which to draw the text in selected lines; default black.		
	show	Display the menu. Not usually needed unless the menu is changed while visible; use <i>window</i> instead.		
	window			
	window <i>n</i>	With no arguments, toggle the menu's visibility; otherwise make it visible (1) or invisible (0). When the selection is made, the menu will remove its window automatically.		
Rad	liobutton			
	The radiobutt	on assembles a group of buttons or textbuttons into a single control with a numeric		

The radiobutton assembles a group of buttons or textbuttons into a single control with a numeric value. Its value is -1 if none of the constituent buttons is pressed; otherwise it is the index, starting at zero, of the button that is pressed. Only one button may be pressed; the radiobutton manipulates its buttons to guarantee this. State changes trigger an event message:

radiobuttonname: value n

Buttons are added to the radio button using the add message; there is no way to remove them, although they may be turned off independently using *deactivate*. The index reported in the value is defined by the order in which the buttons are added. The constituent buttons should be

configured and layed out in the usual way; the rectangle of the radiobutton is used only to 'catch' mouse events and should almost always correspond to the bounding box of the constituent buttons. In other words, the geometry is not maintained automatically.

The control messages the radiobutton accepts are:

add name Add the control with the specified name to the radiobutton.
focus n
format fmt
hide
rect minx miny maxx maxy
reveal
size minx miny maxx maxy
show
value n

Row

A row groups a number of member controls left to right in a rectangle. Rows behave exactly like columns with the roles of x and y interchanged.

The control messages it accepts are:

add name ... border width bordercolor color hide image color rect minx miny maxx maxy remove name reveal separation width show size [min∆x min∆y max∆x max∆y]

Scribble

The scribble control provides a region in which strokes drawn with mouse button 1 are interpreted as characters in the manner of *scribble*(2). In most respects, including the format of its event messages, it is equivalent to a keyboard control.

The control messages it accepts are:

align a Controls the placement of the image in the rectangle (unimplemented). border b bordercolor name focus n font name Used to display the indicia. hide image name linecolor name The color in which to draw the strokes; default black. rect minx miny maxx maxy reveal size minx miny maxx maxy show

Stack

A stack groups a number of member controls in the same shared rectangle. Only one of these controls will be visible (revealed), the others are hidden.

The control messages it accepts are:

hide
rect minx miny maxx maxy
remove name
reveal [n] Without argument, reveal is the opposite of hide: it makes its selected control visible after it was hidden. With an argument, it makes the n'th added control visible, hiding all others.

show

size [$min\Delta x min\Delta y max\Delta x max\Delta y$]

Without argument, *size* computes the maximum of the minimum and maximum sizes of its constituent controls. With arguments, it sets the size to the given values.

Slider

A slider controls an integer value by dragging the mouse with a button. Configured appropriately, it can serve as a scroll bar with the standard Plan 9 behavior. When the value changes, an event message is sent:

slidername: value n

The slider is a good candidate for connecting to another control by setting its format and rewiring its event channel to the other's ctl channel.

The geometry of the slider is defined by three numbers: max is a number representing the range of the slider; vis is a number representing how much of what is being controlled is visible; and value is a number representing the value of the slider within its range. For example, if the slider is managing a textual display of 1000 lines, with 18 visible, and the first visible line (numbered starting form 0) is 304, max will be 1000, vis will be 18, and value will be 304. The *indicator* is the visual representation of the *vis* portion of the controlled object.

The control messages the slider accepts are:

	absolute n	If n is zero, the slider behaves like a Plan 9 scroll bar: button 2 sets absolute position, button 1 decreases the value, and button 3 increases it. If n is non-zero, all buttons behave like button 2, setting the absolute value.			
	bordercolor	name			
		The <i>end</i> is either the word high or low; <i>n</i> sets whether that end is clamped or not. If it is clamped, that end of the indicator is always at its supremum. A standard scroll bar has neither end clamped; a volume slider would have its low end clamped. If the low end is clamped, the value of the slider is represented by the high end of the indicator; otherwise it is represented by the low end.			
	focus n				
	format <i>fmt</i>				
	hide				
	image <i>name</i>				
		ndicatorcolor name			
		Set the color in which to draw the indicator; default black.			
	max n	Set the maximum value of the range covered by the slider.			
	orient <i>dir</i>	The string <i>dir</i> begins either hor or ver to specify the orientation of the slider. The default is vertical. The value always increases to the right for horizontal sliders and downwards for vertical sliders.			
	rect minx miny	тахх таху			
	reveal				
	size minx miny	тахх таху			
	show				
	value n				
	vis n	Set the visible area shown by the indicator.			
Tak					

A tab control combines radiobottuns with a stack of windows giving the appearance of tabbed controls. Currently, the tabs are positioned at the top of the stack. The radiobutton consists of textbuttons, the stack can be composed of any type of control.

Control messages are

add button control button control ...

Adds a button to the radiobutton, and an associated control to the stack. Buttons and controls are numbered in the order of addition. There is no remove operation.

border b

bordercolor	color
focus n	
format <i>fmt</i>	When a format string is defined, the tab control reports which tab is selected using the format string (which must print a $char^*$ and an int).
image <i>color</i>	Color between member controls.
separation n	Spacing between buttons in the radiobutton and between the row of buttons and the stack below it.
rect nnnn hide reveal size nnnn show	
value <i>n</i>	Value must be an integer indicating which tab to bring to the top.

Text

A text control presents a set of lines of text. The text cannot be edited with the keyboard, but can be changed by control messages. (A more interactive text control will be created eventually.) The mouse can be used to select lines of text. The only event message reports a state change in the selection of a line:

textname: select ns

states that line n has changed its selection state to s, either zero (unselected) or non-zero (selected). The non-zero value encodes the mouse buttons that were down when the selection occurred.

The control messages the text control accepts are:

accumulate s accumulate n s add s				
add n s	With one argument, append the string s as a new last line of the control; if n is specified, add the line <i>before</i> the current line n , making the new line number n . The lines are zero indexed and n can be no greater than the current number of lines. <i>Add</i> refreshes the display, but <i>accumulate</i> does not, to avoid n-squared behavior when assembling a piece of text.			
align <i>a</i>	Controls the placement of each line of text left-to-right in its rectangle. Ver- tically, lines are tightly packed with separation set by the font's interline spacing.			
border b				
bordercolor nan				
clear	Delete all text.			
delete n	Delete line <i>n</i> .			
focus n				
font name				
image <i>name</i>				
rect minx miny ma				
replace <i>ns</i> reveal	Replace line <i>n</i> by the string <i>s</i> .			
scroll n	If <i>n</i> is non-zero, the text will automatically scroll so the last line is always visible when new text is added.			
select n m	Set the selection state of line <i>n</i> to <i>m</i> .			
selectcolor name				
	Set the color in which to highlight selected lines; default yellow.			
selectmode s	The string <i>s</i> is either single or multi. If single, the default, only one line may be selected at a time; when a line is selected, other lines are unselected. If multi, the selection state of individual lines can be toggled independently.			
size minx miny ma show textcolor name	xx maxy			
LEXICOTOT. Name				

topline <i>n</i>	Scroll the text so the top visible line is number <i>n</i> .
value s	Delete all the text in the control and then add the single line <i>s</i> .

Textbutton

A textbutton is a textual variant of a plain button. Each state change triggers an event message:

textbuttonname: value n

where *n* encodes the mouse buttons used to make the selection.

Like a regular button, the value of a textbutton is an integer; the *text* is the string that appears in the button. It uses the image, light, mask method of indicating its state; moreover, the color of the text can be set to change when the button is pressed. The control messages it accepts are:

align a Controls the placement of the text in the rectangle. border b bordercolor name focus n font *name* format *fmt* hide image *name* light name mask name pressedtextcolor *name* Set the color in which to display text when the textbutton is pressed. rect minx miny maxx maxy reveal size minx miny maxx maxy show

text *s* Set the text displayed in the button.

textcolor name

value *n* Set the button to 'on' (if *n* is non-zero) or 'off' (if *n* is zero).

Helper functions

The function *ctlerror* is called when the library encounters an error. It prints the formatted message and exits the program.

The functions *ctImalloc*, *ctIrealloc*, *ctIstrdup*, and *ctIrunestrdup* are packagings of the corresponding C library functions. They call *ctIerror* if they fail to allocate memory, and *ctImalloc* zeros the memory it returns.

Finally, for debugging, if the global variable *ctldeletequits* is set to a non-zero value, typing a DEL will cause the program to call

ctlerror("delete");

Caveat

This library is very new and is still missing a number of important features. The details are all subject to change. Another level of library that handles geometry and has sensible default appearances for the controls would be useful.

One unusual design goal of this library was to make the controls themselves easy to implement. The reader is encouraged to create new controls by adapting the source to existing ones.

EXAMPLES

This example creates two entry boxes, top and bot, and copies the contents of one to the other whenever a newline is typed.

#include <u.h>
#include <libc.h>
#include <libc.h>
#include <thread.h>
#include <draw.h>
#include <mouse.h>
#include <keyboard.h>
#include <control.h>
Controlset *cs;

```
int ctldeletequits = 1;
void
resizecontrolset(Controlset*)
{
   int i;
   Rectangle r, r1, r2;
   if(getwindow(display, Refnone) < 0)</pre>
      sysfatal("resize failed: %r");
   r = insetrect(screen->r, 10);
   r1 = r;
   r2 = r;
   r1.max.y = r1.min.y+1+font->height+1;
   r2.min.y = r1.max.y+10;
   r2.max.y = r2.min.y+1+font->height+1;
   chanprint(cs->ctl, "top rect %R\ntop show", r1);
chanprint(cs->ctl, "bot rect %R\nbot show", r2);
}
void
threadmain(int argc, char *argv[])
{
   char *s, *args[3];
   Channel *c;
   Control *top, *bot;
   int n;
   initdraw(0, 0, "example");
   initcontrols();
   cs = newcontrolset(screen, nil, nil, nil);
   cs->clicktotype = 1;
   top = createentry(cs, "top");
   chanprint(cs->ctl, "top image paleyellow");
chanprint(cs->ctl, "top border 1");
   bot = createentry(cs, "bot");
   chanprint(cs->ctl, "bot image paleyellow");
chanprint(cs->ctl, "bot border 1");
   c = chancreate(sizeof(char*), 0);
   controlwire(top, "event", c);
controlwire(bot, "event", c);
   activate(top);
   activate(bot);
   resizecontrolset(cs);
   for(;;){
      s = recvp(c);
      n = tokenize(s, args, nelem(args));
      if(n==3 && strcmp(args[1], "value")==0){
         if(strcmp(args[0], "top:") == 0)
             chanprint(cs->ctl, "bot value %q", args[2]);
         else
             chanprint(cs->ctl, "top value %q", args[2]);
      }
   }
   threadexitsall(nil);
}
```

A richer variant couples a text entry box to a slider. Since the value of a slider is its numerical setting, as a decimal number, all that needs changing is the setup of bot:

```
bot = createslider(cs, "bot");
chanprint(cs->ctl, "bot border 1");
chanprint(cs->ctl, "bot image paleyellow");
chanprint(cs->ctl, "bot indicatorcolor red");
chanprint(cs->ctl, "bot max 100");
chanprint(cs->ctl, "bot clamp low 1");
chanprint(cs->ctl, "bot orient horizontal");
```

The rest is the same. Of course, the value of the entry box is only meaningful to the slider if it is also a decimal number.

Finally, we can avoid processing events altogether by cross-coupling the controls. Replace the rest of threadmain with this:

```
chanprint(cs->ctl, "bot format %q", "%q: top value %q");
chanprint(cs->ctl, "top format %q", "%q: bot value %q");
controlwire(top, "event", cs->ctl);
controlwire(bot, "event", cs->ctl);
activate(top);
activate(bot);
resizecontrolset(cs);
for(;;)
    yield();
threadexitsall(nil);
```

SOURCE

/sys/src/libcontrol

SEE ALSO

draw(2), frame(2), graphics(2), quote(2), thread(2)

BUGS

The library is strict about matters of formatting, argument count in messages, etc., and calls *ctlerror* in situations where it may be fine to ignore the error and continue.

cputime, times, cycles - cpu time in this process and children

SYNOPSIS

#include <u.h>

```
#include <libc.h>
```

long times(long t[4])

double cputime(void)

void cycles(uvlong *cyclep)

DESCRIPTION

If t is non-null, times fills it in with the number of milliseconds spent in user code, system calls, child processes in user code, and child processes in system calls. *Cputime* returns the sum of those same times, converted to seconds. *Times* returns the elapsed real time, in milliseconds, that the process has been running.

These functions read /dev/cputime, opening that file when they are first called.

Cycles reads the processor's timestamp counter of cycles since reset, if any, and stores it via *cyclep*. Currently supported architectures are 386, amd64, and power; on all others, *cycles* will store zero.

SOURCE

```
/sys/src/libc/9sys
/sys/src/libc/*/cycles.[cs]
```

SEE ALSO

exec(2), cons(3)

BUGS

Only 386 processors starting with the Pentium have timestamp counters; calling *cycles* on earlier processors may execute an illegal instruction.

ctime, localtime, gmtime, asctime, tm2sec, timezone - convert date and time

SYNOPSIS

```
#include <u.h>
#include <libc.h>
char* ctime(long clock)
Tm* localtime(long clock)
Tm* gmtime(long clock)
char* asctime(Tm *tm)
long tm2sec(Tm *tm)
/env/timezone
```

DESCRIPTION

Ctime converts a time *clock* such as returned by *time*(2) into ASCII (sic) and returns a pointer to a 30-byte string in the following form. All the fields have constant width.

Wed Aug 5 01:07:47 EST 1973\n\0

Localtime and *gmtime* return pointers to structures containing the broken-down time. *Localtime* corrects for the time zone and possible daylight savings time; *gmtime* converts directly to GMT. *Asctime* converts a broken-down time to ASCII and returns a pointer to a 30-byte string.

typedef struct {		/ **	
	sec;		seconds (range 059) */
int	min;	/*	minutes (059) */
int	hour;	/*	hours (023) */
int	mday;	/*	day of the month $(131) */$
int	mon;	/*	month of the year (011) $*/$
int	year;	/*	year A.D 1900 */
int	wday;	/*	day of week (06, Sunday = 0) $*/$
int	yday;	/*	day of year (0365) */
char	zone[4];	/*	time zone name */
int	tzoff;	/*	time zone delta from GMT */
} Tm;			

Tm2sec converts a broken-down time to seconds since the start of the epoch. It ignores wday, and assumes the local time zone if zone is not GMT.

When local time is first requested, the program consults the timezone environment variable to determine the time zone and converts accordingly. (This variable is set at system boot time by *init*(8).) The timezone variable contains the normal time zone name and its difference from GMT in seconds followed by an alternate (daylight) time zone name and its difference followed by a newline. The remainder is a list of pairs of times (seconds past the start of 1970, in the first time zone) when the alternate time zone applies. For example:

```
EST -18000 EDT -14400
9943200 25664400 41392800 57718800 ...
```

Greenwich Mean Time is represented by

GMT 0 GMT 0

SOURCE

/sys/src/libc/9sys

SEE ALSO

date(1), time(2), tmdate(2), init(8)

BUGS

The return values point to static data whose content is overwritten by each call.

Daylight Savings Time is "normal" in the Southern hemisphere. These routines are not equipped to handle non-ASCII text, and are provincial anyway. These routines may garble the date when passed a date parsed with *tmparse*(2).

isalpha, isupper, islower, isdigit, isxdigit, isalnum, isspace, ispunct, isprint, isgraph, iscntrl, isascii, toascii, _toupper, _tolower, toupper, tolower - ASCII character classification

SYNOPSIS

<pre>#include <u.h> #include <libc.h> #include <ctype.h></ctype.h></libc.h></u.h></pre>	
isalpha(c)	isgraph(c)
<pre>isupper(c)</pre>	<pre>iscntrl(c)</pre>
islower(c)	isascii(c)
isdigit(c)	_toupper(c)
isxdigit(c)	_tolower(c)
isalnum(c)	<pre>toupper(c)</pre>
isspace(c)	<pre>tolower(c)</pre>
ispunct(c)	toascii(c)
<pre>isprint(c)</pre>	

DESCRIPTION

These macros classify ASCII-coded integer values by table lookup. Each is a predicate returning nonzero for true, zero for false. *Isascii* is defined on all integer values; the rest are defined only where *isascii* is true and on the single non-ASCII value EOF; see *fopen*(2).

isalpha c is a letter, a-z or A-Z

isupper c is an upper case letter, A-Z

islower c is a lower case letter, a-z

isdigit c is a digit, 0-9

isxdigit c is a hexadecimal digit, 0-9 or a-f or A-F

isalnum c is an alphanumeric character, a-z or A-Z or 0-9

isspace c is a space, horizontal tab, newline, vertical tab, formfeed, or carriage return (0x20, 0x9, 0xA, 0xB, 0xC, 0xD)

ispunct c is a punctuation character (one of ! "#%&'()*+,-./:;<=>?@[\]^_'{{|}~)

isprint c is a printing character, 0x20 (space) through 0x7E (tilde)

isgraph c is a visible printing character, 0x21 (exclamation) through 0x7E (tilde)

iscntrl c is a delete character, 0x7F, or ordinary control character, 0x0 through 0x1F

isascii c is an ASCII character, 0x0 through 0x7F

Toascii is not a classification macro; it converts its argument to ASCII range by anding with 0x7F.

If *c* is an upper case letter, *tolower* returns the lower case version of the character; otherwise it returns the original character. *Toupper* is similar, returning the upper case version of a character or the original character. *Tolower* and *toupper* are functions; *_tolower* and *_toupper* are corresponding macros which should only be used when it is known that the argument is upper case or lower case, respectively.

SOURCE

```
/sys/include/ctype.h for the macros.
/sys/src/libc/port/ctype.c for the tables.
```

SEE ALSO

isalpharune(2)

BUGS

These macros are ASCII-centric.

cisctrace, risctrace, ciscframe, riscframe, localaddr, symoff, fpformat, beieee80ftos, beieeesftos, beieeedftos, leieee80ftos, leieeesftos, ieeesftos, ieeesftos, ieeedftos - machine-independent debugger functions

SYNOPSIS

#include <u.h> #include <libc.h> #include <bio.h> #include <mach.h> int cisctrace(Map *map, uvlong pc, uvlong sp, uvlong link, Tracer trace) int risctrace(Map *map, uvlong pc, uvlong sp, uvlong link, Tracer trace) uvlong ciscframe(Map *map, uvlong addr, uvlong pc, uvlong sp, uvlong link) uvlong riscframe(Map *map, uvlong addr, uvlong pc, uvlong sp, uvlong link) int localaddr(Map *map, char *fn, char *var, uvlong *ret, Rgetter rget) int symoff(char *buf, int n, uvlong addr, int type) int fpformat(Map *map, Reglist *rp, char *buf, int n, int code) int beieee80ftos(char *buf, int n, void *fp) int beieeesftos(char *buf, int n, void *fp) int beieeedftos(char *buf, int n, void *fp) int leieee80ftos(char *buf, int n, void *fp) int leieeesftos(char *buf, int n, void *fp) int leieeedftos(char *buf, int n, void *fp) int ieeesftos(char *buf, int n, ulong f) int ieeedftos(char *buf, int n, ulong high, ulong low) extern Machdata *machdata:

DESCRIPTION

These functions provide machine-independent implementations of common debugger functions. Many of the functions assume that global variables *mach* and *machdata* point to the *Mach* and *Machdata* data structures describing the target architecture. The former contains machine parameters and a description of the register set; it is usually set by invoking *crackhdr* (see *mach*(2)) to interpret the header of an executable. The *Machdata* structure is primarily a jump table specifying functions appropriate for processing an executable image for a given architecture. Each application is responsible for setting *machdata* to the address of the *Machdata* structure for the target architecture. Many of the functions described here are not called directly; instead, they are invoked indirectly through the *Machdata* jump table.

These functions must retrieve data and register contents from an executing image. The *Map* (see mach(2)) data structure supports the consistent retrieval of data, but no uniform access mechanism exists for registers. The application passes the address of a register retrieval function as an argument to those functions requiring register values. This function, called an *Rgetter*, is of the form

ulong rget(Map *map, char *name);

It returns the contents of a register when given the address of a *Map* associated with an executing image and the name of the register.

Cisctrace and *risctrace* unwind the stack for up to 40 levels or until the frame for *main* is found. They return the count of the number of levels unwound. These functions process stacks conforming to the generic compiler model for RISC and CISC architectures, respectively. *Map* is the address of a *Map* data structure associated with the image of an executing process. *Sp*, *pc* and *link* are starting values for the stack pointer, program counter, and link register from which the unwinding is to take place. Normally, they are the current contents of the appropriate registers but they can be any values defining a legitimate process context, for example, an alternate stack in a multi-threaded process. *Trace* is the address of an application-supplied function to be called on each iteration as the frame unwinds. The prototype of this function is:

void tracer(Map *map, ulong pc, ulong fp, Symbol *s);

where *Map* is the *Map* pointer passed to *cisctrace* or *risctrace* and *pc* and *fp* are the program counter and frame pointer. S is the address of a *Symbol* structure, as defined in *symbol*(2), containing the symbol table information for the function owning the frame (i.e., the function that caused the frame to be instantiated).

Ciscframe and *riscframe* calculate the frame pointer associated with a function. They are suitable for programs conforming to the CISC and RISC stack models. *Map* is the address of a *Map* associated with the memory image of an executing process. *Addr* is the entry point of the desired function. *Pc*, *sp* and *link* are the program counter, stack pointer and link register of an execution context. As with the stack trace functions, these can be the current values of the registers or any legitimate execution context. The value of the frame pointer is returned. A return value of zero indicates an error.

Localaddr fills the location pointed to by *ret* with the address of a local variable. *Map* is the address of a *Map* associated with an executing memory image. *Fn* and *var* are pointers to the names of the function and variable of interest. *Rget* is the address of a register retrieval function. If both *fn* and *var* are non-zero, the frame for function *fn* is calculated and the address of the automatic or argument named *var* in that frame is returned. If *var* is zero, the address of the frame for function *n* is returned. In all cases, the frame for the function named *fn* must be instantiated somewhere on the current stack. If there are multiple frames for the function (that is, if it is recursive), the most recent frame is used. The search starts from the context defined by the current value of the program counter and stack pointer. If a valid address is found, *localaddr* returns 1. A negative return indicates an error in resolving the address.

Symoff converts a virtual address to a symbolic reference. The string containing that reference is of the form 'name+offset', where 'name' is the name of the nearest symbol with an address less than or equal to the target address and 'offset' is the hexadecimal offset beyond that symbol. If 'offset' is zero, only the name of the symbol is printed. If no symbol is found within 4,096 bytes of the address, the address is formatted as a hexadecimal address. *Buf* is the address of a buffer of *n* characters to receive the formatted string. *Addr* is the address to be converted. *Type* is the type code of the search space: CTEXT, CDATA, or CANY. *Symoff* returns the length of the formatted string contained in *buf*.

Fpformat converts the contents of a floating point register to a string. *Map* is the address of a *Map* associated with an executing process. *Rp* is the address of a *Reglist* data structure describing the desired register. *Buf* is the address of a buffer of *n* characters to hold the resulting string. *Code* must be either F or f, selecting double or single precision, respectively. If *code* is F, the contents of the specified register and the following register are interpreted as a double precision floating point number; this is only meaningful for architectures that implement double precision floats by combining adjacent single precision registers. For *code* f, the specified register is formatted as a single precision float. *Fpformat* returns 1 if the number is successfully converted or -1 in the case of an error.

Beieee80ftos, beieeesftos and beieeedftos convert big-endian 80-bit extended, 32-bit single precision, and 64-bit double precision floating point values to a string. Leieee80ftos, leieeesftos, and leieeedftos are the little-endian counterparts. Buf is the address of a buffer of n characters to receive the formatted string. Fp is the address of the floating point value to be converted. These functions return the length of the resulting string.

leeesftos converts the 32-bit single precision floating point value f, to a string in *buf*, a buffer of n bytes. It returns the length of the resulting string.

leeedftos converts a 64-bit double precision floating point value to a character string. *Buf* is the address of a buffer of *n* characters to hold the resulting string. *High* and *low* contain the most and least significant 32 bits of the floating point value, respectively. *leeedftos* returns the number of characters in the resulting string.

SOURCE

/sys/src/libmach

SEE ALSO

mach(2), symbol(2), errstr(2)

DIAGNOSTICS

Set errstr.

setupDESstate, des_key_setup, block_cipher, desCBCencrypt, desCBCdecrypt, desECBencrypt, desECBdecrypt, des3CBCencrypt, des3CBCdecrypt, des3ECBencrypt, des3ECBdecrypt, key_setup, des56to64, des64to56, setupDES3state, triple_block_cipher - single and triple digital encryption standard

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <mp.h>
#include <libsec.h>
void des_key_setup(uchar key[8], ulong schedule[32])
void block_cipher(ulong *schedule, uchar *data, int decrypting)
void setupDESstate(DESstate *s, uchar key[8], uchar *ivec)
void desCBCencrypt(uchar *p, int len, DESstate *s)
void desCBCdecrypt(uchar *p, int len, DESstate *s)
void desECBencrypt(uchar *p, int len, DESstate *s)
void desECBdecrypt(uchar *p, int len, DESstate *s)
void triple_block_cipher(ulong expanded_key[3][32], uchar text[8],
     int ende)
void setupDES3state(DES3state *s, uchar key[3][8], uchar *ivec)
void des3CBCencrypt(uchar *p, int len, DES3state *s)
void des3CBCdecrypt(uchar *p, int len, DES3state *s)
void des3ECBencrypt(uchar *p, int len, DES3state *s)
void des3ECBdecrypt(uchar *p, int len, DES3state *s)
void key_setup(uchar[7], ulong[32])
void des56to64(uchar *k56, uchar *k64)
void des64to56(uchar *k64, uchar *k56)
```

DESCRIPTION

The Digital Encryption Standard (DES) is a shared-key or symmetric encryption algorithm using either a 56-bit key for single DES or three 56-bit keys for triple DES. The keys are encoded into 64 bits where every eight bit is parity.

The basic DES function, *block_cipher*, works on a block of 8 bytes, converting them in place. It takes a key schedule, a pointer to the block, and a flag indicating encrypting (0) or decrypting (1). The key schedule is created from the key using *des_key_setup*.

Since it is a bit awkward, *block_cipher* is rarely called directly. Instead, one normally uses routines that encrypt larger buffers of data and which may chain the encryption state from one buffer to the next. These routines keep track of the state of the encryption using a DESstate structure that contains the key schedule and any chained state. *SetupDESstate* sets up the DESstate structure using the key and an 8-byte initialization vector.

Electronic code book, using *desECBencrypt* and *desECBdecrypt*, is the less secure mode. The encryption of each 8 bytes does not depend on the encryption of any other. Hence the encryption is a substitution cipher using 64 bit characters.

Cipher block chaining mode, using *desCBCencrypt* and *desCBCdecrypt*, is more secure. Every block encrypted depends on the initialization vector and all blocks encrypted before it.

For both CBC and ECB modes, a stream of data can be encrypted as multiple buffers. However, all buffers except the last must be a multiple of 8 bytes to ensure successful decryption of the stream.

There are equivalent triple-DES (DES3-EDE) functions for each of the DES functions.

In the past, Plan 9 used a 56-bit or 7-byte format for DES keys. To be compatible with the rest of the world, we've abandoned this format. There are two functions, *des56to64* and *des64to56*, to convert back and forth between the two formats. Also a key schedule can be set up from the 7-byte format using *key_setup*.

SOURCE

/sys/src/libsec

SEE ALSO

mp(2), *aes*(2), *blowfish*(2), *dsa*(2), *elgamal*(2), *rc4*(2), *rsa*(2), *sechash*(2), *prime*(2), *rand*(2) *Breaking DES*, Electronic Frontier Foundation, O'Reilly, 1998

BUGS

Single DES can be realistically broken by brute-force; its 56-bit key is just too short. It should not be used in new code, which should probably use *aes*(2) instead, or at least triple DES.

dial, hangup, announce, listen, accept, reject, netmkaddr, setnetmtpt, getnetconninfo, freenetconninfo - make and break network connections

SYNOPSIS

```
#include <u.h>
#include <libc.h>
int
      dial(char *addr, char *local, char *dir, int *cfdp)
int
      hangup(int ctl)
      announce(char *addr, char *dir)
int
      listen(char *dir, char *newdir)
int
      accept(int ctl, char *dir)
int
      reject(int ctl, char *dir, char *cause)
int
char* netmkaddr(char *addr, char *defnet, char *defservice)
      setnetmtpt(char *to, int tolen, char *from)
void
NetConnInfo*
              getnetconninfo(char *conndir, int fd)
void freenetconninfo(NetConnInfo*)
```

DESCRIPTION

For these routines, *addr* is a network address of the form *network*! *netaddr*! *service*, *network*! *netaddr*, or simply *netaddr*. *Network* is any directory listed in /net or the special token, net. Net is a free variable that stands for any network in common between the source and the host *netaddr*. *Netaddr* can be a host name, a domain name, a network address, or a meta-name of the form \$ *attribute*, which is replaced by *value* from the value-attribute pair *attribute=value* most closely associated with the source host in the network data base (see *ndb*(6)).

If a connection attempt is successful and *dir* is non-zero, the path name of a *line directory* that has files for accessing the connection is copied into *dir*. The path name is guaranteed to be less than 40 bytes long. One line directory exists for each possible connection. The data file in the line directory should be used to communicate with the destination. The ctl file in the line directory can be used to send commands to the line. See ip(3) for messages that can be written to the ctl file. The last close of the data or ctl file will close the connection.

Dial makes a call to destination addr on a multiplexed network. If the network in addr is net, dial will try all addresses on networks in common between source and destination until a call succeeds. It returns a file descriptor open for reading and writing the data file in the line directory. The addr file in the line directory contains the address called. If the network allows the local address to be set, as is the case with UDP and TCP port numbers, and *local* is non-zero, the local address will be set to *local*. If *cfdp* is non-zero, * *cfdp* is set to a file descriptor open for reading and writing the control file.

Hangup is a means of forcing a connection to hang up without closing the ctl and data files.

Announce and listen are the complements of dial. Announce establishes a network name to which calls can be made. Like dial, announce returns an open ctl file. The netaddr used in announce may be a local address or an asterisk, to indicate all local addresses, e.g. tcp!*!echo. The listen routine takes as its first argument the dir of a previous announce. When a call is received, listen returns an open ctl file for the line the call was received on. It sets newdir to the path name of the new line directory. Accept accepts a call received by listen, while reject refuses the call because of cause. Accept returns a file descriptor for the data file opened ORDWR.

Netmkaddr makes an address suitable for dialing or announcing. It takes an address along with a default network and service to use if they are not specified in the address. It returns a pointer to static data holding the actual address to use.

Getnetconninfo returns a structure containing information about a network connection. The structure is:

typedef struct NetConnInfo NetConnInfo; struct NetConnInfo

```
{
                      /* connection directory */
  char *dir;
  char *root;
                      /* network root */
                      /* binding spec */
  char *spec;
                      /* local system */
   char *lsys;
                      /* local service */
   char *lserv:
                      /* remote system */
   char *rsys;
  char *rserv;
                      /* remote service */
  char *laddr;
                       /* local address */
                       /* remote address */
   char *raddr;
};
```

The information is obtained from the connection directory, *conndir*. If *conndir* is nil, the directory is obtained by performing fd2path(2) on fd. *Getnetconninfo* returns either a completely specified structure, or nil if either the structure can't be allocated or the network directory can't be determined. The structure is freed using *freenetconninfo*.

Setnetmtpt copies the name of the network mount point into the buffer to, whose length is tolen. It exists to merge two pre-existing conventions for specifying the mount point. Commands that take a network mount point as a parameter (such as dns, cs (see ndb(8)), and ipconfig(8)) should now call setnetmtpt. If from is nil, the mount point is set to the default, /net. If from points to a string starting with a slash, the mount point is that path. Otherwise, the mount point is the string pointed to by from appended to the string /net. The last form is obsolete and is should be avoided. It exists only to aid in conversion.

EXAMPLES

Make a call and return an open file descriptor to use for communications:

```
int callkremvax(void)
{
    return dial("kremvax", nil, nil, nil);
}
```

Call the local authentication server:

```
int dialauth(char *service)
{
    return dial(netmkaddr("$auth", nil, service), nil, nil, nil);
}
```

Announce as kremvax on TCP/IP and loop forever receiving calls and echoing back to the caller anything sent:

```
int
bekremvax(void)
{
     int dfd, acfd, lcfd;
     char adir[40], ldir[40];
     int n:
     char buf[256];
     acfd = announce("tcp!*!7", adir);
     if(acfd < 0)
          return -1;
     for(;;){
          /* listen for a call */
          lcfd = listen(adir, ldir);
          if(lcfd < 0)
               return -1;
          /* fork a process to echo */
          switch(fork()){
          case -1:
               perror("forking");
               close(lcfd);
```

```
break;
                    case 0:
                         /* accept the call and open the data file */
                         dfd = accept(lcfd, ldir);
                         if(dfd < 0)
                              return -1;
                         /* echo until EOF */
                         while((n = read(dfd, buf, sizeof(buf))) > 0)
                              write(dfd, buf, n);
                         exits(nil);
                    default:
                         close(lcfd);
                         break;
                    }
               }
          }
SOURCE
     /sys/src/libc/9sys,/sys/src/libc/port
```

SEE ALSO

auth(2), ip(3), ndb(8)

DIAGNOSTICS

Dial, announce, and listen return -1 if they fail. Hangup returns nonzero if it fails.

dirread, dirreadall - read directory

SYNOPSIS

#include <u.h>
#include <libc.h>

long dirread(int fd, Dir **buf)

long dirreadall(int fd, Dir **buf)

#define STATMAX 65535U

#define DIRMAX (sizeof(Dir)+STATMAX)

DESCRIPTION

The data returned by a *read*(2) on a directory is a set of complete directory entries in a machineindependent format, exactly equivalent to the result of a *stat*(2) on each file or subdirectory in the directory. *Dirread* decodes the directory entries into a machine-dependent form. It reads from *fd* and unpacks the data into an array of Dir structures whose address is returned in *buf (see *stat*(2) for the layout of a Dir). The array is allocated with *malloc*(2) each time *dirread* is called.

Dirreadall is like *dirread*, but reads in the entire directory; by contrast, *dirread* steps through a directory one *read*(2) at a time.

Directory entries have variable length. A successful *read* of a directory always returns an integral number of complete directory entries; *dirread* always returns complete Dir structures. See *read*(5) for more information.

The constant STATMAX is the maximum size that a directory entry can occupy. The constant DIRMAX is an upper limit on the size necessary to hold a Dir structure and all the associated data.

Dirread and *dirreadall* return the number of Dir structures filled in buf. The file offset is advanced by the number of bytes actually read.

SOURCE

/sys/src/libc/9sys/dirread.c

SEE ALSO

intro(2), open(2), read(2)

DIAGNOSTICS

Dirread and *Dirreadall* return zero for end of file and a negative value for error. In either case, *buf is set to nil so the pointer can always be freed with impunity.

These functions set *errstr*.

opendisk, Disk - generic disk device interface

```
SYNOPSIS
    #include <u.h>
    #include <libc.h>
    #include <libc.h>
    #include <disk.h>
    typedef struct Disk {
        char *prefix;
        char part[NAMELEN];
        int fd, wfd, ctlfd, rdonly;
        int type;
        vlong secs, secsize, size, offset;
        int c, h, s;
    } Disk;
    Disk* opendisk(char *file, int rdonly, int noctl)
```

DESCRIPTION

These routines provide a simple way to gather and use information about floppy(3) and sd(3) disks and disk partitions, as well as plain files.

Opendisk opens *file* for reading and stores the file descriptor in the fd field of the Disk structure. If *rdonly* is not set, *opendisk* also opens *file* for writing and stores that file descriptor in wfd. The two file descriptors are kept separate to help prevent accidents.

If *noctl* is not set, *opendisk* looks for a ctl file in the same directory as the disk file; if it finds one, it declares the disk to be an *sd* device, setting the type field in the Disk structure to Tsd. If the passed *file* is named fd*n*disk, it looks for a file fd*n*ctl, and if it finds that, declares the disk to be a floppy disk, of type Tfloppy. If either control file is found, it is opened for reading and writing, and the resulting file descriptor is saved as ctlfd. Otherwise the returned disk has type Tfile.

Opendisk then stats the file and stores its length in size. If the disk is an *sd* partition, *opendisk* reads the sector size from the control file and stores it in secsize; otherwise the sector size is assumed to be 512, as is the case for floppy disks. *Opendisk* then stores the disk size measured in sectors in secs.

If the disk is an *sd* partition, *opendisk* parses the control file to find the partition's offset within its disk; otherwise it sets offset to zero. If the disk is an ATA disk, *opendisk* reads the disk geometry (number of cylinders, heads, and sectors) from the geometry line in the *sd* control file; otherwise it sets these to zero as well. Name is initialized with the base name of the disk partition, and is useful for forming messages to the *sd* control file. Prefix is set to the passed filename without the name suffix.

The IBM PC BIOS interface allocates 10 bits for the number of cylinders, 8 for the number of heads, and 6 for the number of sectors per track. Disk geometries are not quite so simple anymore, but to keep the interface useful, modern disks and BIOSes present geometries that still fit within these constraints. These numbers are still used when partitioning and formatting disks. *Opendisk* employs a number of heuristics to discover this supposed geometry and store it in the c, h, and s fields. Disk offsets in partition tables and in FAT descriptors are stored in a form dependent upon these numbers, so *opendisk* works hard to report numbers that agree with those used by other operating systems; the numbers bear little or no resemblance to reality.

SOURCE

/sys/src/libdisk/disk.c

SEE ALSO

floppy(3), sd(3)

Image, draw, gendraw, drawreplxy, drawrepl, replclipr, line, poly, fillpoly, bezier, bezspline, fillbezier, fillbezspline, ellipse, fillellipse, arc, fillarc, icossin, icossin2, border, string, stringn, runestring, runestringn, stringbg, stringnbg, runestringbg, runestringnbg, _string, ARROW, drawsetdebug - graphics functions

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <draw.h>
typedef
struct Image
{
               *display; /* display holding data */
     Display
                         /* id of system-held Image */
     int
               id:
                         /* rectangle in data area, local coords */
     Rectangle r;
                         /* clipping region */
     Rectangle clipr;
                         /* pixel channel format descriptor */
     ulong
               chan;
     int
               depth;
                         /* number of bits per pixel */
     int
               repl;
                         /* flag: data replicates to tile clipr */
               *screen; /* 0 if not a window */
     Screen
                         /* next in list of windows */
     Image
               *next;
} Image;
typedef enum
{
     /* Porter-Duff compositing operators */
     Clear
               = 0.
     SinD = 8,
     DinS = 4,
     SoutD
               = 2,
     DoutS
               = 1,
     S
               = SinD|SoutD,
     SoverD
               = SinD|SoutD|DoutS,
     SatopD
             = SinD|DoutS,
     SxorD
              = SoutD|DoutS,
     D
               = DinS|DoutS,
               = DinS|DoutS|SoutD,
     DoverS
     DatopS
               = DinS|SoutD,
     DxorS
               = DoutS|SoutD, /* == SxorD */
     Ncomp = 12,
} Drawop;
void
     draw(Image *dst, Rectangle r, Image *src,
          Image *mask, Point p)
      drawop(Image *dst, Rectangle r, Image *src,
void
          Image *mask, Point p, Drawop op)
      gendraw(Image *dst, Rectangle r, Image *src, Point sp,
void
          Image *mask, Point mp)
      gendrawop(Image *dst, Rectangle r, Image *src, Point sp,
void
          Image *mask, Point mp, Drawop op)
      drawreplxy(int min, int max, int x)
int
Point drawrepl(Rectangle r, Point p)
      replclipr(Image *i, int repl, Rectangle clipr)
void
      line(Image *dst, Point p0, Point p1, int end0, int end1,
void
          int radius, Image *src, Point sp)
      lineop(Image *dst, Point p0, Point p1, int end0, int end1,
void
          int radius, Image *src, Point sp, Drawop op)
```

poly(Image *dst, Point *p, int np, int end0, int end1, void int radius, Image *src, Point sp) polyop(Image *dst, Point *p, int np, int end0, int end1, void int radius, Image *src, Point sp, Drawop op)
fillpoly(Image *dst, Point *p, int np, int wind, void Image *src, Point sp) fillpolyop(Image *dst, Point *p, int np, int wind, void Image *src, Point sp, Drawop op) bezier(Image *dst, Point p0, Point p1, Point p2, Point p3, int int end0, int end1, int radius, Image *src, Point sp) bezierop(Image *dst, Point p0, Point p1, Point p2, Point p3, int int end0, int end1, int radius, Image *src, Point sp, Drawop op) bezierpts(Point p0, Point p1, Point p2, Point p3, Point **pp) int int bezspline(Image *dst, Point *pt, int npt, int end0, int end1, int radius, Image *src, Point sp) bezsplineop(Image *dst, Point *pt, int npt, int end0, int end1, int int radius, Image *src, Point sp, Drawop op) bezsplinepts(Point *pt, int npt, Point **pp) int int fillbezier(Image *dst, Point p0, Point p1, Point p2, Point p3, int w, Image *src, Point sp) fillbezierop(Image *dst, Point p0, Point p1, Point p2, Point p3, int int w, Image *src, Point sp, Drawop op) fillbezspline(Image *dst, Point *pt, int npt, int w, int Image *src, Point sp) fillbezsplineop(Image *dst, Point *pt, int npt, int w, int Image *src, Point sp, Drawop op) ellipse(Image *dst, Point c, int a, int b, int thick, void Image *src, Point sp) void ellipseop(Image *dst, Point c, int a, int b, int thick, Image *src, Point sp, Drawop op) void fillellipse(Image *dst, Point c, int a, int b, Image *src, Point sp) fillellipseop(Image *dst, Point c, int a, int b, Image *src, Point sp, Drawop op) void arc(Image *dst, Point c, int a, int b, int thick, void Image *src, Point sp, int alpha, int phi) void arcop(Image *dst, Point c, int a, int b, int thick, Image *src, Point sp, int alpha, int phi, Drawop op) fillarc(Image *dst, Point c, int a, int b, Image *src, void Point sp, int alpha, int phi) void fillarcop(Image *dst, Point c, int a, int b, Image *src, Point sp, int alpha, int phi, Drawop op) void icossin(int deg, int *cosp, int *sinp) icossin2(int x, int y, int *cosp, int *sinp) void border(Image *dst, Rectangle r, int i, Image *color, Point sp) void void borderop(Image *dst, Rectangle r, int i, Image *color, Point sp, Drawop op) Point string(Image *dst, Point p, Image *src, Point sp, Font *f, char *s) Point stringop(Image *dst, Point p, Image *src, Point sp, Font *f, char *s, Drawop op) Point stringn(Image *dst, Point p, Image *src, Point sp, Font *f, char *s, int len) Point stringnop(Image *dst, Point p, Image *src, Point sp, Font *f, char *s, int len, Drawop op) Point runestring(Image *dst, Point p, Image *src, Point sp, Font *f, Rune *r)

```
Point runestringop(Image *dst, Point p, Image *src, Point sp,
          Font *f, Rune *r, Drawop op)
Point runestringn(Image *dst, Point p, Image *src, Point sp,
          Font *f, Rune *r, int len)
Point runestringnop(Image *dst, Point p, Image *src, Point sp,
          Font *f, Rune *r, int len, Drawop op)
Point stringbg(Image *dst, Point p, Image *src, Point sp,
          Font *f, char *s, Image *bg, Point bgp)
Point stringbgop(Image *dst, Point p, Image *src, Point sp,
          Font *f, char *s, Image *bg, Point bgp, Drawop op)
Point stringnbg(Image *dst, Point p, Image *src, Point sp,
Font *f, char *s, int len, Image *bg, Point bgp)
Point stringnbgop(Image *dst, Point p, Image *src, Point sp,
          Font *f, char *s, int len, Image *bg, Point bgp, Drawop op)
Point runestringbg(Image *dst, Point p, Image *src, Point sp,
          Font *f, Rune *r, Image *bg, Point bgp)
Point runestringbgop(Image *dst, Point p, Image *src, Point sp,
          Font *f, Rune *r, Image *bg, Point bgp, Drawop op)
Point runestringnbg(Image *dst, Point p, Image *src, Point sp,
          Font *f, Rune *r, int len, Image *bg, Point bgp)
Point runestringnbgop(Image *dst, Point p, Image *src, Point sp,
          Font *f, Rune *r, int len, Image *bg, Point bgp, Drawop op)
Point _string(Image *dst, Point p, Image *src,
          Point sp, Font *f, char *s, Rune *r, int len,
          Rectangle clipr, Image *bg, Point bgp, Drawop op)
void
      drawsetdebug(int on)
enum
{
      /* line ends */
      Endsquare = 0,
      Enddisc
                 = 1,
      Endarrow = 2,
      Endmask
                 = 0x1F
};
#define ARROW(a, b, c) (Endarrow|((a)<<5)|((b)<<14)|((c)<<23))
```

DESCRIPTION

The Image type defines rectangular pictures and the methods to draw upon them; it is also the building block for higher level objects such as windows and fonts. In particular, a window is represented as an Image; no special operators are needed to draw on a window.

- r The coordinates of the rectangle in the plane for which the Image has defined pixel values. It should not be modified after the image is created.
- clipr The clipping rectangle: operations that read or write the image will not access pixels outside clipr. Frequently, clipr is the same as r, but it may differ; see in particular the discussion of repl. The clipping region may be modified dynamically using replclipr (q.v.).
- chan The pixel channel format descriptor, as described in *image*(6). The value should not be modified after the image is created.
- depth The number of bits per pixel in the picture; it is identically chantodepth(chan) (see *graphics*(2)) and is provided as a convenience. The value should not be modified after the image is created.
- repl A boolean value specifying whether the image is tiled to cover the plane when used as a source for a drawing operation. If repl is zero, operations are restricted to the intersection of r and clipr. If repl is set, r defines the tile to be replicated and clipr defines the portion of the plane covered by the tiling, in other words, r is replicated to cover clipr; in such cases r and clipr are independent.

For example, a replicated image with r set to ((0, 0), (1, 1)) and clipr set to ((0, 0), (100, 100)), with the single pixel of r set to blue, behaves identically to an image with r and clipr both set to ((0, 0), (100, 100)) and all pixels set to blue. However, the first image requires far less memory. The replication flag may be modified dynamically using *replclipr* (*q.v.*).

Most of the drawing functions come in two forms: a basic form, and an extended form that takes an extra Drawop to specify a Porter-Duff compositing operator to use. The basic forms assume the operator is SoverD, which suffices for the vast majority of applications. The extended forms are named by adding an -op suffix to the basic form. Only the basic forms are listed below.

draw(dst, r, src, mask, p)

Draw is the standard drawing function. Only those pixels within the intersection of $dst \rightarrow r$ and $dst \rightarrow clipr$ will be affected; *draw* ignores $dst \rightarrow repl$. The operation proceeds as follows (this is a description of the behavior, not the implementation):

- 1. If repl is set in *src* or *mask*, replicate their contents to fill their clip rectangles.
- 2. Translate *src* and *mask* so *p* is aligned with *r*.min.
- 3. Set *r* to the intersection of *r* and $dst \rightarrow r$.
- 4. Intersect *r* with $src \rightarrow clipr$. If $src \rightarrow repl$ is false, also intersect *r* with $src \rightarrow r$.
- 5. Intersect r with mask->clipr. If mask->repl is false, also intersect r with mask->r.
- 6. For each location in *r*, combine the *dst* pixel with the *src* pixel using the alpha value corresponding to the *mask* pixel. If the *mask* has an explicit alpha channel, the alpha value corresponding to the *mask* pixel is simply that pixel's alpha channel. Otherwise, the alpha value is the NTSC greyscale equivalent of the color value, with white meaning opaque and black transparent. In terms of the Porter–Duff compositing algebra, *draw* replaces the *dst* pixels with (*src* in *mask*) over *dst*. (In the extended form, "over" is replaced by *op*).

The various pixel channel formats involved need not be identical. If the channels involved are smaller than 8-bits, they will be promoted before the calculation by replicating the extant bits; after the calculation, they will be truncated to their proper sizes.

gendraw(dst, r, src, p0, mask, p1)

Similar to *draw* except that *gendraw* aligns the source and mask differently: *src* is aligned so p0 corresponds to *r*.min and *mask* is aligned so p1 corresponds to *r*.min. For most purposes with simple masks and source images, draw is sufficient, but gendraw is the general operator and the one all other drawing primitives are built upon.

drawreplxy(min,max,x)

Clips x to be in the half-open interval [*min*, *max*) by adding or subtracting a multiple of *max-min*.

drawrepl(r,p)

Clips the point p to be within the rectangle r by translating the point horizontally by an integer multiple of rectangle width and vertically by the height.

replclipr(i, repl, clipr)

Because the image data is stored on the server, local modifications to the Image data structure itself will have no effect. *Replclipr* modifies the local Image data structure's repl and clipr fields, and notifies the server of their modification.

line(dst, p0, p1, end0, end1, thick, src, sp)

Line draws in *dst* a line of width 1+2* *thick* pixels joining points *p0* and *p1*. The line is drawn using pixels from the *src* image aligned so *sp* in the source corresponds to *p0* in the destination. The line touches both *p0* and *p1*, and *end0* and *end1* specify how the ends of the line are drawn. Endsquare terminates the line perpendicularly to the direction of the line; a thick line with Endsquare on both ends will be a rectangle. Enddisc terminates the line by drawing a disc of diameter 1+2* *thick* centered on the end point. Endarrow terminates the line with an arrowhead whose tip touches the endpoint.

The macro ARROW permits explicit control of the shape of the arrow. If all three parameters are zero, it produces the default arrowhead, otherwise, a sets the distance along line from end of the regular line to tip, b sets the distance along line from the barb to the tip, and c sets the distance perpendicular to the line from edge of line to the tip of the barb, all in pixels.

Line and the other geometrical operators are equivalent to calls to *gendraw* using a mask produced by the geometric procedure.

poly(dst, p, np, end0, end1, thick, src, sp)

Poly draws a general polygon; it is conceptually equivalent to a series of calls to *line* joining adjacent points in the array of Points p, which has np elements. The ends of the polygon are specified as in *line*; interior lines are terminated with Enddisc to make smooth joins. The source is aligned so sp corresponds to p[0].

fillpoly(dst, p, np, wind, src, sp)

Fillpoly is like *poly* but fills in the resulting polygon rather than outlining it. The source is aligned so *sp* corresponds to p[0]. The winding rule parameter *wind* resolves ambiguities about what to fill if the polygon is self-intersecting. If *wind* is ~0, a pixel is inside the polygon if the polygon's winding number about the point is non-zero. If *wind* is 1, a pixel is inside if the winding number is odd. Complementary values (0 or ~1) cause outside pixels to be filled. The meaning of other values is undefined. The polygon is closed with a line if necessary.

bezier(dst, a, b, c, d, end0, end1, thick, src, sp)

Bezier draws the cubic Bezier curve defined by Points *a*, *b*, *c*, and *d*. The end styles are determined by *end0* and *end1*; the thickness of the curve is 1+2* thick. The source is aligned so *sp* in *src* corresponds to *a* in *dst*.

- bezierpts(a, b, c, d, pp)
 Bezierpts returns in pp a list of points making up the open polygon that bezier would draw.
 The caller is responsible for freeing *pp.
- bezspline(dst, p, np, end0, end1, thick, src, sp)
 Bezspline takes the same arguments as poly but draws a quadratic B-spline (despite its
 name) rather than a polygon. If the first and last points in p are equal, the spline has periodic end conditions.
- bezsplinepts(pt, npt, pp)
 Bezsplinepts returns in pp a list of points making up the open polygon that bezspline would
 draw. The caller is responsible for freeing *pp.
- fillbezier(dst, a, b, c, d, wind, src, sp)
 Fillbezier is to bezier as fillpoly is to poly.
- fillbezspline(dst, p, wind, src, sp)
 Fillbezspline is like fillpoly but fills the quadratic B-spline rather than the polygon outlined
 by p. The spline is closed with a line if necessary.
- ellipse(dst, c, a, b, thick, src, sp)
 Ellipse draws in dst an ellipse centered on c with horizontal and vertical semiaxes a and b.
 The source is aligned so sp in src corresponds to c in dst. The ellipse is drawn with thick ness 1+2* thick.
- fillellipse(dst, c, a, b, src, sp)
 Fillellipse is like ellipse but fills the ellipse rather than outlining it.
- arc(dst, c, a, b, thick, src, sp, alpha, phi) Arc is like ellipse, but draws only that portion of the ellipse starting at angle alpha and extending through an angle of phi. The angles are measured in degrees counterclockwise from the positive x axis.
- fillarc(dst, c, a, b, src, sp, alpha, phi)
 Fillarc is like arc, but fills the sector with the source color.

icossin2(x, y, cosp, sinp)

lcossin2 is analogous to *icossin*, with the angle represented not in degrees but implicitly by the point (x, y). It is to *icossin* what atan2 is to atan (see *sin*(2)).

border(dst, r, i, color, sp)

Border draws an outline of rectangle r in the specified *color*. The outline has width i; if positive, the border goes inside the rectangle; negative, outside. The source is aligned so sp corresponds to r.min.

string(dst, p, src, sp, font, s)

String draws in dst characters specified by the string s and font; it is equivalent to a series of calls to gendraw using source src and masks determined by the character shapes. The text is positioned with the left of the first character at $p \cdot x$ and the top of the line of text at $p \cdot y$. The source is positioned so sp in src corresponds to p in dst. String returns a Point that is the position of the next character that would be drawn if the string were longer.

For characters with undefined or zero-width images in the font, the character at font position 0 (NUL) is drawn.

The other string routines are variants of this basic form, and have names that encode their variant behavior. Routines whose names contain rune accept a string of Runes rather than UTF-encoded bytes. Routines ending in n accept an argument, n, that defines the number of characters to draw rather than accepting a NUL-terminated string. Routines containing bg draw the background behind the characters in the specified color (*bg*) and alignment (*bgp*); normally the text is drawn leaving the background intact.

The routine *_string* captures all this behavior into a single operator. Whether it draws a UTF string or Rune string depends on whether *s* or *r* is null (the string length is always determined by *len*). If *bg* is non-null, it is used as a background color. The *clipr* argument allows further management of clipping when drawing the string; it is intersected with the usual clipping rectangles to further limit the extent of the text.

drawsetdebug(on)

Turns on or off debugging output (usually to a serial line) according to whether *on* is non-zero.

SOURCE

/sys/src/libdraw

SEE ALSO

graphics(2), stringsize(2), color(6), utf(6), addpt(2)

T. Porter, T. Duff. "Compositing Digital Images", *Computer Graphics* (Proc. SIGGRAPH), 18:3, pp. 253-259, 1984.

DIAGNOSTICS

These routines call the graphics error function on fatal errors.

BUGS

Anti-aliased characters can be drawn by defining a font with multiple bits per pixel, but there are no anti-aliasing geometric primitives.

dsagen, dsasign, dsaverify, dsapuballoc, dsapubfree, dsaprivalloc, dsaprivfree, dsasigalloc, dsasigfree, dsaprivtopub - digital signature algorithm

SYNOPSIS

515	
<pre>#include #include</pre>	
<pre>#include</pre>	1 I I I I I I I I I I I I I I I I I I I
#include	<libsec.h></libsec.h>
DSApriv*	dsagen(DSApub *opub)
DSAsig*	dsasign(DSApriv *k, mpint *m)
int	<pre>dsaverify(DSApub *k, DSAsig *sig, mpint *m)</pre>
DSApub*	dsapuballoc(void)
void	dsapubfree(DSApub*)
DSApriv*	dsaprivalloc(void)
void	dsaprivfree(DSApriv*)
DSAsig*	dsasigalloc(void)
void	dsasigfree(DSAsig*)
DSApub*	dsaprivtopub(DSApriv*)

DESCRIPTION

DSA is the NIST approved digital signature algorithm. The owner of a key publishes the public part of the key:

```
struct DSApub
{
    mpint *p; // modulus
    mpint *q; // group order, q divides p-1
    mpint *alpha; // group generator
    mpint *key; // alpha**secret mod p
};
```

This part can be used for verifying signatures (with *dsaverify*) created by the owner. The owner signs (with *dsasign*) using his private key:

```
struct DSApriv
{
    DSApub    pub;
    mpint *secret; // (decryption key)
};
```

Keys are generated using *dsagen*. If *dsagen*'s argument *opub* is nil, a key is created using a new p and q generated by *DSAprimes* (see *prime*(2)). Otherwise, p and q are copied from the old key.

Dsaprivtopub returns a newly allocated copy of the public key corresponding to the private key.

The routines *dsapuballoc*, *dsapubfree*, *dsaprivalloc*, and *dsaprivfree* are provided to manage key storage.

Dsasign signs message m using a private key k yielding a

struct DSAsig
{
 mpint *r, *s;
};

Dsaverify returns 0 if the signature is valid and -1 if not.

The routines *dsasigalloc* and *dsasigfree* are provided to manage signature storage.

SOURCE

/sys/src/libsec

mp(2), *aes*(2), *blowfish*(2), *des*(2), *rc4*(2), *rsa*(2), *sechash*(2), *prime*(2), *rand*(2)

dup - duplicate an open file descriptor

SYNOPSIS

#include <u.h>
#include <libc.h>

int dup(int oldfd, int newfd)

DESCRIPTION

Given a file descriptor, *oldfd*, referring to an open file, *dup* returns a new file descriptor referring to the same file.

If *newfd* is -1 the system chooses the lowest available file descriptor. Otherwise, *dup* will use *newfd* for the new file descriptor (closing any old file associated with *newfd*). File descriptors are allocated dynamically, so to prevent unwarranted growth of the file descriptor table, *dup* requires that *newfd* be no greater than 20 more than the highest file descriptor ever used by the program.

Dup does not copy the per file descriptor OCEXEC flag, meaning that *newfd* will not be closed on *exec(2)* syscall, when *oldfd* had been previously opend with it.

SOURCE

/sys/src/libc/9syscall

SEE ALSO

intro(2), dup(3)

DIAGNOSTICS

Sets errstr.

secp256r1, secp256k1, secp384r1, ecdominit, ecdomfree, ecassign, ecadd, ecmul, strtoec, ecgen, ecverify, ecpubverify, ecdsasign, ecdsaverify, ecencodepub, ecdecodepub, ecpubfree, X509toECpub, X509ecdsaverify, X509ecdsaverifydigest – elliptic curve cryptography

SYNOPSIS

#include <u.h> #include <libc.h> #include <mp.h> #include <libsec.h> void secp256r1(mpint *p, mpint *a, mpint *b, mpint *x, mpint *y, mpint *n, mpint *h) void secp256k1(mpint *p, mpint *a, mpint *b, mpint *x, mpint *y, mpint *n, mpint *h) void secp384r1(mpint *p, mpint *a, mpint *b, mpint *x, mpint *y, mpint *n, mpint *h) void ecdominit(ECdomain *dom, void (*init)(mpint *p, mpint *a, mpint *b, mpint *x, mpint *y, mpint *n, mpint *h)) void ecdomfree(ECdomain *dom) void ecassign(ECdomain *dom, ECpoint *old, ECpoint *new) void ecadd(ECdomain *dom, ECpoint *a, ECpoint *b, ECpoint *s) void ecmul(ECdomain *dom, ECpoint *a, mpint *k, ECpoint *s) strtoec(ECdomain *dom, char *s, char **rptr, ECpoint *p) ECpoint* ecgen(ECdomain *dom, ECpriv *p) ECpriv* ecverify(ECdomain *dom, ECpoint *p) int ecpubverify(ECdomain *dom, ECpub *p) int void ecdsasign(ECdomain *dom, ECpriv *priv, uchar *dig, int dlen, mpint *r, mpint *s) int ecdsaverify(ECdomain *dom, ECpub *pub, uchar *dig, int dlen, mpint *r, mpint *s) int ecencodepub(ECdomain *dom, ECpub *pub, uchar *data, int len) ecdecodepub(ECdomain *dom, uchar *data, int len) ECpub* void ecpubfree(ECpub *p); ECpub* X509toECpub(uchar *cert, int ncert, char *name. int nname, ECdomain *dom) char* X509ecdsaverify(uchar *cert, int ncert, ECdomain *dom, ECpub *pub) char* X509ecdsaverifydigest(uchar *sig, int siglen, uchar *edigest, int edigestlen, ECdomain *dom, ECpub *pub)

DESCRIPTION

These functions implement elliptic curve cryptography. An elliptic curve together with cryptographic parameters are specified using an ECdomain struct. Points on the curve are represented by ECpoint structs.

ecdominit initializes a ECdomain struct and calls the init function such as secp256r1 which fills in the parameters of the curve.

ecdomfree frees the parameters of the curve and zeros the struct. It does not free the memory of the struct itself.

ecassign, ecadd and ecmul are analogous to their counterparts in *mp*(2).

strtoec converts a hex string representing an octet string as specified in *Standards for Efficient Cryptography (SEC) 1* to an ECpoint struct. Both uncompressed and compressed formats are supported. If rptr is not nil, it is used to return the position in the string where the parser stopped. If p is nil space is allocated automatically, else the given struct is used.

ecverify and ecpubverify verify that the given point or public key, respectively, is valid.

ecgen generates a keypair and returns a pointer to it. If p is nil space is allocated automatically, else the given struct is used.

ecdsasign and ecdsaverify create or verify, respectively, a signature using the ECDSA scheme specified in *SEC 1*. It is absolutely vital that dig is a cryptographic hash to the message. ecdsasign writes the signature to r and s which are assumed to be allocated properly.

ecencodepub and ecdecodepub handle encoding and decoding of public keys in uncompressed format. Note that ecdecodepub also verifies that the public key is valid in the specified domain.

ecpubfree frees a ECpub structure and its associated members.

Given a binary X.509 cert, the function X509toECpub initializes domain parameters and returns the ECDSA public key. if *name* is not nil, the CN part of the Distinguished Name of the certificate's Subject is returned. X509ecdsaverify and X509ecdsaverifydigest are analogs to the routines described by *rsa*(2).

RETURN VALUE

*verify functions return 1 for a positive result. Functions returning pointers may return nil in case of error (*e.g.* failing *malloc*(2)).

SOURCE

/sys/src/libsec/port/ecc.c

SEE ALSO

rsa(2)

Standards for Efficient Cryptography (SEC) 1: Elliptic Curve Cryptography – Certicom Research, 2009

HISTORY

This implementation of elliptic curve cryptography first appeared in 9front (June, 2012).

eggen, egencrypt, egdecrypt, egsign, egverify, egpuballoc, egpubfree, egprivalloc, egprivfree, egsigalloc, egsigfree, egprivtopub – elgamal encryption

SYNOPSIS

<pre>#include #include #include #include</pre>	<libc.h></libc.h>
EGpriv*	eggen(int nlen, int nrep)
mpint*	<pre>egencrypt(EGpub *k, mpint *in, mpint *out)</pre>
mpint*	<pre>egdecrypt(EGpriv *k, mpint *in, mpint *out)</pre>
EGsig*	egsign(EGpriv *k, mpint *m)
int	egverify(EGpub *k, EGsig *sig, mpint *m)
EGpub*	egpuballoc(void)
void	egpubfree(EGpub*)
EGpriv*	egprivalloc(void)
void	egprivfree(EGpriv*)
EGsig*	egsigalloc(void)
void	egsigfree(EGsig*)
EGpub*	egprivtopub(EGpriv*)

DESCRIPTION

Elgamal is a public key encryption and signature algorithm. The owner of a key publishes the public part of the key:

```
struct EGpub
{
    mpint *p; // modulus
    mpint *alpha; // generator
    mpint *key; // (encryption key) alpha**secret mod p
};
```

This part can be used for encrypting data (with *egencrypt*) to be sent to the owner. The owner decrypts (with *egdecrypt*) using his private key:

```
struct EGpriv
{
    EGpub    pub;
    mpint  *secret; // (decryption key)
};
```

Keys are generated using *eggen*. *Eggen* takes both bit length of the modulus and the number of repetitions of the Miller-Rabin primality test to run. If the latter is 0, it does the default number of rounds. *Egprivtopub* returns a newly allocated copy of the public key corresponding to the private key.

The routines *egpuballoc*, *egpubfree*, *egprivalloc*, and *egprivfree* are provided to manage key storage.

Egsign signs message m using a private key k yielding a

struct EGsig
{
 mpint *r, *s;
}:

Egverify returns 0 if the signature is valid and -1 if not.

The routines *egsigalloc* and *egsigfree* are provided to manage signature storage.

SOURCE

/sys/src/libsec

SEE ALSO

mp(2), *aes*(2), *blowfish*(2), *des*(2), *dsa*(2), *rc4*(2), *rsa*(2), *sechash*(2), *prime*(2), *rand*(2)

dec64, enc64, dec32, enc32, dec16, enc16, dec64chr, enc64chr, dec32chr, enc32chr, dec16chr, enc16chr, encodefmt - encoding byte arrays as strings

SYNOPSIS

```
#include <u.h>
#include <libc.h>
int
     dec64(uchar *out, int lim, char *in, int n)
     enc64(char *out, int lim, uchar *in, int n)
int
     dec32(uchar *out, int lim, char *in, int n)
int
     enc32(char *out, int lim, uchar *in, int n)
int
     dec16(uchar *out, int lim, char *in, int n)
int
     enc16(char *out, int lim, uchar *in, int n)
int
     dec64chr(int c)
int
int
     enc64chr(int o)
int
     dec32chr(int c)
int
     enc32chr(int o)
     dec16chr(int c)
int
int
     enc16chr(int o)
     encodefmt(Fmt*)
int
```

DESCRIPTION

The functions described here handle encoding and decoding of bytes to printable ASCII strings as specified by RFC4648.

Enc16, *enc32* and *enc64* create null terminated strings. They return the size of the encoded string (without the null) or -1 if the encoding fails. The encoding fails if *lim*, the length of the output buffer (including null), is too small.

Dec16, *dec32* and *dec64* return the number of bytes decoded or -1 if the decoding fails. The decoding fails if the output buffer is not large enough or, for base 32, if the input buffer length is not a multiple of 8.

Dec16chr, *dec32chr* and *dec64chr* return the value for a symbol of the alphabet or -1 when the symbol is not in the alphabet.

Enc16chr, *enc32chr* and *enc64chr* encode a symbol of the alphabet given a value. if the value is out of range then zero is returned.

Encodefmt can be used with *fmtinstall*(2) and *print*(2) to print encoded representations of byte arrays. The verbs are

- H base 16 (i.e. hexadecimal). The default encoding is in upper case. The 1 flag forces lower case.
- < base 32. The default is upper case, same as H.
- [base 64 (same as MIME)

The length of the array is specified as f^2 . For example, to display a 15 byte array as hex:

char x[15];

```
fmtinstall('H', encodefmt);
print("%.*H\n", sizeof x, x);
```

SOURCE

```
/sys/src/libc/port/u16.c
/sys/src/libc/port/u32.c
```

```
/sys/src/libc/port/u64.c
/sys/src/libc/port/encodefmt.c
```

HISTORY

In Jan 2018, base 32 encoding was changed from non-standard to standard RFC4648 alphabet.

- old: 23456789abcdefghijkmnpqrstuvwxyz
- new: ABCDEFGHIJKLMNOPQRSTUVWXYZ234567

encrypt, decrypt, netcrypt – DES encryption

SYNOPSIS

#include <u.h>
#include <libc.h>
int encrypt(void *key, void *data, int len)
int decrypt(void *key, void *data, int len)

int netcrypt(void *key, void *data)

DESCRIPTION

Encrypt and *decrypt* perform DES encryption and decryption. *Key* is an array of DESKEYLEN (defined as 7 in <auth.h>) bytes containing the encryption key. *Data* is an array of *len* bytes; it must be at least 8 bytes long. The bytes are encrypted or decrypted in place.

The DES algorithm encrypts an individual 8-byte block of data. *Encrypt* uses the following method to encrypt data longer than 8 bytes. The first 8 bytes are encrypted as usual. The last byte of the encrypted result is prefixed to the next 7 unencrypted bytes to make the next 8 bytes to encrypt. This is repeated until fewer than 7 bytes remain unencrypted. Any remaining unencrypted bytes are encrypted with enough of the preceding encrypted bytes to make a full 8-byte block. *Decrypt* uses the inverse algorithm.

Netcrypt performs the same encryption as a SecureNet Key. *Data* points to an ASCII string of decimal digits with numeric value between 0 and 10000. These digits are copied into an 8-byte buffer with trailing binary zero fill and encrypted as one DES block. The first four bytes are each formatted as two digit ASCII hexadecimal numbers, and the string is copied into *data*.

SOURCE

/sys/src/libc/port

DIAGNOSTICS

These routines return 1 if the data was encrypted, and 0 if the encryption fails. *Encrypt* and *decrypt* fail if the data passed is less than 8 bytes long. *Netcrypt* can fail if it is passed invalid data.

SEE ALSO

securenet(8)

BUGS

The implementation is broken in a way that makes it unsuitable for anything but authentication.

errstr, rerrstr, werrstr - description of last system call error

SYNOPSIS

#include <u.h>

#include <libc.h>

int errstr(char *err, uint nerr)

```
void rerrstr(char *err, uint nerr)
```

void werrstr(char *fmt, ...)

DESCRIPTION

When a system call fails it returns -1 and records a null terminated string describing the error in a per-process buffer. *Errstr* swaps the contents of that buffer with the contents of the array *err*. *Errstr* will write at most *nerr* bytes into *err*; if the per-process error string does not fit, it is silently truncated at a UTF character boundary. The returned string is NUL-terminated. Usually *errstr* will be called with an empty string, but the exchange property provides a mechanism for libraries to set the return value for the next call to *errstr*.

The per-process buffer is ERRMAX bytes long. Any error string provided by the user will be truncated at ERRMAX-1 bytes. ERRMAX is defined in <libc.h>.

If no system call has generated an error since the last call to *errstr* with an empty string, the result is an empty string.

The verb r in *print*(2) calls *errstr* and outputs the error string.

Rerrstr reads the error string but does not modify the per-process buffer, so a subsequent *errstr* will recover the same string.

Werrstr takes a *print* style format as its argument and uses it to format a string to pass to *errstr*. The string returned from *errstr* is discarded.

SOURCE

/sys/src/libc/9syscall
/sys/src/libc/9sys/rerrstr.c
/sys/src/libc/9sys/werrstr.c

DIAGNOSTICS

Errstr always returns 0.

SEE ALSO

intro(2), *perror*(2)

event, einit, estart, estartfn, etimer, eread, emouse, ekbd, ecanread, ecanmouse, ecankbd, ereadmouse, eatomouse, eresized, egetrect, edrawgetrect, emenuhit, eenter, emoveto, esetcursor, Event, Mouse, Menu – graphics events

SYNOPSIS

515	-
<pre>#include</pre>	<u.h></u.h>
#include #include	chipc.h>
<pre>#include #include</pre>	
<pre>#include</pre>	
void	einit(ulong keys)
ulong	event(Event *e)
Mouse	emouse(void)
int	ekbd(void)
int	ecanmouse(void)
int	ecankbd(void)
int	ereadmouse(Mouse *m)
int	<pre>eatomouse(Mouse *m, char *buf, int n)</pre>
ulong	estart(ulong key, int fd, int n)
ulong	estartfn(ulong key, int fd, int n, int (*fn)(int, Event*, uchar*, int))
ulong	etimer(ulong key, int n)
ulong	eread(ulong keys, Event *e)
int	ecanread(ulong keys)
void	eresized(int new)
Rectangle	egetrect(int but, Mouse *m)
void	edrawgetrect(Rectangle r, int up)
int	emenuhit(int but, Mouse *m, Menu *menu)
void	emoveto(Point p)
void	esetcursor(Cursor *c)
int	<pre>eenter(char *ask, char *buf, int len, Mouse *m)</pre>
extern Mou	ise *mouse
enum{	
	Emouse = 1, $Ekoupheand = 2$
}:	Ekeyboard = 2 ,

};

DESCRIPTION

These routines provide an interface to multiple sources of input for unthreaded programs. Threaded programs (see *thread*(2)) should instead use the threaded mouse and keyboard interface described in *mouse*(2) and *keyboard*(2).

Einit must be called first. If the argument to *einit* has the Emouse and Ekeyboard bits set, the mouse and keyboard events will be enabled; in this case, *initdraw* (see *graphics*(2)) must have already been called. The user must provide a function called *eresized* to be called whenever the window in which the process is running has been resized; the argument *new* is a flag specifying whether the program must call *getwindow* (see *graphics*(2)) to re-establish a connection to its window. After resizing (and perhaps calling *getwindow*), the global variable screen will be updated to point to the new window's Image structure.

As characters are typed on the keyboard, they are read by the event mechanism and put in a queue. *Ekbd* returns the next rune from the queue, blocking until the queue is non-empty. The characters are read in raw mode (see *cons*(3)), so they are available as soon as a complete rune is typed.

When the mouse moves or a mouse button is pressed or released, a new mouse event is queued by the event mechanism. *Emouse* returns the next mouse event from the queue, blocking until the queue is non-empty. *Emouse* returns a Mouse structure:

```
struct Mouse
{
    int buttons;
    Point xy;
    ulong msec;
};
```

Buttons&1 is set when the left mouse button is pressed, buttons&2 when the middle button is pressed, and buttons&4 when the right button is pressed. The current mouse position is always returned in xy. Msec is a time stamp in units of milliseconds.

Ecankbd and *ecanmouse* return non-zero when there are keyboard or mouse events available to be read.

Ereadmouse reads the next mouse event from the file descriptor connected to the mouse, converts the textual data into a Mouse structure by calling *eatomouse* with the buffer and count from the read call, and returns the number of bytes read, or -1 for an error.

Estart can be used to register additional file descriptors to scan for input. It takes as arguments the file descriptor to register, the maximum length of an event message on that descriptor, and a key to be used in accessing the event. The key must be a power of 2 and must not conflict with any previous keys. If a zero key is given, a key will be allocated and returned. *Estartfn* is similar to *estart*, but processes the data received by calling *fn* before returning the event to the user. The function *fn* is called with the id of the event; it should return id if the event is to be passed to the user, 0 if it is to be ignored. The variable Event \cdot v can be used by *fn* to attach an arbitrary data item to the returned Event structure. Ekeyboard and Emouse are the keyboard and mouse event keys.

Etimer starts a repeating timer with a period of n milliseconds; it returns the timer event key, or zero if it fails. Only one timer can be started. Extra timer events are not queued and the timer channel has no associated data.

Eread waits for the next event specified by the mask *keys* of event keys submitted to *estart*. It fills in the appropriate field of the argument Event structure, which looks like:

```
struct Event
{
    int kbdc;
    Mouse mouse;
    int n;
    void *v;
    uchar data[EMAXMSG];
};
```

Data is an array which is large enough to hold a 9P message. *Eread* returns the key for the event which was chosen. For example, if a mouse event was read, Emouse will be returned.

Event waits for the next event of any kind. The return is the same as for eread.

As described in *graphics*(2), the graphics functions are buffered. *Event*, *eread*, *emouse*, and *ekbd* all cause a buffer flush unless there is an event of the appropriate type already queued.

Ecanread checks whether a call to eread(keys) would block, returning 0 if it would, 1 if it would not.

Getrect prompts the user to sweep a rectangle. It should be called with m holding the mouse event that triggered the *egetrect* (or, if none, a Mouse with buttons set to 7). It changes to the sweep cursor, waits for the buttons all to be released, and then waits for button number *but* to be pressed, marking the initial corner. If another button is pressed instead, *egetrect* returns a

rectangle with zero for both corners, after waiting for all the buttons to be released. Otherwise, *egetrect* continually draws the swept rectangle until the button is released again, and returns the swept rectangle. The mouse structure pointed to by *m* will contain the final mouse event.

Egetrect uses successive calls to *edrawgetrect* to maintain the red rectangle showing the sweepin-progress. The rectangle to be drawn is specified by *rc* and the *up* parameter says whether to draw (1) or erase (0) the rectangle.

Emenuhit displays a menu and returns a selected menu item number. It should be called with *m* holding the mouse event that triggered the *emenuhit*; it will call *emouse* to update it. A Menu is a structure:

```
struct Menu
{
     char **item;
     char *(*gen)(int);
     int lasthit;
};
```

If item is nonzero, it should be a null-terminated array of the character strings to be displayed as menu items. Otherwise, gen should be a function that, given an item number, returns the character string for that item, or zero if the number is past the end of the list. Items are numbered starting at zero. *Menuhit* waits until *but* is released, and then returns the number of the selection, or -1 for no selection. The *m* argument is filled in with the final mouse event.

Emoveto moves the mouse cursor to the position p on the screen.

Esetcursor changes the cursor image to that described by the Cursor c (see *mouse*(2)). If c is nil, it restores the image to the default arrow.

Eenter provides a simple method of text input in graphical programs. It displays a box at the current position of the mouse cursor (passed in the Mouse *m argument) in which text can be typed and edited. If the string argument ask is not nil, it is displayed as a static label before the input string. The buf parameter contains the null-terminated input string to be edited. The len argument specifies the length of buf in bytes including the terminating null byte. If buf or len is zero, no text can be entered. On success, *eenter* returns the number of bytes in the edited string buf or -1 on error.

SOURCE

/sys/src/libdraw

SEE ALSO

rio(1), graphics(2), plumb(2), cons(3), draw(3)

```
exec, execl, _privates, _nprivates, _tos - execute a file
SYNOPSIS
     #include <u.h>
     #include <libc.h>
     int exec(char *name, char* argv[])
     int execl(char *name, ...)
     void **_privates;
     int _nprivates;
     #include <tos.h>
     typedef struct Tos Tos;
     struct Tos {
                                    /* profiling data */
/* cycle clock frequency */
          struct { ... } prof;
          uvlong cyclefreq;
                  kcycles;
                                    /* kernel cycles */
          vlong
                  pcycles;
          vlong
                                    /* process cycles (kernel + user) */
                                    /* process id */
          ulong
                  pid;
          ulong
                  clock;
                                    /* profiling clock */
          /* top of stack is here */
     };
```

extern Tos *_tos;

DESCRIPTION

Exec and *execl* overlay the calling process with the named file, then transfer to the entry point of the image of the file.

Name points to the name of the file to be executed; it must not be a directory, and the permissions must allow the current user to execute it (see stat(2)). It should also be a valid binary image, as defined in the *a.out*(6) for the current machine architecture, or a shell script (see rc(1)). The first line of a shell script must begin with #! followed by the name of the program to interpret the file and any initial arguments to that program, for example

#!/bin/rc
ls | mc

When a C program is executed, it is called as follows:

void main(int argc, char *argv[])

Argv is a copy of the array of argument pointers passed to *exec*; that array must end in a null pointer, and *argc* is the number of elements before the null pointer. By convention, the first argument should be the name of the program to be executed. *Execl* is like *exec* except that *argv* will be an array of the parameters that follow *name* in the call. The last argument to *execl* must be a null pointer.

For a file beginning #!, the arguments passed to the program (/bin/rc in the example above) will be the name of the file being executed, any arguments on the #! line, the name of the file again, and finally the second and subsequent arguments given to the original *exec* call. The result honors the two conventions of a program accepting as argument a file to be interpreted and $\argv[0]$ naming the file being executed.

Most attributes of the calling process are carried into the result; in particular, files remain open across *exec* (except those opened with OCEXEC OR'd into the open mode; see *open*(2)); and the working directory and environment (see *env*(3)) remain the same. However, a newly *exec'ed* process has no notification handler (see *notify*(2)).

The global cell _privates points to an array of _nprivates elements of per-process private data. This storage is private for each process, even if the processes share data segments.

When the new program begins, the global pointer _tos is set to the address of a structure that holds information allowing accurate time keeping and clock reading in user space. These data are

updated by the kernel during of the life of the process, including across *rforks* and *execs*. If there is a user-space accessible fast clock (a processor cycle counter), cyclefreq will be set to its frequency in Hz. Kcycles (pcycles) counts the number of cycles this process has spent in kernel mode (kernel and user mode). Pid is the current process's id. Clock is the user-profiling clock (see *prof*(1)). Its time is measured in milliseconds but is updated at a system-dependent lower rate. This clock is typically used by the profiler but is available to all programs.

The above conventions apply to C programs; the raw system interface to the new image is as follows: the word pointed to by the stack pointer is argc; the words beyond that are the zeroth and subsequent elements of argv, followed by a terminating null pointer; and the return register (e.g. R0 on the 68020) contains the address of the Tos structure.

SOURCE

/sys/src/libc/9syscall
/sys/src/libc/port/execl.c

SEE ALSO

prof(1), *intro*(2), *stat*(2)

DIAGNOSTICS

If these functions fail, they return and set *errstr*. There can be no return to the calling process from a successful *exec* or *execl*; the calling image is lost.

exits, _exits, atexit, atexitdont, terminate - terminate process, process cleanup

SYNOPSIS

```
#include <u.h>
#include <libc.h>
void _exits(char *msg)
void exits(char *msg)
int atexit(void(*)(void))
void atexitdont(void(*)(void))
```

DESCRIPTION

Exits is the conventional way to terminate a process. *_Exits* is the underlying system call. They can never return.

Msg conventionally includes a brief (maximum length ERRLEN) explanation of the reason for exiting, or a null pointer or empty string to indicate normal termination. The string is passed to the parent process, prefixed by the name and process id of the exiting process, when the parent does a *wait*(2).

Before calling _*exits* with *msg* as an argument, *exits* calls in reverse order all the functions recorded by *atexit*.

Atexit records *fn* as a function to be called by *exits*. It returns zero if it failed, nonzero otherwise. A typical use is to register a cleanup routine for an I/O package. To simplify programs that fork or share memory, *exits* only calls those *atexit*-registered functions that were registered by the same process as that calling *exits*.

Calling *atexit* twice (or more) with the same function argument causes *exits* to invoke the function twice (or more).

There is a limit to the number of exit functions that will be recorded; *atexit* returns 0 if that limit has been reached.

Atexitdont cancels a previous registration of an exit function.

SOURCE

/sys/src/libc/port/exits.c
/sys/src/libc/port/atexit.c

SEE ALSO

fork(2), wait(2)

exp, log, log10, pow, pow10, sqrt - exponential, logarithm, power, square root

SYNOPSIS

```
#include <u.h>
#include <libc.h>
double exp(double x)
double log(double x)
double log10(double x)
double pow(double x, double y)
double pow10(int n)
double sqrt(double x)
```

DESCRIPTION

Exp returns the exponential function of x.

Log returns the natural logarithm of x; log10 returns the base 10 logarithm.

Pow returns x^{γ} and *pow10* returns 10^{n} as a double.

Sqrt returns the square root of *x*.

SOURCE

All these routines have portable C implementations in /sys/src/libc/port. Most also have machine-dependent implementations, written either in assembler or C, in /sys/src/libc/\$objtype.

SEE ALSO

hypot(2), sinh(2), intro(2)

fauth - set up authentication on a file descriptor to a file server

SYNOPSIS

#include <u.h>
#include <libc.h>

int fauth(int fd, char *aname)

DESCRIPTION

Fauth is used to establish authentication for the current user to access the resources available through the 9P connection represented by fd. The return value is a file descriptor, conventionally called afd, that is subsequently used to negotiate the authentication protocol for the server, typically using *auth_proxy* or *fauth_proxy* (see *auth*(2)). After successful authentication, afd may be passed as the second argument to a subsequent mount call (see *bind*(2)), with the same *aname*, as a ticket-of-entry for the user.

If *fauth* returns -1, the error case, that means the file server does not require authentication for the connection, and afd should be set to -1 in the call to mount.

It is rare to use *fauth* directly; more commonly *amount* (see *auth*(2)) is used.

SOURCE

/sys/src/libc/9syscall

SEE ALSO

attach(5), auth(2) (particularly amount), authsrv(6), auth(8)

DIAGNOSTICS

Sets errstr.

Fcall, convS2M, convD2M, convM2S, convM2D, fcallfmt, dirfmt, dirmodefmt, read9pmsg, statcheck, sizeS2M, sizeD2M - interface to Plan 9 File protocol

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <fcall.h>
uint convS2M(Fcall *f, uchar *ap, uint nap)
uint convD2M(Dir *d, uchar *ap, uint nap)
uint convM2S(uchar *ap, uint nap, Fcall *f)
uint convM2D(uchar *ap, uint nap, Dir *d, char *strs)
int dirfmt(Fmt*)
int fcallfmt(Fmt*)
int dirmodefmt(Fmt*)
int read9pmsg(int fd, void *buf, uint nbuf)
int statcheck(uchar *buf, uint nbuf)
uint sizeS2M(Fcall *f)
uint sizeD2M(Dir *d)
```

DESCRIPTION

{

These routines convert messages in the machine-independent format of the Plan 9 file protocol, 9P, to and from a more convenient form, an Fcall structure:

```
#define MAXWELEM 16
```

```
typedef
struct Fcall
    uchar type;
    u32int
              fid:
    ushort
              tag;
    union {
          struct {
                                         /* Tversion, Rversion */
              u32int msize;
                                         /* Tversion, Rversion */
              char
                    *version;
          };
          struct {
              ushort oldtag;
                                         /* Tflush */
          };
          struct {
                                          /* Rerror */
              char
                      *ename;
          };
          struct {
                                         /* Rattach, Ropen, Rcreate */
              Qid
                      qid;
              u32int iounit;
                                         /* Ropen, Rcreate */
          };
          struct {
                                         /* Rauth */
              Qid
                      aqid;
          }:
          struct {
              u32int afid;
                                         /* Tauth, Tattach */
                                         /* Tauth, Tattach */
              char
                      *uname;
                                         /* Tauth, Tattach */
              char
                      *aname:
          };
```

```
struct {
              u32int perm;
                                          /* Tcreate */
                      *name;
                                          /* Tcreate */
              char
                                          /* Tcreate, Topen */
              uchar
                     mode:
          };
          struct {
              u32int newfid;
                                          /* Twalk */
                                          /* Twalk */
              ushort nwname:
                                         /* Twalk */
              char
                      *wname[MAXWELEM];
          };
          struct {
              ushort nwqid;
                                          /* Rwalk */
              Oid
                      wqid[MAXWELEM];
                                          /* Rwalk */
          };
          struct {
              vlong offset:
                                          /* Tread, Twrite */
                                         /* Tread, Twrite, Rread */
              u32int count;
              char
                      *data:
                                         /* Twrite, Rread */
          };
          struct {
              ushort nstat;
                                         /* Twstat, Rstat */
                                         /* Twstat, Rstat */
              uchar *stat;
          };
    }:
} Fcall;
/* these are implemented as macros */
uchar
          GBIT8(uchar*)
ushort
          GBIT16(uchar*)
ulong
          GBIT32(uchar*)
vlong
          GBIT64(uchar*)
void
          PBIT8(uchar*, uchar)
          PBIT16(uchar*, ushort)
void
void
          PBIT32(uchar*, ulong)
void
          PBIT64(uchar*, vlong)
#define
          BIT8SZ
                      1
#define
                      2
          BIT16SZ
#define
                      4
          BIT32SZ
#define
          BIT64SZ
                      8
```

This structure is defined in <fcall.h>. See section 5 for a full description of 9P messages and their encoding. For all message types, the type field of an Fcall holds one of Tversion, Rversion, Tattach, Rattach, etc. (defined in an enumerated type in <fcall.h>). Fid is used by most messages, and tag is used by all messages. The other fields are used selectively by the message types given in comments.

ConvM2S takes a 9P message at *ap* of length *nap*, and uses it to fill in Fcall structure *f*. If the passed message including any data for Twrite and Rread messages is formatted properly, the return value is the number of bytes the message occupied in the buffer *ap*, which will always be less than or equal to *nap*; otherwise it is 0. For Twrite and Tread messages, data is set to a pointer into the argument message, not a copy.

ConvS2M does the reverse conversion, turning f into a message starting at ap. The length of the resulting message is returned. For Twrite and Rread messages, count bytes starting at data are copied into the message.

The constant IOHDRSZ is a suitable amount of buffer to reserve for storing the 9P header; the data portion of a Twrite or Rread will be no more than the buffer size negotiated in the Tversion/Rversion exchange, minus IOHDRSZ.

The routine *sizeS2M* returns the number of bytes required to store the machine-independent representation of the Fcall structure f, including its initial 32-bit size field. In other words, it reports the number of bytes produced by a successful call to *convS2M*.

Another structure is Dir, used by the routines described in *stat*(2). *ConvM2D* converts the machine-independent form starting at *ap* into *d* and returns the length of the machine-independent encoding. The strings in the returned Dir structure are stored at successive locations starting at strs. Usually strs will point to storage immediately after the Dir itself. It can also be a nil pointer, in which case the string pointers in the returned Dir are all nil; however, the return value still includes their length.

ConvD2M does the reverse translation, also returning the length of the encoding. If the buffer is too short, the return value will be BIT16SZ and the correct size will be returned in the first BIT16SZ bytes. (If the buffer is less that BIT16SZ, the return value is zero; therefore a correct test for complete packing of the message is that the return value is greater than BIT16SZ). The macro GBIT16 can be used to extract the correct value. The related macros with different sizes retrieve the corresponding-sized quantities. PBIT16 and its brethren place values in messages. With the exception of handling short buffers in *convD2M*, these macros are not usually needed except by internal routines.

Analogous to *sizeS2M*, *sizeD2M* returns the number of bytes required to store the machineindependent representation of the Dir structure *d*, including its initial 16-bit size field.

The routine statcheck checks whether the *nbuf* bytes of *buf* contain a validly formatted machine-independent Dir entry suitable as an argument, for example, for the wstat (see *stat*(2)) system call. It checks that the sizes of all the elements of the entry sum to exactly *nbuf*, which is a simple but effective test of validity. *Nbuf* and *buf* should include the second two-byte (16-bit) length field that precedes the entry when formatted in a 9P message (see *stat*(5)); in other words, *nbuf* is 2 plus the sum of the sizes of the entry itself. *Statcheck* also verifies that the length field has the correct value (that is, *nbuf*-2). It returns 0 for a valid entry and -1 for an incorrectly formatted entry.

Dirfmt, fcallfmt, and dirmodefmt are formatting routines, suitable for fmtinstall(2). They convert Dir*, Fcall*, and long values into string representations of the directory buffer, Fcall buffer, or file mode value. Fcallfmt assumes that dirfmt has been installed with format letter D and dirmodefmt with format letter M.

Read9pmsg calls *read*(2) multiple times, if necessary, to read an entire 9P message into buf. The return value is 0 for end of file, or -1 for error; it does not return partial messages.

SOURCE

/sys/src/libc/9sys

SEE ALSO

intro(2), 9*p*(2), *stat*(2), *intro*(5)

fd2path - return file name associated with file descriptor

SYNOPSIS

#include <u.h>
#include <libc.h>
int fd2path(int fd, char *buf, int nbuf)

DESCRIPTION

As described in *intro*(2), the kernel stores a rooted path name with every open file or directory; typically, it is the name used in the original access of the file. *Fd2path* returns the path name associated with open file descriptor *fd*. Up to *nbuf* bytes of the name are stored in *buf*; if the name is too long, it will be silently truncated at a UTF-8 character boundary. The name is always null-terminated. The return value of *fd2path* will be zero unless an error occurs.

Changes to the underlying name space do not update the path name stored with the file descriptor. Therefore, the path returned by *fd2path* may no longer refer to the same file (or indeed any file) after some component directory or file in the path has been removed, renamed or rebound.

As an example, *getwd*(2) is implemented by opening . and executing *fd2path* on the resulting file descriptor.

SOURCE

/sys/src/libc/9syscall

SEE ALSO

bind(1), ns(1), bind(2), intro(2), getwd(2), proc(3)

DIAGNOSTICS

Sets errstr.

fgetc, getc, getchar, fputc, putc, putchar, ungetc, fgets, gets, fputs, puts, fread, fwrite - Stdio input and output

SYNOPSIS

```
#include <u.h>
#include <stdio.h>
int
    fgetc(FILE *f)
int
    getc(FILE *f)
int
    getchar(void)
    fputc(int c, FILE *f)
int
    putc(int c, FILE *f)
int
int
    putchar(int c)
int ungetc(int c, FILE *f)
char *fgets(char *s, int n, FILE *f)
char *gets(char *s)
    fputs(char *s, FILE *f)
int
int puts(char *s)
long fread(void *ptr, long itemsize, long nitems, FILE *stream)
long fwrite(void *ptr, long itemsize, long nitems, FILE *stream)
```

DESCRIPTION

The functions described here work on open Stdio streams (see fopen).

Fgetc returns as an int the next unsigned char from input stream *f*. If the stream is at end-of-file, the end-of-file indicator for the stream is set and *fgetc* returns EOF. If a read error occurs, the error indicator for the stream is set and *fgetc* returns EOF. *Getc* is like *fgetc* except that it is implemented as a macro. *Getchar* is like *getc* except that it always reads from stdin.

Ungetc pushes character c back onto the input stream f. The pushed-back character will be returned by subsequent reads in the reverse order of their pushing. A successful intervening *fseek*, *fsetpos*, or *rewind* on *f* discards any pushed-back characters for *f*. One character of pushback is guaranteed. Ungetc returns the character pushed back (converted to unsigned char), or EOF if the operation fails. A successful call to ungetc clears the end-of-file indicator for the stream. The file position indicator for the stream after reading or discarding all pushed-back characters is the same as it was before the characters were pushed back.

Fputc writes character c (converted to unsigned char) to output stream f at the position indicated by the position indicator for the stream and advances the indicator appropriately. If the file cannot support positioning requests, or if the stream was opened with append mode, the character is appended to the output stream. *Fputc* returns the character written or EOF if there was a write error. *Putc* is like *fputc* but is implemented as a macro. *Putchar* is like *putc* except that it always writes to stdout.

All other input takes place as if characters were read by successive calls to *fgetc* and all other output takes place as if characters were written by successive calls to *fputc*.

Fgets reads up to and including the next newline, but not past end-of-file or more than n-1 characters, from stream f into array s. A null character is written immediately after the last character read into the array (if any characters are read at all). Fgets returns s if successful, otherwise a null pointer. Gets is similar to fgets except that it always reads from stdin and it discards the terminating newline, if any. Gets does not check for overflow of the receiving array, so its use is deprecated.

Fputs writes the string s to stream f, returning EOF if a write error occurred, otherwise a nonnegative value. The terminating null character is not written. *Puts* is the same, writing to stdout.

Fread reads from the named input *stream* at most *nitems* of data of size *itemsize* and the type of **ptr* into a block beginning at *ptr*. It returns the number of items actually read.

Fwrite appends to the named output *stream* at most *nitems* of data of size *itemsize* and the type of **ptr* from a block beginning at *ptr*. It returns the number of items actually written.

SOURCE

/sys/src/libstdio

SEE ALSO

read(2), fopen(2), bio(2)

BUGS

Stdio does not handle UTF or runes; use Bio instead.

deflateinit, deflate, deflatezlib, deflateblock, deflatezlibblock, inflateinit, inflate, inflatezlib, inflateblock, inflatezlibblock, flateerr, mkcrctab, blockcrc, adler32 - deflate compression

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <flate.h>
      deflateinit(void)
int
      deflate(void *wr, int (*w)(void*,void*,int),
int
      void *rr, int (*r)(void*,void*,int),
      int level, int debug)
      deflatezlib(void *wr, int (*w)(void*,void*,int),
int
      void *rr, int (*r)(void*,void*,int),
      int level, int debug)
      deflateblock(uchar *dst, int dsize,
int
      uchar *src, int ssize,
      int level, int debug)
      deflatezlibblock(uchar *dst, int dsize,
int
      uchar *src, int ssize,
      int level, int debug)
      inflateinit(void)
int
int
      inflate(void *wr, int (*w)(void*, void*, int),
      void *getr, int (*get)(void*))
      inflatezlib(void *wr, int (*w)(void*, void*, int),
int
      void *getr. int (*get)(void*))
      inflateblock(uchar *dst, int dsize,
int
      uchar *src, int ssize)
      inflatezlibblock(uchar *dst, int dsize,
int
      uchar *src, int ssize)
char
      *flateerr(int error)
ulong *mkcrctab(ulong poly)
ulong blockcrc(ulong *tab, ulong crc, void *buf, int n)
ulong adler32(ulong adler, void *buf, int n)
```

DESCRIPTION

These routines compress and decompress data using the deflate compression algorithm, which is used for most gzip, zip, and zlib files.

Deflate compresses input data retrieved by calls to r with arguments rr, an input buffer, and a count of bytes to read. R should return the number of bytes read; end of input is signaled by returning zero, an input error by returning a negative number. The compressed output is written to w with arguments wr, the output data, and the number of bytes to write. W should return the number of bytes written; writing fewer than the requested number of bytes is an error. Level indicates the amount of computation deflate should do while compressing the data. Higher levels usually take more time and produce smaller outputs. Valid values are 1 to 9, inclusive; 6 is a good compromise. If debug is non-zero, cryptic debugging information is produced on standard error.

Inflate reverses the process, converting compressed data into uncompressed output. Input is retrieved one byte at a time by calling *get* with the argument *getr*. End of input is signaled by returning a negative value. The uncompressed output is written to *w*, which has the same interface as for *deflate*.

Deflateblock and inflateblock operate on blocks of memory but are otherwise similar to deflate and inflate.

The zlib functions are similar, but operate on files with a zlib header and trailer.

Deflateinit or inflateinit must be called once before any call to the corresponding routines.

If the above routines fail, they return a negative number indicating the problem. The possible values are *FlateNoMem*, *FlateInputFail*, *FlateOutputFail*, *FlateCorrupted*, and *FlateInternal*. *Flateerr* converts the number into a printable message. *FlateOk* is defined to be zero, the successful return value for *deflateinit*, *deflate*, *deflatezlib*, *inflateinit*, *inflate*, and *inflatezlib*. The block functions return the number of bytes produced when they succeed.

Mkcrctab allocates (using *malloc*(2)), initializes, and returns a table for rapid computation of 32 bit CRC values using the polynomial *poly*. *Blockcrc* uses *tab*, a table returned by *mkcrctab*, to update *crc* for the *n* bytes of data in *buf*, and returns the new value. *Crc* should initially be zero. *Blockcrc* pre-conditions and post-conditions *crc* by ones complementation.

Adler 32 updates the Adler 32-bit checksum of the *n* bytes of data in *buf*. The initial value of *adler* (that is, its value after seeing zero bytes) should be 1.

SOURCE

/sys/src/libflate

fabs, fmod, floor, ceil - absolute value, remainder, floor, ceiling functions

SYNOPSIS

#include <u.h>

#include <libc.h>

double floor(double x)

double ceil(double x)

double fabs(double x)

double fmod(double x, double y)

DESCRIPTION

Fabs returns the absolute value |x|.

Floor returns the largest integer not greater than *x*.

Ceil returns the smallest integer not less than *x*.

Fmod returns x if y is zero, otherwise the number f with the same sign as x, such that x = iy + f for some integer i, and |f| < |y|.

SOURCE

/sys/src/libc/port

SEE ALSO

abs(2), frexp(2)

FMTINSTALL(2)

NAME

fmtinstall, dofmt, dorfmt, fmtprint, fmtvprint, fmtrune, fmtstrcpy, fmtrunestrcpy, fmtfdinit, fmtfdflush, fmtstrinit, fmtstrflush, runefmtstrinit, runefmtstrflush, errfmt - support for user-defined print formats and output routines

SYNOPSIS

```
#include <u.h>
#include <libc.h>
typedef struct Fmt
                   Fmt;
struct Fmt{
                    /* output buffer is runes or chars? */
    uchar
            runes;
            *start; /* of buffer */
    void
                    /* current place in the buffer */
    void
            *to:
                   /* end of the buffer; overwritten if flush fails */
            *stop;
    void
            (*flush)(Fmt*);/* called when to == stop */
    int
            *farg; /* to make flush a closure */
    void
                    /* num chars formatted so far */
    int
            nfmt;
    va_list args;
                    /* args passed to dofmt */
    int
            r;
                    /* % format Rune */
    int
            width;
    int
            prec;
    ulong
            flags;
};
enum{
    FmtWidth
                = 1,
    FmtLeft
                = FmtWidth << 1,
    FmtPrec
                = FmtLeft << 1,
    FmtSharp
                = FmtPrec \ll 1,
    FmtSpace
                = FmtSharp << 1,
    FmtSign
                = FmtSpace << 1,
                = FmtSign \ll 1,
    FmtZero
    FmtUnsigned = FmtZero << 1,</pre>
                = FmtUnsigned << 1,
    FmtShort
    FmtLong
                = FmtShort << 1,
    FmtVLong
                = FmtLong << 1,
    FmtComma
                = FmtVLong << 1,
    FmtFlag
                = FmtComma << 1
};
      fmtfdinit(Fmt *f, int fd, char *buf, int nbuf);
int
      fmtfdflush(Fmt *f);
int
int
      fmtstrinit(Fmt *f);
char* fmtstrflush(Fmt *f);
int
      runefmtstrinit(Fmt *f);
Rune* runefmtstrflush(Fmt *f);
      fmtinstall(int c, int (*fn)(Fmt*));
int
      dofmt(Fmt *f, char *fmt);
int
      dorfmt(Fmt*, Rune *fmt);
int
      fmtprint(Fmt *f, char *fmt, ...);
int
      fmtvprint(Fmt *f, char *fmt, va_list v);
int
      fmtrune(Fmt *f, int r);
int
      fmtstrcpy(Fmt *f, char *s);
int
```

int fmtrunestrcpy(Fmt *f, Rune *s);

int errfmt(Fmt *f);

DESCRIPTION

The interface described here allows the construction of custom *print*(2) verbs and output routines. In essence, they provide access to the workings of the formatted print code.

The *print*(2) suite maintains its state with a data structure called Fmt. A typical call to *print*(2) or its relatives initializes a Fmt structure, passes it to subsidiary routines to process the output, and finishes by emitting any saved state recorded in the Fmt. The details of the Fmt are unimportant to outside users, except insofar as the general design influences the interface. The Fmt records whether the output is in runes or bytes, the verb being processed, its precision and width, and buffering parameters. Most important, it also records a *flush* routine that the library will call if a buffer overflows. When printing to a file descriptor, the flush routine will emit saved characters and reset the buffer; when printing to an allocated string, it will resize the string to receive more output. The flush routine is nil when printing to fixed-size buffers. User code need never provide a flush routine; this is done internally by the library.

Custom output routines

To write a custom output routine, such as an error handler that formats and prints custom error messages, the output sequence can be run from outside the library using the routines described here. There are two main cases: output to an open file descriptor and output to a string.

To write to a file descriptor, call *fmtfdinit* to initialize the local Fmt structure f, giving the file descriptor fd, the buffer *buf*, and its size *nbuf*. Then call *fmtprint* or *fmtvprint* to generate the output. These behave like fprint (see *print*(2)) or vfprint except that the characters are buffered until *fmtfdflush* is called and the return value is either 0 or -1. A typical example of this sequence appears in the Examples section.

The same basic sequence applies when outputting to an allocated string: call *fmtstrinit* to initialize the Fmt, then call *fmtprint* and *fmtvprint* to generate the output. Finally, *fmtstrflush* will return the allocated string, which should be freed after use. To output to a rune string, use *runefmtstrinit* and *runefmtstrflush*. Regardless of the output style or type, *fmtprint* or *fmtvprint* generates the characters.

Custom format verbs

Fmtinstall is used to install custom verbs and flags labeled by character c, which may be any non-zero Unicode character. *Fn* should be declared as

int fn(Fmt*)

 $Fp \rightarrow r$ is the flag or verb character to cause fn to be called. In fn, $fp \rightarrow width$, $fp \rightarrow prec$ are the width and precision, and $fp \rightarrow flags$ the decoded flags for the verb (see *print*(2) for a description of these items). The standard flag values are: FmtSign (+), FmtLeft (-), FmtSpace (' '), FmtSharp (#), FmtComma (,), FmtLong (1), FmtShort (h), FmtUnsigned (u), and FmtVLong (11). The flag bits FmtWidth and FmtPrec identify whether a width and precision were specified.

Fn is passed a pointer to the Fmt structure recording the state of the output. If $fp \rightarrow r$ is a verb (rather than a flag), *fn* should use Fmt \rightarrow args to fetch its argument from the list, then format it, and return zero. If $fp \rightarrow r$ is a flag, *fn* should return one. All interpretation of $fp \rightarrow$ width, $fp \rightarrow prec$, and $fp \rightarrow flags$ is left up to the conversion routine. *Fmtinstall* returns 0 if the installation succeeds, -1 if it fails.

Fmtprint and *fmtvprint* may be called to help prepare output in custom conversion routines. However, these functions clear the width, precision, and flags. Both functions return 0 for success and -1 for failure.

The functions *dofmt* and *dorfmt* are the underlying formatters; they use the existing contents of Fmt and should be called only by sophisticated conversion routines. These routines return the number of characters (bytes of UTF or runes) produced.

Some internal functions may be useful to format primitive types. They honor the width, precision and flags as described in *print*(2). *Fmtrune* formats a single character r. *Fmtstrcpy* formats a string s; *fmtrunestrcpy* formats a rune string s. *Errfmt* formats the system error string. All these routines return zero for successful execution. Conversion routines that call these functions will

work properly regardless of whether the output is bytes or runes.

2c(1) describes the C directive #pragma varargck that can be used to provide type-checking for custom print verbs and output routines.

EXAMPLES

This function prints an error message with a variable number of arguments and then quits. Compared to the corresponding example in *print*(2), this version uses a smaller buffer, will never truncate the output message, but might generate multiple write system calls to produce its output.

```
#pragma varargckargpos fatal 1
void
fatal(char *fmt, ...)
{
    Fmt f;
    char buf[64];
    va_list arg;
    fmtfdinit(&f, 1, buf, sizeof buf);
    fmtprint(&f, "fatal: ");
    va_start(arg, fmt);
    fmtvprint(&f, fmt, arg);
    va_end(arg);
    fmtprint(&f, "\n");
    fmtfdflush(&f);
    exits("fatal error");
}
```

}

This example adds a verb to print complex numbers.

```
typedef struct {
     double r, i;
} Complex;
#pragma varargcktype"X" Complex
int
Xfmt(Fmt *f)
{
     Complex c;
     c = va_arg(f->args, Complex);
return fmtprint(f, "(%g,%g)", c.r, c.i);
}
main(...)
{
     Complex x = (Complex) \{ 1.5, -2.3 \};
     fmtinstall('X', Xfmt);
     print("x = %X \setminus n", x);
}
```

SOURCE

```
/sys/src/libc/fmt
```

SEE ALSO

print(2), utf(6), errstr(2)

DIAGNOSTICS

These routines return negative numbers or nil for errors and set *errstr*.

fopen, freopen, fdopen, fileno, fclose, sopenr, sopenw, sclose, fflush, setvbuf, setbuf, fgetpos, ftell, fsetpos, fseek, rewind, feof, ferror, clearerr - standard buffered input/output package

SYNOPSIS

```
#include <u.h>
#include <stdio.h>
FILE *fopen(char *filename, char *mode)
FILE *freopen(char *filename, char *mode, FILE *f)
FILE *fdopen(int fd, char *mode)
int fileno(FILE *f)
FILE *sopenr(char *s)
FILE *sopenw(void)
char *sclose(FILE *f)
int fclose(FILE *f)
int fflush(FILE *f)
    setvbuf(FILE *f, char *buf, int type, long size)
int
void setbuf(FILE *f, char *buf)
int fgetpos(FILE *f, long *pos)
long ftell(FILE *f)
int
    fsetpos(FILE *f, long *pos)
    fseek(FILE *f, long offset, int whence)
int
void rewind(FILE *f)
    feof(FILE *f)
int
int ferror(FILE *f)
void clearerr(FILE *f)
```

DESCRIPTION

The functions described in this and related pages (*fgetc*(2), *fprintf*(2), *fscanf*(2), and *tmpfile*(2)) implement the ANSI C buffered I/O package with extensions.

A file with associated buffering is called a *stream* and is declared to be a pointer to a defined type FILE. *Fopen*(2) creates certain descriptive data for a stream and returns a pointer to designate the stream in all further transactions. There are three normally open streams with constant pointers declared in the include file and associated with the standard open files:

stdin standard input file stdout standard output file stderr standard error file

A constant pointer NULL designates no stream at all.

Fopen opens the file named by *filename* and associates a stream with it. *Fopen* returns a pointer to be used to identify the stream in subsequent operations, or NULL if the open fails. *Mode* is a character string having one of the following values:

- "r" open for reading
- "w" truncate to zero length or create for writing
- "a" append; open or create for writing at end of file
- "r+" open for update (reading and writing)
- "w+" truncate to zero length or create for update
- "a+" append; open or create for update at end of file

In addition, each of the above strings can have a b somewhere after the first character, meaning 'binary file', but this implementation makes no distinction between binary and text files.

Eclose causes the stream pointed to by f to be flushed (see below) and does a *close* (see *open*(2)) on the associated file. It frees any automatically allocated buffer. *Eclose* is called automatically on *exits*(2) for all open streams.

Freopen is like open except that it reuses stream pointer f. *Freopen* first attempts to close any file associated with f; it ignores any errors in that close.

Fdopen associates a stream with an open Plan 9 file descriptor.

Fileno returns the number of the Plan 9 file descriptor associated with the stream.

Sopenr associates a read-only stream with a null-terminated string.

Sopenw opens a stream for writing. No file descriptor is associated with the stream; instead, all output is written to the stream buffer.

Sclose closes a stream opened with *sopenr* or *sopenw*. It returns a pointer to the 0 terminated buffer associated with the stream.

By default, output to a stream is fully buffered: it is accumulated in a buffer until the buffer is full, and then *write* (see *read*(2)) is used to write the buffer. An exception is standard error, which is line buffered: output is accumulated in a buffer until a newline is written. Input is also fully buffered by default; this means that *read*(2) is used to fill a buffer as much as it can, and then characters are taken from that buffer until it empties. *Setvbuf* changes the buffering method for file *f* according to *type:* either _IOFBF for fully buffered, _IOLBF for line buffered, or _IONBF for unbuffered (each character causes a *read* or *write*). If *buf* is supplied, it is used as the buffer and *size* should be its size; If *buf* is zero, a buffer of the given size is allocated (except for the unbuffered case) using *malloc*(2).

Setbuf is an older method for changing buffering. If *buf* is supplied, it changes to fully buffered with the given buffer, which should be of size BUFSIZ (defined in stdio.h). If *buf* is zero, the buffering method changes to unbuffered.

Fflush flushes the buffer of output stream *f*, delivering any unwritten buffered data to the host file.

There is a *file position indicator* associated with each stream. It starts out pointing at the first character (unless the file is opened with append mode, in which case the indicator is always ignored). The file position indicator is maintained by the reading and writing functions described in *fgetc*(2).

Fgetpos stores the current value of the file position indicator for stream f in the object pointed to by *pos*. It returns zero on success, nonzero otherwise. *Ftell* returns the current value of the file position indicator. The file position indicator is to be used only as an argument to *fseek*.

Fsetpos sets the file position indicator for stream *f* to the value of the object pointed to by *pos*, which shall be a value returned by an earlier call to *fgetpos* on the same stream. It returns zero on success, nonzero otherwise. *Fseek* obtains a new position, measured in characters from the beginning of the file, by adding *offset* to the position specified by *whence*: the beginning of the file if *whence* is SEEK_SET; the current value of the file position indicator for SEEK_CUR; and the end-of-file for SEEK_END. *Rewind* sets the file position indicator to the beginning of the file.

An integer constant EOF is returned upon end of file or error by integer-valued functions that deal with streams. *Feof* returns non-zero if and only if f is at its end of file.

Ferror returns non-zero if and only if f is in the error state. It can get into the error state if a system call failed on the associated file or a memory allocation failed. *Clearerr* takes a stream out of the error state.

SOURCE

/sys/src/libstdio

SEE ALSO

fprintf(2), fscanf(2), fgetc(2)
open(2), read(2)

DIAGNOSTICS

The value EOF is returned uniformly to indicate that a FILE pointer has not been initialized with *fopen*, input (output) has been attempted on an output (input) stream, or a FILE pointer designates corrupt or otherwise unintelligible FILE data. Some of these functions set *errstr*.

470

BUGS

Buffering of output can prevent output data from being seen until long after it is computed - perhaps never, as when an abort occurs between buffer filling and flushing.

Buffering of input can cause a process to consume more input than it actually uses. This can cause trouble across *exec*(2).

Buffering may delay the receipt of a write error until a subsequent *stdio* writing, seeking, or file-closing call.

ANSI says that a file can be fully buffered only if the file is not attached to an interactive device. In Plan 9 all are fully buffered except standard error.

Fdopen, fileno, sopenr, sopenw, and sclose are not ANSI Stdio functions.

Stdio offers no support for runes or UTF characters. Unless external compatibility is necessary, use *bio*(2), which supports UTF and is smaller, faster, and simpler than Stdio.

fork, rfork - manipulate process resources

SYNOPSIS

#include <u.h>

#include <libc.h>

int fork(void)

int rfork(int flags)

DESCRIPTION

Forking is the only way new processes are created. The *flags* argument to *rfork* selects which resources of the invoking process (parent) are shared by the new process (child) or initialized to their default values. The resources include the file name space, the open file descriptor table (which, when shared, permits processes to open and close files for other processes), the set of environment variables (see env(3)), the note group (the set of processes that receive notes written to a member's notepg file; see proc(3)), the set of rendezvous tags (see *rendezvous*(2)); and open files. *Flags* is the logical OR of some subset of

RFPROC If set a new process is created; otherwise changes affect the current process.

- RFNOWAIT If set, the child process will be dissociated from the parent. Upon exit the child will leave no Waitmsg (see *wait*(2)) for the parent to collect.
- RFNAMEG If set, the new process inherits a copy of the parent's name space; otherwise the new process shares the parent's name space. Is mutually exclusive with RFCNAMEG.
- RFCNAMEG If set, the new process starts with a clean name space. A new name space must be built from a mount of an open file descriptor. Is mutually exclusive with RFNAMEG.
- RFNOMNT If set, subsequent mounts into the new name space and dereferencing of pathnames starting with # are disallowed.
- RFENVG If set, the environment variables are copied; otherwise the two processes share environment variables. Is mutually exclusive with RFCENVG.
- RFCENVG If set, the new process starts with an empty environment. Is mutually exclusive with RFENVG.
- RFNOTEG Each process is a member of a group of processes that all receive notes when a note is written to any of their notepg files (see *proc*(3)). The group of a new process is by default the same as its parent, but if RFNOTEG is set (regardless of RFPROC), the process becomes the first in a new group, isolated from previous processes.
- RFFDG If set, the invoker's file descriptor table (see *intro*(2)) is copied; otherwise the two processes share a single table.
- RFCFDG If set, the new process starts with a clean file descriptor table. Is mutually exclusive with RFFDG.
- RFREND If set, the process will be unable to *rendezvous*(2) with any of its ancestors; its children will, however, be able to rendezvous with it. In effect, RFREND makes the process the first in a group of processes that share a space for rendezvous tags.
- RFMEM If set, the child and the parent will share data and bss segments. Otherwise, the child inherits a copy of those segments. Other segment types, in particular stack segments, will be unaffected. May be set only with RFPROC.

File descriptors in a shared file descriptor table are kept open until either they are explicitly closed or all processes sharing the table exit.

If RFPROC is set, the value returned in the parent process is the process id of the child process; the value returned in the child is zero. Without RFPROC, the return value is zero. Process ids range from 1 to the maximum integer (int) value. *Rfork* will sleep, if necessary, until required process resources are available.

Fork is just a call of rfork(RFFDG|RFREND|RFPROC).

SOURCE

/sys/src/libc/9syscall
/sys/src/libc/9sys/fork.c

SEE ALSO

intro(2), proc(3),

DIAGNOSTICS

These functions set *errstr*.

fprintf, printf, sprintf, snprintf, vfprintf, vprintf, vsprintf, vsnprintf - print formatted output

SYNOPSIS

#include <u.h>
#include <u.h>
#include <stdio.h>
int fprintf(FILE *f, char *format, ...)
int printf(char *format, ...)
int sprintf(char *s, char *format, ...)
int snprintf(char *s, int n, char *format, ...)
int vfprintf(FILE *f, char *format, va_list args)
int vprintf(char *s, char *format, va_list args)
int vsprintf(char *s, int n, char *format, va_list args)
int vsnprintf(char *s, int n, char *format, va_list args)

DESCRIPTION

Fprintf places output on the named output stream f (see *fopen*(2)). *Printf* places output on the standard output stream *stdout*. *Sprintf* places output followed by the null character (\0) in consecutive bytes starting at s; it is the user's responsibility to ensure that enough storage is available. *Snprintf* is like *sprintf* but writes at most n bytes (including the null character) into s. *Vfprintf*, *vprintf*, *vsnprintf*, and *vsprintf* are the same, except the *args* argument is the argument list of the calling function, and the effect is as if the calling function's argument list from that point on is passed to the *printf* routines.

Each function returns the number of characters transmitted (not including the $\0$ in the case of *sprintf* and friends), or a negative value if an output error was encountered.

These functions convert, format, and print their trailing arguments under control of a *format* string. The *format* contains two types of objects: plain characters, which are simply copied to the output stream, and conversion specifications, each of which results in fetching of zero or more arguments. The results are undefined if there are arguments of the wrong type or too few arguments for the format. If the format is exhausted while arguments remain, the excess are ignored.

Each conversion specification is introduced by the character %. After the %, the following appear in sequence:

Zero or more *flags*, which modify the meaning of the conversion specification.

An optional decimal digit string specifying a minimum *field width*. If the converted value has fewer characters than the field width, it will be padded with spaces on the left (or right, if the left adjustment, described later, has been given) to the field width.

An optional *precision* that gives the minimum number of digits to appear for the d, i, o, u, x, and X conversions, the number of digits to appear after the decimal point for the e, E, and f conversions, the maximum number of significant digits for the g and G conversions, or the maximum number of characters to be written from a string in s conversion. The precision takes the form of a period (.) followed by an optional decimal integer; if the integer is omitted, it is treated as zero.

An optional h specifying that a following d, i, o, u, x or X conversion specifier applies to a short int or unsigned short argument (the argument will have been promoted according to the integral promotions, and its value shall be converted to short or unsigned short before printing); an optional h specifying that a following n conversion specifier applies to a pointer to a short argument; an optional l (ell) specifying that a following d, i, o, u, x, or X conversion character applies to a long or unsigned long argument; an optional l specifying that a following n conversion specifier applies to a long int argument; or an optional L specifying that a following e, E, f, g, or G conversion specifier applies to a long double argument. If an h, l, or L appears with any other conversion specifier, the behavior is undefined.

A character that indicates the type of conversion to be applied.

A field width or precision, or both, may be indicated by an asterisk (*) instead of a digit string. In this case, an int *arg* supplies the field width or precision. The arguments specifying field width or precision, or both, shall appear (in that order) before the argument (if any) to be converted. A negative field width argument is taken as a - flag followed by a positive field width. A negative precision is taken as if it were missing.

The flag characters and their meanings are:

- The result of the conversion is left-justified within the field.
- + The result of a signed conversion always begins with a sign (+ or –).
- blank If the first character of a signed conversion is not a sign, or a signed conversion results in no characters, a blank is prefixed to the result. This implies that if the blank and + flags both appear, the blank flag is ignored.
- # The result is to be converted to an "alternate form." For o conversion, it increases the precision to force the first digit of the result to be a zero. For x or X conversion, a non-zero result has 0x or 0X prefixed to it. For e, E, f, g, and G conversions, the result always contains a decimal point, even if no digits follow the point (normally, a decimal point appears in the result of these conversions only if a digit follows it). For g and G conversions, trailing zeros are *not* be removed from the result as they normally are. For other conversions, the behavior is undefined.
- 0 For d, i, o, u, x, X, e, E, f, g, and G conversions, leading zeros (following any indication of sign or base) are used to pad the field width; no space padding is performed. If the 0 and - flags both appear, the 0 flag will be ignored. For d, i, o, u, x, and X conversions, if a precision is specified, the 0 flag will be ignored. For other conversions, the behavior is undefined.

The conversion characters and their meanings are:

d,o,u,x,X

The integer *arg* is converted to signed decimal (d or i), unsigned octal (o), unsigned decimal (u), or unsigned hexadecimal notation (x or X); the letters abcdef are used for x conversion and the letters ABCDEF for X conversion. The precision specifies the minimum number of digits to appear; if the value being converted can be represented in fewer digits, it is expanded with leading zeros. The default precision is 1. The result of converting a zero value with a precision of zero is no characters.

- f The double argument is converted to decimal notation in the style [-]*ddd*.*ddd*, where the number of digits after the decimal point is equal to the precision specification. If the precision is missing, it is taken as 6; if the precision is explicitly 0, no decimal point appears.
- e,E The double argument is converted in the style $[-]d. ddde \pm dd$, where there is one digit before the decimal point and the number of digits after it is equal to the precision; when the precision is missing, it is taken as 6; if the precision is zero, no decimal point appears. The E format code produces a number with E instead of e introducing the exponent. The exponent always contains at least two digits.
- g,G The double argument is printed in style f or e (or in style E in the case of a G conversion specifier), with the precision specifying the number of significant digits. If an explicit precision is zero, it is taken as 1. The style used depends on the value converted: style e is used only if the exponent resulting from the conversion is less than -4 or greater than or equal to the precision. Trailing zeros are removed from the fractional portion of the result; a decimal point appears only if it is followed by a digit.
- c The int argument is converted to an unsigned char, and the resulting character is written.
- s The argument is taken to be a string (character pointer) and characters from the string are printed until a null character (\0) is encountered or the number of characters indicated by the precision specification is reached. If the precision is missing, it is taken to be infinite, so all characters up to the first null character are printed. A zero value for the argument yields undefined results.
- P The void* argument is printed in an implementation-defined way (for Plan 9: the address as hexadecimal number).
- n The argument shall be a pointer to an integer into which is *written* the number of characters written to the output stream so far by this call to *fprintf*. No argument is

converted.

% Print a %; no argument is converted.

If a conversion specification is invalid, the behavior is undefined.

If any argument is, or points to, a union or an aggregate (except for an array of character type using %s conversion, or a pointer cast to be a pointer to void using %P conversion), the behavior is undefined.

In no case does a nonexistent or small field width cause truncation of a field; if the result of a conversion is wider than the field width, the field is expanded to contain the conversion result.

SOURCE

/sys/src/libstdio

SEE ALSO

fopen(2), fscanf(2), print(2)

BUGS

There is no way to print a wide character (rune); use *print*(2) or *bio*(2).

frinit, frsetrects, frinittick, frclear, frcharofpt, frptofchar, frinsert, frdelete, frselect, frtick, frselectpaint, frdrawsel, frdrawsel0, frgetmouse - frames of text

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <draw.h>
#include <thread.h>
#include <mouse.h>
#include <frame.h>
void frinit(Frame *f, Rectangle r, Font *ft, Image *b, Image **cols)
      frsetrects(Frame *f, Rectangle r, Image *b)
void
void frinittick(Frame *f)
void frclear(Frame *f, int resize)
ulong frcharofpt(Frame *f, Point pt)
Point frptofchar(Frame *f, ulong p)
      frinsert(Frame *f, Rune *r0, Rune *r1, ulong p)
void
      frdelete(Frame *f, ulong p0, ulong p1)
int
void frselect(Frame *f, Mousectl *m)
      frtick(Frame *f, Point pt, int up)
void
void
      frselectpaint(Frame *f, Point p0, Point p1, Image *col)
void
      frdrawsel(Frame *f, Point pt0, ulong p0, ulong p1,
          int highlighted)
       frdrawsel0(Frame *f, Point pt0, ulong p0, ulong p1,
Point
          Image *back, Image *text)
enum{
     BACK,
     HIGH,
     BORD,
     TEXT,
     HTEXT,
     NCOL
};
```

DESCRIPTION

This library supports *frames* of editable text in a single font on raster displays, such as in sam(1) and rio(1). Frames may hold any character except NUL (0). Long lines are folded and tabs are at fixed intervals.

The user-visible data structure, a Frame, is defined in <frame.h>:

```
typedef struct Frame Frame;
struct Frame
{
                               /* of chars in the frame */
    Font
              *font:
    Display
                               /* on which frame appears */
              *display;
                               /* on which frame appears */
    Image
              *b:
              *cols[NCOL];
                               /* text and background colors */
    Image
                               /* in which text appears */
    Rectangle r;
                               /* of full frame */
    Rectangle entire;
    Frbox
              *box;
    ulong
              p0, p1;
                               /* selection */
              nbox, nalloc;
    ushort
                               /* max size of tab, in pixels */
    ushort
              maxtab;
```

ushort ushort ushort	<pre>nchars; nlines; maxlines;</pre>	/* /*	<pre># runes in frame */ # lines with text */ total # lines in frame */</pre>
ushort	lastlinefull;	/*	last line fills frame */
ushort	<pre>modified;</pre>	/*	<pre>changed since frselect() */</pre>
Image	<pre>*tick;</pre>	/*	typing tick */
Image	<pre>*tickback;</pre>	/*	saved image under tick */
int	<pre>ticked;</pre>	/*	<pre>flag: is tick onscreen? */</pre>

};

Frbox is an internal type and is not used by the interface. P0 and p1 may be changed by the application provided the selection routines are called afterwards to maintain a consistent display. *Maxtab* determines the size of tab stops. *Frinit* sets it to 8 times the width of a 0 (zero) character in the font; it may be changed before any text is added to the frame. The other elements of the structure are maintained by the library and should not be modified directly.

The text within frames is not directly addressable; instead frames are designed to work alongside another structure that holds the text. The typical application is to display a section of a longer document such as a text file or terminal session. Usually the program will keep its own copy of the text in the window (probably as an array of Runes) and pass components of this text to the frame routines to display the visible portion. Only the text that is visible is held by the Frame; the application must check maxlines, nlines, and lastlinefull to determine, for example, whether new text needs to be appended at the end of the Frame after calling *frdelete* (q.v.).

There are no routines in the library to allocate Frames; instead the interface assumes that Frames will be components of larger structures. *Frinit* prepares the Frame f so characters drawn in it will appear in the single Font ft. It then calls *frsetrects* and *frinittick* to initialize the geometry for the Frame. The Image b is where the Frame is to be drawn; Rectangle r defines the limit of the portion of the Image the text will occupy. The Image pointer may be null, allowing the other routines to be called to maintain the associated data structure in, for example, an obscured window.

The array of Images cols sets the colors in which text and borders will be drawn. The background of the frame will be drawn in cols[BACK]; the background of highlighted text in cols[HIGH]; borders and scroll bar in cols[BORD]; regular text in cols[TEXT]; and highlighted text in cols[HTEXT].

Frclear frees the internal structures associated with f, permitting another *frinit* or *frsetrects* on the Frame. It does not clear the associated display. If f is to be deallocated, the associated Font and Image must be freed separately. The resize argument should be non-zero if the frame is to be redrawn with a different font; otherwise the frame will maintain some data structures associated with the font.

To resize a Frame, use *frclear* and *frinit* and then *frinsert* (q.v.) to recreate the display. If a Frame is being moved but not resized, that is, if the shape of its containing rectangle is unchanged, it is sufficient to use *draw*(2) to copy the containing rectangle from the old to the new location and then call *frsetrects* to establish the new geometry. (It is unnecessary to call *frinittick* unless the font size has changed.) No redrawing is necessary.

Frames hold text as runes, not as bytes. *Frptofchar* returns the location of the upper left corner of the *p'th* rune, starting from 0, in the Frame *f*. If *f* holds fewer than *p* runes, *frptofchar* returns the location of the upper right corner of the last character in *f*. *Frcharofpt* is the inverse: it returns the index of the closest rune whose image's upper left corner is up and to the left of *pt*.

Frinsert inserts into Frame f starting at rune index p the runes between r0 and r1. If a NUL (0) character is inserted, chaos will ensue. Tabs and newlines are handled by the library, but all other characters, including control characters, are just displayed. For example, backspaces are printed; to erase a character, use *frdelete*.

Frdelete deletes from the Frame the text between p0 and p1; p1 points at the first rune beyond the deletion.

Frselect tracks the mouse to select a contiguous string of text in the Frame. When called, a mouse button is typically down. *Frselect* will return when the button state has changed (some buttons may still be down) and will set $f \rightarrow p0$ and $f \rightarrow p1$ to the selected range of text.

Programs that wish to manage the selection themselves have several routines to help. They involve the maintenance of the 'tick', the vertical line indicating a null selection between characters, and the colored region representing a non-null selection. *Frtick* draws (if *up* is non-zero) or removes (if *up* is zero) the tick at the screen position indicated by *pt*. *Frdrawsel* repaints a section of the frame, delimited by character positions p0 and p1, either with plain background or entirely highlighted, according to the flag *highlighted*, managing the tick appropriately. The point *pt0* is the geometrical location of p0 on the screen; like all of the selection-helper routines' Point arguments, it must be a value generated by *frptofchar*. *Frdrawsel0* is a lower-level routine, taking as arguments a background color, *back*, and text color, *text*. It assumes that the tick is being handled (removed beforehand, replaced afterwards, as required) by its caller. *Frselectpaint* uses a solid color, *col*, to paint a region of the frame defined by the Points p0 and p1.

SOURCE

/sys/src/libframe

SEE ALSO

graphics(2), draw(2), cachechars(2).

frexp, ldexp, modf - split into mantissa and exponent

SYNOPSIS

#include <u.h>
#include <libc.h>

double frexp(double value, int *eptr)

double ldexp(double value, int exp)

double modf(double value, double *iptr)

DESCRIPTION

Frexp returns the mantissa of *value* and stores the exponent indirectly through *eptr*, so that *value* = $frexp(value) \times 2^{(*eptr)}$

Ldexp returns the quantity *value*×2^{*exp*}.

Modf returns the signed fractional part of *value* and stores the integer part indirectly through *iptr*.

SOURCE

/sys/src/libc/port/frexp.c

SEE ALSO

intro(2)

DIAGNOSTICS

Ldexp returns 0 for underflow and the appropriately signed infinity for overflow.

fscanf, scanf, sscanf, vfscanf - scan formatted input

SYNOPSIS

```
#include <u.h>
#include <u.h>
#include <stdio.h>
int fscanf(FILE *f, char *format, ...)
int scanf(char *format, ... )
int sscanf(char *s, char *format, ...)
int vfscanf(FILE *stream, char *format, char *args)
```

DESCRIPTION

Fscanf reads from the named input stream f (see *fopen*(2)) under control of the string pointed to by *format* that specifies the admissible input sequences and how they are to be converted for assignment, using subsequent arguments as pointers to the objects to receive the converted input. If there are insufficient arguments for the format, the behavior is undefined. If the format is exhausted while arguments remain, the excess arguments are evaluated (as always) but are otherwise ignored.

Scanf and sscanf are the same, but they read from stdin and the character string s, respectively. Vfscanf is like scanf, except the args argument is a pointer to an argument in an argument list of the calling function and the effect is as if the calling function's argument list from that point on is passed to the scanf routines.

The format is composed of zero or more directives: one or more white-space characters; an ordinary character (not %); or a conversion specification. Each conversion specification is introduced by the character %. After the %, the following appear in sequence:

An optional assignment-suppressing character *.

An optional decimal integer that specifies the maximum field width.

An optional h, 1 (ell) or L indicating the size of the receiving object. The conversion specifiers d, i, and n shall be preceded by h if the corresponding argument is a pointer to short rather than a pointer to int, or by 1 if it is a pointer to long. Similarly, the conversion specifiers o, u, and x shall be preceded by h if the corresponding argument is a pointer to unsigned short rather than a pointer to unsigned, or by 1 if it is a pointer to unsigned long. Finally, the conversion specifiers e, f, and g shall be preceded by 1 if the corresponding argument is a pointer to double rather than a pointer to float, or by L if it is a pointer to long double. If an h, 1, or L appears with any other conversion specifier, the behavior is undefined.

A character that specifies the type of conversion to be applied. The valid conversion specifiers are described below.

Fscanf executes each directive of the format in turn. If a directive fails, as detailed below, *fscanf* returns. Failures are described as input failures (due to the unavailability of input), or matching failures (due to inappropriate input).

A directive composed of white space is executed by reading input up to the first non-white-space character (which remains unread), or until no more characters can be read.

A directive that is an ordinary character is executed by reading the next character from the stream. If if differs from the one comprising the directive, the directive fails, and the differing and subsequent characters remain unread.

A directive that is a conversion specification defines a set of matching input sequences, as described below for each specifier. A conversion specification is executed in the following steps:

Input white-space characters (as specified by *isspace*, see *ctype*(2)) are skipped, unless the specification includes a [, c, or n specifier.

An input item is read from the stream, unless the specification includes an n specifier. An input item is defined as the longest sequence of input characters (up to any specified maximum field width) which is an initial subsequence of a matching sequence. The first character, if any, after the

input item remains unread. If the length of the input item is zero, the execution of the directive fails: this condition is a matching failure, unless an error prevented input from the stream, in which case it is an input failure.

Except in the case of a % specifier, the input item (or, in the case of a %n directive, the count of input characters) is converted to a type appropriate to the conversion specifier. If the input item is not a matching sequence, the execution of the directive fails: this condition is a matching failure. Unless assignment suppression was indicated by a *, the result of the conversion is placed in the object pointed to by the first argument following the *format* argument that has not already received a conversion result. If this object does not have an appropriate type, or if the result of the conversion cannot be represented in the space provided, the behavior is undefined.

The following conversion specifiers are valid:

- d Matches an optionally signed decimal integer, whose format is the same as expected for the subject sequence of the *strtol* (see *atof*(2)) function with 10 for the base argument. The corresponding argument shall be a pointer to int.
- i Matches an optionally signed decimal integer, whose format is the same as expected for the subject sequence of the *strtol* function with 0 for the base argument. The corresponding argument shall be a pointer to int.
- o Matches an optionally signed octal integer, whose format is the same as expected for the subject sequence of the *strtoul* (see *atof*(2)) function with 8 for the base argument. The corresponding argument shall be a pointer to unsigned int.
- u Matches an optionally signed decimal integer, whose format is the same as expected for the subject sequence of the *strtoul* function with 10 for the base argument. The corresponding argument shall be a pointer to unsigned int.
- x Matches an optionally signed hexadecimal integer, whose format is the same as expected for the subject sequence of the *strtoul* function with 16 for the base argument. The corresponding argument shall be a pointer to unsigned int.

e,f,g

Matches an optionally signed floating-point number, whose format is the same as expected for the subject string of the *strtod* (see *atof*(2)) function. The corresponding argument shall be a pointer to float.

- s Matches a sequence of non-white-space characters. The corresponding argument shall be a pointer to the initial character of an array large enough to accept the sequence and a terminating NUL (0) character, which will be added automatically.
- [Matches a nonempty sequence of characters from a set of expected characters (the *scanset*). The corresponding argument shall be a pointer to the initial character of an array large enough to accept the sequence and a terminating NUL character, which will be added automatically. The conversion specifier includes all subsequent characters in the *format* string, up to and including the matching right brace (]). The characters between the brackets (the *scanlist*) comprise the scanset, unless the character after the left bracket is a circumflex (\land), in which case the scanset contains all characters that do not appear in the scanlist between the circumflex and the right bracket. As a special case, if the conversion specifier begins with [] or [\land], the right bracket character is in the scanlist and the next right bracket character is the matching right bracket that ends the specification. If a character is in the scanlist and is not the first, nor the second where the first character is a \land , nor the last character, the behavior is implementation–defined (in Plan 9: the scanlist includes all characters in the ASCII (sic) range between the two characters on either side of the –).
- c Matches a sequence of characters of the number specified by the field width (1 if no field width is present in the directive). The corresponding argument shall be a pointer to the initial character of an array large enough to accept the sequence. No NUL character is added.
- P Matches an implementation-defined set of sequences, which should be the same as the set of sequences that may be produced by the %P conversion of the *fprintf*(2) function (in Plan 9, a hexadecimal number). The corresponding argument shall be a pointer to a pointer to void. The interpretation of the input item is implementation defined; however, for any input item other than a value converted earlier during the same program execution, the behavior of the %P conversion is undefined.

- n No input is consumed. The corresponding argument shall be a pointer to integer into which is written the number of characters read from the input stream so far by this call to *fscanf*. Execution of a %n directive does not increment the assignment count returned at the completion of *fscanf*.
- % Matches a single %; no conversion or assignment occurs. The complete conversion specification shall be %%.

If a conversion specification is invalid, the behavior is undefined.

The conversion specifiers E, G, and X are also valid and behave the same as, respectively, e, g, and x.

If end-of-file is encountered during input, conversion is terminated. If end-of-file occurs before any characters matching the current directive have been read (other than leading white space, where permitted), execution of the current directive terminates with an input failure; otherwise, unless execution of the current directive is terminated with a matching failure, execution of the following directive (if any) is terminated with an input failure.

If conversion terminates on a conflicting input character, the offending input character is left unread in the input stream. Trailing white space (including newline characters) is left unread unless matched by a directive. The success of literal matches and suppressed assignments is not directly determinable other than via the %n directive.

The return value from *fscanf* is the number of input items assigned, which can be fewer than provided for, or even zero, in the event of an early matching failure. However, if an input failure occurs before any conversion, EOF is returned.

SOURCE

/sys/src/libstdio

SEE ALSO

fopen(2), fgetc(2)

BUGS

Does not know about UTF.

fversion - initialize 9P connection and negotiate version

SYNOPSIS

#include <u.h>
#include <libc.h>

int fversion(int fd, int bufsize, char *version, int nversion)

DESCRIPTION

Eversion is used to initialize the 9P connection represented by *fd* and to negotiate the version of the protocol to be used.

The *bufsize* determines the size of the I/O buffer used to stage 9P requests to the server, subject to the constraints of the server itself. The *version* is a text string that represents the highest version level the protocol will support. The *version* will be overwritten with the negotiated, possibly lower, version of the protocol. The return value of *fversion* is the length of the returned version string; the value of *nversion* is therefore not the length of the version string presented to the system call, but the total length of the buffer to accept the final result, in the manner of a read system call.

Default values of zero for *bufsize* and the empty string for *version* will negotiate sensible defaults for the connection. If *version* is the empty string, *nversion* must still be large enough to receive the returned version string.

The interpretation of the version strings is defined in *version*(5).

It is rare to use *fversion* directly; usually the default negotiation performed by the kernel during mount (see bind(2)) or even more commonly amount (see auth(2)) is sufficient.

SOURCE

/sys/src/libc/9syscall

SEE ALSO

intro(5), version(5), fauth(2).

DIAGNOSTICS

Sets errstr.

getcallerpc - fetch return PC of current function

SYNOPSIS

#include <u.h>
#include <libc.h>
wintata geteellerme(weid *finetere

uintptr getcallerpc(void *firstarg)

DESCRIPTION

Getcallerpc is a portable way to discover the PC to which the current function will return. *Firstarg* should be a pointer to the first argument to the function in question.

EXAMPLE

```
void
printpc(int arg)
{
    print("Called from %p\n", getcallerpc(&arg));
}
void
main(int argc, char *argv[])
{
    printpc(0);
    printpc(0);
    printpc(0);
}
```

SOURCE

```
/sys/src/libc/$objtype/getcallerpc.[cs]
```

BUGS

The *firstarg* parameter should not be necessary.

getenv, putenv - access environment variables

SYNOPSIS

#include <u.h>
#include <libc.h>
char* getenv(char *name)
int putenv(char *name, char *val)

DESCRIPTION

Getenv reads the contents of /env/name (see env(3)) into memory allocated with malloc(2), 0-terminates it, and returns a pointer to that area. If no file exists, 0 is returned.

Putenv creates the file /env/name and writes the string *val* to it. The terminating 0 is not written. If the file value cannot be written, -1 is returned.

SOURCE

/sys/src/libc/9sys

SEE ALSO

env(3)

DIAGNOSTICS

Sets errstr.

getfcr, setfcr, getfsr, setfsr - control floating point

SYNOPSIS

#include <u.h>

```
#include <libc.h>
```

ulong getfcr(void)

void setfcr(ulong fcr)

ulong getfsr(void)

void setfsr(ulong fsr)

DESCRIPTION

These routines provide a fairly portable interface to control the rounding and exception characteristics of IEEE 754 floating point units. In effect, they define a pair of pseudo-registers, the floating point control register, fcr, which affects rounding, precision, and exceptions, and the floating point status register, fsr, which holds the accrued exception bits. Each register has a *get* routine to retrieve its value, a *set* routine to modify it, and macros that identify its contents.

The fcr contains bits that, when set, halt execution upon exceptions: FPINEX (enable inexact exceptions), FPOVFL (enable overflow exceptions), FPUNFL (enable underflow exceptions), FPZDIV (enable zero divide exceptions), and FPINVAL (enable invalid operation exceptions). Rounding is controlled by installing in fcr, under mask FPRMASK, one of the values FPRNR (round to nearest), FPRZ (round towards zero), FPRPINF (round towards positive infinity), and FPRNINF (round towards negative infinity). Precision is controlled by installing in fcr, under mask FPPMASK, one of the values FPPEXT (extended precision), FPPSGL (single precision), and FPPDBL (double precision).

The fsr holds the accrued exception bits FPAINEX, FPAOVFL, FPAUNFL, FPAZDIV, and FPAINVAL, corresponding to the fsr bits without the A in the name.

Not all machines support all modes. If the corresponding mask is zero, the machine does not support the rounding or precision modes. On some machines it is not possible to clear selective accrued exception bits; a *setfsr* clears them all. The exception bits defined here work on all architectures. Where possible, the initial state is equivalent to

```
setfcr(FPPDBL|FPRNR|FPINVAL|FPZDIV|FPOVFL);
```

However, this may vary between architectures: the default is to provide what the hardware does most efficiently. Use these routines if you need guaranteed behavior. Also, gradual underflow is not available on some machines.

EXAMPLE

To enable overflow traps and make sure registers are rounded to double precision (for example on the MC68020, where the internal registers are 80 bits long):

setfcr((getfcr() & ~FPPMASK) | FPPDBL | FPOVFL);

SOURCE

/sys/src/libc/\$objtype/getfcr.s

getfields, gettokens, tokenize - break a string into fields

SYNOPSIS

DESCRIPTION

Getfields places into the array *args* pointers to the first *maxargs* fields of the null terminated UTF string *str*. Delimiters between these fields are set to null.

Fields are substrings of *str* whose definition depends on the value of *multiflag*. If *multiflag* is zero, adjacent fields are separated by exactly one delimiter. For example

getfields("#alice#bob##charles###", arg, 3, 0, "#");

yields three substrings: null-string, alice, and bob##charles###. If the *multiflag* argument is not zero, a field is a non-empty string of non-delimiters. For example

```
getfields("#alice#bob##charles###", arg, 3, 1, "#");
```

yields the three substrings: alice, bob, and charles###.

Getfields returns the number of fields pointed to.

Gettokens is the same as *getfields* with *multiflag* non-zero, except that fields may be quoted using single quotes, in the manner of rc(1). Any such quotes remain in the resulting *args*. See *quote*(2) for related quote-handling software.

Tokenize is similar to *gettokens* with *delims* set to "t r n ", except that quotes are interpreted but do not appear in the resulting *args*.

SOURCE

```
/sys/src/libc/port/getfields.c
/sys/src/libc/port/tokenize.c
```

SEE ALSO

strtok in strcat(2), quote(2).

getpid, getppid – get process ids

SYNOPSIS

#include <u.h>

#include <libc.h>

int getpid(void)

int getppid(void)

DESCRIPTION

Getpid returns the process id of the current process, a number guaranteed to be unique among all running processes on the machine executing *getpid*.

Getppid returns the process id of the parent of the current process.

SOURCE

/sys/src/libc/9sys

SEE ALSO

intro(2), exec(2), proc(3)

DIAGNOSTICS

Returns 0 and sets errstr if unsuccessful.

getuser, sysname – get user or system name

SYNOPSIS

#include <u.h>
#include <libc.h>
char* getuser(void)

char* sysname(void)

DESCRIPTION

Getuser returns a pointer to static data which contains the null-terminated name of the user who owns the current process. Getuser stats the file /proc/pid/status to find the name.

Sysname reads the file /dev/sysname, which contains the name of the machine. Unlike getuser, sysname caches the string, reading the file only once.

SOURCE

/sys/src/libc/9sys/getuser.c
/sys/src/libc/9sys/sysname.c

SEE ALSO

intro(2), proc(3), cons(3)

getwd - get current directory

SYNOPSIS

#include <u.h>
#include <libc.h>

char* getwd(char *buf, int size)

DESCRIPTION

Getwd fills buf with a null-terminated string representing the current directory and returns buf.

Getwd places no more than size bytes in the buffer provided.

SOURCE

/sys/src/libc/9sys/getwd.c

SEE ALSO

pwd(1), getwd(2), fd2path(2)

DIAGNOSTICS

On error, zero is returned. *Errstr*(2) may be consulted for more information.

BUGS

Although the name returned by *getwd* is guaranteed to be the path used to reach the directory, if the name space has changed underfoot, the name may be incorrect.

Display, Point, Rectangle, Cursor, initdraw, geninitdraw, newwindow, drawerror, initdisplay, closedisplay, getdefont, getwindow, gengetwindow, flushimage, bufimage, lockdisplay, unlockdisplay, openfont, buildfont, freefont, Pfmt, Rfmt, strtochan, chantostr, chantodepth - interactive graphics

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <draw.h>
#include <cursor.h>
int
      initdraw(void (*errfun)(Display*, char*), char *font,
         char *label)
      geninitdraw(char *devdir, void(*errfun)(Display*, char*),
int
         char *font, char *label, char *windir,
         int ref)
      newwindow(char *str)
int
void
      drawerror(Display *d, char *msg)
Display*initdisplay(char *devdir, char *win, void(*errfun)(Display*, char*))
void closedisplay(Display *d)
Subfont*getdefont(Display *d)
int
      flushimage(Display *d, int vis)
uchar*bufimage(Display *d, int n)
void lockdisplay(Display *d)
void unlockdisplay(Display *d)
      getwindow(Display *d, int ref)
int
int
      gengetwindow(Display *d, char *winname,
         Image **ip, Screen **sp, int ref)
Font* openfont(Display *d, char *name)
Font* buildfont(Display *d, char *desc, char *name)
void
      freefont(Font *f)
      Pfmt(Fmt*)
int
      Rfmt(Fmt*)
int
ulong strtochan(char *s)
char* chantostr(char *s, ulong chan)
int
      chantodepth(ulong chan)
extern Display *display
extern Image
               *screen
extern Screen
                *_screen
extern Font
               *font
```

DESCRIPTION

A Display structure represents a connection to the graphics device, *draw*(3), holding all graphics resources associated with the connection, including in particular raster image data in use by the client program. The structure is defined (in part) as:

```
typedef
struct Display
{
```

```
. . .
       (*error)(Display*, char*);
void
. . .
       *black:
Image
Image
       *white:
Image
       *opaque;
Image
       *transparent;
Image
       *image:
       *defaultfont;
Font
Subfont*defaultsubfont;
. . .
```

```
};
```

A Point is a location in an Image (see below and *draw*(2)), such as the display, and is defined as:

```
typedef
struct Point {
    int x;
    int y;
} Point;
```

The coordinate system has x increasing to the right and y increasing down.

A Rectangle is a rectangular area in an image.

```
typedef
struct Rectangle {
    Point min; /* upper left */
    Point max; /* lower right */
} Rectangle;
```

By definition, $\min.x \le \max.x$ and $\min.y \le \max.y$. By convention, the right (maximum x) and bottom (maximum y) edges are excluded from the represented rectangle, so abutting rectangles have no points in common. Thus, max contains the coordinates of the first point beyond the rectangle.

The Image data structure is defined in *draw*(2).

A Font is a set of character images, indexed by runes (see *utf*(6)). The images are organized into Subfonts, each containing the images for a small, contiguous set of runes. The detailed format of these data structures, which are described in detail in *cachechars*(2), is immaterial for most applications. Font and Subfont structures contain two interrelated fields: ascent, the distance from the top of the highest character (actually the top of the image holding all the characters) to the baseline, and height, the distance from the top of the highest character to the bottom of the lowest character (and hence, the interline spacing). See *cachechars*(2) for more details.

Buildfont parses the font description in the buffer desc, returning a Font* pointer that can be used by string (see draw(2)) to draw characters from the font. Openfont does the same, but reads the description from the named file. Freefont frees a font. The convention for naming font files is:

/lib/font/bit/name/range.size.font

where *size* is approximately the height in pixels of the lower case letters (without ascenders or descenders). *Range* gives some indication of which characters will be available: for example ascii, latin1, euro, or unicode. Euro includes most European languages, punctuation marks, the International Phonetic Alphabet, etc., but no Oriental languages. Unicode includes every character for which appropriate-sized images exist on the system.

A Cursor is defined:

```
typedef struct
Cursor {
    Point offset;
    uchar clr[2*16];
    uchar set[2*16];
} Cursor;
```

The arrays are arranged in rows, two bytes per row, left to right in big-endian order to give 16 rows of 16 bits each. A cursor is displayed on the screen by adding offset to the current mouse position, using clr as a mask to draw white at the pixels where clr is one, and then drawing black at the pixels where set is one. *Setcursor* and *moveto* (see *mouse*(2)) and *esetcursor* and *emoveto* (see *event*(2)) change the cursor image and its location on the screen.

The routine *initdraw* connects to the display; it returns -1 if it fails and sets the error string. *Initdraw* sets up the global variables display (the Display structure representing the connection), screen (an Image representing the display memory itself or, if rio(1) is running, the client's window), and font (the default font for text). The arguments to *initdraw* include a *label*, which is written to /dev/label if non-nil so that it can be used to identify the window when hidden (see rio(1)). The font is created by reading the named *font* file. If font is null, *initdraw* reads the file named in the environment variable \$font; if \$font is not set, it imports the default (usually minimal) font from the operating system. The global *font* will be set to point to the resulting Font structure. The *errfun* argument is a *graphics error function* to call in the event of a fatal error in the library; it must never return. Its arguments are the display pointer and an error string. If *errfun* is nil, the library provides a default, called *drawerror*. Another effect of *initdraw* is that it installs *print*(2) formats *Pfmt* and *Rfmt* as %P and %R for printing Points and Rectangles.

The *geninitdraw* function provides a less automated way to establish a connection, for programs that wish to connect to multiple displays. *Devdir* is the name of the directory containing the device files for the display (if nil, default /dev); *errfun*, *font*, and *label* are as in *initdraw*; *windir* is the directory holding the winname file; and *ref* specifies the refresh function to be used to create the window, if running under *rio*(1) (see *window*(2)).

The function *newwindow* may be called before *initdraw* or *geninitdraw* to cause the program to occupy a newly created window rather than take over the one in which it is running when it starts. The *str* argument, if non-null, is concatenated to the string "new " that is used to create the window (see *rio*(4)). For example, newwindow("-hide -dy 100") will cause the program to run in a newly created, hidden window 100 pixels high.

Initdisplay is part of *geninitdraw*; it sets up the display structures but does not allocate any fonts or call *getwindow*. The arguments are similar to those of *initdraw*; *win* names the directory, default /dev, in which the files associated with the window reside. *Closedisplay* disconnects the display and frees the associated data structures. *Getdefont* builds a Subfont structure from in-core data describing a default subfont. None of these routines are needed by most programs, since *initdraw* calls them as needed.

The data structures associated with the display must be protected in a multi-process program, because they assume only one process will be using them at a time. Multi-process programs should set display->locking to 1, to notify the library to use a locking protocol for its own accesses, and call *lockdisplay* and *unlockdisplay* around any calls to the graphics library that will cause messages to be sent to the display device. *Initdraw* and *geninitdraw* initialize the display to the locked state.

Getwindow returns a pointer to the window associated with the application; it is called automatically by *initdraw* to establish the screen pointer but must be called after each resizing of the window to restore the library's connection to the window. If rio is not running, it returns display->image; otherwise it negotiates with rio by looking in /dev/winname to find the name of the window and opening it using namedimage (see *allocimage*(2)). The resulting window will be created using the refresh method *ref* (see *window*(2)); this should almost always be Refnone because rio provides backing store for the window.

Getwindow overwrites the global variables screen, a pointer to the Image defining the window (or the overall display, if no window system is running); and _screen, a pointer to the Screen representing the root of the window's hierarchy. (See *window*(2). The overloading of the screen word is an unfortunate historical accident.) *Getwindow* arranges that screen point to the portion of the window inside the border; sophisticated clients may use _screen to make further subwindows. Programs desiring multiple independent windows may use the mechanisms of *rio*(4) to create more windows (usually by a fresh mount of the window sytem in a directory other than /dev), then use *gengetwindow* to connect to them. *Gengetwindow*'s extra arguments are the full path of the window's winname file and pointers to be overwritten with the values of the 'global' Image and Screen variables for the new window. The graphics functions described in draw(2), allocimage(2), cachechars(2), and subfont(2) are implemented by writing commands to files under /dev/draw (see draw(3)); the writes are buffered, so the functions may not take effect immediately. *Flushimage* flushes the buffer, doing all pending graphics operations. If *vis* is non-zero, any changes are also copied from the 'soft screen' (if any) in the driver to the visible frame buffer. The various allocation routines in the library flush automatically, as does the event package (see *event*(2)); most programs do not need to call *flushimage*. It returns -1 on error.

Bufimage is used to allocate space for *n* bytes in the display buffer. It is used by all the graphics routines to send messages to the display.

The functions *strtochan* and *chantostr* convert between the channel descriptor strings used by *image*(6) and the internal ulong representation used by the graphics protocol (see *draw*(3)'s b message). Chantostr writes at most nine bytes into the buffer pointed at by *s* and returns *s* on success, 0 on failure. Chantodepth returns the number of bits per pixel used by the format specified by *chan*. Both chantodepth and strtochan return 0 when presented with bad input.

EXAMPLES

To reconnect to the window after a resize event,

```
if(getwindow(display, Refnone) < 0)
    sysfatal("resize failed: %r");</pre>
```

To create and set up a new *rio*(1) window,

```
Image *screen2;
Screen *_screen2;
srvwsys = getenv("wsys");
if(srvwsys == nil)
    sysfatal("can't find $wsys: %r");
rfork(RFNAMEG); /* keep mount of rio private */
fd = open(srvwsys, ORDWR);
if(fd < 0)
    sysfatal("can't open $wsys: %r");
/* mount creates window; see rio(4) */
if(mount(fd, -1, "/tmp", MREPL, "new -dx 300-dy 200") < 0)
    sysfatal("can't mount new window: %r");
if(gengetwindow(display, "/tmp/winname",
   &screen2, &_screen2, Refnone) < 0)</pre>
    sysfatal("resize failed: %r");
/* now open /tmp/cons, /tmp/mouse */
. . .
```

FILES

/lib/font/bit directory of fonts

SOURCE

/sys/src/libdraw

SEE ALSO

rio(1), addpt(2), allocimage(2), cachechars(2), subfont(2), draw(2), event(2), frame(2), print(2), window(2), draw(3), rio(4), image(6), font(6)

DIAGNOSTICS

An error function may call *errstr*(2) for further diagnostics.

BUGS

The names clr and set in the Cursor structure are reminders of an archaic color map and might be more appropriately called white and black.

parsehtml, printitems, validitems, freeitems, freedocinfo, dimenkind, dimenspec, targetid, targetname, fromStr, toStr - HTML parser

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <html.h>
Item*
       parsehtml(uchar* data, int datalen, Rune* src, int mtype,
       int chset, Docinfo** pdi)
void
       printitems(Item* items, char* msg)
int
       validitems(Item* items)
void
       freeitems(Item* items)
void
       freedocinfo(Docinfo* d)
       dimenkind(Dimen d)
int
int
       dimenspec(Dimen d)
       targetid(Rune* s)
int
       targetname(int targid)
Rune*
uchar* fromStr(Rune* buf, int n, int chset)
       toStr(uchar* buf, int n, int chset)
Rune*
```

DESCRIPTION

This library implements a parser for HTML 4.0 documents. The parsed HTML is converted into an intermediate representation that describes how the formatted HTML should be laid out.

Parsehtml parses an entire HTML document contained in the buffer *data* and having length *datalen*. The URL of the document should be passed in as *src*. *Mtype* is the media type of the document, which should be either TextHtml or TextPlain. The character set of the document is described in *chset*, which can be one of US_Ascii, ISO_8859_1, UTF_8 or Unicode. The return value is a linked list of Item structures, described in detail below. As a side effect, * *pdi* is set to point to a newly created Docinfo structure, containing information pertaining to the entire document.

The library expects two allocation routines to be provided by the caller, emalloc and erealloc. These routines are analogous to the standard malloc and realloc routines, except that they should not return if the memory allocation fails. In addition, emalloc is required to zero the memory.

For debugging purposes, *printitems* may be called to display the contents of an item list; individual items may be printed using the %I print verb, installed on the first call to *parsehtml*. *validitems* traverses the item list, checking that all of the pointers are valid. It returns 1 is everything is ok, and 0 if an error was found. Normally, one would not call these routines directly. Instead, one sets the global variable *dbgbuild* and the library calls them automatically. One can also set *warn*, to cause the library to print a warning whenever it finds a problem with the input document, and *dbglex*, to print debugging information in the lexer.

When an item list is finished with, it should be freed with *freeitems*. Then, *freedocinfo* should be called on the pointer returned in * *pdi*.

Dimenkind and dimenspec are provided to interpret the Dimen type, as described in the section Dimension Specifications.

Frame target names are mapped to integer ids via a global, permanent mapping. To find the value for a given name, call *targetid*, which allocates a new id if the name hasn't been seen before. The name of a given, known id may be retrieved using *targetname*. The library predefines FTtop, FTself, FTparent and FTblank.

The library handles all text as Unicode strings (type Rune*). Character set conversion is provided by *fromStr* and *toStr*. *FromStr* takes *n* Unicode characters from *buf* and converts them to the

character set described by *chset*. *ToStr* takes *n* bytes from *buf*, interpretted as belonging to character set *chset*, and converts them to a Unicode string. Both routines null-terminate the result, and use emalloc to allocate space for it.

ltems

The return value of *parsehtml* is a linked list of variant structures, with the generic portion described by the following definition:

```
typedef struct Item Item;
struct Item
{
    Item*
              next;
    int
              width:
    int
              height;
    int
              ascent;
    int
              anchorid;
    int
              state;
    Genattr* genattr;
    int
              tag;
```

};

The field next points to the successor in the linked list of items, while width, height, and ascent are intended for use by the caller as part of the layout process. Anchorid, if non-zero, gives the integer id assigned by the parser to the anchor that this item is in (see section Anchors). State is a collection of flags and values described as follows:

enum {

IFbrk =	0x80000000,
IFbrksp =	0x40000000,
IFnobrk =	0x20000000,
IFcleft =	0x10000000,
IFcright =	0x08000000,
IFwrap =	0x04000000,
IFhang =	0x02000000,
IFrjust =	0x01000000,
IFcjust =	0x00800000,
IFsmap =	0x00400000,
IFindentshift =	8,
IFindentmask =	(255< <ifindentshift),< td=""></ifindentshift),<>
IFhangmask =	255
•	

};

IFbrk is set if a break is to be forced before placing this item. IFbrksp is set if a 1 line space should be added to the break (in which case IFbrk is also set). IFnobrk is set if a break is not permitted before the item. IFcleft is set if left floats should be cleared (that is, if the list of pending left floats should be placed) before this item is placed, and IFcright is set for right floats. In both cases, IFbrk is also set. IFwrap is set if the line containing this item is allowed to wrap. IFhang is set if this item hangs into the left indent. IFrjust is set if the line containing this item should be right justified, and IFcjust is set for center justified lines. IFsmap is used to indicate that an image is a server-side map. The low 8 bits, represented by IFhangmask, indicate the current hang into left indent, in tenths of a tabstop. The next 8 bits, represented by IFindentmask and IFindentshift, indicate the current indent in tab stops.

The field genattr is an optional pointer to an auxiliary structure, described in the section *Generic Attributes*.

Finally, tag describes which variant type this item has. It can have one of the values Itexttag, Iruletag, Iimagetag, Iformfieldtag, Itabletag, Ifloattag or Ispacertag. For each of these values, there is an additional structure defined, which includes Item as an unnamed initial substructure, and then defines additional fields.

Items of type Itexttag represent a piece of text, using the following structure:

```
struct Itext
{
    Item:
    Rune* s:
    int
           fnt;
    int
           fg;
    uchar voff;
    uchar ul:
};
```

Here s is a null-terminated Unicode string of the actual characters making up this text item, fnt is the font number (described in the section *Font Numbers*), and fg is the RGB encoded color for the text. Voff measures the vertical offset from the baseline; subtract Voffbias to get the actual value (negative values represent a displacement down the page). The field u1 is the underline style: ULnone if no underline, ULunder for conventional underline, and ULmid for strikethrough.

Items of type Iruletag represent a horizontal rule, as follows:

```
struct Irule
{
    Item;
    uchar align;
    uchar noshade;
    int
           size;
    Dimen wspec;
```

}:

Here align is the alignment specification (described in the corresponding section), noshade is set if the rule should not be shaded, size is the height of the rule (as set by the size attribute), and wspec is the desired width (see section *Dimension Specifications*).

Items of type Iimagetag describe embedded images, for which the following structure is defined:

```
struct Iimage
{
    Item;
    Rune*
             imsrc;
    int
             imwidth;
    int
             imheight;
    Rune*
             altrep;
             map;
    Map*
    int
             ctlid;
    uchar
             align;
    uchar
             hspace;
    uchar
             vspace;
    uchar
             border;
    Iimage* nextimage;
```

};

Here imsrc is the URL of the image source, imwidth and imheight, if non-zero, contain the specified width and height for the image, and altrep is the text to use as an alternative to the image, if the image is not displayed. Map, if set, points to a structure describing an associated client-side image map. Ctlid is reserved for use by the application, for handling animated images. Align encodes the alignment specification of the image. Hspace contains the number of pixels to pad the image with on either side, and Vspace the padding above and below. Border is the width of the border to draw around the image. Nextimage points to the next image in the document (the head of this list is Docinfo.images).

For items of type Iformfieldtag, the following structure is defined:

struct Iformfield { Item;

```
Formfield* formfield;
```

};

This adds a single field, formfield, which points to a structure describing a field in a form, described in section *Forms*.

For items of type Itabletag, the following structure is defined:

```
struct Itable
{
    Item;
    Table* table;
.
```

};

Table points to a structure describing the table, described in the section *Tables*.

For items of type Ifloattag, the following structure is defined:

```
struct Ifloat
{
    Item;
    Item* item;
    int x;
    int y;
    uchar side;
    uchar infloats;
    Ifloat* nextfloat;
}
```

};

The item points to a single item (either a table or an image) that floats (the text of the document flows around it), and side indicates the margin that this float sticks to; it is either ALleft or ALright. X and y are reserved for use by the caller; these are typically used for the coordinates of the top of the float. Infloats is used by the caller to keep track of whether it has placed the float. Nextfloat is used by the caller to link together all of the floats that it has placed.

For items of type Ispacertag, the following structure is defined:

```
struct Ispacer
{
    Item;
    int spkind;
}
```

};

Spkind encodes the kind of spacer, and may be one of ISPnull (zero height and width), ISPvline (takes on height and ascent of the current font), ISPhspace (has the width of a space in the current font) and ISPgeneral (for all other purposes, such as between markers and lists).

Generic Attributes

The genattr field of an item, if non-nil, points to a structure that holds the values of attributes not specific to any particular item type, as they occur on a wide variety of underlying HTML tags. The structure is as follows:

```
typedef struct Genattr Genattr;
struct Genattr
{
    Rune* id;
    Rune* class;
    Rune* style;
    Rune* title;
    SEvent* events;
```

};

Fields id, class, style and title, when non-nil, contain values of correspondingly named attributes of the HTML tag associated with this item. Events is a linked list of events (with corresponding scripted actions) associated with the item:

```
typedef struct SEvent SEvent;
struct SEvent
{
    SEvent* next:
    int
            type;
    Rune*
            script;
```

}:

Here, next points to the next event in the list, type is one of SEonblur, SEonchange, SEonclick, SEondblclick, SEonfocus, SEonkeypress, SEonkeyup, SEonload, SEonmousedown, SEonmousemove, SEonmouseout, SEonmouseover, SEonmouseup, SEonreset, SEonselect, SEonsubmit or SEonunload, and script is the text of the associated script.

Dimension Specifications

Some structures include a dimension specification, used where a number can be followed by a % or a * to indicate percentage of total or relative weight. This is encoded using the following structure:

```
typedef struct Dimen Dimen;
struct Dimen
{
    int kindspec;
```

};

Separate kind and spec values are extracted using dimenkind and dimenspec. Dimenkind returns one of Dnone, Dpixels, Dpercent or Drelative. Dnone means that no dimension was specified. In all other cases, *dimenspec* should be called to find the absolute number of pixels, the percentage of total, or the relative weight.

Background Specifications

It is possible to set the background of the entire document, and also for some parts of the document (such as tables). This is encoded as follows:

```
typedef struct Background Background;
struct Background
{
    Rune* image;
    int
          color;
};
```

Image, if non-nil, is the URL of an image to use as the background. If this is nil, color is used instead, as the RGB value for a solid fill color.

Alignment Specifications

Certain items have alignment specifiers taken from the following enumerated type:

```
enum
{
    ALnone = 0, ALleft, ALcenter, ALright, ALjustify,
    ALchar, ALtop, ALmiddle, ALbottom, ALbaseline
```

};

These values correspond to the various alignment types named in the HTML 4.0 standard. If an item has an alignment of ALleft or ALright, the library automatically encapsulates it inside a float item.

Tables, and the various rows, columns and cells within them, have a more complex alignment specification, composed of separate vertical and horizontal alignments:

```
typedef struct Align Align;
struct Align
{
    uchar halign;
    uchar valign;
};
```

Halign can be one of ALnone, ALleft, ALcenter, ALright, ALjustify or ALchar. Valign can be one of ALnone, ALmiddle, ALbottom, ALtop or ALbaseline.

Font Numbers

Text items have an associated font number (the fnt field), which is encoded as style *NumSize+size. Here, style is one of FntR, FntI, FntB or FntT, for roman, italic, bold and typewriter font styles, respectively, and size is Tiny, Small, Normal, Large or Verylarge. The total number of possible font numbers is NumFnt, and the default font number is DefFnt (which is roman style, normal size).

Document Info

Global information about an HTML page is stored in the following structure:

```
typedef struct Docinfo Docinfo;
struct Docinfo
{
    // stuff from HTTP headers, doc head, and body tag
    Rune*
                 src:
    Rune*
                 base;
    Rune*
                 doctitle;
    Background
                 background:
    Iimage*
                 backgrounditem;
    int
                 text;
    int
                 link;
    int
                 vlink;
    int
                 alink;
    int
                 target:
    int
                 chset;
    int
                 mediatype;
                 scripttype;
    int
                 hasscripts;
    int
    Rune*
                 refresh;
    Kidinfo*
                 kidinfo;
                 frameid;
    int
    // info needed to respond to user actions
    Anchor*
                 anchors;
    DestAnchor* dests;
    Form*
                 forms:
    Table*
                 tables;
    Map*
                 maps;
    Iimage*
                 images;
};
```

Src gives the URL of the original source of the document, and base is the base URL. Doctitle is the document's title, as set by a <title> element. Background is as described in the section *Background Specifications*, and backgrounditem is set to be an image item for the document's background image (if given as a URL), or else nil. Text gives the default foregound text color of the document, link the unvisited hyperlink color, vlink the visited hyperlink color, and alink the color for highlighting hyperlinks (all in 24-bit RGB format). Target is the default target frame id. Chset and mediatype are as for the chset and mtype parameters to parsentml. Scripttype is the type of any scripts contained in the document, and is always TextJavascript. Hasscripts is set if the document contains any scripts. Scripting is currently unsupported. Refresh is the contents of a <meta http-equiv=Refresh ...> tag, if any. Kidinfo is set if this document is a frameset (see section *Frames*). Frameid is this document's frame id.

Anchors is a list of hyperlinks contained in the document, and dests is a list of hyperlink destinations within the page (see the following section for details). Forms, tables and maps are lists of the various forms, tables and client-side maps contained in the document, as described in subsequent sections. Images is a list of all the image items in the document.

Anchors

The library builds two lists for all of the $\langle a \rangle$ elements (anchors) in a document. Each anchor is assigned a unique anchor id within the document. For anchors which are hyperlinks (the href attribute was supplied), the following structure is defined:

```
typedef struct Anchor Anchor;
struct Anchor
{
    Anchor* next;
    int index;
    Rune* name;
    Rune* href;
    int target;
```

};

Next points to the next anchor in the list (the head of this list is Docinfo.anchors). Index is the anchor id; each item within this hyperlink is tagged with this value in its anchorid field. Name and href are the values of the correspondingly named attributes of the anchor (in particular, href is the URL to go to). Target is the value of the target attribute (if provided) converted to a frame id.

Destinations within the document (anchors with the name attribute set) are held in the Docinfo.dests list, using the following structure:

typedef struct DestAnchor DestAnchor; struct DestAnchor
{
 DestAnchor* next;
 int index;
 Rune* name;
 Item* item;

};

Next is the next element of the list, index is the anchor id, name is the value of the name attribute, and item is points to the item within the parsed document that should be considered to be the destination.

Forms

Any forms within a document are kept in a list, headed by Docinfo.forms. The elements of this list are as follows:

```
typedef struct Form Form;
struct Form
{
    Form*
                next;
    int
                formid:
    Rune*
                name;
    Rune*
                action;
    int
                target;
    int
                method;
    int
                nfields;
    Formfield* fields;
```

};

Next points to the next form in the list. Formid is a serial number for the form within the document. Name is the value of the form's name or id attribute. Action is the value of any action attribute. Target is the value of the target attribute (if any) converted to a frame target id. Method is one of HGet or HPost. Nfields is the number of fields in the form, and fields is a linked list of the actual fields.

The individual fields in a form are described by the following structure:

```
typedef struct Formfield Formfield;
struct Formfield
{
```

```
Formfield* next;
int
            ftype;
            fieldid:
int
Form*
            form:
Rune*
            name;
Rune*
            value:
int
            size;
int
            maxlength;
int
            rows;
            cols;
int
uchar
            flags;
Option*
            options:
Item*
            image:
int
            ctlid:
SEvent*
            events:
```

};

Here, next points to the next field in the list. Ftype is the type of the field, which can be one of Ftext, Fpassword, Fcheckbox, Fradio, Fsubmit, Fhidden, Fimage, Freset, Ffile, Fbutton, Fselect or Ftextarea. Fieldid is a serial number for the field within the form. Form points back to the form containing this field. Name, value, size, maxlength, rows and cols each contain the values of corresponding attributes of the field, if present. Flags contains per-field flags, of which FFchecked and FFmultiple are defined. Image is only used for fields of type Fimage; it points to an image item containing the image to be displayed. Ctlid is reserved for use by the caller, typically to store a unique id of an associated control used to implement the field. Events is the same as the corresponding field of the generic attributes associated with the item containing this field. Options is only used by fields of type Fselect; it consists of a list of possible options that may be selected for that field, using the following structure:

```
typedef struct Option Option;
struct Option
{
    Option* next;
    int selected;
    Rune* value;
    Rune* display;
```

};

Next points to the next element of the list. Selected is set if this option is to be displayed initially. Value is the value to send when the form is submitted if this option is selected. Display is the string to display on the screen for this option.

Tables

The library builds a list of all the tables in the document, headed by Docinfo.tables. Each element of this list has the following format:

```
typedef struct Table Table;
struct Table
{
    Table*
                  next:
    int
                  tableid:
    Tablerow*
                  rows;
    int
                  nrow;
    Tablecol*
                  cols:
    int
                  ncol:
    Tablecell*
                  cells:
    int
                  ncell;
    Tablecell*** grid;
    Align
                  align;
    Dimen
                  width:
```

border;

int

};

Next points to the next element in the list of tables. Tableid is a serial number for the table within the document. Rows is an array of row specifications (described below) and nrow is the number of elements in this array. Similarly, cols is an array of column specifications, and ncol the size of this array. Cells is a list of all cells within the table (structure described below) and ncell is the number of elements in this list. Note that a cell may span multiple rows and/or columns, thus ncell may be smaller than nrow*ncol. Grid is a two-dimensional array of cells within the table; the cell at row i and column j is Table.grid[i][j]. A cell that spans multiple rows and/or columns will be referenced by grid multiple times, however it will only occur once in cells. Align gives the alignment specification for the entire table, and width gives the requested width as a dimension specification. Border, cellspacing and cellpadding give the values of the corresponding attributes for the table, and background gives the requested background for the table. Caption is a linked list of items to be displayed as the caption of the table, either above or below depending on whether caption_place is ALtop or ALbottom. Most of the remaining fields are reserved for use by the caller, except tabletok, which is reserved for internal use. The type Lay is not defined by the library; the caller can provide its own definition.

The Tablecol structure is defined for use by the caller. The library ensures that the correct number of these is allocated, but leaves them blank. The fields are as follows:

```
typedef struct Tablecol Tablecol;
struct Tablecol
{
    int
          width:
    Align align;
```

```
Point pos;
```

};

The rows in the table are specified as follows:

```
typedef struct Tablerow Tablerow:
struct Tablerow
{
    Tablerow*
               next;
    Tablecell* cells:
    int
               height;
    int
                ascent:
    Align
                align:
    Background background;
    Point
```

pos;

flags:

};

uchar

Next is only used during parsing; it should be ignored by the caller. Cells provides a list of all the cells in a row, linked through their nextinrow fields (see below). Height, ascent and pos are reserved for use by the caller. Align is the alignment specification for the row, and background is the background to use, if specified. Flags is used by the parser; ignore this field.

The individual cells of the table are described as follows:

```
typedef struct Tablecell Tablecell;
struct Tablecell
{
    Tablecell* next;
    Tablecell* nextinrow;
    int
                cellid;
    Item*
                content;
    Lay*
                lay;
    int
                rowspan;
    int
                colspan;
    Align
                align;
    uchar
                flags;
    Dimen
                wspec;
    int
                hspec:
    Background background;
                minw;
    int
    int
                maxw;
    int
                ascent;
    int
                row;
    int
                col;
    Point
                pos;
```

```
};
```

Client-side Maps

The library builds a list of client-side maps, headed by Docinfo.maps, and having the following structure:

```
typedef struct Map Map;
struct Map
{
    Map* next;
    Rune* name;
    Area* areas;
```

```
};
```

Next points to the next element in the list, name is the name of the map (use to bind it to an image), and areas is a list of the areas within the image that comprise the map, using the following structure:

```
typedef struct Area Area;
struct Area
{
    Area* next;
    int shape;
    Rune* href;
```

```
int target;
Dimen* coords;
int ncoords;
```

};

Next points to the next element in the map's list of areas. Shape describes the shape of the area, and is one of SHrect, SHcircle or SHpoly. Href is the URL associated with this area in its role as a hypertext link, and target is the target frame it should be loaded in. Coords is an array of coordinates for the shape, and ncoords is the size of this array (number of elements).

Frames

If the Docinfo.kidinfo field is set, the document is a frameset. In this case, it is typical for *parsehtml* to return nil, as a document which is a frameset should have no actual items that need to be laid out (such will appear only in subsidiary documents). It is possible that items will be returned by a malformed document; the caller should check for this and free any such items.

The Kidinfo structure itself reflects the fact that framesets can be nested within a document. If is defined as follows:

```
typedef struct Kidinfo Kidinfo;
struct Kidinfo
{
    Kidinfo* next;
    int
              isframeset:
    // fields for "frame"
    Rune*
              src;
    Rune*
              name;
    int
              marginw;
    int
              marginh;
              framebd;
    int
    int
              flags;
    // fields for "frameset"
    Dimen*
              rows:
    int
              nrows;
    Dimen*
              cols:
    int
              ncols:
    Kidinfo* kidinfos;
    Kidinfo* nextframeset;
};
```

Next is only used if this structure is part of a containing frameset; it points to the next element in the list of children of that frameset. Isframeset is set when this structure represents a frameset; if clear, it is an individual frame.

Some fields are used only for framesets. Rows is an array of dimension specifications for rows in the frameset, and nrows is the length of this array. Cols is the corresponding array for columns, of length ncols. Kidinfos points to a list of components contained within this frameset, each of which may be a frameset or a frame. Nextframeset is only used during parsing, and should be ignored.

The remaining fields are used if the structure describes a frame, not a frameset. Src provides the URL for the document that should be initially loaded into this frame. Note that this may be a relative URL, in which case it should be interpretted using the containing document's URL as the base. Name gives the name of the frame, typically supplied via a name attribute in the HTML. If no name was given, the library allocates one. Marginw, marginh and framebd are the values of the marginwidth, marginheight and frameborder attributes, respectively. Flags can contain some combination of the following: FRnoresize (the frame had the noresize attribute set, and the user should not be allowed to resize it), FRnoscroll (the frame should not have any scroll bars), FRhscroll (the frame should have a horizontal scroll bar), FRvscroll (the frame should have a vertical scroll bar), FRhscrollauto (the frame should be automatically given a horizontal scroll bar if its contents would not otherwise fit), and FRvscrollauto (the frame gets a vertical scrollbar only if required).

SOURCE

/sys/src/libhtml

SEE ALSO

fmt(1)

W3C World Wide Web Consortium, "HTML 4.01 Specification".

BUGS

The entire HTML document must be loaded into memory before any of it can be parsed.

HConnect, HContent, HContents, HETag, HFields, Hio, Htmlesc, HttpHead, HttpReq, HRange, HSPairs, hmydomain, hversion, htmlesc, halloc, hbodypush, hbuflen, hcheckcontent, hclose, hdate2sec, hdatefmt, hfail, hflush, hgetc, hgethead, hinit, hiserror, hload, hlower, hmkcontent, hmkhfields, hmkmimeboundary, hmkspairs, hmoved, hokheaders, hparseheaders, hparsequery, hparsereq, hprint, hputc, hreadbuf, hredirected, hreqcleanup, hrevhfields, hrevspairs, hstrdup, http11, httpfmt, httpunesc, hunallowed, hungetc, hunload, hurlfmt, hurlunesc, hvprint, hwrite, hxferenc,

- routines for creating an http server

SYNOPSIS

#include <u.h>
#include <libc.h>
#include <libc.h>
#include <httpd.h>
typedef struct HConnect HConnect;
typedef struct HContent HContent;

```
typedef struct HContents HContents;
typedef struct HETag HETag;
typedef struct HFields HFields;
typedef struct Hio Hio;
typedef struct Htmlesc Htmlesc;
typedef struct HttpHead HttpHead;
typedef struct HttpReq HttpReq;
typedef struct HRange HRange;
typedef struct HSPairs HSPairs;
```

typedef struct Bin Bin;

```
struct Htmlesc
{
```

char *name; Rune value;

HFields

```
struct HContent
{
```

};

};

```
HContent *next;
char *generic;
char *specific;
```

```
char *specific;
float q;
int mxb;
```

/* desirability of this kind of f /* max uchars until worthless */

```
struct HContents
{
          HContent
                       *type;
                        *encoding;
          HContent
};
/*
* generic http header with a list of tokens,
* each with an optional list of parameters
*/
struct HFields
{
                       *s:
          char
          HSPairs
                       *params;
```

*next;

HTTPD(2)

```
};
/*
* list of pairs a strings
* used for tag=val pairs for a search or form submission,
* and attribute=value pairs in headers.
 */
struct HSPairs
{
          char
                      *s;
          char
                      *t;
          HSPairs
                     *next;
};
/*
 * byte ranges within a file
*/
struct HRange
{
                                             /* is this a suffix request? */
                     suffix;
          int
          ulong
                     start;
                                             /* ~0UL -> not given */
          ulong
                      stop;
          HRange
                      *next;
};
/*
* list of http/1.1 entity tags
*/
struct HETag
{
          char
                     *etag:
          int
                     weak;
                     *next;
         HETag
};
/*
* HTTP custom IO
* supports chunked transfer encoding
 * and initialization of the input buffer from a string.
 */
enum
{
          Hnone,
          Hread,
          Hend,
          Hwrite,
          Herr,
          Hsize = HBufSize
};
struct Hio {
                      *hh;
                                             /* next lower layer Hio, or nil i
          Hio
                                             /* associated file descriptor */
          int
                      fd;
                                             /* of start */
          ulong
                      seek;
          uchar
                      state;
                                             /* state of the file */
          uchar
                                             /* chunked transfer encoding stat
                      xferenc;
                                             /* current position in the buffer
          uchar
                      *pos;
                                             /* last character active in the b
          uchar
                      *stop;
```

```
/* start of data buffer */
          uchar
                       *start:
                      bodylen;
                                              /* remaining length of message bo
          ulong
          uchar
                       buf[Hsize+32];
};
/*
 * request line
 */
struct HttpReq
{
          char
                       *meth;
          char
                       *uri;
          char
                       *urihost;
          char
                      *search;
          int
                      vermaj;
          int
                      vermin;
};
/*
 * header lines
 */
struct HttpHead
{
          int
                       closeit;
                                              /* http1.1 close connection after
                                              /* http/1.1 requests a persistent
          uchar
                      persist;
          uchar
                       expectcont;
                                              /* expect a 100-continue */
                                              /* expect anything else; should r
          uchar
                       expectother;
                                              /* if != ~OUL, length of included
          ulong
                       contlen;
                                              /* if present, encoding of includ
          HFields
                       *transenc:
                       *client;
          char
          char
                       *host;
          HContent
                       *okencode;
          HContent
                       *oklang;
          HContent
                       *oktype;
                       *okchar;
          HContent
                      ifmodsince;
          ulong
          ulong
                      ifunmodsince;
                      ifrangedate;
          ulong
                      *ifmatch;
          HETag
                      *ifnomatch;
          HETag
                      *ifrangeetag;
          HETag
                       *range;
          HRange
                                              /* authorization info */
          char
                       *authuser;
                       *authpass;
          char
          /*
           * experimental headers
           */
                      fresh_thresh;
          int
                      fresh_have;
          int
};
/*
* all of the state for a particular connection
*/
struct HConnect
{
                                              /* for the library clients */
          void
                      *private;
```

```
(*replog)(HConnect*, char*, ...);/* called when reply se
           void
          HttpReq
                       req;
          HttpHead
                       head;
           Bin
                        *bin;
                                                 /* time at start of request */
          ulong
                       reqtime;
                                                 /* buffer for making up or transf
           char
                       xferbuf[HBufSize];
                                                /* room for n = x/n = x/n
                       header[HBufSize + 2];
          uchar
          uchar
                        *hpos;
          uchar
                        *hstop:
          Hio
                       hin;
          Hio
                       hout:
};
/*
 * configuration for all connections within the server
 */
                        *hmydomain;
           char
extern
                        *hversion:
          char
extern
                       htmlesc[];
extern
          Htmlesc
void
           *halloc(HConnect *c, ulong size);
           *hbodypush(Hio *hh, ulong len, HFields *te);
Hio
          hbuflen(Hio *h, void *p);
int
int
          hcheckcontent(HContent*, HContent*, char*, int);
          hclose(Hio*);
void
ulong
          hdate2sec(char*);
int
          hdatefmt(Fmt*);
int
          hfail(HConnect*, int, ...);
          hflush(Hio*);
int
          hgetc(Hio*);
int
          hgethead(HConnect *c, int many);
int
int
          hinit(Hio*, int, int);
int
          hiserror(Hio *h);
          hload(Hio*, char*);
int
char
           *hlower(char*);
HContent
           *hmkcontent(HConnect *c, char *generic, char *specific, HContent *ne
           *hmkhfields(HConnect *c, char *s, HSPairs *p, HFields *next);
HFields
           *hmkmimeboundary(HConnect *c);
char
HSPairs
           *hmkspairs(HConnect *c, char *s, char *t, HSPairs *next);
           hmoved(HConnect *c, char *uri);
int
void
          hokheaders(HConnect *c);
          hparseheaders(HConnect*, int timeout);
int
          *hparsequery(HConnect *c, char *search);
hparsereq(HConnect *c, int timeout);
HSPairs
int
          hprint(Hio*, char*, ...);
hputc(Hio*, int);
int
int
           *hreadbuf(Hio *h, void *vsave);
void
          hredirected(HConnect *c, char *how, char *uri);
int
          hreqcleanup(HConnect *c);
void
           *hrevhfields(HFields *hf);
HFields
HSPairs
           *hrevspairs(HSPairs *sp);
           *hstrdup(HConnect *c, char *s);
char
int
          http11(HConnect*);
          httpfmt(Fmt*);
int
           *httpunesc(HConnect *c, char *s);
char
          hunallowed(HConnect *, char *allowed);
int
```

int	hungetc(Hio *h);
char	<pre>*hunload(Hio*);</pre>
int	<pre>hurlfmt(Fmt*);</pre>
char	<pre>*hurlunesc(HConnect *c, char *s);</pre>
int	hvprint(Hio*, char*, va_list);
int	<pre>hwrite(Hio*, void*, int);</pre>
int	<pre>hxferenc(Hio*, int);</pre>

DESCRIPTION

For now, look at the source, or *httpd*(8).

FOR

SOURCE /sys/src/libhttpd

SEE ALSO

bin(2)

BUGS

This is a rough implementation and many details are going to change.

hypot - Euclidean distance

SYNOPSIS

#include <u.h>
#include <libc.h>

double hypot(double x, double y)

DESCRIPTION

Hypot returns sqrt(x*x + y*y)taking precautions against unwarranted overflows.

SOURCE

/sys/src/libc/port/hypot.c

utf2idn, idn2utf - convert internationalized domain names to and from unicode

SYNOPSIS

#include <u.h>
#include <libc.h>
int utf2idn(char *name, char *buf, int nbuf);
int idn2utf(char *name, char *buf, int nbuf);

DESCRIPTION

These routines handle encoding and decoding of domain names as specified by RFC5890.

Utf2idn encodes the UTF string *name* to ASCII internationalized domain name in *buf*. *Idn2utf* does the reverse, decoding the ASCII string *name* back to UTF in *buf*. The maximum size of *buf* is gived by *nbuf*.

SOURCE

/sys/src/libc/9sys/idn.c

SEE ALSO

/lib/rfc/rfc5890
utf(6)

DIAGNOSTICS

The return value is the number of bytes (excluding the terminating NULL) in *buf* or -1 on failure.

Intmap, allocmap, freemap, insertkey, caninsertkey, lookupkey, deletekey - integer to data structure maps

SYNOPSIS

#include <u.h>
#include <libc.h>
#include <fcall.h>
#include <thread.h>
#include <9p.h>

```
Intmap* allocmap(void (*inc)(void*))
void freemap(Intmap *map, void (*dec)(void*))
void* lookupkey(Intmap *map, ulong key)
void* insertkey(Intmap *map, ulong key, void *val)
int caninsertkey(Intmap *map, ulong key, void *val)
void* lookupkey(Intmap *map, ulong key)
void* deletekey(Intmap *map, ulong key)
```

DESCRIPTION

An Intmap is an arbitrary mapping from integers to pointers. *Allocmap* creates a new map, and *freemap* destroys it. The *inc* function is called each time a new pointer is added to the map; similarly, *dec* is called on each pointer left in the map when it is being freed. Typically these functions maintain reference counts. New entries are added to the map by calling *insertkey*, which will return the previous value associated with the given *key*, or zero if there was no previous value. *Caninsertkey* is like *insertkey* but only inserts *val* if there is no current mapping. It returns 1 if *val* was inserted, 0 otherwise. *Lookupkey* returns the pointer associated with *key*, or zero if there is no such pointer. *Deletekey* removes the entry for *id* from the map, returning the associated pointer, if any.

Concurrent access to Intmaps is safe, moderated via a QLock stored in the Intmap structure.

In anticipation of the storage of reference-counted structures, an increment function *inc* may be specified at map creation time. *Lookupkey* calls *inc* (if non-zero) on pointers before returning them. If the reference count adjustments were left to the caller (and thus not protected by the lock), it would be possible to accidentally reclaim a structure if, for example, it was deleted from the map and its reference count decremented between the return of *insertkey* and the external increment. *Insertkey* and *caninsertkey* do *not* call *inc* when inserting *val* into the map, nor do *insertkey* or *deletekey* call *inc* when returning old map entries. The rationale is that calling an insertion function transfers responsibility for the reference to the map, and responsibility is given back via the return value of *deletekey* or the next *insertkey*.

Intmaps are used by the 9P library to implement Fidpools and Reqpools.

SOURCE

```
/sys/src/lib9p/intmap.c
```

SEE ALSO

9p(2), 9pfid(2).

closeioproc, iocall, ioclose, ioflush, iointerrupt, iodial, ioopen, ioproc, ioread, ioreadn, iosleep, iowrite - slave I/O processes for threaded programs

SYNOPSIS

#include <u.h> #include <libc.h> #include <thread.h>

typedef struct Ioproc Ioproc;

Ioproc* ioproc(void);

int int long long int int	<pre>ioopen(Ioproc *io, char *file, int omode); ioclose(Ioproc *io, int fd); ioread(Ioproc *io, int fd, void *a, long n); ioreadn(Ioproc *io, int fd, void *a, long n); iowrite(Ioproc *io, int fd, void *a, long n); iodial(Ioproc *io, char *addr, char *local, char *dir, int *cdfp); iosleep(Ioproc *io, long n);</pre>
int void void	<pre>ioflush(Ioproc *io); iointerrupt(Ioproc *io); closeioproc(Ioproc *io);</pre>
long	iocall(Ioproc *io, long (*op)(va_list *arg),);

DESCRIPTION

These routines provide access to I/O in slave procs. Since the I/O itself is done in a slave proc, other threads in the calling proc can run while the calling thread waits for the I/O to complete.

loproc forks a new slave proc and returns a pointer to the Ioproc associated with it. *loproc* uses *mallocz* and *proccreate*; if either fails, it calls *sysfatal* rather than return an error.

loopen, ioclose, ioread, ioreadn, iowrite, iosleep, and iodial execute the similarly named library or system calls (see open(2), read(2), and dial(2)) in the slave process associated with io.

lointerrupt interrupts the next or currently executing call in the I/O proc. If there was no call executing, the interrupt will stay pending and the next I/O call will get interrupted.

loflush executes a non-op in the I/O proc. It is commonly called after *iointerrupt* to clear a pending interrupt.

Closeioproc terminates the I/O proc and frees the associated Ioproc .

locall is a primitive that may be used to implement more slave I/O routines. *locall* arranges for op to be called in *io*'s proc, with arg set to the variable parameter list, returning the value that op returns.

EXAMPLE

Relay messages between two file descriptors, counting the total number of bytes seen:

```
int tot;
void
relaythread(void *v)
{
    int *fd, n;
    char buf[1024];
    Ioproc *io;
    fd = v;
    io = ioproc();
    while((n = ioread(io, fd[0], buf, sizeof buf)) > 0){
        if(iowrite(io, fd[1], buf, n) != n)
            sysfatal("iowrite: %r");
```

```
tot += n;
    }
    closeioproc(io);
}
void
relay(int fd0, int fd1)
{
    int fd[4];
    fd[0] = fd[3] = fd0;
    fd[1] = fd[2] = fd1;
    threadcreate(relaythread, fd, 8192);
    threadcreate(relaythread, fd+2, 8192);
}
```

If the two *relaythread* instances were running in different procs, the common access to *tot* would be unsafe.

Implement *ioread*:

SOURCE

```
static long
           _ioread(va_list *arg)
           {
                int fd;
               void *a;
               long n;
                fd = va_arg(*arg, int);
               a = va_arg(*arg, void*);
n = va_arg(*arg, long);
               return read(fd, a, n);
           }
           long
           ioread(Ioproc *io, int fd, void *a, long n)
           {
               return iocall(io, _ioread, fd, a, n);
           }
     /sys/src/libthread/io*.c
SEE ALSO
```

dial(2), open(2), read(2), sleep(2), thread(2)

iounit - return size of atomic I/O unit for file descriptor

SYNOPSIS

#include <u.h>
#include <libc.h>

int iounit(int fd)

DESCRIPTION

Reads and writes of files are transmitted using the 9P protocol (see *intro*(5)) and in general, operations involving large amounts of data must be broken into smaller pieces by the operating system. The 'I/O unit' associated with each file descriptor records the maximum size, in bytes, that may be read or written without breaking up the transfer.

The *iounit* routine uses the dup(3) interface to discover the I/O unit size for the file descriptor *fd* and returns its value. Certain file descriptors, particularly those associated with devices, may have no specific I/O unit, in which case *iounit* will return 0.

SOURCE

/sys/src/libc/9sys

SEE ALSO

dup(3), read(5)

DIAGNOSTICS

Returns zero if any error occurs or if the I/O unit size of the fd is unspecified or unknown.

eipfmt, parseip, parseipmask, parseipandmask, v4parseip, parseether, myipaddr, myetheraddr, maskip, equivip4, equivip6, defmask, isv4, v4tov6, v6tov4, nhgetv, nhgetl, nhgets, hnputv, hnputl, hnputs, ptclbsum, readipifc – Internet Protocol addressing

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <ip.h>
int eipfmt(Fmt*)
          parseip(uchar *ipaddr, char *str)
vlong
          parseipmask(uchar *ipaddr, char *str, int v4)
vlong
          parseipandmask(uchar *ipaddr, uchar *ipmask, char *ipstr,
vlong
char *maskstr)
char*
          v4parseip(uchar *ipaddr, char *str)
int
    parseether(uchar *eaddr, char *str)
    myetheraddr(uchar *eaddr, char *dev)
int
    myipaddr(uchar *ipaddr, char *net)
int
void maskip(uchar *from, uchar *mask, uchar *to)
    equivip4(uchar *ipaddr1, uchar *ipaddr2)
int
    equivip6(uchar *ipaddr1, uchar *ipaddr2)
int
uchar*
          defmask(uchar *ipaddr)
int
    isv4(uchar *ipaddr)
void v4tov6(uchar *ipv6, uchar *ipv4)
int
    v6tov4(uchar *ipv4, uchar *ipv6)
ushort
          nhgets(void *p)
uint nhgetl(void *p)
         nhgetv(void *p)
uvlong
void hnputs(void *p, ushort v)
void hnputl(void *p, uint v)
void hnputv(void *p, uvlong v)
ushort
          ptclbsum(uchar *a, int n)
Ipifc*
          readipifc(char *net, Ipifc *ifc, int index)
uchar
          IPv4bcast[IPaddrlen];
uchar
          IPv4allsys[IPaddrlen];
uchar
          IPv4allrouter[IPaddrlen];
uchar
          IPallbits[IPaddrlen];
          IPnoaddr[IPaddrlen];
uchar
uchar
          v4prefix[IPaddrlen];
```

DESCRIPTION

These routines are used by Internet Protocol (IP) programs to manipulate IP and Ethernet addresses. Plan 9, by default, uses V6 format IP addresses. Since V4 addresses fit into the V6 space, all IP addresses can be represented. IP addresses are stored as a string of 16 unsigned chars, Ethernet addresses as 6 unsigned chars. Either V4 or V6 string representation can be used for IP addresses. For V4 addresses, the representation can be (up to) 4 decimal integers from 0 to 255 separated by periods. For V6 addresses, the representation is (up to) 8 hex integers from 0x0 to 0xFFFF separated by colons. Strings of 0 integers can be elided using two colons. For

Eipfmt is a *print*(2) formatter for Ethernet (verb E) addresses, IP V6 (verb I) addresses, IP V4 (verb V) addresses, and IP V6 (verb M) masks.

Parseip converts a string pointed to by *str* to a 16-byte IP address starting at *ipaddr*. As a concession to backwards compatibility, if the string is a V4 address, the return value is an unsigned long integer containing the big-endian V4 address. If not, the return value is 6.

Parseipmask converts a string pointed to by *str* to a 16-byte IP mask starting at *ipaddr*. It too returns an unsigned long big-endian V4 address or 6. *Parseipmask* accepts a mask in */ prefixlen* slash notation. When the *v4* argument is non-zero, then *prefixlen* in range [0..32] is offset by 96 to yield a mask for a V4 address.

Parseipandmask combines *parseip* and *parseipmask* into a single call, interpreting the mask in context of the supplied IP address type. The returned IP mask is /128 when *maskstr* is nil.

All three functions return -1 on errors.

V4parseip converts a string pointed to by str to a 4-byte V4 IP address starting at ipaddr.

Myipaddr returns the first valid IP address in the IP stack rooted at net.

Parseether converts a string pointed to by str to a 6-byte Ethernet address starting at eaddr. Myetheraddr reads the Ethernet address string from file dev/addr and parses it into eaddr. Both routines return a negative number on errors.

Maskip places the bit-wise AND of the IP addresses pointed to by its first two arguments into the buffer pointed to by the third.

Equivip returns non-zero if the IP addresses pointed to by its two arguments are equal. *Equivip4* operates on v4 addresses, *equivip6* operates on v6 addresses.

Defmask returns the standard class A, B, or C mask for ipaddr.

Isv4 returns non-zero if the V6 address is in the V4 space, that is, if it starts with 0:0:0:0:0:0:FFFF. *V4tov6* converts the 4-byte V4 address, *v4ip*, to a V6 address and puts the result in *v6ip*. *V6tov4* converts the V6 address, *v6ip*, to a 4-byte V4 address and puts the result in *v4ip*.

Hnputs, *hnputl* and *hnputv* are used to store 16-bit, 32-bit, and 64-bit integers, respectively, into IP big-endian form. *Nhgets*, *nhgetl* and *nhgetv* convert big-endian 2, 4 and 8 byte quantities into integers (or *uvlongs*).

Pctlbsum returns the one's complement checksum used in IP protocols, typically invoked as

hnputs(hdr->cksum, ~ptclbsum(data, len) & 0xffff);

A number of standard IP addresses in V6 format are also defined. They are:

IPv4bcast	the V4 broadcast address
IPv4allsys	the V4 all systems multicast address
IPv4allrouter	the V4 all routers multicast address
IPallbits	the V6 all bits on address
IPnoaddr	the V6 null address, all zeros
v4prefix	the IP V6 prefix to all embedded V4 addresses

Readipifc returns information about a particular interface (*index* >= 0) or all IP interfaces (*index* < 0) configured under a mount point *net*, default /net. Each interface is described by one *Ipifc* structure which in turn points to a linked list of *Iplifc* structures describing the addresses assigned to this interface. If the list *ifc* is supplied, that list is freed. Thus, subsequent calls can be used to free the list returned by the previous call. *Ipifc* is:

typedef struct Ipifc
{
 Ipifc *next;
 Iplifc *lifc; /* local addressses */

```
/* per ip interface */
                        /* number of interface in ipifc dir */
     int index;
     char dev[64]; /* associated physical device */
                    /* max transfer unit */
     int
         mtu;
               sendra6; /* on == send router adv */
     uchar
     uchar
               recvra6; /* on == rcv router adv */
                               /* packets read */
     ulong
               pktin;
                               /* packets written */
/* read errors */
     ulong
               pktout;
     ulong
               errin;
                               /* write errors */
     ulong
               errout:
     Ipv6rp
                          /* route advertisement params */
               rp;
} Ipifc;
Iplifc is:
struct Iplifc
{
     Iplifc
               *next;
               ip[IPaddrlen];
     uchar
     uchar
               mask[IPaddrlen];
                                        /* ip & mask */
     uchar
               net[IPaddrlen];
     ulong
               preflt;
                                    /* preferred lifetime */
                               /* valid lifetime */
     ulong
               validlt;
};
Ipv6rp is:
struct Ipv6rp
{
     int mflag;
     int
         oflag;
     int maxraint; /* max route adv interval */
     int
          minraint; /* min route adv interval */
         linkmtu;
     int
     int reachtime;
     int rxmitra;
     int
         ttl;
     int routerlt;
```

```
};
```

Dev contains the first 64 bytes of the device configured with this interface. *Net* is *ip*&*mask* if the network is multipoint or the remote address if the network is point to point.

SOURCE

/sys/src/libip

SEE ALSO

print(2), *ip*(3)

isalpharune, islowerrune, isspacerune, istitlerune, isupperrune, isdigitrune, tolowerrune, totitlerune, toupperrune - Unicode character classes and cases

SYNOPSIS

```
#include <u.h>
#include <libc.h>
int isalpharune(Rune c)
int islowerrune(Rune c)
int isspacerune(Rune c)
int istitlerune(Rune c)
int isdigitrune(Rune c)
int isdigitrune(Rune c)
Rune tolowerrune(Rune c)
Rune totitlerune(Rune c)
Rune toupperrune(Rune c)
```

DESCRIPTION

These routines examine and operate on Unicode characters, in particular a subset of their properties as defined in the Unicode standard. Unicode defines some characters as alphabetic and specifies three cases: upper, lower, and title. Analogously to *ctype*(2) for ASCII, these routines test types and modify cases for Unicode characters. The names are self-explanatory.

The case-conversion routines return the character unchanged if it has no case.

SOURCE

/sys/src/libc/port/runetype.c

SEE ALSO

ctype(2), The Unicode Standard.

```
jsonparse, jsonfree, jsonbyname, jsonstr - JSON parser
SYNOPSIS
     #include <u.h>
     #include <libc.h>
     #include <json.h>
     enum {
              JSONNull,
              JSONBool,
              JSONNumber,
              JSONString,
              JSONArray,
              JSONObject,
     };
     typedef struct JSONEl JSONEl;
     struct JSONEl {
              char *name;
              JSON *val;
              JSONEl *next;
     };
     typedef struct JSON JSON;
     struct JSON
     {
              int t;
              union {
                      double n;
                      char *s;
                      JSONEl *first;
              };
     };
     JSON*
              jsonparse(char *s);
     void
              jsonfree(JSON *j);
     JSON*
              jsonbyname(JSON *j, char *s);
              jsonstr(JSON *j);
     char*
              JSONfmt(Fmt *f)
     int
              JSONfmtinstall(void);
     void
```

DESCRIPTION

The JSON structure represents a variant ison value. The variant type is stored in the t member of the structure. String values use s, booleans and numbers use the n members in the structure. Arrays and objects (dictionaries) are represented by a singly-linked list of JSONE1 structures referred to from the first pointer in the JSON structure. Each JSONEl has a val pointer to the associated value and a next pointer to the next element in the array or object. Dictionary objects have the name member set to the key of the association.

A json object is parsed by calling *jsonparse* with a UTF-8 string of the json encoded data. On success, a non-nil pointer to a newly allocated JSON structure is returned. To free the parsed objects, *isonfree* has to be called.

The *isonbyname* function returns the associated value of a dictionary item.

The function *jsonstr* returns the string value of a json object or nil for any other object type.

JSONfmt is a print(2) formatting routine that prints a well-formatted JSON structure. It can be installed by hand but JSONfmtinstall installs it under the standard format character J. The header <json.h> contains a #pragma statement so the compiler can type-check uses of %J in print(2) format strings.

SOURCE

/sys/src/libjson

DIAGNOSTICS The functions *jsonparse, jsonbyname* and *jsonstr* return nil on error and set an error string (see errstr(2)).

initkeyboard, ctlkeyboard, closekeyboard - keyboard control

SYNOPSIS

515	
<pre>#include <u.< pre=""></u.<></pre>	h>
<pre>#include <li< pre=""></li<></pre>	bc.h>
<pre>#include <th< pre=""></th<></pre>	read.h>
<pre>#include <ke< pre=""></ke<></pre>	yboard.h>
Keyboardctl	<pre>*initkeyboard(char *file)</pre>
int	ctlkeyboard(Keyboardctl *kc, char *msg)
void	closekeyboard(Keyboard *kc)

DESCRIPTION

These functions access and control a keyboard interface for character-at-a-time I/O in a multithreaded environment, usually in combination with mouse(2). They use the message-passing Channel interface in the threads library (see *thread*(2)); programs that wish a more event-driven, single-threaded approach should use *event*(2).

Initkeyboard opens a connection to the keyboard and returns a Keyboardctl structure:

```
typedef struct Keyboardctl Keyboardctl;
struct Keyboardctl
{
    Channel *c:
                      /* chan(Rune[20]) */
    char
            *file:
    int
            consfd;
                      /* to cons file */
                      /* to ctl file */
    int
            ctlfd;
                      /* of slave proc */
            pid;
    int
}:
```

The argument to *initkeyboard* is a *file* naming the device file from which characters may be read, typically /dev/cons. If *file* is nil, /dev/cons is assumed.

Once the Keyboardctl is set up, a message containing a Rune will be sent on the Channel Keyboardctl.c to report each character read from the device.

Ctlkeyboard is used to set the state of the interface, typically to turn raw mode on and off (see *cons*(3)). It writes the string *msg* to the control file associated with the device, which is assumed to be the regular device file name with the string ctl appended.

Closekeyboard closes the file descriptors associated with the keyboard, kills the slave processes, and frees the Keyboardctl structure.

SOURCE

/sys/src/libdraw

SEE ALSO

graphics(2), draw(2), event(2), thread(2).

BUGS

Because the interface delivers complete runes, there is no way to report lesser actions such as shift keys or even individual bytes.

lock, canlock, unlock, qlock, canqlock, qunlock, rlock, canrlock, runlock, wlock, canwlock, wunlock, rsleep, rwakeup, rwakeupall, incref, decref - spin locks, queueing rendezvous locks, readerwriter locks, rendezvous points, and reference counts

SYNOPSIS

```
#include <u.h>
#include <libc.h>
void lock(Lock *1)
int canlock(Lock *1)
void unlock(Lock *1)
void qlock(QLock *1)
int canqlock(QLock *1)
void qunlock(QLock *1)
void rlock(RWLock *1)
int canrlock(RWLock *1)
void runlock(RWLock *1)
void wlock(RWLock *1)
int canwlock(RWLock *1)
void wunlock(RWLock *1)
typedef struct Rendez {
     QLock *1;
} Rendez;
void rsleep(Rendez *r)
    rwakeup(Rendez *r)
int
     rwakeupall(Rendez *r)
int
#include <thread.h>
typedef struct Ref {
     long ref;
} Ref:
void incref(Ref*)
long decref(Ref*)
```

DESCRIPTION

These routines are used to synchronize processes sharing memory.

Locks are spin locks, QLocks and RWLocks are different types of queueing rendezvous locks, and Rendezes are rendezvous points.

Locks and rendezvous points work in regular programs as well as programs that use the thread library (see *thread*(2)). The thread library replaces the *rendezvous*(2) system call with its own implementation, *threadrendezvous*, so that threads as well as processes may be synchronized by locking calls in threaded programs.

Used carelessly, spin locks can be expensive and can easily generate deadlocks. Their use is discouraged, especially in programs that use the thread library because they prevent context switches between threads.

Lock blocks until the lock has been obtained. *Canlock* is non-blocking. It tries to obtain a lock and returns a non-zero value if it was successful, 0 otherwise. *Unlock* releases a lock.

QLocks have the same interface but are not spin locks; instead if the lock is taken *qlock* will suspend execution of the calling task until it is released.

Although Locks are the more primitive lock, they have limitations; for example, they cannot synchronize between tasks in the same *proc*. Use QLocks instead.

RWLocks manage access to a data structure that has distinct readers and writers. *Rlock* grants read access; *runlock* releases it. *Wlock* grants write access; *wunlock* releases it. *Canrlock* and

canwlock are the non-blocking versions. There may be any number of simultaneous readers, but only one writer. Moreover, if write access is granted no one may have read access until write access is released.

All types of lock should be initialized to all zeros before use; this puts them in the unlocked state.

Rendezes are rendezvous points. Each Rendez r is protected by a QLock r > I, which must be held by the callers of *rsleep*, *rwakeup*, and *rwakeupall*. *Rsleep* atomically releases r > I and suspends execution of the calling task. After resuming execution, *rsleep* will reacquire r > Ibefore returning. If any processes are sleeping on r, *rwakeup* wakes one of them. it returns 1 if a process was awakened, 0 if not. *Rwakeupall* wakes all processes sleeping on r, returning the number of processes awakened. *Rwakeup* and *rwakeupall* do not release r > I and do not suspend execution of the current task.

Before use, Rendezes should be initialized to all zeros except for $r \rightarrow l$ pointer, which should point at the QLock that will guard r. It is important that this QLock is the same one that protects the rendezvous condition; see the example.

A Ref contains a long that can be incremented and decremented atomically: *Incref* increments the *Ref* in one atomic operation. *Decref* atomically decrements the Ref and returns zero if the resulting value is zero, non-zero otherwise.

EXAMPLE

Implement a buffered single-element channel using *rsleep* and *rwakeup*:

```
typedef struct Chan
{
   QLock 1:
   Rendez full, empty;
   int val, haveval;
} Chan;
Chan*
mkchan(void)
{
   Chan *c;
   c = mallocz(sizeof *c, 1);
   c \rightarrow full.l = \&c \rightarrow l;
   c \rightarrow empty.l = \&c \rightarrow l;
   return c;
}
void
send(Chan *c, int val)
{
   qlock(&c->1);
   while(c->haveval)
      rsleep(&c->full);
   c \rightarrow haveval = 1;
   c->val = val;
   rwakeup(&c->empty); /* no longer empty */
   qunlock(&c->1);
}
int
recv(Chan *c)
{
   int v;
   qlock(\&c \rightarrow 1);
   while(!c->haveval)
      rsleep(&c->empty);
   c \rightarrow haveval = 0;
   v = c -> val;
```

```
rwakeup(&c->full); /* no longer full */
qunlock(&c->l);
return v;
```

Note that the QLock protecting the Chan is the same QLock used for the Rendez; this ensures that wakeups are not missed.

SOURCE

```
/sys/src/libc/port/lock.c
/sys/src/libc/9sys/qlock.c
/sys/src/libthread/ref.c
```

SEE ALSO

rfork in fork(2)

}

BUGS

Locks are not strictly spin locks. After each unsuccessful attempt, *lock* calls sleep(0) to yield the CPU; this handles the common case where some other process holds the lock. After a thousand unsuccessful attempts, *lock* sleeps for 100ms between attempts. After another thousand unsuccessful attempts, *lock* sleeps for a full second between attempts. Locks are not intended to be held for long periods of time. The 100ms and full second sleeps are only heuristics to avoid tying up the CPU when a process deadlocks. As discussed above, if a lock is to be held for much more than a few instructions, the queueing lock types should almost always be used.

It is an error for a program to *fork* when it holds a lock in shared memory, since this will result in two processes holding the same lock at the same time, which should not happen.

crackhdr, machbytype, machbyname, newmap, setmap, findseg, unusemap, loadmap, attachproc, get1, get2, get4, get8, geta, put1, put2, put4, put8, puta beswab, beswal, beswav, leswab, leswal, leswav - machine-independent access to executable files

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <bio.h>
#include <mach.h>
int crackhdr(int fd, Fhdr *fp)
void machbytype(int type)
int machbyname(char *name)
Map *newmap(Map *map, int n)
int setmap(Map *map, int fd, uvlong base, uvlong end,
            vlong foffset, char *name)
int findseg(Map *map, char *name)
void unusemap(Map *map, int seg)
Map *loadmap(Map *map, int fd, Fhdr *fp)
Map *attachproc(int pid, int kflag, int corefd, Fhdr *fp)
int get1(Map *map, uvlong addr, uchar *buf, int n)
int get2(Map *map, uvlong addr, ushort *val)
int get4(Map *map, uvlong addr, ulong *val)
int get8(Map *map, uvlong addr, uvlong *val)
int geta(Map *map, uvlong addr, uvlong *val)
int put1(Map *map, uvlong addr, uchar *buf, int n)
int put2(Map *map, uvlong addr, ushort val)
int put4(Map *map, uvlong addr, ulong val)
int put8(Map *map, uvlong addr, uvlong val)
int puta(Map *map, uvlong addr, uvlong val)
ushort beswab(ushort val)
ulong beswal(ulong val)
uvlong beswav(uvlong val)
ushort leswab(ushort val)
ulong leswal(ulong val)
uvlong leswav(uvlong val)
extern Mach mach;
extern Machdata machdata:
```

DESCRIPTION

These functions provide a processor-independent interface for accessing the executable files or executing images of all architectures. Related library functions described in *symbol*(2) and *object*(2) provide similar access to symbol tables and object files.

An *executable* is a file containing an executable program or the text file of the /proc file system associated with an executing process as described in *proc*(3). After opening an executable, an application invokes a library function which parses the file header, determines the target architecture and initializes data structures with parameters and pointers to functions appropriate for that architecture. Next, the application invokes functions to construct one or more *maps*, data

structures that translate references in the address space of the executable to offsets in the file. Each *map* comprises one or more segments, each associating a non-overlapping range of memory addresses with a logical section of the executable. Other library functions then use a map and the architecture-specific data structures to provide a generic interface to the processor-dependent data.

Crackhdr interprets the header of the executable associated with the open file descriptor *fd*. It loads the data structure *fp* with a machine-independent description of the header information and points global variable *mach* to the Mach data structure containing processor-dependent parameters of the target architecture.

Machbytype selects architecture-specific data structures and parameter values based on the code stored in the field named *type* in the Fhdr data structure. *Machbyname* performs the same selection based on the name of a processor class; see 2c(1) for a list of valid names. Both functions point global variables *mach* and *machdata* to the *Mach* and *Machdata* data structures appropriate for the target architecture and load global variable *asstype* with the proper disassembler type code.

Newmap creates an empty map with *n* segments. If *map* is zero, the new map is dynamically allocated, otherwise it is assumed to point to an existing dynamically allocated map whose size is adjusted, as necessary. A zero return value indicates an allocation error.

Setmap loads the first unused segment in *map* with the segment mapping parameters. *Fd* is an open file descriptor associated with an executable. *Base* and *end* contain the lowest and highest virtual addresses mapped by the segment. *Foffset* is the offset to the start of the segment in the file. *Name* is a name to be attached to the segment.

Findseg returns the index of the segment named name in map. A return of -1 indicates that no segment matches name.

Unusemap marks segment number seg in map map unused. Other segments in the map remain unaffected.

Loadmap initializes a default map containing segments named 'text' and 'data' that map the instruction and data segments of the executable described in the Fhdr structure pointed to by *fp*. Usually that structure was loaded by *crackhdr* and can be passed to this function without modification. If *map* is non-zero, that map, which must have been dynamically allocated, is resized to contain two segments; otherwise a new map is allocated. This function returns zero if allocation fails. Loadmap is usually used to build a map for accessing a static executable, for example, an executable program file.

Attachproc constructs a map for accessing a running process. It returns the address of a *Map* containing segments mapping the address space of the running process whose process ID is pid. If kflag is non-zero, the process is assumed to be a kernel process. Corefd is an file descriptor opened to /proc/pid/mem. Fp points to the *Fhdr* structure describing the header of the executable. For most architectures the resulting *Map* contains four segments named 'text', 'data', 'regs' and 'fpregs'. The latter two provide access to the general and floating point registers, respectively. If the executable is a kernel process (indicated by a non-zero kflag argument), the data segment extends to the maximum supported address, currently 0xffffffff, and the register sets are read-only. In user-level programs, the data segment extends to the top of the stack or 0x7fffffff if the stack top cannot be found, and the register sets are readable and writable. *Attachproc* returns zero if it is unable to build the map for the specified process.

Get1, *get2*, *get4*, and *get8* retrieve the data stored at address *addr* in the executable associated with *map*. *Get1* retrieves *n* bytes of data beginning at *addr* into *buf*. *Get2*, *get4* and *get8* retrieve 16-bit, 32-bit and 64-bit values respectively, into the location pointed to by *val*. The value is byte-swapped if the source byte order differs from that of the current architecture. This implies that the value returned by *get2*, *get4*, and *get8* may not be the same as the byte sequences returned by *get1* when *n* is two, four or eight; the former may be byte-swapped, the latter reflects the byte order of the target architecture. If the file descriptor associated with the applicable segment in *map* is negative, the address itself is placed in the return location. These functions return the number of bytes read or a -1 when there is an error.

Put1, put2, put4, and put8 write to the executable associated with map. The address is translated using the map parameters and multi-byte quantities are byte-swapped, if necessary, before they

are written. *Put1* transfers *n* bytes stored at *buf*; *put2*, *put4*, and *put8* write the 16-bit, 32-bit or 64-bit quantity contained in *val*, respectively. The number of bytes transferred is returned. A -1 return value indicates an error.

Beswab, beswal, and beswav return the ushort, long, and vlong big-endian representation of val, respectively. Leswab, leswal, and leswav return the little-endian representation of the ushort, long, and vlong contained in val.

SOURCE

/sys/src/libmach

SEE ALSO

2c(1), symbol(2), object(2), errstr(2), proc(3), a.out(6)

DIAGNOSTICS

These routines set *errstr*.

malloc, mallocalign, mallocz, free, realloc, calloc, msize, setmalloctag, setrealloctag, getmalloctag, getmalloctag, malloctopoolblock - memory allocator

SYNOPSIS

```
#include <u.h>
#include <libc.h>
void* malloc(ulong size)
void* mallocalign(ulong size, ulong align, long offset, ulong span)
void* mallocz(ulong size, int clr)
void free(void *ptr)
void* realloc(void *ptr, ulong size)
void* calloc(ulong nelem, ulong elsize)
ulong msize(void *ptr)
void setmalloctag(void *ptr, uintptr tag)
uintptrgetmalloctag(void *ptr, uintptr tag)
uintptrgetrealloctag(void *ptr)
void* malloctopoolblock(void*)
```

DESCRIPTION

Malloc and *free* provide a simple memory allocation package. *Malloc* returns a pointer to a new block of at least *size* bytes. The block is suitably aligned for storage of any type of object. No two active pointers from *malloc* will have the same value. The call malloc(0) returns a valid pointer rather than null.

The argument to *free* is a pointer to a block previously allocated by *malloc*; this space is made available for further allocation. It is legal to free a null pointer; the effect is a no-op. The contents of the space returned by *malloc* are undefined. *Mallocz* behaves as *malloc*, except that if *clr* is non-zero, the memory returned will be zeroed.

Mallocalign allocates a block of at least *n* bytes of memory respecting alignment contraints. If *align* is non-zero, the returned pointer is aligned to be equal to *offset* modulo *align*. If *span* is non-zero, the *n* byte block allocated will not span a *span*-byte boundary.

Realloc changes the size of the block pointed to by *ptr* to *size* bytes and returns a pointer to the (possibly moved) block. The contents will be unchanged up to the lesser of the new and old sizes. *Realloc* takes on special meanings when one or both arguments are zero:

realloc(0, size)
 means malloc(size); returns a pointer to the newly-allocated memory
realloc(ptr, 0)
 means free(ptr); returns null

realloc(0, 0)

no-op; returns null

Calloc allocates space for an array of *nelem* elements of size *elsize*. The space is initialized to zeros. *Free* frees such a block.

When a block is allocated, sometimes there is some extra unused space at the end. *Msize* grows the block to encompass this unused space and returns the new number of bytes that may be used.

The memory allocator maintains two word-sized fields associated with each block, the "malloc tag" and the "realloc tag". By convention, the malloc tag is the PC that allocated the block, and the realloc tag the PC that last reallocated the block. These may be set or examined with *setmalloctag*, *getmalloctag*, *setrealloctag*, and *getrealloctag*. When allocating blocks directly with *malloc* and *realloc*, these tags will be set properly. If a custom allocator wrapper is used, the allocator wrapper can set the tags itself (usually by passing the result of *getcallerpc*(2) to

setmalloctag) to provide more useful information about the source of allocation.

Malloctopoolblock takes the address of a block returned by *malloc* and returns the address of the corresponding block allocated by the *pool*(2) routines.

SOURCE

/sys/src/libc/port/malloc.c

SEE ALSO

leak(1), trump (in acid(1)), brk(2), getcallerpc(2), pool(2)

DIAGNOSTICS

Malloc, realloc and *calloc* return 0 if there is no available memory. *Errstr* is likely to be set. If the allocated blocks have no malloc or realloc tags, *getmalloctag* and *getrealloctag* return ~0.

After including pool.h, the call poolcheck(mainmem) can be used to scan the storage arena for inconsistencies such as data written beyond the bounds of allocated blocks. It is often useful to combine this with setting

mainmem->flags |= POOL_NOREUSE;

at the beginning of your program. This will cause malloc not to reallocate blocks even once they are freed; poolcheck(mainmem) will then detect writes to freed blocks.

The *trump* library for *acid* can be used to obtain traces of malloc execution; see *acid*(1).

BUGS

The different specification of *calloc* is bizarre.

User errors can corrupt the storage arena. The most common gaffes are (1) freeing an already freed block, (2) storing beyond the bounds of an allocated block, and (3) freeing data that was not obtained from the allocator. When *malloc* and *free* detect such corruption, they abort.

ident, matmul, matmulr, determinant, adjoint, invertmat, xformpoint, xformpointd, xformplane, pushmat, popmat, rot, qrot, scale, move, xform, ixform, persp, look, viewport - Geometric transformations

SYNOPSIS

#include <draw.h> #include <geometry.h> void ident(Matrix m) void matmul(Matrix a, Matrix b) void matmulr(Matrix a, Matrix b) double determinant(Matrix m) void adjoint(Matrix m, Matrix madj) double invertmat(Matrix m, Matrix inv) Point3 xformpoint(Point3 p, Space *to, Space *from) Point3 xformpointd(Point3 p, Space *to, Space *from) Point3 xformplane(Point3 p, Space *to, Space *from) Space *pushmat(Space *t) Space *popmat(Space *t) void rot(Space *t, double theta, int axis) void qrot(Space *t, Quaternion q) void scale(Space *t, double x, double y, double z) void move(Space *t, double x, double y, double z) void xform(Space *t, Matrix m) void ixform(Space *t, Matrix m, Matrix inv) int persp(Space *t, double fov, double n, double f) void look(Space *t, Point3 eye, Point3 look, Point3 up) void viewport(Space *t, Rectangle r, double aspect)

DESCRIPTION

These routines manipulate 3-space affine and projective transformations, represented as 4×4 matrices, thus:

typedef double Matrix[4][4];

Ident stores an identity matrix in its argument. *Matmul* stores $a \times b$ in *a*. *Matmulr* stores $b \times a$ in *b*. *Determinant* returns the determinant of matrix *m*. *Adjoint* stores the adjoint (matrix of cofactors) of *m* in *madj*. *Invertmat* stores the inverse of matrix *m* in *minv*, returning *m*'s determinant. Should *m* be singular (determinant zero), *invertmat* stores its adjoint in *minv*.

The rest of the routines described here manipulate *Spaces* and transform *Point3s*. A *Point3* is a point in three-space, represented by its homogeneous coordinates:

```
typedef struct Point3 Point3;
struct Point3{
    double x, y, z, w;
};
```

The homogeneous coordinates (x, y, z, w) represent the Euclidean point (x/w, y/w, z/w) if $w \neq 0$, and a "point at infinity" if w=0.

A Space is just a data structure describing a coordinate system:

```
typedef struct Space Space;
struct Space{
```

```
Matrix t;
Matrix tinv;
Space *next;
};
```

It contains a pair of transformation matrices and a pointer to the *Space*'s parent. The matrices transform points to and from the "root coordinate system," which is represented by a null *Space* pointer.

Pushmat creates a new *Space*. Its argument is a pointer to the parent space. Its result is a newly allocated copy of the parent, but with its next pointer pointing at the parent. *Popmat* discards the Space that is its argument, returning a pointer to the stack. Nominally, these two functions define a stack of transformations, but pushmat can be called multiple times on the same Space multiple times, creating a transformation tree.

Xformpoint and *Xformpointd* both transform points from the Space pointed to by *from* to the space pointed to by *to*. Either pointer may be null, indicating the root coordinate system. The difference between the two functions is that xformpointd divides x, y, z, and w by w, if $w \neq 0$, making (x, y, z) the Euclidean coordinates of the point.

Xformplane transforms planes or normal vectors. A plane is specified by the coefficients (a, b, c, d) of its implicit equation ax+by+cz+d=0. Since this representation is dual to the homogeneous representation of points, libgeometry represents planes by Point3 structures, with (a, b, c, d) stored in (x, y, z, w).

The remaining functions transform the coordinate system represented by a Space. Their Space * argument must be non-null — you can't modify the root Space. *Rot* rotates by angle *theta* (in radians) about the given *axis*, which must be one of XAXIS, YAXIS or ZAXIS. *Qrot* transforms by a rotation about an arbitrary axis, specified by Quaternion *q*.

Scale scales the coordinate system by the given scale factors in the directions of the three axes. *Move* translates by the given displacement in the three axial directions.

Xform transforms the coordinate system by the given Matrix. If the matrix's inverse is known *a priori*, calling *ixform* will save the work of recomputing it.

Persp does a perspective transformation. The transformation maps the frustum with apex at the origin, central axis down the positive y axis, and apex angle *fov* and clipping planes y=n and y=f into the double-unit cube. The plane y=n maps to y'=-1, y=f maps to y'=1.

Look does a view-pointing transformation. The eye point is moved to the origin. The line through the *eye* and *look* points is aligned with the y axis, and the plane containing the eye, look and up points is rotated into the x-y plane.

Viewport maps the unit-cube window into the given screen viewport. The viewport rectangle r has r.min at the top left-hand corner, and r.max just outside the lower right-hand corner. Argument *aspect* is the aspect ratio (dx/dy) of the viewport's pixels (not of the whole viewport). The whole window is transformed to fit centered inside the viewport with equal slop on either top and bottom or left and right, depending on the viewport's aspect ratio. The window is viewed down the y axis, with x to the left and z up. The viewport has x increasing to the right and y increasing down. The window's y coordinates are mapped, unchanged, into the viewport's z coordinates.

SOURCE

/sys/src/libgeometry/matrix.c

SEE ALSO

arith3(2)

Memimage, Memdata, Memdrawparam, memimageinit, wordaddr, byteaddr, memimagemove, allocmemimage, allocmemimaged, readmemimage, creadmemimage, writememimage, freememimage, age, memsetchan, loadmemimage, cloadmemimage, unloadmemimage, memfillcolor, memarc, mempoly, memellipse, memfillpoly, memimageline, memimagedraw, drawclip, drawclipnorepl, memlinebbox, memlineendsize, allocmemsubfont, openmemsubfont, freememsubfont, memsubfontwidth, getmemdefont, memimagestring, hwdraw – drawing routines for memory-resident images

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <draw.h>
#include <memdraw.h>
typedef struct Memdata
{
                         /* allocated data pointer */
     ulong
               *base:
     uchar
               *bdata;
                         /* first byte of actual data; word-aligned */
     int
               ref;
                         /* number of Memimages using this data */
     void*
               imref;
                        /* last image that pointed at this */
     int
               allocd;
                         /* is this malloc'd? */
} Memdata;
enum {
               = 1<<0,
                         /* is replicated */
     Frepl
     Fsimple
               = 1<<1,
                         /* is 1x1 */
                         /* is grey */
     Fgrey
               = 1<<2,
     Falpha
                         /* has explicit alpha */
               = 1 < < 3,
                       /* has cmap channel */
               = 1<<4,
     Fcmap
     Fbytes
               = 1 < < 5.
                         /* has only 8-bit channels */
};
typedef struct Memimage
{
     Rectangle r;
                         /* rectangle in data area, local coords */
     Rectangle clipr;
                         /* clipping region */
                         /* number of bits of storage per pixel */
     int
               depth;
                         /* number of channels */
               nchan;
     int
                         /* channel descriptions */
     ulong
               chan;
                         /* pointer to data */
     Memdata
               *data;
                         /* data->bdata+zero==&byte containing (0,0) */
     int
               zero:
                         /* width in words of a single scan line */
     ulong
               width:
     Memlayer
               *layer;
                         /* nil if not a layer*/
               flags;
     ulong
     ...
} Memimage;
typedef struct Memdrawparam
{
     Memimage *dst;
     Rectangle r;
     Memimage *src;
     Rectangle sr;
     Memimage
              *mask:
     Rectangle mr;
} Memdrawparam;
```

int	drawdebug;
int ulong* uchar* void	memimageinit(void) wordaddr(Memimage *i, Point p) byteaddr(Memimage *i, Point p) memimagemove(void *from, void *to)
Memimage* Memimage* Memimage* int void int	<pre>allocmemimage(Rectangle r, ulong chan) allocmemimaged(Rectangle r, ulong chan, Memdata *data) readmemimage(int fd) creadmemimage(int fd) writememimage(int fd, Memimage *i) freememimage(Memimage *i) memsetchan(Memimage*, ulong)</pre>
int	<pre>loadmemimage(Memimage *i, Rectangle r, uchar *buf, int nbuf)</pre>
int	cloadmemimage(Memimage *i, Rectangle r, uchar *buf, int nbuf)
int	unloadmemimage(Memimage *i, Rectangle r, uchar *buf, int nbuf)
void	memfillcolor(Memimage *i, ulong color)
void	<pre>memarc(Memimage *dst, Point c, int a, int b, int thick, Memimage *src, Point sp, int alpha, int phi, Drawop op)</pre>
void	<pre>mempoly(Memimage *dst, Point *p, int np, int end0,</pre>
void	<pre>memellipse(Memimage *dst, Point c, int a, int b,</pre>
void	<pre>memfillpoly(Memimage *dst, Point *p, int np, int wind, Memimage *src, Point sp, Drawop op)</pre>
void	<pre>memimageline(Memimage *dst, Point p0, Point p1, int end0,</pre>
void	<pre>memimagedraw(Memimage *dst, Rectangle r, Memimage *src, Point sp, Memimage *mask, Point mp, Drawop op)</pre>
int	drawclip(Memimage *dst, Rectangle *dr, Memimage *src, Point *sp, Memimage *mask, Point *mp, Rectangle *sr, Rectangle *mr)
int	<pre>drawclipnorepl(Memimage *dst, Rectangle *dr, Memimage *src,</pre>
Rectangle	Rectangle *sr, Rectangle *mr) memlinebbox(Point p0, Point p1, int end0, int end1, int radius)
int	memlineendsize(int end)
Memsubfont*	allocmemsubfont(char *name, int n, int height, int ascent, Fontchar *info, Memimage *i)
void Point	<pre>openmemsubfont(char *name) freememsubfont(Memsubfont *f) memsubfontwidth(Memsubfont *f, char *s) getmemdefont(void) memimagestring(Memimage *dst, Point p, Memimage *color,</pre>
int	hwdraw(Memdrawparam *param)

DESCRIPTION

The Memimage type defines memory-resident rectangular pictures and the methods to draw upon them; Memimages differ from Images (see draw(2)) in that they are manipulated directly in user memory rather than by RPCs to the /dev/draw hierarchy. The memdraw library is the basis for the kernel draw(3) driver and also used by a number of programs that must manipulate images without a display.

The r, clipr, depth, nchan, and chan structure elements are identical to the ones of the same name in the Image structure.

The flags element of the Memimage structure holds a number of bits of information about the image. In particular, it subsumes the purpose of the repl element of Image structures.

Memimageinit initializes various static data that the library depends on, as well as the replicated solid color images memopaque, memtransparent, memblack, and memwhite. It should be called before referring to any of these images and before calling any of the other library functions. It returns non-zero on error.

Each Memimage points at a Memdata structure that in turn points at the actual pixel data for the image. This allows multiple images to be associated with the same Memdata. The first word of the data pointed at by the base element of Memdata points back at the Memdata structure, so that the memory allocator (see *pool*(2)) can compact image memory using *memimagemove*.

Because images can have different coordinate systems, the zero element of the Memimage structure contains the offset that must be added to the bdata element of the corresponding Memdata structure in order to yield a pointer to the data for the pixel (0,0). Adding width machine words to this pointer moves it down one scan line. The depth element can be used to determine how to move the pointer horizontally. Note that this method works even for images whose rectangles do not include the origin, although one should only dereference pointers corresponding to pixels within the image rectangle. *Wordaddr* and *byteaddr* perform these calculations, returning pointers to the word and byte, respectively, that contain the beginning of the data for a given pixel.

Allocmemimage allocates images with a given rectangle and channel descriptor (see strtochan in graphics(2)), creating a fresh Memdata structure and associated storage. Allocmemimaged is similar but uses the supplied Memdata structure rather than a new one. The readmemimage function reads an uncompressed bitmap from the given file descriptor, while creadmemimage reads a compressed bitmap. Writememimage writes a compressed representation of *i* to file descriptor *fd*. For more on bitmap formats, see image(6). Freememimage frees images returned by any of these routines. The Memimage structure contains some tables that are used to store precomputed values depending on the channel descriptor. Memsetchan updates the chan element of the structure as well as these tables, returning -1 if passed a bad channel descriptor.

Loadmemimage and cloadmemimage replace the pixel data for a given rectangle of an image with the given buffer of uncompressed or compressed data, respectively. When calling *cloadmemimage*, the buffer must contain an integral number of compressed chunks of data that exactly cover the rectangle. Unloadmemimage retrieves the uncompressed pixel data for a given rectangle of an image. All three return the number of bytes consumed on success, and -1 in case of an error.

Memfillcolor fills an image with the given color, a 32-bit number as described in *color*(2).

Memarc, mempoly, memellipse, memfillpoly, memimageline, and memimagedraw are identical to the arc, poly, ellipse, fillpoly, line, and gendraw, routines described in draw(2), except that they operate on Memimages rather than Images. Similarly, allocmemsubfont, openmemsubfont, freememsubfont, memsubfontwidth, getmemdefont, and memimagestring are the Memimage analogues of allocsubfont, openfont, freesubfont, strsubfontwidth, getdefont, and string (see subfont(2) and graphics(2)), except that they operate only on Memsubfonts rather than Fonts.

Drawclip takes the images involved in a draw operation, together with the destination rectangle dr and source and mask alignment points sp and mp, and clips them according to the clipping rectangles of the images involved. It also fills in the rectangles sr and mr with rectangles congruent to the returned destination rectangle but translated so the upper left corners are the returned sp and mp. Drawclipnorepl does the same as drawclip but avoids clamping sp and mr within the image rectangle of source and mask when replicated. Drawclip and drawclipnorepl return zero when the clipped rectangle is empty. Memlinebbox returns a conservative bounding box containing a line between two points with given end styles and radius. Memlineendsize calculates the extra length added to a line by attaching an end of a given style.

The *hwdraw* function is a no-op stub that may be overridden by clients of the library. *Hwdraw* is called at each call to *memimagedraw* with the current request's parameters. If it can satisfy the request, it should do so and return 1. If it cannot satisfy the request, it should return 0. This

allows (for instance) the kernel to take advantage of hardware acceleration.

SOURCE

/sys/src/libmemdraw

SEE ALSO

addpt(2), color(2), draw(2), graphics(2), memlayer(2), stringsize(2), subfont(2), color(6), utf(6)

BUGS

Memimagestring is unusual in using a subfont rather than a font, and in having no parameter to align the source.

memdraw, memlalloc, memldelete, memlexpose, memlfree, memlhide, memline, memlnorefresh, memload, memunload, memlorigin, memlsetrefresh, memltofront, memltofrontn, memltorear, memltorearn – windows of memory-resident images

```
SYNOPSIS
#inc
```

```
#include <u.h>
#include <libc.h>
#include <draw.h>
#include <memdraw.h>
#include <memlayer.h>
typedef struct Memscreen Memscreen;
typedef struct Memlayer Memlayer;
typedef void (*Refreshfn)(Memimage*, Rectangle, void*);
struct Memscreen
{
             *frontmost; /* frontmost layer on screen */
  Memimage
             *rearmost; /* rearmost layer on screen */
  Memimage
  Memimage
            *image;
                        /* upon which all layers are drawn */
  Memimage
             *fill;
                        /* if non-zero, picture to use when repainting */
};
struct Memlayer
{
  Rectangle screenr;
                         /* true position of layer on screen */
                         /* add delta to go from image coords to screen */
  Point
            delta;
                         /* screen this layer belongs to */
  Memscreen *screen;
                         /* window in front of this one */
  Memimage *front;
                         /* window behind this one*/
  Memimage
             *rear;
                         /* layer is fully visible */
  int
             clear;
                         /* save area for obscured parts */
  Memimage
            *save;
  Refreshfn refreshfn; /* fn to refresh obscured parts if save==nil */
  void
             *refreshptr;/* argument to refreshfn */
};
Memimage* memlalloc(Memscreen *s, Rectangle r, Refreshfn fn, void *arg, ulong
void
          memlnorefresh(Memimage *i, Rectangle r, void *arg)
          memlsetrefresh(Memimage *i, Refreshfn fn, void *arg)
int
void
          memldelete(Memimage *i)
void
          memlfree(Memimage *i)
void
          memlexpose(Memimage *i, Rectangle r)
          memlhide(Memimage *i, Rectangle r)
void
void
          memltofront(Memimage *i)
void
          memltofrontn(Memimage**ia, int n)
void
          memltorear(Memimage *i)
void
          memltorearn(Memimage **ia , int n)
          memlorigin(Memimage *i, Point log, Point phys)
int
          memdraw(Memimage *dst, Rectangle r,
void
             Memimage *src, Point sp, Memimage *mask, Point mp, Drawop op)
          memload(Memimage *i, Rectangle r,
int
          uchar *buf, int n, int iscompressed)
int
          memunload(Memimage *i, Rectangle r,
          uchar *buf, int n)
```

DESCRIPTION

These functions build upon the *memdraw*(2) interface to maintain overlapping graphical windows on in-memory images. They are used by the kernel to implement the windows interface presented by *draw*(3) and *window*(2) and probably have little use outside of the kernel.

The basic function is to extend the definition of a Memimage (see *memdraw*(2)) to include overlapping windows defined by the Memlayer type. The first fields of the Memlayer structure are identical to those in Memimage, permitting a function that expects a Memimage to be passed a Memlayer, and vice versa. Both structures have a save field, which is nil in a Memimage and points to 'backing store' in a Memlayer. The layer routines accept Memimages or Memlayers; if the image is a Memimage the underlying Memimage routine is called; otherwise the layer routines recursively subdivide the geometry, reducing the operation into a smaller component that ultimately can be performed on a Memimage, either the display on which the window appears, or the backing store.

Memlayers are associated with a Memscreen that holds the data structures to maintain the windows and connects them to the associated image. The fill color is used to paint the background when a window is deleted. There is no function to establish a Memscreen; to create one, allocate the memory, zero frontmost and rearmost, set fill to a valid fill color or image, and set image to the Memimage (or Memlayer) on which the windows will be displayed.

Memlalloc allocates a Memlayer of size *r* on Memscreen *s*. If *col* is not DNofill, the new window will be initialized by painting it that color.

The refresh function *fn* and associated argument *arg* will be called by routines in the library to restore portions of the window uncovered due to another window being deleted or this window being pulled to the front of the stack. The function, when called, receives a pointer to the image (window) being refreshed, the rectangle that has been uncovered, and the *arg* recorded when the window was created. A couple of predefined functions provide built-in management methods: *memInorefresh* does no backup at all, useful for making efficient temporary windows; while a *nil* function specifies that the backing store (Memlayer.save) will be used to keep the obscured data. Other functions may be provided by the client. *MemIsetrefresh* allows one to change the function associated with the window.

Memldelete deletes the window *i*, restoring the underlying display. *Memlfree* frees the data structures without unlinking the window from the associated Memscreen or doing any graphics.

Memlexpose restores rectangle *r* within the window, using the backing store or appropriate refresh method. *Memlhide* goes the other way, backing up *r* so that portion of the screen may be modified without losing the data in this window.

Memltofront pulls *i* to the front of the stack of windows, making it fully visible. *Memltofrontn* pulls the *n* windows in the array *ia* to the front as a group, leaving their internal order unaffected. *Memltorear* and *memltorearn* push the windows to the rear.

Memlorigin changes the coordinate systems associated with the window *i*. The points *log* and *phys* represent the upper left corner (min) of the window's internal coordinate system and its physical location on the screen. Changing *log* changes the interpretation of coordinates within the window; for example, setting it to (0, 0) makes the upper left corner of the window appear to be the origin of the coordinate system, regardless of its position on the screen. Changing *phys* changes the physical location of the window on the screen. When a window is created, its logical and physical coordinates are the same, so

memlorigin(i, i->r.min, i->r.min)

would be a no-op.

Memdraw and *memline* are implemented in the layer library but provide the main entry points for drawing on memory-resident windows. They have the signatures of *memimagedraw* and *memimageline* (see *memdraw*(2)) but accept Memlayer or Memimage arguments both.

Memload and *memunload* are similarly layer-savvy versions of *loadmemimage* and *unloadmemimage*. The *iscompressed* flag to *memload* specifies whether the *n* bytes of data in *buf* are in compressed image format (see *image*(6)).

SOURCE

/sys/src/libmemlayer

SEE ALSO

graphics(2), memdraw(2), stringsize(2), window(2), draw(3)

memccpy, memchr, memcmp, memcpy, memmove, memset - memory operations

SYNOPSIS

```
#include <u.h>
#include <u.h>
#include <libc.h>
void* memccpy(void *s1, void *s2, int c, ulong n)
void* memchr(void *s1, void *s2, ulong n)
int memcmp(void *s1, void *s2, ulong n)
void* memmove(void *s1, void *s2, ulong n)
void* memmove(void *s1, void *s2, ulong n)
void* memset(void *s, int c, ulong n)
```

DESCRIPTION

These functions operate efficiently on memory areas (arrays of bytes bounded by a count, not terminated by a zero byte). They do not check for the overflow of any receiving memory area.

Memccpy copies bytes from memory area s_2 into s_1 , stopping after the first occurrence of byte c has been copied, or after n bytes have been copied, whichever comes first. It returns a pointer to the byte after the copy of c in s_1 , or zero if c was not found in the first n bytes of s_2 .

Memchr returns a pointer to the first occurrence of byte c in the first n bytes of memory area s, or zero if c does not occur.

Memcmp compares its arguments, looking at the first n bytes only, and returns an integer less than, equal to, or greater than 0, according as s1 is lexicographically less than, equal to, or greater than s2. The comparison is bytewise unsigned.

Memcpy copies *n* bytes from memory area *s2* to *s1*. It returns *s1*.

Memmove works like *memcpy*, except that it is guaranteed to work if *s1* and *s2* overlap.

Memset sets the first *n* bytes in memory area *s* to the value of byte *c*. It returns *s*.

SOURCE

All these routines have portable C implementations in /sys/src/libc/port. Most also have machine-dependent assembly language implementations in /sys/src/libc/\$objtype.

SEE ALSO

strcat(2)

BUGS

ANSI C does not require *memcpy* to handle overlapping source and destination; on Plan 9, it does, so *memmove* and *memcpy* behave identically.

If *memcpy* and *memmove* are handed a negative count, they abort.

mktemp - make a unique file name

SYNOPSIS

#include <u.h>
#include <libc.h>

char* mktemp(char *template)

DESCRIPTION

Mktemp replaces *template* by a unique file name, and returns the address of the template. The template should look like a file name with eleven trailing Xs. The Xs are replaced by a letter followed by the current process id. Letters from a to z are tried until a name that can be accessed (see *access*(2)) is generated. If no such name can be generated, *mktemp* returns "/".

SOURCE

/sys/src/libc/port/mktemp.c

SEE ALSO

getpid(2), access(2)

initmouse, readmouse, closemouse, moveto, getrect, drawgetrect, menuhit, setcursor, enter - mouse control

SYNOPSIS

DESCRIPTION

These functions access and control a mouse in a multi-threaded environment. They use the message-passing Channel interface in the threads library (see *thread*(2)); programs that wish a more event-driven, single-threaded approach should use *event*(2).

The state of the mouse is recorded in a structure, Mouse, defined in <mouse.h>:

```
typedef struct Mouse Mouse;
struct Mouse
{
    int buttons; /* bit array: LMR=124 */
    Point xy;
    ulong msec;
};
```

The Point xy records the position of the cursor, buttons the state of the buttons (three bits representing, from bit 0 up, the buttons from left to right, 0 if the button is released, 1 if it is pressed), and msec, a millisecond time stamp.

The routine initmouse returns a structure through which one may access the mouse:

```
typedef struct Mousectl Mousectl;
struct Mousectl
{
    Mouse:
                         /* chan(Mouse)[16] */
    Channel
              *c;
              *resizec; /* chan(int)[2] */
    Channel
    char
              *file;
                          /* to mouse file */
    int
              mfd;
                          /* to cursor file */
    int
              cfd;
                         /* of slave proc */
    int
              pid;
                          /* of associated window/display */
    Image*
              image;
};
```

The arguments to *initmouse* are a *file* naming the device file connected to the mouse and an *Image* (see draw(2)) on which the mouse will be visible. Typically the file is nil, which requests the

default /dev/mouse; and the image is the window in which the program is running, held in the variable screen after a call to *initdraw*.

Once the Mousectl is set up, mouse motion will be reported by messages of type Mouse sent on the Channel Mousectl.c. Typically, a message will be sent every time a read of /dev/mouse succeeds, which is every time the state of the mouse changes.

When the window is resized, a message is sent on Mousectl.resizec. The actual value sent may be discarded; the receipt of the message tells the program that it should call getwindow (see *graphics*(2)) to reconnect to the window.

Readmouse updates the Mouse structure held in the Mousectl, blocking if the state has not changed since the last *readmouse* or message sent on the channel. It calls flushimage (see *graphics*(2)) before blocking, so any buffered graphics requests are displayed.

Closemouse closes the file descriptors associated with the mouse, kills the slave processes, and frees the Mousectl structure.

Moveto moves the mouse cursor on the display to the position specified by *pt*.

Setcursor sets the image of the cursor to that specified by c. If c is nil, the cursor is set to the default. The format of the cursor data is spelled out in <cursor.h> and described in graphics(2).

Getrect returns the dimensions of a rectangle swept by the user, using the mouse, in the manner rio(1) or sam(1) uses to create a new window. The *but* argument specifies which button the user must press to sweep the window; any other button press cancels the action. The returned rectangle is all zeros if the user cancels.

Getrect uses successive calls to *drawgetrect* to maintain the red rectangle showing the sweep-inprogress. The rectangle to be drawn is specified by *rc* and the *up* parameter says whether to draw (1) or erase (0) the rectangle.

Menuhit provides a simple menu mechanism. It uses a Menu structure defined in <mouse.h>:

```
typedef struct Menu Menu;
struct Menu
{
    char **item;
    char *(*gen)(int);
    int lasthit;
};
```

Menuhit behaves the same as its namesake *emenuhit* described in *event*(2), with two exceptions. First, it uses a Mousectl to access the mouse rather than using the event interface; and second, it creates the menu as a true window on the Screen *scr* (see *window*(2)), permitting the menu to be displayed in parallel with other activities on the display. If *scr* is null, *menuhit* behaves like *emenuhit*, creating backing store for the menu, writing the menu directly on the display, and restoring the display when the menu is removed.

Enter is a multithreded version of the *eenter* function described in *event*(2). Like *menuhit*, it has a optional scr argument to create a window. Keyboard input is read from the channel in the Keyboardctl *kc argument (see *keyboard*(2)).

SOURCE

/sys/src/libdraw

SEE ALSO

graphics(2), draw(2), event(2), keyboard(2), thread(2).

mpsetminbits, mpnew, mpfree, mpbits, mpnorm, mpcopy, mpassign, mprand, mpnrand, strtomp, mpfmt, mptoa, betomp, mptobe, mptober, letomp, mptole, mptolel, mptoui, uitomp, mptoi, itomp, uvtomp, mptouv, vtomp, mptov, mptod, dtomp, mpdigdiv, mpadd, mpsub, mpleft, mpright, mpmul, mpexp, mpmod, mpmodadd, mpmodsub, mpmodmul, mpdiv, mpcmp, mpsel, mpfactorial, mpextendedgcd, mpinvert, mpsignif, mplowbits0, mpvecdigmuladd, mpwecdigmulsub, mpvecadd, mpvecsub, mpveccmp, mpvecmul, mpmagcmp, mpmagadd, mpmagsub, crtpre, crtin, crtout, crtprefree, crtresfree – extended precision arithmetic

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <mp.h>
mpint*
       mpnew(int n)
void
        mpfree(mpint *b)
void
        mpsetminbits(int n)
void
        mpbits(mpint *b, int n)
mpint*
        mpnorm(mpint *b)
mpint*
        mpcopy(mpint *b)
void
        mpassign(mpint *old, mpint *new)
mpint*
        mprand(int bits, void (*gen)(uchar*, int), mpint *b)
        mpnrand(mpint *n, void (*gen)(uchar*, int), mpint *b)
mpint*
        strtomp(char *buf, char **rptr, int base, mpint *b)
mpint*
char*
        mptoa(mpint *b, int base, char *buf, int blen)
        mpfmt(Fmt*)
int
        betomp(uchar *buf, uint blen, mpint *b)
mpint*
int
        mptobe(mpint *b, uchar *buf, uint blen, uchar **bufp)
void
        mptober(mpint *b, uchar *buf, int blen)
mpint*
        letomp(uchar *buf, uint blen, mpint *b)
        mptole(mpint *b, uchar *buf, uint blen, uchar **bufp)
int
void
        mptolel(mpint *b, uchar *buf, int blen)
uint
        mptoui(mpint*)
mpint*
        uitomp(uint, mpint*)
int
        mptoi(mpint*)
mpint*
        itomp(int, mpint*)
        vtomp(vlong, mpint*)
mpint*
vlong
        mptov(mpint*)
mpint*
        uvtomp(uvlong, mpint*)
uvlong
        mptouv(mpint*)
mpint*
        dtomp(double, mpint*)
double
        mptod(mpint*)
void
        mpadd(mpint *b1, mpint *b2, mpint *sum)
void
        mpmagadd(mpint *b1, mpint *b2, mpint *sum)
        mpsub(mpint *b1, mpint *b2, mpint *diff)
void
void
        mpmagsub(mpint *b1, mpint *b2, mpint *diff)
```

```
void
        mpleft(mpint *b, int shift, mpint *res)
        mpright(mpint *b, int shift, mpint *res)
void
        mpand(mpint *b1, mpint *b2, mpint *res)
void
void
        mpbic(mpint *b1, mpint *b2, mpint *res)
        mpor(mpint *b1, mpint *b2, mpint *res)
void
        mpnot(mpint *b, mpint *res)
void
void
        mpxor(mpint *b1, mpint *b2, mpint *res)
        mptrunc(mpint *b, int n, mpint *res)
void
void
        mpxtend(mpint *b, int n, mpint *res)
        mpasr(mpint *b, int n, mpint *res)
void
void
        mpmul(mpint *b1, mpint *b2, mpint *prod)
void
        mpexp(mpint *b, mpint *e, mpint *m, mpint *res)
        mpmod(mpint *b, mpint *m, mpint *remainder)
void
void
        mpdiv(mpint *dividend, mpint *divisor,
                                                 mpint *quotient,
        mpint *remainder)
        mpmodadd(mpint *b1, mpint *b2, mpint *m, mpint *sum)
void
        mpmodsub(mpint *b1, mpint *b2, mpint *m, mpint *diff)
void
        mpmodmul(mpint *b1, mpint *b2, mpint *m, mpint *prod)
void
int
        mpcmp(mpint *b1, mpint *b2)
int
        mpmagcmp(mpint *b1, mpint *b2)
void
        mpsel(int s, mpint *b1, mpint *b2, mpint *res)
mpint*
        mpfactorial(ulong n)
void
        mpextendedgcd(mpint *a, mpint *b, mpint *d, mpint *x,
        mpint *y)
void
        mpinvert(mpint *b, mpint *m, mpint *res)
int
        mpsignif(mpint *b)
        mplowbits0(mpint *b)
int
        mpdigdiv(mpdigit *dividend, mpdigit divisor,
void
        mpdigit *quotient)
        mpvecadd(mpdigit *a, int alen, mpdigit *b, int blen,
void
        mpdigit *sum)
void
        mpvecsub(mpdigit *a, int alen, mpdigit *b, int blen,
        mpdigit *diff)
void
        mpvecdigmuladd(mpdigit *b, int n, mpdigit m, mpdigit *p)
        mpvecdigmulsub(mpdigit *b, int n, mpdigit m, mpdigit *p)
int
void
        mpvecmul(mpdigit *a, int alen, mpdigit *b, int blen,
        mpdigit *p)
        mpveccmp(mpdigit *a, int alen, mpdigit *b, int blen)
int
CRTpre* crtpre(int nfactors, mpint **factors)
CRTres* crtin(CRTpre *crt, mpint *x)
void
        crtout(CRTpre *crt, CRTres *r, mpint *x)
void
        crtprefree(CRTpre *cre)
void
        crtresfree(CRTres *res)
mpint
        *mpzero, *mpone, *mptwo
```

DESCRIPTION

These routines perform extended precision integer arithmetic. The basic type is mpint, which points to an array of mpdigits, stored in little-endian order:

```
typedef struct mpint mpint;
struct mpint
{
    int sign; /* +1 or -1 */
    int size; /* allocated digits */
    int top; /* significant digits */
    mpdigit *p;
    char flags;
};
```

The sign of 0 is +1.

The size of mpdigit is architecture-dependent and defined in /\$cputype/include/u.h. Mpints are dynamically allocated and must be explicitly freed. Operations grow the array of digits as needed.

In general, the result parameters are last in the argument list.

Routines that return an mpint will allocate the mpint if the result parameter is nil. This includes *strtomp*, *itomp*, *uitomp*, *btomp*, and *dtomp*. These functions, in addition to *mpnew* and *mpcopy*, will call sysfatal (see *perror*(2)) if the allocation fails.

Input and result parameters may point to the same mpint. The routines check and copy where necessary.

Mpnew creates an mpint with an initial allocation of *n* bits. If *n* is zero, the allocation will be whatever was specified in the last call to *mpsetminbits* or to the initial value, 1056. *Mpfree* frees an mpint. *Mpbits* grows the allocation of *b* to fit at least *n* bits. If $b \rightarrow top$ doesn't cover *n* bits, *mpbits* increases it to do so. Unless you are writing new basic operations, you can restrict yourself to mpnew(0) and mpfree(b).

Mpnorm normalizes the representation by trimming any high order zero digits. All routines except mpbits return normalized results.

Mpcopy creates a new mpint with the same value as *b* while *mpassign* sets the value of *new* to be that of *old*.

Mprand creates an *n* bit random number using the generator *gen*. *Gen* takes a pointer to a string of uchar's and the number to fill in.

Mpnrand uses *gen* to generate a uniform random number x, $0 \le x < n$.

Strtomp and mptoa convert between ASCII and mpint representations using the base indicated. Only the bases 2, 4, 8, 10, 16, 32, and 64 are supported. Strtomp skips any leading spaces or tabs. Strtomp's scan stops when encountering a digit not valid in the base. If base is zero then C-style prefixes are interpreted to find the base: Ox for hexadecimal, Ob for binary and O for octal. Otherwise decimal is assumed. rptr is not zero, *rptr is set to point to the character immediately after the string converted. If the parse terminates before any digits are found, strtomp return nil. Mptoa returns a pointer to the ASCII filled buffer. If the parameter buf is nil, the buffer is allocated. Setting base to zero uses hexadecimal default. Mpfmt can be used with fmtinstall(2) and print(2) to print ASCII representations of mpints. The conventional verb is B, for which mp.h provides a pragma. The precision in the format string changes the base, defaulting to hexadecimal when omited.

Mptobe and *mptole* convert an *mpint* to a byte array. The former creates a big endian representation, the latter a little endian one. If the destination *buf* is not nil, it specifies the buffer of length *blen* for the result. If the representation is less than *blen* bytes, the rest of the buffer is zero filled. If *buf* is nil, then a buffer is allocated and a pointer to it is deposited in the location pointed to by *bufp*. Sign is ignored in these conversions, i.e., the byte array version is always positive.

Mptober and *mptolel* fill *blen* lower bytes of an *mpint* into a fixed length byte array. *Mptober* fills the bytes right adjusted in big endian order so that the least significant byte is at *buf[blen-1]* while *mptolel* fills in little endian order; left adjusted; so that the least significat byte is filled into *buf[0]*.

Betomp, and *letomp* convert from a big or little endian byte array at *buf* of length *blen* to an *mpint*. If *b* is not *nil*, it refers to a preallocated *mpint* for the result. If *b* is nil, a new integer is allocated and returned as the result.

The integer (and floating point) conversions are:

mptoui uitomp mptoi itomp mptouv uvtomp mptov vtomp	<pre>mpint->unsigned int unsigned int->mpint mpint->int int->mpint mpint->unsigned vlong unsigned vlong->mpint mpint->vlong vlong->mpint</pre>
,	

When converting to the base integer types, if the integer is too large, the largest integer of the appropriate sign and size is returned.

When converting to and from floating point, results are rounded using IEEE 754 "round to nearest". If the integer is too large in magnitude, *mptod* returns infinity of the appropriate sign.

The mathematical functions are:

mpadd	sum = b1 + b2.	
mpmagadd	sum = abs(b1) + abs(b2).	
mpsub	diff = b1 - b2.	
mpmagsub	diff = abs(b1) - abs(b2).	
mpleft	res = b< <shift.< td=""></shift.<>	
mpright	res = b>>shift.	
mpmul	prod = b1*b2.	
трехр	if m is nil, res = b**e. Otherwise, res = b**e mod m.	
mpmod	remainder = b % m.	
mpdiv	<pre>quotient = dividend/divisor. remainder = dividend %</pre>	
	divisor.	
трстр	returns -1 , 0, or $+1$ as b1 is less than, equal to, or greater than b2.	
тртадстр	the same as <i>mpcmp</i> but ignores the sign and just compares magnitudes.	
mpsel	assigns $b1$ to res when s is not zero, otherwise $b2$ is assigned to res.	
mpfactorial	returns <i>n</i> !.	
in protocor for		

Logical operations (treating negative numbers using two's complement):

mpand	res = b1 & b2.
mpbic	res = b1 & ~b2.
mpor	res = b1 b2.
mpxor	res = $b1 \wedge b2$.
mpnot	res = ~b1.
mpasr	<pre>res = b>>shift (mpasr, unlike mpright, uses two's complement).</pre>
mptrunc	truncates <i>b</i> to <i>n</i> bits and stores the result in <i>res</i> . The result is never negative.
mpxtend	truncates b to n bits, sign extends the MSB and stores the result in <i>res</i> .

Modular arithmetic:

mpmodadd	$sum = b1+b2 \mod m$.
mpmodsub	diff = $b1-b2 \mod m$.
mpmodmul	$prod = b1*b2 \mod m$.

Mpextendedgcd computes the greatest common denominator, *d*, of *a* and *b*. It also computes *x* and *y* such that a*x + b*y = d. Both *a* and *b* are required to be positive. If called with negative arguments, it will return a gcd of 0.

Mpinvert computes the multiplicative inverse of *b* mod *m*.

Mpsignif returns the number of significant bits in *b*. *Mplowbits0* returns the number of consecutive zero bits at the low end of the significant bits. For example, for 0x14, *mpsignif* returns 5 and *mplowbits0* returns 2. For 0, *mpsignif* and *mplowbits0* both return 0.

The remaining routines all work on arrays of mpdigit rather than mpint's. They are the basis of all the other routines. They are separated out to allow them to be rewritten in assembler for each architecture. There is also a portable C version for each one.

mpdigdiv	<pre>quotient = dividend[0:1] / divisor.</pre>
mpvecadd	sum[0:alen] = a[0:alen-1] + b[0:blen-1]. We assume alen >= blen and that sum has room for alen+1 digits.
mpvecsub	diff[0:alen-1] = a[0:alen-1] - b[0:blen-1]. We assume that alen >= blen and that diff has room for alen digits.
mpvecdigmuladd	p[0:n] += m * b[0:n-1]. This multiplies a an array of digits times a scalar and adds it to another array. We assume p has room for n+1 dig-
	its.
mpvecdigmulsub	p[0:n] = m * b[0:n-1]. This multiplies a an array of digits times a scalar and subtracts it from another array. We assume p has room for
mpvecmul	n+1 digits. It returns $+1$ is the result is positive and -1 if negative. p[0:alen+blen] = a[0:alen-1] * b[0:blen-1]. We assume
mpveemu	that p has room for alen+blen+1 digits.
трvесстр	This returns -1, 0, or +1 as a - b is negative, 0, or positive.

mptwo, mpone and mpzero are the constants 2, 1 and 0. These cannot be freed.

Time invariant computation

In the field of cryptography, it is sometimes neccesary to implement algorithms such that the runtime of the algorithm is not depdenent on the input data. This library provides partial support for time invariant computation with the *MPtimesafe* flag that can be set on input or destination operands to request timing safe operation. The result of a timing safe operation will also have the *MPtimesafe* flag set and is not normalized.

Chinese remainder theorem

When computing in a non-prime modulus, n, it is possible to perform the computations on the residues modulo the prime factors of n instead. Since these numbers are smaller, multiplication and exponentiation can be much faster.

Crtin computes the residues of *x* and returns them in a newly allocated structure:

```
typedef struct CRTres CRTres;
{
    int n; /* number of residues */
    mpint *r[n]; /* residues */
};
```

Crtout takes a residue representation of a number and converts it back into the number. It also frees the residue structure.

Crepre saves a copy of the factors and precomputes the constants necessary for converting the residue form back into a number modulo the product of the factors. It returns a newly allocated structure containing values.

Crtprefree and crtresfree free CRTpre and CRTres structures respectively.

SOURCE

/sys/src/libmp

muldiv, umuldiv - high-precision multiplication and division

SYNOPSIS

#include <u.h>

#include <libc.h>

long muldiv(long a, long b, long c)

ulong umuldiv(ulong a, ulong b, ulong c)

DESCRIPTION

Muldiv returns a*b/c, using a vlong to hold the intermediate result. *Umuldiv* is the equivalent for unsigned integers. They can be used to scale integer values without worry about overflowing the intermediate result.

On some architectures, these routines can generate a trap if the final result does not fit in a long or ulong; on others they will silently truncate.

NaN, Inf, isNaN, isInf - not-a-number and infinity functions

SYNOPSIS

#include <u.h>
#include <libc.h>
double NaN(void)
double Inf(int)
int isNaN(double)

int isInf(double, int)

DESCRIPTION

The IEEE floating point standard defines values called 'not-a-number' and positive and negative 'infinity'. These values can be produced by such things as overflow and division by zero. Also, the library functions sometimes return them when the arguments are not in the domain, or the result is out of range. By default, manipulating these values may cause a floating point exception on some processors but *setfcr* (see *getfcr*(2)) can change that behavior.

NaN returns a double that is not-a-number. IsNaN returns true if its argument is not-a-number.

Inf(i) returns positive infinity if *i* is greater than or equal to zero, else negative infinity. *IsInf* returns true if its first argument is infinity with the same sign as the second argument.

SOURCE

/sys/src/libc/port/nan.c

SEE ALSO

getfcr(2)

ndbopen, ndbcat, ndbchanged, ndbclose, ndbreopen, ndbsearch, ndbsnext, ndbgetvalue, ndbfree, ipattr, ndbgetipaddr, ndbipinfo, csipinfo, ndbhash, ndbparse, csgetvalue, ndbfindattr, dnsquery, ndbdiscard, ndbconcatenate, ndbreorder, ndbsubstitute, ndbdedup – network database

SYNOPSIS

<pre>#include <u #<="" #include="" <1="" th=""><th>Libc.h> pio.h></th></u></pre>	Libc.h> pio.h>
Ndb*	ndbopen(char *file)
Ndb*	ndbcat(Ndb *db1, Ndb *db2)
int	ndbchanged(Ndb *db)
int	ndbreopen(Ndb *db)
void	ndbclose(Ndb *db)
Ndbtuple*	ndbsearch(Ndb *db, Ndbs *s, char *attr, char *val)
Ndbtuple*	ndbsnext(Ndbs *s, char *attr, char *val)
char*	ndbgetvalue(Ndb *db, Ndbs *s, char *attr, char *val, char *rattr, Ndbtuple **tp)
char*	<pre>csgetvalue(char *netroot, char *attr, char *val, char *rattr, Ndbtuple **tp)</pre>
char*	<pre>ipattr(char *name)</pre>
Ndbtuple*	ndbgetipaddr(Ndb *db, char *sys);
Ndbtuple*	ndbipinfo(Ndb *db, char *attr, char *val, char **attrs, int nattr)
Ndbtuple*	csipinfo(char *netroot, char *attr, char *val, char **attrs, int nattr)
ulong	ndbhash(char *val, int hlen)
Ndbtuple*	ndbparse(Ndb *db)
Ndbtuple*	<pre>dnsquery(char *netroot, char *domainname, char *type)</pre>
Ndbtuple*	<pre>ndbfindattr(Ndbtuple *entry, Ndbtuple *line, char *attr)</pre>
void	ndbfree(Ndbtuple *db)
Ndbtuple*	ndbdiscard(Ndbtuple *t, Ndbtuple *a)
Ndbtuple*	ndbconcatenate(Ndbtuple *a, Ndbtuple *b)
Ndbtuple*	ndbreorder(Ndbtuple *t, Ndbtuple *a)
Ndbtuple*	<pre>ndbsubstitute(Ndbtuple *t, Ndbtuple *from, Ndbtuple *to)</pre>
Ndbtuple*	ndbdedup(Ndbtuple *t)
void	ndbsetmalloctag(Ndbtuple *t, uintptr tag)

DESCRIPTION

These routines are used by network administrative programs to search the network database. They operate on the database files described in ndb(6).

Ndbopen opens the database *file* and calls *malloc*(2) to allocate a buffer for it. If *file* is zero, all network database files are opened.

Ndbcat concatenates two open databases. Either argument may be nil.

Ndbreopen throws out any cached information for the database files associated with db and reopens the files.

Ndbclose closes any database files associated with *db* and frees all storage associated with them.

Ndbsearch and ndbsnext search a database for an entry containing the attribute/value pair, attr=val. Ndbsearch is used to find the first match and ndbsnext is used to find each successive match. On a successful search both return a linked list of Ndbtuple structures acquired by malloc(2) that represent the attribute/value pairs in the entry. On failure they return zero.

```
typedef struct Ndbtuple Ndbtuple;
struct Ndbtuple {
        char
                  attr[Ndbalen];
        char
                  *val:
        Ndbtuple
                  *entry;
        Ndbtuple
                  *line:
        ulong
                           /* for the application; starts 0 */
                  ptr;
                  valbuf[Ndbvlen]; /* initial allocation for val */
        char
};
```

The *entry* pointers chain together all pairs in the entry in a null-terminated list. The *line* pointers chain together all pairs on the same line in a circular list. Thus, a program can implement 2 levels of binding for pairs in an entry. In general, pairs on the same line are bound tighter than pairs on different lines.

The argument *s* of *ndbsearch* has type *Ndbs* and should be pointed to valid storage before calling *ndbsearch*, which will fill it with information used by *ndbsnext* to link successive searches. The structure *Ndbs* looks like:

```
typedef struct Ndbs Ndbs;
struct Ndbs {
     Ndb  *db; /* data base file being searched */
     ...
     Ndbtuple *t; /* last attribute value pair found */
};
```

The *t* field points to the pair within the entry matched by the *ndbsearch* or *ndbsnext*.

Ndbgetvalue searches the database for an entry containing not only an attribute/value pair, attr = val, but also a pair with the attribute *rattr*. If successful, it returns a malloced copy of the NUL-terminated value associated with *rattr*. If *tp* is non nil, **tp* will point to the entry. Otherwise the entry will be freed.

Csgetvalue is like *ndbgetvalue* but queries the connection server instead of looking directly at the database. Its first argument specifies the network root to use. If the argument is 0, it defaults to "/net".

Ndbfree frees a list of tuples returned by one of the other routines.

Ipattr takes the name of an IP system and returns the attribute it corresponds to:

- dom domain name
- ip Internet number
- sys system name

Ndbgetipaddr looks in *db* for entries matching *sys* as the value of a sys= or dom= attribute/value pair and returns all IP addresses. If *sys* is already an IP address, a tuple containing just that address is returned.

Ndbipinfo looks up Internet protocol information about a system. This is an IP aware search. It looks first for information in the system's database entry and then in the database entries for any IP subnets or networks containing the system. The system is identified by the attribute/value pair, attr=val. *Ndbipinfo* returns a list of tuples whose attributes match the attributes in the *n* element array *attrs*. If any *attrs* begin with @, the @ is excluded from the attribute name, but causes any corresponding value returned to be a resolved IP address(es), not a name. For example, consider the following database entries describing a network, a subnetwork, and a system.

```
ipnet=big ip=10.0.0.0
    dns=dns.big.com
    smtp=smtp.big.com
```

Calling

ndbipinfo(db, "dom", "x.big.com", ["bootf" "smtp" "dns"], 3)

will return the tuples bootf=/386/9pc, smtp=smtp1.big.com, and dns=dns.big.com.

Csipinfo is to ndbipinfo as csgetvalue is to ndbgetvalue.

The next three routines are used by programs that create the hash tables and database files. *Ndbhash* computes a hash offset into a table of length *hlen* for the string *val*. *Ndbparse* reads and parses the next entry from the database file. Multiple calls to *ndbparse* parse sequential entries in the database file. A zero is returned at end of file.

Dnsquery submits a query about *domainname* to the *ndb/dns* mounted at *netroot/dns*. It returns a linked list of *Ndbtuple's* representing a single database entry. The tuples are logically arranged into lines using the line field in the structure. The possible *type*'s of query are and the attributes on each returned tuple line is:

- ip find the IP addresses. Returns domain name (*dom*) and ip address (*ip*).
- ipv6 find the IPv6 addresses. Returns domain name (*dom*) and ipv6 address (*ip*).
- mx look up the mail exchangers. Returns preference (*pref*) and exchanger (*mx*).
- ptr do a reverse query. Here *domainname* must be an ASCII IP address. Returns reverse name (*ptr*) and domain name (*dom*).

cname

get the system that this name is a nickname for. Returns the nickname (*dom*) and the real name (*cname*).

- soa return the start of area record for this field. Returns area name (*dom*), primary name server (*ns*), serial number (*serial*), refresh time in seconds (*refresh*), retry time in seconds (*retry*), expiration time in seconds (*expire*), and minimum time to lie (*ttl*).
- srv get the service records. Returns the priority of target host (*pri*), relative weight (*weight*) for entries with the same priority, port on this target host of this service (*port*), and the domain name of the target host (*target*).
- txt get the descriptive text. The semantics of the text depends on the domain.

ns name servers. Returns domain name (*dom*) and name server (*ns*).

Ndbfindattr searches *entry* for the tuple with attribute *attr* and returns a pointer to the tuple. If *line* points to a particular line in the entry, the search starts there and then wraps around to the beginning of the entry.

All of the routines provided to search the database provide an always consistent view of the relevant files. However, it may be advantageous for an application to read in the whole database using *ndbopen* and *ndbparse* and provide its own search routines. The *ndbchanged* routine can be used by the application to periodically check for changes. It returns zero if none of the files comprising the database have changes and non-zero if they have.

Finally, a number of routines are provided for manipulating tuples.

Ndbdiscard removes attr/val pair *a* from tuple *t* and frees it. If *a* isn't in *t* it is just freed.

Ndbconcatenate concatenates two tuples and returns the result. Either or both tuples may be nil.

Ndbreorder reorders a tuple *t* to make the line containing attr/val pair *a* first in the entry and making *a* first in its line.

Ndbsubstitute replaces a single attr/val pair *from* in *t* with the tuple *to*. All attr/val pairs in *to* end up on the same line. *from* is freed.

Ndbdedup removes duplicate attr/val pairs from tuple list *t*.

Ndbsetmalloctag sets the malloc tag (see setmalloctag in malloc(2)) of each tuple in the list t to tag.

FILES

/lib/ndb directory of network database files

SOURCE

/sys/src/libndb

SEE ALSO

ndb(6), ndb(8)

notify, noted, atnotify - handle asynchronous process notification

SYNOPSIS

#include <u.h>
#include <libc.h>
int notify(void (*f)(void*, char*))
int noted(int v)
int atnotify(int (*f)(void*, char*), int in)

DESCRIPTION

When a process raises an exceptional condition such as dividing by zero or writing on a closed pipe, a *note* is posted to communicate the exception. A note may also be posted by a *write* (see *read*(2)) to the process's /proc/n/note file or to the /proc/m/notepg file of a process in the same process group (see *proc*(3)). When the note is received the behavior of the process depends on the origin of the note. If the note was posted by an external process, the process receiving the note exits; if generated by the system the note string, preceded by the name and id of the process and the string "suicide: ", is printed on the process's standard error file and the process is suspended in the Broken state for debugging.

These default actions may be overridden. The *notify* function registers a *notification handler* to be called within the process when a note is received. The argument to *notify* replaces the previous handler, if any. An argument of zero cancels a previous handler, restoring the default action. A *fork*(2) system call leaves the handler registered in both the parent and the child; *exec*(2) restores the default behavior. Handlers may not perform floating point operations.

After a note is posted, the handler is called with two arguments: the first is a pointer to a Ureg structure (defined in /\$objtype/include/ureg.h) giving the current values of registers; the second is a pointer to the note itself, a null-terminated string with no more than ERRLEN characters in it including the terminal NUL. The Ureg argument is usually not needed; it is provided to help recover from traps such as floating point exceptions. Its use and layout are machine- and system-specific.

A notification handler must finish either by exiting the program or by calling *noted*; if the handler returns the behavior is undefined and probably erroneous. Until the program calls *noted*, any further externally-generated notes (e.g., hangup or alarm) will be held off, and any further notes generated by erroneous behavior by the program (such as divide by zero) will kill the program. The argument to *noted* defines the action to take: NDFLT instructs the system to perform the default action as if the handler had never been registered; NCONT instructs the system to resume the process at the point it was notified. In neither case does *noted* return to the handler. If the note interrupted an incomplete system call, that call returns an error (with error string interrupted) after the process resumes. A notification handler can also jump out to an environment set up with *setjmp* using the *notejmp* function (see *setjmp*(2)), which is implemented by modifying the saved state and calling noted (NCONT).

Regardless of the origin of the note or the presence of a handler, if the process is being debugged (see *proc*(3)) the arrival of a note puts the process in the Stopped state and awakens the debugger.

Atnotify

Rather than using the system calls *notify* and *noted*, most programs should use *atnotify* to register notification handlers. The parameter *in* is non-zero to register the function *f*, and zero to cancel registration. A handler must return a non-zero number if the note was recognized (and resolved); otherwise it must return zero. When the system posts a note to the process, each handler registered with *atnotify* is called with arguments as described above until one of the handlers returns non-zero. Then *noted* is called with argument NCONT. If no registered function returns non-zero, *atnotify* calls *noted* with argument NDFLT.

APE

Noted has two other possible values for its argument. NSAVE returns from the handler and clears the note, enabling the receipt of another, but does not return to the program. Instead it starts a new handler with the same stack, stack pointer, and arguments as the original, at the address

recorded in the program counter of the Ureg structure. Typically, the program counter will be overridden by the first note handler to be the address of a separate function; NSAVE is then a 'trampoline' to that handler. That handler may execute noted(NRSTR) to return to the original program, usually after restoring the original program counter. NRSTR is identical to NCONT except that it can only be executed after an NSAVE. NSAVE and NRSTR are designed to improve the emulation of signals by the ANSI C/POSIX environment; their use elsewhere is discouraged.

Notes

The set of notes a process may receive is system-dependent, but there is a common set that includes:

Note	Meaning
interrupt	user interrupt (DEL key)
hangup	I/O connection closed
alarm	alarm expired
sys: breakpoint	breakpoint instruction
sys: bad address	system call address argument out of range
sys: odd address	system call address argument unaligned
sys: bad sys call	system call number out of range
sys: odd stack	system call user stack unaligned
sys: write on closed pipe	write on closed pipe
sys: fp: fptrap	floating point exception
sys: trap: <i>trap</i>	other exception (see below)

The notes prefixed sys: are generated by the operating system. They are suffixed by the user program counter in format pc=0x1234. If the note is due to a floating point exception, just before the pc is the address of the offending instruction in format fppc=0x1234. Notes are limited to ERRLEN bytes; if they would be longer they are truncated but the pc is always reported correctly.

The types and syntax of the *trap* and *fptrap* portions of the notes are machine-dependent.

SOURCE

/sys/src/libc/9syscall
/sys/src/libc/port/atnotify.c

SEE ALSO

postnote(2), intro(2), notejmp in setjmp(2)

BUGS

Since *exec*(2) discards the notification handler, there is a window of vulnerability to notes in a new process.

usbcmd, classname, closedev, configdev, devctl, getdev, loaddevstr, opendev, opendevdata, openep, unstall – USB device driver library

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include "../lib/usb.h"
struct Dev {
     Ref;
     char* dir;
                     /* path for the endpoint dir */
                     /* usb id for device or ep. number */
     int id;
                     /* descriptor for the data file */
     int
          dfd:
                     /* descriptor for the control file */
     int
          cfd;
                           /* cached from usb description */
     int
          maxpkt;
     Usbdev* usb;
                           /* USB description */
                     /* for the device driver */
     void* aux;
     void (*free)(void*); /* idem. to release aux */
     char* hname;
                           /* hash name, unique for device */
};
struct Usbdev {
                     /* USB class/subclass/proto */
     ulong csp;
                     /* vendor id */
     int vid;
                     /* product (device) id */
     int
          did;
     int
          dno;
                     /* device release number */
     char* vendor;
     char* product;
     char* serial;
     int ls;
                     /* low speed */
     int class;
                           /* from descriptor */
                           /* from descriptor */
     int nconf;
                         /* configurations */
     Conf* conf[Nconf];
     Ep* ep[Nep]; /* all endpoints in device */
     Desc* ddesc[Nddesc]; /* (raw) device specific descriptors */
};
struct Ep {
     uchar addr;
                     /* endpt address */
                     /* direction, Ein/Eout */
     uchar dir;
     uchar type;
                    /* Econtrol, Eiso, Ebulk, Eintr */
                     /* Eunknown, Easync, Eadapt, Esync */
     uchar isotype;
          id;
     int
     int maxpkt;
                           /* max. packet size */
     Conf* conf;
                     /* the endpoint belongs to */
     Iface*
                iface; /* the endpoint belongs to */
};
struct Altc {
     int attrib;
     int
          interval;
                     /* for the driver program */
     void* aux;
};
struct Iface {
     int id;
                     /* interface number */
     ulong csp;
                     /* USB class/subclass/proto */
     Altc* altc[Naltc];
     Ep* ep[Nep];
                    /* for the driver program */
     void* aux;
};
```

```
struct Conf {
          cval;
                      /* value for set configuration */
     int
     int
           attrib;
           milliamps; /* maximum power in this config. */
     int
     Iface*
                 iface[Niface];
                                /* up to 16 interfaces */
}:
struct Desc {
     Conf* conf;
                      /* where this descriptor was read */
     Iface*
                 iface;
                                 /* last iface before desc in conf. */
                      /* last endpt before desc in conf. */
     Ep*
          ep;
                      /* last alt.c. before desc in conf. */
     Altc* altc;
                      /* unparsed standard USB descriptor */
     DDesc data;
};
struct DDesc {
     uchar bLength;
     uchar bDescriptorType;
     uchar bbytes[1];
     /* extra bytes allocated here to keep the rest of it */
};
#define Class(csp)
                       ((csp)&0xff)
#define Subclass(csp) (((csp)>>8)&0xff)
#define Proto(csp)
                       (((csp)>>16)&0xff)
#define CSP(c, s, p)
                      ((c) | ((s)<<8) | ((p)<<16))
#define
           GET2(p)
                            . . .
#define
           PUT2(p,v)
                       . . .
           GET4(p)
#define
                            . . .
#define
           PUT4(p,v)
                       . . .
#define dprint
                 if(usbdebug)fprint
#define ddprint if(usbdebug > 1)fprint
int
     Ufmt(Fmt *f);
char* classname(int c);
void closedev(Dev *d);
     configdev(Dev *d);
int
     devctl(Dev *dev, char *fmt, ...);
int
void* emallocz(ulong size, int zero);
char* estrdup(char *s);
char* hexstr(void *a, int n);
char* loaddevstr(Dev *d, int sid);
Dev* opendev(char *fn);
     opendevdata(Dev *d, int mode);
int
Dev* openep(Dev *d, int id);
int
     unstall(Dev *dev, Dev *ep, int dir);
     usbcmd(Dev *d, int type, int req,
int
           int value, int index, uchar *data, int count);
Dev* getdev(char *devid);
extern int usbdebug: /* more messages for bigger values */
```

DESCRIPTION

This library provides convenience structures and functions to write USB device drivers. It is not intended for user programs using USB devices. See usb(3) for a description of the interfaces provided for that purpose.

Usb drivers rely on usb(3) to perform I/O through USB as well as on usbd to perform the initial configuration for the device's setup endpoint. The rest of the work is up to the driver and is where this library may help.

An endpoint as provided by usb(3) is represented by a Dev data structure. The setup endpoint for a device represents the USB device, because it is the means to configure and operate the device. This structure is reference counted. Functions creating Devs adjust the number of references to one, initially. The driver is free to call *incref* (in *lock*(2)) to add references and *closedev* to drop

references (and release resources when the last one vanishes). As an aid to the driver, the field aux may keep driver-specific data and the function free will be called (if not null) to release the aux structure when the reference count goes down to zero.

Dev.dir holds the path for the endpoint's directory.

The field id keeps the device number for setup endpoints and the endpoint number for all other endpoints. For example, it would be 3 for /dev/usb/ep3.0 and 1 for /dev/usb/ep3.1. It is easy to remember this because the former is created to operate on the device, while the later has been created as a particular endpoint to perform I/O.

Fields dfd and cfd keep the data and control file descriptors, respectively. When a Dev is created the control file is open, initially. Opening the data file requires calling *opendevdata* with the appropriate mode.

When the device configuration information has been loaded (see below), maxpkt holds the maximum packet size (in bytes) for the endpoint and usb keeps the rest of the USB information.

Most of the information in usb comes from parsing various device and configuration descriptors provided by the device, by calling one of the functions described later. Only descriptors unknown to the library are kept unparsed at usb.ddesc as an aid for the driver (which should know how to parse them and what to do with the information).

Configuration

Getdev is the primary entry point for device setup. It takes a numeric device address or device path which usually gets passed to drivers as a program argument and sets up the device, retuning a configured Dev representing the setup endpoint of the device.

Opendev creates a Dev for the endpoint with directory *fn*. Usually, the endpoint is a setup endpoint representing a device. The endpoint control file is open, but the data file is not. The USB description is void. In most cases drivers call *getdev* and *openep* and do not call this function directly.

Configdev opens the data file for the device supplied and loads and parses its configuration information. After calling it, the device is ready for I/O and the USB description in Dev.usb is valid. In most cases drivers call *getdev* and do not call this function directly.

Control requests for an endpoint may be written by calling *devctl* in the style of *print*(2). It is better not to call *print* directly because the control request should be issued as a single *write* system call. See *usb*(3) for a list of available control requests (not to be confused with USB control transfers performed on a control endpoint).

Input/Output

Opendevdata opens the data file for the device according to the given *mode*. The mode must match that of the endpoint, doing otherwise is considered an error. Actual I/O is performed by reading/writing the descriptor kept in the dfd field of Dev.

For control endpoints, it is not necessary to call *read* and *write* directly. Instead, *usbcmd* issues a USB control request to the device *d* (not to be confused with a *usb*(3) control request sent to its control file). *Usbcmd* retries the control request several times upon failure because some devices require it. The format of requests is fixed per the USB standard: *type* is the type of request and *req* identifies the request. Arguments *value* and *index* are parameters to the request and the last two arguments, *data* and *count*, are similar to *read* and *write* arguments. However, *data* may be nil if no transfer (other than the control request) has to take place. The library header file includes numerous symbols defined to help writing the type and arguments for a request.

The return value from *usbcmd* is the number of bytes transferred, zero to indicate a stall and -1 to indicate an error.

A common request is to unstall an endpoint that has been stalled due to some reason by the device (eg., when read or write indicate a count of zero bytes read or written on the endpoint). The function *unstall* does this. It is given the device that stalled the endpoint, *dev*, the stalled endpoint, *ep*, and the direction of the stall (one of Ein or Eout). The function takes care of notifying the device of the unstall as well as notifying the kernel.

Tools

Class returns the class part of the number given, representing a CSP. *Subclass* does the same for the device subclass and *Proto* for the protocol. The counterpart is *CSP*, which builds a CSP from

the device class, subclass, and protocol. For some classes, *classname* knows the name (for those with constants in the library header file).

The macros *GET2* and *PUT2* get and put a (little-endian) two-byte value and are useful to parse descriptors and replies for control requests.

Functions *emallocz* and *estrdup* are similar to *mallocz* and *strdup* but abort program operation upon failure.

The function Ufmt is a format routine suitable for fmtinstall(2) to print a Dev data structure. The auxiliary *hexstr* returns a string representing a dump (in hexadecimal) of *n* bytes starting at *a*. The string is allocated using *malloc*(2) and memory must be released by the caller.

Loaddevstr returns the string obtained by reading the device string descriptor number sid.

SOURCE

/sys/src/cmd/nusb/lib

SEE ALSO

usb(3), nusb(4).

BUGS

Not heavily exercised yet.

objtype, readobj, objtraverse, isar, nextar, readar - object file interpretation functions

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <libc.h>
#include <bio.h>
#include <mach.h>
int objtype(Biobuf *bp, char **name)
int readobj(Biobuf *bp, int objtype)
void objtraverse(void(*)(Sym*, void*), void*)
int isar(Biobuf *bp)
int nextar(Biobuf *bp, int offset, char *buf)
int readar(Biobuf *bp, int objtype, vlong end, int doautos)
```

DESCRIPTION

These functions provide machine-independent access to object files in a directory or an archive. *Mach*(2) and *symbol*(2) describe additional library functions for interpreting executable files and executing images.

Object files contain no formal symbol table; instead, references to symbols must be extracted from the encoded object representation and resolved. The resulting symbol information is loaded into a dummy symbol table where it is available for processing by an application. The organization of the dummy symbol table is identical to that produced by the loader and described in *symbol*(2) and *a.out*(6): a vector of Sym data structures defining the name, type and relative offset of each symbol.

Objtype reads the header at the current position of the file associated with bp (see Bio(2)) to see if it is an intermediate object file. If it is, a code indicating the architecture type of the file is returned and the second argument, if it is non-zero, is set pointing to a string describing the type of the file. If the header does not indicate an object file, -1 is returned. The header may be at the start of an object file or at the beginning of an archive member. The file is rewound to its starting position after decoding the header.

Readobj constructs a symbol table for the object file associated with *bp*. The second argument contains the type code produced by function *objtype*. The file must be positioned at the start of the object file. Each invocation of *readobj* destroys the symbol definitions for any previous file.

Objtraverse scans the symbol table previously built by *readobj* or *readar*. *Objtraverse* requires two arguments: the address of a call-back function and a generic pointer. The call-back function is invoked once for each symbol in the symbol table with the address of a *Sym* data structure as the first argument and the generic pointer as the second.

Isar reads the header at the current point in the file associated with *bp* and returns 1 if it is an archive or zero otherwise. The file is positioned at the end of the archive header and at the beginning of the first member of the archive.

Nextar extracts information describing the archive member stored at *offset* in the file associated with *bp*. If the header describing the member can be extracted and decoded, the size of the member is returned. Adding this value to *offset* yields the offset of the beginning of the next member in the archive. On return the input file is positioned at the end of the member header and the name of the member is stored in *buf*, a buffer of SARNAME characters. If there are no more members, *nextar* returns zero; a negative return indicates a missing or malformed header.

Readar constructs the symbol table of the object file stored at the current position in the archive associated with *bp*. This function operates exactly as *readobj*; the only difference is the extra argument, *end*, specifying the offset to the beginning of the next member in the archive. *Readar* leaves the file positioned at that point.

SOURCE

/sys/src/libmach

SEE ALSO

mach(2), symbol(2), bio(2), a.out(6)

DIAGNOSTICS These routines set *errstr*.

open, create, close - open a file for reading or writing, create file

SYNOPSIS

#include <u.h>

#include <libc.h>

int open(char *file, int omode)

int create(char *file, int omode, ulong perm)

int close(int fd)

DESCRIPTION

Open opens the *file* for I/O and returns an associated file descriptor. *Omode* is one of OREAD, OWRITE, ORDWR, or OEXEC, asking for permission to read, write, read and write, or execute, respectively. In addition, there are three values that can be ORed with the *omode*: OTRUNC says to truncate the file to zero length before opening it; OCEXEC says to close the file when an *exec*(2) or *execl* system call is made; and ORCLOSE says to remove the file when it is closed (by everyone who has a copy of the file descriptor). *Open* fails if the file does not exist or the user does not have permission to open it for the requested purpose (see *stat*(2) for a description of permissions). The user must have write permission on the *file* if the OTRUNC bit is set. For the *open* system call (unlike the implicit *open* in *exec*(2)), OEXEC is actually identical to OREAD.

Create creates a new *file* or prepares to rewrite an existing *file*, opens it according to *omode* (as described for *open*), and returns an associated file descriptor. If the file is new, the owner is set to the userid of the creating process group; the group to that of the containing directory; the permissions to *perm* ANDed with the permissions of the containing directory. If the file already exists, it is truncated to 0 length, and the permissions, owner, and group remain unchanged. The created file is a directory if the DMDIR bit is set in *perm*, an exclusive-use file if the DMEXCL bit is set, and an append-only file if the DMAPPEND bit is set. Exclusive-use files may be open for I/O by only one client at a time, but the file descriptor may become invalid if no I/O is done for an extended period; see *open*(5).

Create fails if the path up to the last element of *file* cannot be evaluated, if the user doesn't have write permission in the final directory, if the file already exists and does not permit the access defined by *omode*, or if there are no free file descriptors. In the last case, the file may be created even when an error is returned. If the file is new and the directory in which it is created is a union directory (see *intro*(2)) then the constituent directory where the file is created depends on the structure of the union: see *bind*(2).

Since *create* may succeed even if the file exists, a special mechanism is necessary for those applications that require an atomic create operation. If the OEXCL (0x1000) bit is set in the *mode* for a *create*, the call succeeds only if the file does not already exist; see *open*(5) for details.

Close closes the file associated with a file descriptor. Provided the file descriptor is a valid open descriptor, *close* is guaranteed to close it; there will be no error. Files are closed automatically upon termination of a process; *close* allows the file descriptor to be reused.

SOURCE

/sys/src/libc/9syscall

SEE ALSO

intro(2), bind(2), stat(2)

DIAGNOSTICS

These functions set errstr.

perror, syslog, sysfatal – system error messages

SYNOPSIS

```
#include <u.h>
#include <libc.h>
void perror(char *s)
void syslog(int cons, char *logname, char *fmt, ...)
void sysfatal(char *fmt, ...)
```

DESCRIPTION

Perror produces a short error message on the standard error file describing the last error encountered during a call to the system. First the argument string *s* is printed, then a colon, then the message and a newline. If *s* is nil, only the error message and newline are printed.

Syslog logs messages in the file named by *logname* in the directory /sys/log; the file must already exist and should be append-only. *Logname* must contain no slashes. The message is a line with several fields: the name of the machine writing the message; the date and time; the message specified by the *print*(2) format *fmt* and any following arguments; and a final newline. If *cons* is set or the log file cannot be opened, the message is also printed on the system console. *Syslog* can be used safely in multi-threaded programs.

Sysfatal prints to standard error the name of the running program, a colon and a space, the message described by the *print*(2) format string *fmt* and subsequent arguments, and a newline. It then calls *exits*(2) with the formatted message as argument. The program's name is the value of $\arg v0$, which will be set if the program uses the *arg*(2) interface to process its arguments. If $\arg v0$ is null, it is ignored and the following colon and space are suppressed.

SOURCE

/sys/src/libc/port/perror.c
/sys/src/libc/9sys/syslog.c
/sys/src/libc/9sys/sysfatal.c

SEE ALSO

intro(2), errstr(2), the %r format in print(2)

BUGS

Perror is a holdover; the %r format in *print*(2) is preferred.

pipe - create an interprocess channel

SYNOPSIS

#include <u.h>
#include <libc.h>

int pipe(int fd[2])

DESCRIPTION

Pipe creates a buffered channel for interprocess I/O communication. Two file descriptors are returned in *fd*. Data written to fd[1] is available for reading from fd[0] and data written to fd[0] is available for reading from fd[1].

After the pipe has been established, cooperating processes created by subsequent fork(2) calls may pass data through the pipe with *read* and *write* calls. The bytes placed on a pipe by one *write* are contiguous even if many processes are writing. Write boundaries are preserved: each read terminates when the read buffer is full or after reading the last byte of a write, whichever comes first.

The number of bytes available to a read(2) is reported in the Length field returned by *fstat* or *dirfstat* on a pipe (see *stat*(2)).

When all the data has been read from a pipe and the writer has closed the pipe or exited, *read*(2) will return 0 bytes. Writes to a pipe with no reader will generate a note sys: write on closed pipe.

SOURCE

/sys/src/libc/9syscall

SEE ALSO

intro(2), read(2), pipe(3)

DIAGNOSTICS

Sets *errstr*.

BUGS

If a read or a write of a pipe is interrupted, some unknown number of bytes may have been transferred.

When a read from a pipe returns 0 bytes, it usually means end of file but is indistinguishable from reading the result of an explicit write of zero bytes.

eplumb, plumbfree, plumbopen, plumbsend, plumbsendtext, plumblookup, plumbpack, plumbpackattr, plumbaddattr, plumbdelattr, plumbrecv, plumbunpack, plumbunpackpartial, plumbunpackattr, Plumbmsg – plumb messages

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <plumb.h>
           plumbopen(char *port, int omode)
int
           plumbsend(int fd, Plumbmsg *m)
int
           plumbsendtext(int fd, char *src, char *dst, char *wdir,
int
char *data)
           plumbfree(Plumbmsg *m)
void
Plumbmsg*
           plumbrecv(int fd)
char*
           plumbpack(Plumbmsg *m, int *np)
           plumbunpack(char *buf, int n)
Plumbmsg*
Plumbmsg*
           plumbunpackpartial(char *buf, int n, int *morep)
char*
           plumbpackattr(Plumbattr *a)
Plumbattr* plumbunpackattr(char *a)
char*
           plumblookup(Plumbattr *a, char *name)
Plumbattr* plumbaddattr(Plumbattr *a, Plumbattr *new)
Plumbattr* plumbdelattr(Plumbattr *a, char *name)
int
           eplumb(int key, char *port)
```

DESCRIPTION

These routines manipulate *plumb*(6) messages, transmitting them, receiving them, and converting them between text and these data structures:

```
typedef
struct Plumbmsg
{
    char
               *src:
    char
               *dst:
               *wdir;
    char
               *type;
    char
    Plumbattr *attr;
    int
               ndata:
    char
               *data;
} Plumbmsg;
typedef
struct Plumbattr
{
    char
               *name:
    char
               *value;
    Plumbattr *next;
} Plumbattr;
```

Plumbopen opens the named plumb *port*, using *open*(2) mode *omode*. If *port* begins with a slash, it is taken as a literal file name; otherwise *plumbopen* searches for the location of the *plumber*(4) service and opens the port there.

For programs using the *event*(2) interface, *eplumb* registers, using the given *key*, receipt of messages from the named *port*.

Plumbsend formats and writes message *m* to the file descriptor *fd*, which will usually be the result of plumbopen("send", OWRITE). *Plumbsendtext* is a simplified version for text-only messages; it assumes type is text, sets attr to nil, and sets ndata to strlen(*data*).

Plumbfree frees all the data associated with the message m, all the components of which must therefore have been allocated with *malloc*(2).

Plumbrecv returns the next message available on the file descriptor *fd*, or nil for error.

Plumbpack encodes message m as a character string in the format of *plumb*(6), setting * np to the length in bytes of the string. *Plumbunpack* does the inverse, translating the n bytes of *buf* into a Plumbmsg.

Plumbunpackpartial enables unpacking of messages that arrive in pieces. The first call to *plumbunpackpartial* for a given message must be sufficient to unpack the header; subsequent calls permit unpacking messages with long data sections. For each call, *buf* points to the beginning of the complete message received so far, and *n* reports the total number of bytes received for that message. If the message is complete, the return value will be as in *plumbunpack*. If not, and *morep* is not null, the return value will be nil and *morep will be set to the number of bytes remaining to be read for this message to be complete (recall that the byte count is in the header). Those bytes should be read by the caller, placed at location buf+n, and the message unpacked again. If an error is encountered, the return value will be nil and **morep* will be zero.

Plumbpackattr converts the list a of Plumbattr structures into a null-terminated string. If an attribute value contains white space, quote characters, or equal signs, the value will be quoted appropriately. A newline character will terminate processing. *Plumbunpackattr* converts the null-terminated string a back into a list of *Plumbattr* structures.

Plumblookup searches the Plumbattr list *a* for an attribute with the given *name* and returns the associated value. The returned string is the original value, not a copy. If the attribute has no value, the returned value will be the empty string; if the attribute does not occur in the list at all, the value will be nil.

Plumbaddattr appends the *new* Plumbattr (which may be a list) to the attribute list *a* and returns the new list. *Plumbdelattr* searches the list *a* for the first attribute with name *name* and deletes it from the list, returning the resulting list. *Plumbdelattr* is a no-op if no such attribute exists.

SOURCE

/sys/src/libplumb

SEE ALSO

plumb(1), event(2), plumber(4), plumb(6)

DIAGNOSTICS

When appropriate, including when a *plumbsend* fails, these routine set *errstr*.

poolalloc, poolallocalign, poolfree, poolmsize, poolisoverlap, poolrealloc, poolcompact, poolcheck, poolblockcheck, pooldump - general memory management routines

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <pool.h>
void*
          poolalloc(Pool* pool, ulong size)
          poolallocalign(Pool *pool, ulong size,
void*
                ulong align, long offset, ulong span)
void poolfree(Pool* pool, void* ptr)
          poolmsize(Pool* pool, void* ptr)
ulong
int poolisoverlap(Pool* pool, void* ptr, ulong len)
void*
          poolrealloc(Pool* pool, void* ptr, ulong size)
int poolcompact(Pool* pool)
void poolcheck(Pool *pool)
void poolblockcheck(Pool *pool, void *ptr)
void pooldump(Pool *pool);
```

DESCRIPTION

These routines provide a general memory management facility. Memory is retrieved from a coarser allocator (e.g. *sbrk* or the kernel's *xalloc*) and then allocated to callers. The routines are locked and thus may safely be used in multiprocess programs.

Poolalloc attempts to allocate a block of size size; it returns a pointer to the block when successful and nil otherwise. The call poolalloc(0) returns a non-nil pointer. *Poolfree* returns an allocated block to the pool. It is an error to free a block more than once or to free a pointer not returned by *poolalloc*. The call poolfree(nil) is legal and is a no-op.

Poolallocalign attempts to allocate a block of size size with the given alignment constraints. If *align* is non-zero, the returned pointer is aligned to be equal to *offset* modulo *align*. If *span* is non-zero, the *n* byte block allocated will not span a *span*-byte boundary.

Poolrealloc attempts to resize to nsize bytes the block associated with ptr, which must have been previously returned by *poolalloc* or *poolrealloc*. If the block's size can be adjusted, a (possibly different) pointer to the new block is returned. The contents up to the lesser of the old and new sizes are unchanged. After a successful call to *poolrealloc*, the return value should be used rather than ptr to access the block. If the request cannot be satisfied, *poolrealloc* returns nil, and the old pointer remains valid.

When blocks are allocated, there is often some extra space left at the end that would usually go unused. *Poolmsize* grows the block to encompass this extra space and returns the new size.

Poolisoverlap checks if the byte span [ptr,ptr+len) overlaps the arenas of the specified pool, returning non-zero when there is overlap or zero if none.

The *poolblockcheck* and *poolcheck* routines validate a single allocated block or the entire pool, respectively. They call panic (see below) if corruption is detected. *Pooldump* prints a summary line for every block in the pool, using the print function (see below).

The Pool structure itself provides much of the setup interface.

```
typedef struct Pool Pool;
struct Pool {
    char* name;
    uintptr maxsize;/* of entire Pool */
    uintptr cursize;/* of Pool */
    uintptr curfree;/* total free bytes in Pool */
    uintptr curalloc;/* total allocated bytes in Pool */
```

```
ulong minarena;
                        /* smallest size of new arena */
   ulong quantum;
                        /* allocated blocks should be multiple of */
                        /* smallest newly allocated block */
   ulong minblock;
    int
          flags;
                        /* number of calls to free */
    int
          nfree:
                        /* nfree at time of last poolcompact */
    int
          lastcompact:
    void* (*alloc)(ulong);
    int
          (*merge)(void*, void*);
          (*move)(void* from, void* to);
    void
          (*lock)(Pool*);
    void
          (*unlock)(Pool*);
    void
    void
          (*print)(Pool*, char*, ...);
    void
          (*panic)(Pool*, char*, ...);
    void
         (*logstack)(Pool*);
    void* private;
};
enum { /* flags */
    POOL_ANTAGONISM = 1 << 0.
    POOL PARANOIA
                    = 1<<1.
    POOL VERBOSITY = 1 << 2.
    POOL_DEBUGGING = 1 << 3,
    POOL_LOGGING
                    = 1<<4,
    POOL_TOLERANCE
                   = 1<<5.
    POOL_NOREUSE
                    = 1 < < 6.
}:
```

The pool obtains arenas of memory to manage by calling the given alloc routine. The total number of requested bytes will not exceed maxsize. Each allocation request will be for at least minarena bytes.

When a new arena is allocated, the pool routines try to merge it with the surrounding arenas, in an attempt to combat fragmentation. If merge is non-nil, it is called with the addresses of two blocks from alloc that the pool routines suspect might be adjacent. If they are not mergeable, merge must return zero. If they are mergeable, merge should merge them into one block in its own bookkeeping and return non-zero.

To ease fragmentation and make block reuse easier, the sizes requested of the pool routines are rounded up to a multiple of quantum before the carrying out requests. If, after rounding, the block size is still less than minblock bytes, minblock will be used as the block size.

Poolcompact defragments the pool, moving blocks in order to aggregate the free space. Each time it moves a block, it notifies the move routine that the contents have moved. At the time that move is called, the contents have already moved, so from should never be dereferenced. If no move routine is supplied (i.e. it is nil), then calling *poolcompact* is a no-op.

When the pool routines need to allocate a new arena but cannot, either because alloc has returned nil or because doing so would use more than maxsize bytes, *poolcompact* is called once to defragment the memory and the request is retried.

Pools are protected by the pool routines calling lock (when non-nil) before modifying the pool, and calling unlock when finished.

When internal corruption is detected, panic is called with a *print*(2) style argument that specifies what happened. It is assumed that panic never returns. When the pool routines wish to convey a message to the caller (usually because logging is turned on; see below), print is called, also with a *print*(2) style argument.

Flags is a bit vector that tweaks the behavior of the pool routines in various ways. Most are useful for debugging in one way or another. When POOL_ANTAGONISM is set, *poolalloc* fills blocks with non-zero garbage before releasing them to the user, and *poolfree* fills the blocks on receipt. This tickles both user programs and the innards of the allocator. Specifically, each 32-bit word of the memory is marked with a pointer value exclusive-or'ed with a constant. The pointer value is the pointer to the beginning of the allocated block and the constant varies in order to distinguish different markings. Freed blocks use the constant 0xF7000000, newly allocated blocks

0xF9000000, and newly created unallocated blocks 0xF1000000. For example, if POOL_ANTAGONISM is set and *poolalloc* returns a block starting at 0x00012345, each word of the block will contain the value 0xF90012345. Recognizing these numbers in memory-related crashes can help diagnose things like double-frees or dangling pointers.

Setting POOL_PARANOIA causes the allocator to walk the entire pool whenever locking or unlocking itself, looking for corruption. This slows runtime by a few orders of magnitude when many blocks are in use. If POOL_VERBOSITY is set, the entire pool structure is printed (via print) each time the pool is locked or unlocked. POOL_DEBUGGING enables internal debugging output, whose format is unspecified and volatile. It should not be used by most programs. When POOL_LOGGING is set, a single line is printed via print at the beginning and end of each pool call. If logstack is not nil, it will be called as well. This provides a mechanism for external programs to search for leaks. (See *leak*(1) for one such program.)

The pool routines are strict about the amount of space callers use. If even a single byte is written past the end of the allotted space of a block, they will notice when that block is next used in a call to *poolrealloc* or *free* (or at the next entry into the allocator, when POOL_PARANOIA is set), and panic will be called. Since forgetting to allocate space for the terminating NUL on strings is such a common error, if POOL_TOLERANCE is set and a single NUL is found written past the end of a block, print will be called with a notification, but panic will not be.

When POOL_NOREUSE is set, poolfree fills the passed block with garbage rather than return it to the free pool.

SOURCE

/sys/src/libc/port/pool.c

SEE ALSO

malloc(2), brk(2)

/sys/src/libc/port/malloc.c is a complete example.

postnote - send a note to a process or process group

SYNOPSIS

#include <u.h>
#include <libc.h>

int postnote(int who, int pid, char *note)

DESCRIPTION

Postnote sends a note to a process or process group. If *who* is PNPROC, then *note* is written to /proc/*pid*/note. If *who* is PNGROUP, the note is delivered to the process group by writing *note* to /proc/*pid*/notepg. For PNGROUP only, if the calling process is in the target group, the note is *not* delivered to that process.

If the write is successful, zero is returned. Otherwise -1 is returned.

SOURCE

/sys/src/libc/9sys/postnote.c

SEE ALSO

notify(2), intro(2), proc(3)

DIAGNOSTICS

Sets errstr.

genprime, gensafeprime, genstrongprime, DSAprimes, probably_prime, smallprimetest - prime number generation

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <libc.h>
#include <mp.h>
#include <libsec.h>
int smallprimetest(mpint *p)
int probably_prime(mpint *p, int nrep)
void genprime(mpint *p, int n, int nrep)
void gensafeprime(mpint *p, mpint *alpha, int n, int accuracy)
void genstrongprime(mpint *p, int n, int nrep)
void DSAprimes(mpint *q, mpint *p, uchar seed[SHA1dlen])
```

DESCRIPTION

Public key algorithms abound in prime numbers. The following routines generate primes or test numbers for primality.

Smallprimetest checks for divisibility by the first 10000 primes. It returns 0 if p is not divisible by the primes and -1 if it is.

Probably_prime uses the Miller-Rabin test to test p. It returns non-zero if P is probably prime. The probability of it not being prime is $1/4^{**}nrep$.

Genprime generates a random *n* bit prime. Since it uses the Miller-Rabin test, *nrep* is the repetition count passed to *probably_prime*. *Gensafegprime* generates an *n*-bit prime *p* and a generator *alpha* of the multiplicative group of integers mod *p*; there is a prime *q* such that p-1=2*q. *Genstrongprime* generates a prime, *p*, with the following properties:

- (p-1)/2 is prime. Therefore p-1 has a large prime factor, p'.
- p'-1 has a large prime factor
- p+1 has a large prime factor

DSAprimes generates two primes, q and p, using the NIST recommended algorithm for DSA primes. q divides p-1. The random seed used is also returned, so that skeptics can later confirm the computation. Be patient; this is a slow algorithm.

SOURCE

/sys/src/libsec

SEE ALSO

aes(2) blowfish(2), des(2), elgamal(2), rsa(2)

print, fprint, sprint, snprint, seprint, smprint, runesprint, runesnprint, runeseprint, runesmprint, vfprint, vsnprint, vseprint, vsmprint, runevsnprint, runevseprint, runevsmprint - print formatted output

SYNOPSIS

```
#include <u.h>
#include <libc.h>
      print(char *format, ...)
int
      fprint(int fd, char *format, ...)
int
      sprint(char *s, char *format, ...)
int
      snprint(char *s, int len, char *format, ...)
int
char* seprint(char *s, char *e, char *format, ...)
char* smprint(char *format, ...)
      runesprint(Rune *s, char *format, ...)
int
      runesnprint(Rune *s, int len, char *format, ...)
int
Rune* runeseprint(Rune *s, Rune *e, char *format, ...)
Rune* runesmprint(char *format, ...)
      vfprint(int fd, char *format, va_list v)
int
      vsnprint(char *s, int len, char *format, va_list v)
int
char* vseprint(char *s, char *e, char *format, va_list v)
char* vsmprint(char *format, va_list v)
int
      runevsnprint(Rune *s, int len, char *format, va_list v)
Rune* runevseprint(Rune *s, Rune *e, char *format, va_list v)
Rune* runevsmprint(char *format, va_list v)
```

DESCRIPTION

Print writes text to the standard output. *Fprint* writes to the named output file descriptor; a buffered form is described in *bio*(2). *Sprint* places text followed by the NUL character (\setminus 0) in consecutive bytes starting at *s*; it is the user's responsibility to ensure that enough storage is available. Each function returns the number of bytes transmitted (not including the NUL in the case of *sprint*), or a negative value if an output error was encountered.

Snprint is like *sprint*, but will not place more than *len* bytes in *s*. Its result is always NUL-terminated and holds the maximal number of complete UTF-8 characters that can fit. *Seprint* is like *snprint*, except that the end is indicated by a pointer *e* rather than a count and the return value points to the terminating NUL of the resulting string. *Smprint* is like *sprint*, except that it prints into and returns a string of the required length, which is allocated by *malloc*(2).

The routines *runesprint*, *runesnprint*, *runeseprint*, and *runesmprint* are the same as *sprint*, *snprint*, *seprint* and *smprint* except that their output is rune strings instead of byte strings.

Finally, the routines *vfprint*, *vsnprint*, *vseprint*, *vsmprint*, *runevsnprint*, *runevseprint*, and *runevsmprint* are like their v-less relatives except they take as arguments a va_list parameter, so they can be called within a variadic function. The Example section shows a representative usage.

Each of these functions converts, formats, and prints its trailing arguments under control of a *format* string. The format contains two types of objects: plain characters, which are simply copied to the output stream, and conversion specifications, each of which results in fetching of zero or more arguments. The results are undefined if there are arguments of the wrong type or too few arguments for the format. If the format is exhausted while arguments remain, the excess is ignored.

Each conversion specification has the following format:

% [flags] verb

The verb is a single character and each flag is a single character or a (decimal) numeric string. Up to two numeric strings may be used; the first is called *width*, the second *precision*. A period can be used to separate them, and if the period is present then *width* and *precision* are taken to be zero if missing, otherwise they are 'omitted'. Either or both of the numbers may be replaced with the character *, meaning that the actual number will be obtained from the argument list as an integer. The flags and numbers are arguments to the *verb* described below.

The numeric verbs d, o, b, x, and X format their arguments in decimal, octal, binary, hexadecimal, and upper case hexadecimal. Each interprets the flags 0, h, hh, 1, 11, u, +, -, ,, and # to mean pad with zeros, short, byte, long, vlong, unsigned, always print a sign, left justified, commas every three digits, and alternate format. Also, a space character in the flag position is like +, but prints a space instead of a plus sign for non-negative values. If neither short nor long is specified, then the argument is an int. If unsigned is specified, then the argument is interpreted as a positive number and no sign is output. If *precision* is not omitted, the number is padded on the left with zeros until at least *precision* digits appear. Then, if alternate format is specified, for o conversion, the number is preceded by a 0 if it doesn't already begin with one; for x conversion, the number is preceded by 0x; for X conversion, the number is preceded by 0X. Finally, if *width* is not omitted, the number is padded on the left (or right, if left justification is specified) with enough blanks to make the field at least *width* characters long.

The floating point verbs f, e, E, g, and G take a double argument. Each interprets the flags +, -, and # to mean always print a sign, left justified, and alternate format. *Width* is the minimum field width and, if the converted value takes up less than *width* characters, it is padded on the left (or right, if 'left justified') with spaces. *Precision* is the number of digits that are converted after the decimal place for e, E, and f conversions, and *precision* is the maximum number of significant digits for g and G conversions. The f verb produces output of the form [-]digits[.digits]. E conversion appends an exponent E[-]digits, and e conversion appends an exponent e[-]digits. The g verb will output the argument in either e or f with the goal of producing the smallest output. Also, trailing zeros are omitted from the fraction part of the output, and a trailing decimal point appears only if it is followed by a digit. The G verb is similar, but uses E format instead of e. When alternate format is specified, the result will always contain a decimal point, and for g and G conversions, trailing zeros are not removed.

The s verb copies a nul-terminated string (pointer to char) to the output. The number of characters copied (n) is the minimum of the size of the string and *precision*. These n characters are justified within a field of *width* characters as described above. If a *precision* is given, it is safe for the string not to be nul-terminated as long as it is at least *precision* characters (not bytes!) long. The S verb is similar, but it interprets its pointer as an array of runes (see *utf*(6)); the runes are converted to UTF before output.

The c verb copies a single char (promoted to int) justified within a field of *width* characters as described above. The C verb is similar, but works on runes.

The p verb formats a single pointer or pointer-sized integer (uintptr, see *intro*(2)) in hexadecimal.

The r verb takes no arguments; it copies the error string returned by a call to *errstr*(2).

Custom verbs may be installed using *fmtinstall*(2).

EXAMPLE

This function prints an error message with a variable number of arguments and then quits.

```
void fatal(char *msg, ...)
{
    char buf[1024], *out;
    va_list arg;
    out = seprint(buf, buf+sizeof(buf), "Fatal error: ");
    va_start(arg, msg);
    out = vseprint(out, buf+sizeof(buf), msg, arg);
    va_end(arg);
```

```
write(2, buf, out-buf);
exits("fatal error");
```

SOURCE

/sys/src/libc/fmt

}

SEE ALSO

fmtinstall(2), fprintf(2), utf(6), errstr(2)

DIAGNOSTICS

Routines that write to a file descriptor or call *malloc* set *errstr*.

BUGS

The formatting is close to that specified for ANSI fprintf(2); the main difference is that b is not in ANSI and u is a flag here instead of a verb. Also, and distinctly not a bug, *print* and friends generate UTF rather than ASCII.

There is no runeprint, runefprint, etc. because runes are byte-order dependent and should not be written directly to a file; use the UTF output of *print* or *fprint* instead. Also, *sprint* is deprecated for safety reasons; use *snprint*, *seprint*, or *smprint* instead. Safety also precludes the existence of *runesprint*.

privalloc - per-process private storage management

SYNOPSIS

#include <u.h>
#include <libc.h>

void** privalloc(void)

DESCRIPTION

Privalloc returns a pointer to a per-process private storage location. The location is not shared among processes, even if they share the same data segments. It returns nil if there are no free slots available.

SOURCE

/sys/src/libc/9sys/privalloc.c

SEE ALSO

exec(2)

procsetname – set process arguments

SYNOPSIS

#include <u.h>
#include <libc.h>

void procsetname(char *fmt, ...)

DESCRIPTION

Procsetname overrides the current process arguments by writing to its /proc/pid/args file. The process arguments are informational only.

SOURCE

/sys/src/libc/9sys/procsetname.c

SEE ALSO

thread(2), proc(3)

rdproto - parse and process a proto file listing

SYNOPSIS

DESCRIPTION

Rdproto reads and interprets the named proto file relative to the root directory root.

Each line of the *proto* file specifies a file to copy except lines in the form of attr=val which sets an attribute (see below). Blank lines and lines beginning with # are ignored. Indentation (usually tabs) is significant, with each level of indentation corresponding to a level in the file tree. Fields within a line are separated by white space. The first field is the last path element in the destination file tree. The second field specifies the permissions. The third field is the owner of the file, and the fourth is the group owning the file. The fifth field is the name of the file from which to copy; this file is read from the current name space, not the source file tree. All fields except the first are optional. Specifying – for permissions, owner, or group causes *rdproto* to fetch the corresponding information from the file rather than override it. (This is the default behavior when the fields are not present; explicitly specifying – is useful when one wishes to set, say, the file owner without setting the permissions.)

Names beginning with a \$ are expanded as environment variables. If the first file specified in a directory is *, all of the files in that directory are considered listed. If the first file is +, all of the files are copied, and all subdirectories are recursively considered listed. All files are considered relative to *root*.

Attributes, lines in the form of attr=val, apply to all files in the current indention level after the attribute line. Attributes are inherited to deeper levels but each level can override them individualy. The attribute skip=regexp skips all file names matching the regular expression regexp for * and + operations using regexp(2). If owner or group is left unspecified on a file, the attributes uid=owner and gid=group will override these fields. The mode=mode attribute adds, sets or masks file permission bits if permissions where not explicitly specified on the file. If multiple mode= lines are given and mode is not a set operation (forced by ! character) the modes are combined. Except for the special ! character, mode has the same syntax as in chmod(1).

For each file named by the *proto*, *enm* is called with *new* pointing at the name of the file (without the root prefix), *old* pointing at the name of the source file (with the root prefix, when applicable), and *Dir* at the desired directory information for the new file. Only the name, uid, gid, mode, mtime, and length fields are guaranteed to be valid. The argument *a* is the same argument passed to *rdproto*; typically it points at some extra state used by the enumeration function.

When files or directories do not exist or cannot be read by *rdproto*, it formats a warning message, calls *warn*, and continues processing; if *warn* is nil, *rdproto* prints the warning message to standard error.

Rdproto returns zero if *proto* was processed, -1 if it could not be opened.

FILES

```
/sys/lib/sysconfig/proto/ directory of prototype files.
/sys/lib/sysconfig/proto/portproto generic prototype file.
```

SOURCE

/sys/src/libdisk/proto.c

SEE ALSO

mk9660(8), mkfs(8), regexp(2), chmod(1).

pushssl - attach SSL version 2 encryption to a communication channel

SYNOPSIS

#include <u.h>
#include <libc.h>

int pushssl(int fd, char *alg, char *secin, char *secout, int *cfd)

DESCRIPTION

Pushssl opens an *ssl*(3) device, connects it to the communications channel fd, and starts up encryption and message authentication as specified in *alg*. The algorithms are separated by a space and either can be first. See *ssl*(3) for the possible algorithms. *Secin* and *secout* contain the encryption keys for the two directions. If either is nil, the other is used in both directions. If *cfd* is non-nil, the SSL control channel is opened and its fd returned.

Pushssl returns a file descriptor for the SSL data channel. Anything written to this descriptor will get encrypted and authenticated and then written to the file descriptor, *fd*. *Pushssl* closes the original file descriptor *fd* on success.

SOURCE

/sys/src/libc/9sys

SEE ALSO

dial(2), ssl(3),

DIAGNOSTICS

return -1 on failure.

pushtls, tlsClient, tlsServer, initThumbprints, freeThumbprints, okThumbprint, okCertificate, readcert, readcertchain - attach TLS1 or SSL3 encryption to a communication channel

SYNOPSIS

```
#include <u.h>
#include <libc.h>
    pushtls(int fd, char *hashalg, char *encalg,
int
          int isclient, char *secret, char *dir)
#include <mp.h>
#include <libsec.h>
    tlsClient(int fd, TLSconn *conn)
int
    tlsServer(int fd, TLSconn *conn)
int
uchar *readcert(char *filename, int *pcertlen)
PEMchain *readcertchain(char *filename)
Thumbprint *initThumbprints(char *ok, char *crl, char *tag)
void freeThumbprints(Thumbprint *table)
int
     okThumbprint(uchar *hash, int len, Thumbprint *table)
     okCertificate(uchar *cert, int len, Thumbprint *table)
int
```

DESCRIPTION

Transport Layer Security (TLS) comprises a record layer protocol, doing message digesting and encrypting in the kernel, and a handshake protocol, doing initial authentication and secret creation at user level and then starting a data channel in the record protocol. TLS is nearly the same as SSL 3.0, and the software should interoperate with implementations of either standard.

To use just the record layer, as described in *tls*(3), call *pushtls* to open the record layer device, connect to the communications channel fd, and start up encryption and message authentication as specified in *hashalq*, *encalq*, and *secret*. These parameters must have been arranged at the two ends of the conversation by other means. For example, *hashalq* could be sha1, *encalq* could be rc4_128, and secret could be the base-64 encoding of two (client-to-server and server-toclient) 20-byte digest keys and two corresponding 16-byte encryption keys. Pushtls returns a file descriptor for the TLS data channel. Anything written to this descriptor will get encrypted and authenticated and then written to the file descriptor, fd. Pushtls, tlsClient and tlsServer close the original file descriptor on success. If *dir* is non-zero, the path name of the connection directory is copied into *dir*. This path name is guaranteed to be less than 40 bytes long.

Certificates

Alternatively, call *tlsClient* to speak the full handshake protocol, negotiate the algorithms and secrets, and return a new data file descriptor for the data channel. Conn points to a (callerallocated) struct:

```
typedef struct TLSconn {
                        /* OUT
                                  connection directory */
    char dir[40];
                        /* IN/OUT certificate */
    uchar *cert;
                        /* IN/OUT session ID */
    uchar *sessionID;
                        /* opt IN pre-shared key */
    uchar *psk;
     int
         certlen, sessionIDlen, psklen;
         (*trace)(char*fmt, ...);
     int
    PEMChain *chain;
     char *sessionType; /* opt IN
                                   session type */
    uchar *sessionKey; /* opt IN/OUT session key */
     int sessionKeylen; /* opt IN session key length */
     char *sessionConst; /* opt IN session constant */
     char *serverName;
                        /* opt IN server name */
    char *pskID;
                        /* opt IN pre-shared key ID */
} TLSconn;
```

defined in *libsec.h*. On input, the caller can provide options such as *cert*, the local certificate, and *sessionID*, used by a client to resume a previously negotiated security association. On output, the connection directory is set, as with listen (see *dial*(2)). The input *cert* is freed and a freshly allocated copy of the remote's certificate is returned in *conn*, to be checked by the caller according to its needs. One way to check the remote certificate is to use *initThumbprints* and *freeThumbprints* which allocate and free, respectively, a table of hashes from files of known trusted and revoked certificates. *okThumbprint* confirms that a particular hash is in the table.

TlsClient will optionally compute a session key for use by higher-level protocols. To compute a session key, the caller must set *sessionType* to a known session type; *sessionKeylen* to the desired key length; *sessionKey* to a buffer of length *sessionKeylen*; and *sessionConst* to the desired salting constant. The only supported session type is ttls, as used by 802.1x.

TIsServer executes the server side of the handshake. The caller must initialize $conn \rightarrow cert$, usually by calling *readcert* to read and decode the PEM-encoded certificate from *filename*, return a pointer to *malloced* storage containing the certificate, and store its length through *pcertlen*. The private key corresponding to *cert.pem* should have been previously loaded into factotum. (See rsa(8) for more about key generation.)

Readcertchain will read a PEM-encoded chain of certificates from *filename* and return a pointer to a linked list of *malloced* PEMChain structures, defined in *libsec.h*:

```
typedef struct PEMChain PEMChain;
struct PEMChain {
        PEMChain*next;
        uchar *pem;
        int pemlen;
};
```

By setting

```
conn->chain = readcertchain("intermediate-certs.pem");
```

the server can present extra certificate evidence to establish the chain of trust to a root authority known to the client.

Conn is not required for the ongoing conversation and may be freed by the application whenever convenient.

EXAMPLES

Start the client half of TLS and check the remote certificate:

```
conn = (TLSconn*)mallocz(sizeof *conn, 1);
fd = tlsClient(fd, conn);
if(!okCertificate(conn->cert, conn->certlen, table))
      sysfatal("suspect server: %r");
```

Run the server side:

```
fd = accept(lcfd, ldir);
conn = (TLSconn*)mallocz(sizeof *conn, 1);
conn->cert = readcert("cert.pem", &conn->certlen);
fd = tlsServer(fd, conn);
```

FILES

/sys/lib/tls thumbprints of trusted services
/sys/lib/ssl PEM certificate files

SOURCE

/sys/src/libc/9sys/pushtls.c
/sys/src/libsec/port

SEE ALSO

dial(2), tls(3), factotum(4), thumbprint(6)

DIAGNOSTICS

Return -1 on failure.

BUGS

Client certificates and client sessionIDs are not yet implemented.

Note that *pushtls*, *tlsClient* and *tlsServer* do not close the original file descriptor on failure, only on success.

The *sessionID* and *cert* pointers in the *TLSconn* structure have to be freed by the caller.

Note that in the TLS protocol *sessionID* itself is public; it is used as a pointer to secrets stored in *factotum*.

qball - 3-d rotation controller

SYNOPSIS

#include <draw.h>
#include <geometry.h>
void qball(Rectangle r, Mouse *mousep,
 Quaternion *orientation,
 void (*redraw)(void), Quaternion *ap)

DESCRIPTION

Qball is an interactive controller that allows arbitrary 3-space rotations to be specified with the mouse. Imagine a sphere with its center at the midpoint of rectangle r, and diameter the smaller of r's dimensions. Dragging from one point on the sphere to another specifies the endpoints of a great-circle arc. (Mouse points outside the sphere are projected to the nearest point on the sphere.) The axis of rotation is normal to the plane of the arc, and the angle of rotation is twice the angle of the arc.

Argument *mousep* is a pointer to the mouse event that triggered the interaction. It should have some button set. *Qball* will read more events into *mousep*, and return when no buttons are down.

While *qball* is reading mouse events, it calls out to the caller-supplied routine *redraw*, which is expected to update the screen to reflect the changing orientation. Argument *orientation* is the orientation that *redraw* should examine, represented as a unit Quaternion (see *quaternion*(2)). The caller may set it to any orientation. It will be updated before each call to *redraw* (and on return) by multiplying by the rotation specified with the mouse.

It is possible to restrict *qball's* attention to rotations about a particular axis. If *ap* is null, the rotation is unconstrained. Otherwise, the rotation will be about the same axis as *ap. This is accomplished by projecting points on the sphere to the nearest point also on the plane through the sphere's center and normal to the axis.

SOURCE

/sys/src/libgeometry/qball.c

SEE ALSO

quaternion(2)

Ken Shoemake, "Animating Rotation with Quaternion Curves", SIGGRAPH '85 Conference Proceedings.

qsort – quicker sort

SYNOPSIS

DESCRIPTION

Qsort (quicker sort) sorts an array into nondecreasing order. The first argument is a pointer to the base of the data; the second is the number of elements; the third is the width of an element in bytes; the last is the name of a comparison routine to be called with pointers to elements being compared. The routine must return an integer less than, equal to, or greater than 0 according as the first argument is to be considered less than, equal to, or greater than the second.

SOURCE

/sys/src/libc/port/qsort.c

SEE ALSO

sort(1)

qtom, mtoq, qadd, qsub, qneg, qmul, qdiv, qunit, qinv, qlen, slerp, qmid, qsqrt - Quaternion arithmetic

SYNOPSIS

```
#include <draw.h>
#include <draw.h>
#include <geometry.h>
Quaternion qadd(Quaternion q, Quaternion r)
Quaternion qsub(Quaternion q, Quaternion r)
Quaternion qneg(Quaternion q)
Quaternion qmul(Quaternion q, Quaternion r)
Quaternion qdiv(Quaternion q, Quaternion r)
Quaternion qinv(Quaternion q)
double qlen(Quaternion p)
Quaternion qunit(Quaternion q)
void qtom(Matrix m, Quaternion q)
Quaternion mtoq(Matrix mat)
Quaternion slerp(Quaternion q, Quaternion r, double a)
Quaternion qmid(Quaternion q)
Quaternion qmid(Quaternion q)
```

DESCRIPTION

The Quaternions are a non-commutative extension field of the Real numbers, designed to do for rotations in 3-space what the complex numbers do for rotations in 2-space. Quaternions have a real component r and an imaginary vector component v=(i,j,k). Quaternions add componentwise and multiply according to the rule $(r,v)(s,w)=(rs-v\cdot w, rw+vs+v\times w)$, where \cdot and \times are the ordinary vector dot and cross products. The multiplicative inverse of a non-zero quaternion (r,v) is $(r, -v)/(r^2-v\cdot v)$.

The following routines do arithmetic on quaternions, represented as

```
typedef struct Quaternion Quaternion;
struct Quaternion{
    double r, i, j, k;
};
```

Name Description

- qadd Add two quaternions.
- gsub Subtract two quaternions.

gneg Negate a quaternion.

qmul Multiply two quaternions.

gdiv Divide two guaternions.

- qinv Return the multiplicative inverse of a quaternion.
- qlen Return sqrt(q.r*q.r+q.i*q.i+q.j*q.j+q.k*q.k), the length of a quaternion.

qunit Return a unit quaternion (*length=1*) with components proportional to q's.

A rotation by angle θ about axis A (where A is a unit vector) can be represented by the unit quaternion $q = (\cos \theta/2, A\sin \theta/2)$. The same rotation is represented by -q; a rotation by $-\theta$ about -A is the same as a rotation by θ about A. The quaternion q transforms points by $(0,x',y',z') = q^{-1}(0,x,y,z)q$. Quaternion multiplication composes rotations. The orientation of an object in 3-space can be represented by a quaternion giving its rotation relative to some 'standard' orientation.

The following routines operate on rotations or orientations represented as unit quaternions:

mtoq Convert a rotation matrix (see *matrix*(2)) to a unit quaternion.

qtom

Convert a unit quaternion to a rotation matrix. Spherical lerp. Interpolate between two orientations. The rotation that carries q to r is $q^{-1}r$, so slerp(q, r, t) is $q(q^{-1}r)^t$. slerp(q, r, .5)slerp

```
qmid
```

The square root of q. This is just a rotation about the same axis by half the angle. qsqrt

SOURCE

/sys/src/libgeometry/quaternion.c

SEE ALSO

matrix(2), *qball*(2)

quotestrdup, quoterunestrdup, unquotestrdup, unquoterunestrdup, quotestrfmt, quoterunestrfmt, quotefmtinstall, doquote, needsrcquote – quoted character strings

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <libc.h>
char *quotestrdup(char *s)
Rune *quoterunestrdup(Rune *s)
char *unquotestrdup(char *s)
Rune *unquoterunestrdup(Rune *s)
int quotestrfmt(Fmt*)
int quoterunestrfmt(Fmt*)
void quotefmtinstall(void)
int (*doquote)(int c)
```

int needsrcquote(int c)

DESCRIPTION

These routines manipulate character strings, either adding or removing quotes as necessary. In the quoted form, the strings are in the style of rc(1), with single quotes surrounding the string. Embedded single quotes are indicated by a doubled single quote. For instance,

Don't worry!

when quoted becomes

'Don''t worry!'

The empty string is represented by two quotes, ''.

The first four functions act as variants of strdup (see *strcat*(2)). Each returns a freshly allocated copy of the string, created using *malloc*(2). *Quotestrdup* returns a quoted copy of *s*, while *unquotestrdup* returns a copy of *s* with the quotes evaluated. The *rune* versions of these functions do the same for strings (see *runestrcat*(2)).

The string returned by *quotestrdup* or *quoterunestrdup* has the following properties:

- 1. If the original string *s* is empty, the returned string is ''.
- 2. If *s* contains no quotes, blanks, or control characters, the returned string is identical to *s*.
- 3. If *s* needs quotes to be added, the first character of the returned string will be a quote. For example, hello world becomes 'hello world' not hello' 'world.

The function pointer *doquote* is nil by default. If it is non-nil, characters are passed to that function to see if they should be quoted. This mechanism allows programs to specify that characters other than blanks, control characters, or quotes be quoted. Regardless of the return value of **doquote*, blanks, control characters, and quotes are always quoted. *Needsrcquote* is provided as a *doquote* function that flags any character special to rc(1).

Quotestrfmt and *quoterunestrfmt* are *print*(2) formatting routines that produce quoted strings as output. They may be installed by hand, but *quotefmtinstall* installs them under the standard format characters q and Q. (They are not installed automatically.) If the format string includes the alternate format character #, for example %#q, the printed string will always be quoted; otherwise quotes will only be provided if necessary to avoid ambiguity. In <libc.h> there are #pragma statements so the compiler can type-check uses of %q and %Q in *print*(2) format strings.

SOURCE

/sys/src/libc/port/quote.c
/sys/src/libc/fmt/fmtquote.c

SEE ALSO

rc(1), *malloc*(2), *print*(2), *strcat*(2)

rand, Irand, frand, nrand, Inrand, srand, truerand, ntruerand, genrandom, prng, fastrand, nfastrand - random number generators

SYNOPSIS

```
#include <u.h>
#include <libc.h>
int rand(void)
long lrand(void)
double frand(void)
int nrand(int val)
long lnrand(long val)
void srand(long seed)
ulong truerand(void)
```

ulong ntruerand(ulong val)

#include <libsec.h>

void genrandom(uchar *buf, int nbytes)

```
void prng(uchar *buf, int nbytes)
```

ulong fastrand(void)

ulong nfastrand(ulong val)

DESCRIPTION

Rand returns a uniform pseudo-random number x, $0 \le x < 2^{15}$.

Lrand returns a uniform long x, $0 \le x < 2^{31}$.

Frand returns a uniform double x, $0.0 \le x < 1.0$, This function calls *lrand* twice to generate a number with as many as 62 significant bits of mantissa.

Nrand returns a uniform integer x, $0 \le x < val$. *Lnrand* is the same, but returns a long.

The algorithm is additive feedback with:

```
x[n] = (x[n-273] + x[n-607]) \mod 2^{31}
```

giving a period of $2^{30} \times (2^{607} - 1)$.

The generators are initialized by calling *srand* with whatever you like as argument. To get a different starting value each time,

```
srand(time(0))
```

will work as long as it is not called more often than once per second. Calling

srand(1)

will initialize the generators to their starting state.

Truerand returns a random unsigned long read from /dev/random.

Ntruerand returns a uniform random integer x, $0 \le x < val \le 2^{32} - 1$.

Genrandom fills a buffer with bytes from the cryptographic pseudo-random number generator. The generator is automatically seeded by *truerand*.

Prng uses the native *rand*(2) pseudo-random number generator to fill the buffer. Used with *srand*, this function can produce a reproducible stream of pseudo random numbers useful in test-ing.

Both *genrandom* and *prng* may be passed to *mprand* (see *mp*(2)).

Fastrand uses *genrandom* to return a uniform unsigned long x, $0 \le x < 2^{32}-1$.

Nfastrand uses *genrandom* to return a uniform unsigned long x, $0 \le x < val \le 2^{32}-1$.

SOURCE

```
/sys/src/libc/port/*rand.c
/sys/src/libc/9sys/truerand.c
/sys/src/libsec/port/genrandom.c
/sys/src/libsec/port/prng.c
/sys/src/libsec/port/*fastrand.c
```

SEE ALSO

cons(3), mp(2)

BUGS

Truerand and *ntruerand* maintain a static file descriptor.

setupRC4state, rc4, rc4skip, rc4back - alleged rc4 encryption

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <libc.h>
#include <mp.h>
#include <libsec.h>
void setupRC4state(RC4state *s, uchar *seed, int slen)
void rc4(RC4state *s, uchar *data, int dlen)
void rc4skip(RC4state *s, int nbytes)
void rc4back(RC4state *s, int nbytes)
```

DESCRIPTION

This is an algorithm alleged to be Rivest's RC4 encryption function. It is a pseudo-random number generator with a 256 byte state and a long cycle. The input buffer is XOR'd with the output of the generator both to encrypt and to decrypt. The seed, entered using *setupRC4state*, can be any length. The generator can be run forward using *rc4*, skip over bytes using *rc4skip* to account lost transmissions, or run backwards using *rc4back* to cover retransmitted data. The *RC4state* structure keeps track of the algorithm.

SOURCE

/sys/src/libsec

SEE ALSO

mp(2), *aes*(2), *blowfish*(2), *des*(2), *dsa*(2), *elgamal*(2), *rsa*(2), *sechash*(2), *prime*(2), *rand*(2)

read, readn, write, pread, pwrite - read or write file

SYNOPSIS

#include <u.h>
#include <u.h>
#include <libc.h>
long read(int fd, void *buf, long nbytes)
long readn(int fd, void *buf, long nbytes)
long write(int fd, void *buf, long nbytes, vlong offset)
long pwrite(int fd, void *buf, long nbytes, vlong offset)

DESCRIPTION

Read reads *nbytes* bytes of data from the offset in the file associated with *fd* into memory at *buf*. The offset is advanced by the number of bytes read. It is not guaranteed that all *nbytes* bytes will be read; for example if the file refers to the console, at most one line will be returned. In any event the number of bytes read is returned. A return value of 0 is conventionally interpreted as end of file.

Readn is just like read, but does successive *read* calls until *nbytes* have been read, or a read system call returns a non-positive count.

Write writes *nbytes* bytes of data starting at *buf* to the file associated with *fd* at the file offset. The offset is advanced by the number of bytes written. The number of characters actually written is returned. It should be regarded as an error if this is not the same as requested.

Pread and *Pwrite* are equivalent to a *seek*(2) to *offset* followed by a *read* or *write*. By combining the operations in a single atomic call, they more closely match the 9P protocol (see *intro*(5)) and, more important, permit multiprocess programs to execute multiple concurrent read and write operations on the same file descriptor without interference.

SOURCE

/sys/src/libc/9syscall
/sys/src/libc/port/readn.c

SEE ALSO

intro(2), dirread(2), dup(2), open(2), pipe(2), readv(2)

DIAGNOSTICS

These functions set *errstr*.

RGB, readcolmap, writecolmap - access display color map

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <libc.h>
void ceadcolmap(Display *d, RGB *map)
void writecolmap(Display *d, RGB *map)
```

DESCRIPTION

Colors are described by their red, green, and blue light intensities, in an RGB datum:

```
typedef
struct RGB {
    ulong red;
    ulong green;
    ulong blue;
} RGB;
```

Black is represented by zero in all three positions and white has the maximum unsigned long value in all three positions.

A color map is an array of RGBs, of length 2^{*depth*}, giving the colors for pixels 0, 1, 2, etc. On displays with color mapped pixels (typically 8-bit displays), one retrieves RGB color information by treating the pixel data as an offset into the color map.

Readcolmap reads the color map for the given display into the provided *map*, which must have enough space to hold it. *Writecolmap* associates the given color map with the given display, if possible. (The hardware might not allow this.) Both return 0 on success, or -1 on error, setting *errstr*.

Changing the hardware color map does not change the color map used by the *draw*(2) operator to convert between mapped and true color or greyscale images, which is described in *color*(6).

SOURCE

/sys/src/libdraw

SEE ALSO

graphics(2), draw(3), color(6)

readv, writev, preadv, pwritev - scatter/gather read and write

SYNOPSIS

```
#include <u.h>
#include <u.h>
#include <libc.h>
typedef
struct IOchunk
{
            void *addr;
            ulong len;
} IOchunk;
long readv(int fd, IOchunk *io, int nio)
long preadv(int fd, IOchunk *io, int nio, vlong off)
long writev(int fd, IOchunk *io, int nio)
long pwritev(int fd, IOchunk *io, int nio)
```

DESCRIPTION

These functions supplement the standard read and write operations of *read*(2) with facilities for scatter/gather I/O. The set of I/O buffers is collected into an array of IOchunk structures passed as an argument.

Readv reads data from *fd* and returns the total number of bytes received. The received data is stored in the successive *nio* elements of the IOchunk array, storing *io*[0].len bytes at *io*[0].addr, the next *io*[1].len at *io*[1].addr, and so on. *Preadv* does the same, but implicitly seeks to I/O offset *off* by analogy with *readv*.

Writev and pwritev are the analogous write routines.

SOURCE

```
/sys/src/libc/9sys/readv.c
/sys/src/libc/9sys/writev.c
```

SEE ALSO

intro(2), read(2)

DIAGNOSTICS

These functions set errstr.

BUGS

The implementations use *malloc*(2) to build a single buffer for a standard call to read or write. They are placeholders for possible future system calls.

regcomp, regcomplit, regcompnl, regexec, regsub, rregexec, rregsub, regerror - regular expression

SYNOPSIS

```
#include <u.h>
#include <u.h>
#include <libc.h>
#include <regexp.h>
Reprog *regcomp(char *exp)
Reprog *regcomplit(char *exp)
int regexec(Reprog *prog, char *string, Resub *match, int msize)
void regsub(char *source, char *dest, int dlen, Resub *match, int msize)
int rregexec(Reprog *prog, Rune *string, Resub *match, int msize)
void rregsub(Rune *source, Rune *dest, int dlen, Resub *match, int msize)
void regerror(char *msg)
```

DESCRIPTION

Regcomp compiles a regular expression and returns a pointer to the generated description. The space is allocated by *malloc*(2) and may be released by *free*. Regular expressions are exactly as in *regexp*(6).

Regcomplit is like *regcomp* except that all characters are treated literally. *Regcompnl* is like *regcomp* except that the . metacharacter matches all characters, including newlines.

Regexec matches a null-terminated string against the compiled regular expression in prog. If it matches, regexec returns 1 and fills in the array match with character pointers to the substrings of string that correspond to the parenthesized subexpressions of exp: match[i].sp points to the beginning and match[i].ep points just beyond the end of the *i*th substring. (Subexpression *i* begins at the *i*th left parenthesis, counting from 1.) Pointers in match[0] pick out the substring that corresponds to the whole regular expression. Unused elements of match are filled with zeros. Matches involving *, +, and ? are extended as far as possible. The number of array elements in match is given by msize. The structure of elements of match is:

```
typedef struct {
    union {
        char *sp;
        Rune *rsp;
    };
    union {
        char *ep;
        Rune *rep;
        };
} Resub;
```

If match[0].sp is nonzero on entry, *regexec* starts matching at that point within *string*. If match[0].ep is nonzero on entry, the last character matched is the one preceding that point.

Regsub places in *dest* a substitution instance of *source* in the context of the last *regexec* performed using *match*. Each instance of n, where *n* is a digit, is replaced by the string delimited by match[n].sp and match[n].ep. Each instance of & is replaced by the string delimited by match[0].sp and match[0].ep. The substitution will always be null terminated and trimmed to fit into dlen bytes.

Regerror, called whenever an error is detected in *regcomp*, writes the string *msg* on the standard error file and exits. *Regerror* can be replaced to perform special error processing. If the user supplied *regerror* returns rather than exits, *regcomp* will return 0.

Rregexec and *rregsub* are variants of *regexec* and *regsub* that use strings of Runes instead of strings of chars. With these routines, the *rsp* and *rep* fields of the *match* array elements should

be used.

SOURCE

/sys/src/libregexp

SEE ALSO

grep(1)

DIAGNOSTICS

Regcomp returns 0 for an illegal expression or other failure. *Regexec* returns 0 if *string* is not matched.

BUGS

There is no way to specify or match a NUL character; NULs terminate patterns and strings. The size of a character class and the number of sub-expression matches are hard-coded limits. The library uses the worst-case space estimate for allocating VM runtime threads.

HISTORY

Regexp(2) first appeared in Plan 9 from Bell Labs. This implementation was written from scratch for 9 front (May, 2016).

remove - remove a file

SYNOPSIS

#include <u.h>
#include <libc.h>

int remove(char *file)

DESCRIPTION

Remove removes *file* from the directory containing it and discards the contents of the file. The user must have write permission in the containing directory. If *file* is a directory, it must be empty.

SOURCE

/sys/src/libc/9syscall

SEE ALSO

intro(2), *remove*(5), the description of ORCLOSE in *open*(2).

DIAGNOSTICS

Sets errstr.

rendezvous - user level process synchronization

SYNOPSIS

#include <u.h>
#include <libc.h>
void* rendezvous(void* tag, void* value)

DESCRIPTION

The rendezvous system call allows two processes to synchronize and exchange a value. In conjunction with the shared memory system calls (see segattach(2) and fork(2)), it enables parallel programs to control their scheduling.

Two processes wishing to synchronize call *rendezvous* with a common *tag*, typically an address in memory they share. One process will arrive at the rendezvous first; it suspends execution until a second arrives. When a second process meets the rendezvous the *value* arguments are exchanged between the processes and returned as the result of the respective *rendezvous* system calls. Both processes are awakened when the rendezvous succeeds.

The set of tag values which two processes may use to rendezvous—their tag space—is inherited when a process forks, unless RFREND is set in the argument to rfork; see *fork*(2).

If a rendezvous is interrupted the return value is ~ 0 , so that value should not be used in normal communication.

SOURCE

/sys/src/libc/9syscall

SEE ALSO

fork(2), lock(2), segattach(2)

DIAGNOSTICS

Sets errstr.

asn1dump, asn1toRSApriv, asn1encodeRSApriv, asn1encodeRSApub, decodePEM, rsadecrypt, rsaencrypt, rsafill, rsagen, rsaprivalloc, rsaprivfree, rsaprivtopub, rsapuballoc, rsapubfree, X509toRSApub, X509rsagen, X509rsareq, X509rsaverify, X509rsaverifydigest - RSA encryption algorithm

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <mp.h>
#include <libsec.h>
RSApriv* rsagen(int nlen, int elen, int nrep)
RSApriv* rsafill(mpint *n, mpint *e, mpint *d, mpint *p, mpint *q)
mpint*
         rsaencrypt(RSApub *k, mpint *in, mpint *out)
mpint*
         rsadecrypt(RSApriv *k, mpint *in, mpint *out)
RSApub*
         rsapuballoc(void)
void
         rsapubfree(RSApub*)
RSApriv* rsaprivalloc(void)
void
         rsaprivfree(RSApriv*)
RSApub*
         rsaprivtopub(RSApriv*)
RSApub*
         X509toRSApub(uchar *cert,
                                     int ncert, char *name,
                                                                 int
nname)
RSApriv* asn1toRSApriv(uchar *priv, int npriv)
int
         asn1encodeRSApriv(RSApriv *k, uchar *buf, int len)
         asn1encodeRSApub(RSApub *pk, uchar *buf, int len)
int
void
         asn1dump(uchar *der, int len)
uchar*
         decodePEM(char *s, char *type, int *len, char **new_s)
uchar*
         X509rsagen(RSApriv *priv, char *subj, ulong valid[2], int
*certlen);
         X509rsareq(RSApriv *priv, char *subj, int *certlen);
uchar*
         X509rsaverify(uchar *cert, int ncert, RSApub *pk)
char*
         X509rsaverifydigest(uchar *sig, int siglen, uchar *edi-
char*
gest, int edigestlen, RSApub *pk)
```

DESCRIPTION

RSA is a public key encryption algorithm. The owner of a key publishes the public part of the key:

```
struct RSApub
{
    mpint *n; /* modulus */
    mpint *ek; /* exp (encryption key) */
};
```

This part can be used for encrypting data (with *rsaencrypt*) to be sent to the owner. The owner decrypts (with *rsadecrypt*) using his private key:

```
struct RSApriv
{
    RSApub    pub;
    mpint   *dk; /* exp (decryption key) */
    /* precomputed crt values */
    mpint   *p;
```

```
mpint *q;
mpint *kp; /* k mod p-1 */
mpint *kq; /* k mod q-1 */
mpint *c2; /* for converting residues to number */
};
```

Keys are generated using *rsagen*. *Rsagen* takes both bit length of the modulus, the bit length of the public key exponent, and the number of repetitions of the Miller-Rabin primality test to run. If the latter is 0, it does the default number of rounds. *Rsagen* returns a newly allocated structure containing both public and private keys. *Rsafill* returns a newly allocated private key by recomputing *kp*, *kq*, and *c2*. *Rsaprivtopub* returns a newly allocated copy of the public key corresponding to the private key.

The routines *rsaalloc*, *rsafree*, *rsapuballoc*, *rsapubfree*, *rsaprivalloc*, and *rsaprivfree* are provided to aid in user provided key I/O.

Given a binary X.509 *cert*, the routine *X509toRSApub* returns the public key and, if *name* is not nil, the CN part of the Distinguished Name of the certificate's Subject. (This is conventionally a userid or a host DNS name.) No verification is done of the certificate signature; the caller should check the fingerprint, *sha1(cert)*, against a table or check the certificate by other means. X.509 certificates are often stored in PEM format; use *dec64* to convert to binary before computing the fingerprint or calling *X509toRSApub*. For the special case of certificates signed by a known trusted key (in a single step, without certificate chains), *X509rsaverify* checks the signature on *cert*. It returns nil if successful, else an error string.

X509rsaverifydigest takes a encoded PKCS #1 signature as used in X.509 as sig[siglen] and verifies it against the expected cryptographic hash *edigest[edigestlen*] of the signed data; returning nil on success or an error string.

X509rsagen creates a self-signed X.509 certificate, given an RSA keypair *priv*, a issuer/subject string *subj*, and the starting and ending validity dates, *valid*. Length of the allocated binary certificate is stored in *certlen*. The subject line is conventionally of the form

C=US ST=NJ L=07922 O=Lucent OU='Bell Labs' CN=Eric

using the quoting conventions of *tokenize* in *getfields*(2).

Asn1toRSApriv converts an ASN1 formatted RSA private key into the corresponding RSApriv structure.

AsnlencodeRSApriv and asnlencodeRSApub export a RSApriv or RSApub structure to ASN1 format. On success, buf is filled and the encoded byte length is returned. Otherwise -1 is returned and error string is set.

Asn1dump prints an ASN1 object to standard output.

DecodePEM takes a zero terminated string, *s*, and decodes the PEM (privacy-enhanced mail) formatted section for *type* within it. If successful, it returns *malloced* storage containing the decoded section, which the caller must free, and sets *len to its decoded length. Otherwise nil is returned and *len is undefined. If not nil, *new_s* is set to the first character beyond the *type* section.

SOURCE

/sys/src/libsec

SEE ALSO

mp(2), aes(2), blowfish(2), des(2), dsa(2), elgamal(2), rc4(2), sechash(2), prime(2), rand(2), rsa(8)

runetochar, chartorune, runelen, runenlen, fullrune, utfecpy, utflen, utfnlen, utfrune, utfrrune, utfutf - rune/UTF conversion

SYNOPSIS

```
#include <u.h>
#include <libc.h>
int
       runetochar(char *s, Rune *r)
int
       chartorune(Rune *r, char *s)
int
       runelen(long r)
       runenlen(Rune *r, int n)
int
       fullrune(char *s, int n)
int
char*
       utfecpy(char *s1, char *es1, char *s2)
int
       utflen(char *s)
       utfnlen(char *s, long n)
int
char*
       utfrune(char *s, long c)
       utfrrune(char *s, long c)
char*
       utfutf(char *s1, char *s2)
char*
```

DESCRIPTION

These routines convert to and from a UTF byte stream and runes.

Runetochar copies one rune at r to at most UTFmax bytes starting at s and returns the number of bytes copied. UTFmax, defined as 4 in <libc.h>, is the maximum number of bytes required to represent a rune.

Chartorune copies at most UTFmax bytes starting at *s* to one rune at *r* and returns the number of bytes copied. If the input is not exactly in UTF format, *chartorune* will convert to Runeerror (0xFFFD) and return 1.

Runelen returns the number of bytes required to convert *r* into UTF.

Runenlen returns the number of bytes required to convert the *n* runes pointed to by *r* into UTF.

Fullrune returns 1 if the string *s* of length *n* is long enough to be decoded by *chartorune* and 0 otherwise. This does not guarantee that the string contains a legal UTF encoding. This routine is used by programs that obtain input a byte at a time and need to know when a full rune has arrived.

The following routines are analogous to the corresponding string routines with utf substituted for str and rune substituted for chr.

Utfecpy copies UTF sequences until a null sequence has been copied, but writes no sequences beyond *es1*. If any sequences are copied, *s1* is terminated by a null sequence, and a pointer to that sequence is returned. Otherwise, the original *s1* is returned.

Utflen returns the number of runes that are represented by the UTF string s.

Utfnlen returns the number of complete runes that are represented by the first *n* bytes of UTF string *s*. If the last few bytes of the string contain an incompletely coded rune, *utfnlen* will not count them; in this way, it differs from *utflen*, which includes every byte of the string.

Utfrune (*utfrrune*) returns a pointer to the first (last) occurrence of rune c in the UTF string s, or 0 if c does not occur in the string. The NUL byte terminating a string is considered to be part of the string s.

Utfutf returns a pointer to the first occurrence of the UTF string s^2 as a UTF substring of s_1 , or 0 if there is none. If s^2 is the null string, utfutf returns s_1 .

SOURCE

/sys/src/libc/port/rune.c
/sys/src/libc/port/utfecpy.c

```
/sys/src/libc/port/utfrune.c
/sys/src/libc/port/utfrrune.c
/sys/src/libc/port/utflen.c
/sys/src/libc/port/utfnlen.c
/sys/src/libc/port/utfutf.c
```

SEE ALSO

utf(6), *tcs*(1)

BUGS

When re-encoding UTF strings with *chartorune* and *runetochar* one has to consider that encoding a *Runeerror* (0xFFFD) that resulted from invalid encoded input can yield a longer UTF sequence on the output.

runestrcat, runestrncat, runestrcmp, runestrncmp, runestrcpy, runestrncpy, runestrecpy, runestrlen, runestrchr, runestrrchr, runestrdup, runestrstr - rune string operations

SYNOPSIS

```
#include <u.h>
#include <libc.h>
Rune* runestrcat(Rune *s1, Rune *s2)
Rune* runestrncat(Rune *s1, Rune *s2, long n)
int
      runestrcmp(Rune *s1, Rune *s2)
      runestrncmp(Rune *s1, Rune *s2, long n)
int
Rune* runestrcpy(Rune *s1, Rune *s2)
Rune* runestrncpy(Rune *s1, Rune *s2, long n)
Rune* runestrecpy(Rune *s1, Rune *es1, Rune *s2)
long runestrlen(Rune *s)
Rune* runestrchr(Rune *s, Rune c)
Rune* runestrrchr(Rune *s, Rune c)
Rune* runestrdup(Rune *s)
Rune* runestrstr(Rune *s1, Rune *s2)
```

DESCRIPTION

These functions are rune string analogues of the corresponding functions in *strcat*(2).

SOURCE

/sys/src/libc/port

SEE ALSO

memory(2), rune(2), strcat(2)

BUGS

The outcome of overlapping moves varies among implementations.

setupSalsastate, salsa_setblock, salsa_setiv, salsa_encrypt, salsa_encrypt2, hsalsa - salsa20 encryption

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <libsec.h>
```

void setupSalsastate(Salsastate *s, uchar key[], ulong keylen, uchar *iv, ulong ivlen, int rounds)

```
void salsa_encrypt(uchar *data, ulong len, Salsastate *s)
```

void salsa_encrypt2(uchar *src, uchar *dst, ulong len, Salsastate
*s)

```
void salsa_setblock(Salsastate *s, u64int blockno)
```

void salsa_setiv(Salsastate *s, uchar *iv);

void hsalsa(uchar h[32], uchar *key, ulong keylen, uchar nonce[16], int rounds);

DESCRIPTION

Salsa20 is a stream cipher designed by D J Berstein. It has an underlying block size of 64 bytes (named as constant SalsaBsize). It supports key sizes of 128 and 256-bit (recommended).

SetupSalsastate takes a reference to a Salsastate structure, a key of keylen bytes, which should normally be SalsaKeylen=32, a *iv* or nonce of *ivlen* bytes (can be SalsaIVlen=8 or XSalsaIVlen=24, set to all zeros if the *iv* argument is nil), and the number of *rounds* (set to the default of 20 if the argument is zero).

Salsa_encrypt encrypts len bytes of buf in place using the Salsastate in s. Len can be any byte length. Encryption and decryption are the same operation given the same starting state s.

Salsa_encrypt2 is similar, but encrypts len bytes of src into dst without modifying src.

Salsa_setblock sets the Salsa block counter for the next encryption to *blockno*, allowing seeking in an encrypted stream.

Salsa_setiv sets the the initialization vector (nonce) to *iv*.

Hsalsa is a key expansion function that takes a 128 or 256-bit key and a 128-bit nonce and produces a new 256-bit key.

SOURCE

/sys/src/libsec/port/salsa.c

SEE ALSO

chacha(2)
http://cr.yp.to/snuffle.html#specification

satnew, satadd1, sataddv, satrange1, satrangev, satsolve, satmore, satval, satreset, satfree - boolean satisfiability (SAT) solver

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <sat.h>
struct SATParam {
     void (*errfun)(char *msg, void *erraux);
     void *erraux;
     long (*randfn)(void *randaux);
     void *randaux;
     /* + finetuning parameters, see sat.h */
};
struct SATSolve {
     SATParam;
     /* + internals */
};
SATSolve* satnew(void);
          satfree(SATSolve *s);
void
SATSolve* satadd1(SATSolve *s, int *lit, int nlit);
SATSolve* sataddv(SATSolve *s, ...);
SATSolve* satrange1(SATSolve *s, int *lit, int nlit,
          int min, int max);
SATSolve* satrangev(SATSolve *s, int min, int max, ...);
int
          satsolve(SATSolve *s);
int
          satmore(SATSolve *s);
int
          satval(SATSolve *s, int lit);
          satget(SATSolve *s, int i, int *lit, int nlit);
int
void
          satreset(SATSolve *s);
```

DESCRIPTION

Libsat is a solver for the boolean satisfiability problem, i.e. given a boolean formula it will either find an assignment to the variables that makes it true, or report that this is impossible. The input formula must be in conjunctive normal form (CNF), i.e. of the form

$$(\mathbf{x}_1 \lor \mathbf{x}_2 \lor \mathbf{x}_3 \lor ...) \land (\mathbf{y}_1 \lor \mathbf{y}_2 \lor \mathbf{y}_3 \lor ...) \land ...,$$

where each x_i or y_i can optionally be negated.

For example, consider

$$(\mathbf{x}_1 \lor \mathbf{x}_2 \lor \mathbf{x}_3) \land (\neg \mathbf{x}_1 \lor \neg \mathbf{x}_2) \land (\neg \mathbf{x}_2 \lor \neg \mathbf{x}_3) \land (\neg \mathbf{x}_1 \lor \neg \mathbf{x}_2).$$

This formula encodes the constraint that exactly one of the three variables be true. To represent this as input for *libsat* we assign positive integers to each variable. Negation is represented by the corresponding negative number, hence our example corresponds to the set of "clauses"

1, 2, 3 -1, -2 -1, -3 -2, -3

To actually solve this problem we would create a SATSolve structure and add clauses one by one using *satadd1* or *sataddv* (the former takes an int array, the latter a variadic list terminated by 0). The SATSolve is modified inplace but returned for convenience. Passing nil as a first argument will create and return a new structure. Alternatively, *satnew* will create an empty structure.

Once clauses have been added, *satsolve* will invoke the actual solver. It returns 1 if it found an assignment and 0 if there is no assignment (the formula is unsatisfiable). If an assignment has been found, further clauses can be added to constrain it further and *satsolve* rerun. *Satmore* performs this automatically, excluding the current values of the variables. It is equivalent to *satsolve*

if no variables have assigned values.

Once a solution has been found, *satval* returns the value of literal *lit*. It returns 1 for true, 0 for false and -1 for undetermined. If the formula is satisfiable, an undetermined variable is one where either value will satisfy the formula. If the formula is unsatisfiable, all variables are undetermined.

Satrange1 and *satrangev* function like their *satadd* brethren but rather than adding a single clause they add multiple clauses corresponding to the constraint that at least *min* and at most *max* literals from the provided array be true. For example, the clause from above corresponds to

satrangev(s, 1, 1, 1, 2, 3, 0);

For debugging purposes, clauses can be retrieved using *satget*. It stores the literals of the clause with index *i* (starting from 0) at location *lit*. If there are more than *nlit* literals, only the first *nlit* literals are stored. If it was successful, it returns the total number of literals in the clause (which may exceed *nlit*). Otherwise (if *idx* was out of bounds) it returns -1.

Satreset resets all solver state, deleting all learned clauses and variable assignments. It retains all user provided clauses. *Satfree* deletes a solver structure and frees all associated storage.

There are a number of user-adjustable parameters in the SATParam structure embedded in SATSolve. *Randfun* is called with argument *randaux* to generate random numbers between 0 and $2^{31}-1$; it defaults to *lrand* (see *rand*(2)). *Errfun* is called on fatal errors (see DIAGNOSTICS). Additionally, a number of finetuning parameters are defined in sat.h. By tweaking their values, the run-time for a given problem can be reduced.

EXAMPLE

Find all solutions to the example clause from above:

SOURCE

/sys/src/libsat

SEE ALSO

Donald Knuth, "The Art of Computer Programming", Volume 4, Fascicle 6.

DIAGNOSTICS

Satnew returns nil on certain fatal error conditions (such as *malloc*(2) failure). Other routines will call *errfun* with an error string and *erraux*. If no *errfun* is provided or if it returns, *sysfatal* (see *perror*(2)) is called. It is permissible to use *setjmp*(2) to return from an error condition. Call *satfree* to clean up the SATSolve structure in this case. Note that calling the *satadd* or *satrange* routines with nil first argument will invoke *sysfatal* on error, since no *errfun* has been defined yet.

BUGS

Variable numbers should be consecutive numbers starting from 1, since variable data is kept in arrays internally.

Large clauses of several thousand literals are probably inefficient and should be split up using auxiliary variables. Very large clauses exceeding about 16,000 literals will not work at all.

There is no way to remove clauses (since it's unclear what the semantics should be).

The details about the tuning parameters are subject to change.

Calling *satadd* or *satrange* after *satsolve* or *satmore* may reset variable values.

Satmore will always return 1 when there are no assigned variables in the solution.

Some debugging routines called under "shouldn't happen" conditions are non-reentrant.

HISTORY

Libsat first appeared in 9front in March, 2018.

scribblealloc, recognize - character recognition

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <libc.h>
#include <draw.h>
#include <scribble.h>
Scribble *scribblealloc(void);
```

```
Rune recognize(Scribble *);
```

DESCRIPTION

The scribble library implements simple character recognition. All characters are drawn using a single stroke of the pen (mouse button 1) as on a palmtop computer.

The library is not really intended for standalone use. Its primary use is by the scribble graphical control (see *control*(2)).

Scribblealloc allocates and returns an appropriately initialized Scribble structure:

#define CS_DI	TTERS GITS NCTUATION	0 1 2
<pre>struct Scribb /* private Point int Stroke Graffiti int int int int int</pre>	•	
了;		

This structure encodes the points making up the stroke to be recognized, as well as the *character group* in which the stroke should be searched.

There are three such groups: *letters*, *digits*, and *punctuation*. The current group is encoded in the curCharSet field of the Scribble structure. Special strokes are recognized to switch between groups. In addition, the charater recognized is influenced by *mode* parameters and modifies them. These are identified by the capsLock, puncShift, tmpShift, and ctrlShift fields of the Scribble structure. When puncShift is non-zero, the character is recognized in the punctuation character set. Similarly, when the character recognized is printable and ctrlShift is set, the associated control character is returned as if the control key were depressed, and when the character is a letter and capsLock or tmpShift is set, the upper-case version is returned. The puncShift and tmpShift flags are turned off once a character has been recognized; the others are left set.

The character to be recognized is encoded as an array of pen_points in the ps field. To allow easy drawing of the stroke as it is drawn, the *pt* and *ppasize* fields are available to the application code for storing an array of points for a call to poly (see *draw*(2)).

Recognize recognizes the character provided in the ps field of the Scribble structure; it returns the rune or zero if nothing was recognized.

FILES

/sys/lib/scribble/classifiers contains the stroke definitions.

SOURCE

/sys/src/libscribble

This library is adapted from software reproduced by permission:

Graffiti.c is based on the file Scribble.c copyrighted by Keith Packard:

Copyright © 1999 Keith Packard

Permission to use, copy, modify, distribute, and sell this software and its documentation for any purpose is hereby granted without fee, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Keith Packard not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission. Keith Packard makes no representations about the suitability of this software for any purpose. It is provided "as is" without express or implied warranty.

Portions of the software Copyright © 1994 by Sun Microsystems Computer Company.

Portions of the software Copyright © 2000 by Compaq Computer Corporation.

SEE ALSO

Keyboard and prompter in *bitsyload*(1), *draw*(2), *control*(2)

openscsi, closescsi, scsiready, scsi, scsicmd, scsierror - SCSI device operations

```
SYNOPSIS
     #include <u.h>
     #include <libc.h>
     #include <disk.h>
     typedef struct Scsi {
          char *inquire;
          int
                rawfd;
          int
                nchange;
          ulong changetime;
     };
     Scsi* openscsi(char *devdir)
     void closescsi(Scsi *s)
           scsiready(Scsi *s)
     int
           scsi(Scsi *s, uchar *cmd, int ncmd,
     int
                          void *data, int ndata, int dir)
     int
           scsicmd(Scsi *s, uchar *cmd, int ncmd,
                          void *data, int ndata, int dir)
     char* scsierror(int asc, int ascq)
           scsiverbose:
     int
```

DESCRIPTION

These routines provide an interface to a SCSI or ATAPI device via sd(3).

Openscsi attempts to open the file *devdir*/raw and use it to send raw SCSI commands. On success, it reads the device's inquiry string and stores it in *inquire* in the returned Scsi structure. *Closescsi* closes the connection and frees the Scsi structure.

Scsiready sends the "unit ready" command up to three times, returning zero if the unit responds that it is ready, or -1 on error.

Scsierror returns a textual description of the SCSI status denoted by the ASC and ASCQ sense codes. The description is found by consulting /sys/lib/scsicodes. The returned string will be overwritten by the next call to *scsierror*.

Scsi and scsicmd execute a single SCSI command on the named device. There should be ncmd bytes of command data in cmd; if dir is Sread, a successful operation will store up to ndata bytes into data, returning the number of bytes stored. If dir is Swrite, the ndata bytes beginning at data are transmitted as the data argument to the command, and the number of bytes written is returned. If dir is Snone, data and ndata are ignored. On error, scsi and scsicmd return -1. Scsicmd simply issues the command and returns the result; scsi works a bit harder and is the more commonly used routine. Scsi attempts to send the command; if it is successful, scsi returns what scsicmd returned. Otherwise, scsi sends a request sense command to obtain the reason for the failure, sends a unit ready command in an attempt to bring the unit out of any inconsistent states, and tries again. If the second try fails, scsi sends the request sense and unit ready commands again and then uses scsierror to set errstr with a reason for failure.

The nchange and changetime fields in the Scsi structure record the number of times a media change has been detected, and the time when the current media was inserted into the drive (really the first time a SCSI command was issued after it was inserted). They are maintained by *scsi*.

If *scsiverbose* is set, these commands will produce a fair amount of debugging output on file descriptor 2 when SCSI commands fail.

FILES

/sys/lib/scsicodes

List of textual messages corresponding to SCSI error codes; consulted by scsierror.

SOURCE /sys/src/libdisk/scsi.c SEE ALSO sd(3), scuzz(8)

md4, md5, ripemd160, sha1, sha2_224, sha2_256, sha2_384, sha2_512, hmac_x, hmac_md5, hmac_sha1, hmac_sha2_224, hmac_sha2_256, hmac_sha2_384, hmac_sha2_512, poly1305 - cryptographically secure hashes

SYNOPSIS

#include <u.h> #include <libc.h> #include <mp.h> #include <libsec.h> #define DS DigestState /* only to abbreviate SYNOPSIS */ DS* md4(uchar *data, ulong dlen, uchar *digest, DS *state) DS* md5(uchar *data, ulong dlen, uchar *digest, DS *state) DS* ripemd160(uchar *data, ulong dlen, uchar *digest, DS *state) DS* sha1(uchar *data, ulong dlen, uchar *digest, DS *state) DS* sha2_224(uchar *data, ulong dlen, uchar *digest, DS *state) DS* sha2_256(uchar *data, ulong dlen, uchar *digest, DS *state) DS* sha2_384(uchar *data, ulong dlen, uchar *digest, DS *state) DS* sha2_512(uchar *data, ulong dlen, uchar *digest, DS *state) DS* hmac_x(uchar *p, ulong len, uchar *key, ulong klen, uchar *digest, DS *s, DS*(*x)(uchar*, ulong, uchar*, DS*), int xlen) DS* hmac_md5(uchar *data, ulong dlen, uchar *key, ulong klen, uchar *digest, DS *state) DS* hmac_sha1(uchar *data, ulong dlen, uchar *key, ulong klen, uchar *digest, DS *state) DS* hmac_sha2_224(uchar *data, ulong dlen, uchar *key, ulong klen, uchar *digest, DS *state) DS* hmac_sha2_256(uchar *data, ulong dlen, uchar *key, ulong klen, uchar *digest, DS *state) DS* hmac_sha2_384(uchar *data, ulong dlen, uchar *key, ulong klen, uchar *digest, DS *state) DS* hmac_sha2_512(uchar *data, ulong dlen, uchar *key, ulong klen, uchar *digest, DS *state)

DS* poly1305(uchar *p, ulong len, uchar *key, ulong klen, uchar *digest, DS *state)

DESCRIPTION

The output of a hash is called a *digest*. A hash is secure if, given the hashed data and the digest, it is difficult to predict the change to the digest resulting from some change to the data without rehashing the whole data. Therefore, if a secret is part of the hashed data, the digest can be used as an integrity check of the data by anyone possessing the secret.

The routines *md4*, *md5*, *ripemd160*, *sha1*, *sha2_224*, *sha2_256*, *sha2_384*, *sha2_512*, differ only in the length of the resulting digest and in the security of the hash. *Sha2_** and *hmac_sha2_** are the SHA-2 functions; the number after the final underscore is the number of bits in the resulting digest. Usage for each is the same. The first call to the routine should have nil as the *state* parameter. This call returns a state which can be used to chain subsequent calls. The last call should have digest non-nil. *Digest* must point to a buffer of at least the size of the digest produced. This last call will free the state and copy the result into *digest*.

The constants MD4dlen, MD5dlen, RIPEMD160dlen, SHA1dlen, SHA2_224dlen, SHA2_256dlen, SHA2_384dlen, SHA2_512dlen and Poly1305dlen define the lengths of the digests.

Hmac_md5, *hmac_sha1*, *hmac_sha2_224*, *hmac_sha2_256*, *hmac_sha2_384*, *hmac_sha2_512* and *poly1305* are used slightly differently. These hash algorithms are keyed and require a key to be specified on every call. The digest lengths for these hashes are the obvious ones from the above list of length constants. The *hmac_** routines all call *hmac_x* internally, but *hmac_x* is not intended for general use.

Poly1305 is a one-time authenticator designed by D. J. Bernstein is documented in *RFC8439*. It takes a 32-byte one-time key and a message and produces a 16-byte tag.

EXAMPLES

To hash a single buffer using *md5*:

uchar digest[MD5dlen];

md5(data, len, digest, nil);

To chain a number of buffers together, bounded on each end by some secret:

SOURCE

/sys/src/libsec

SEE ALSO

blowfish(2), des(2), elgamal(2), rc4(2), rsa(2)
/lib/rfc/rfc2104 HMAC specification

seek - change file offset

SYNOPSIS

#include <u.h>
#include <libc.h>

vlong seek(int fd, vlong n, int type)

DESCRIPTION

Seek sets the offset for the file associated with fd as follows:

If *type* is 0, the offset is set to *n* bytes.

If *type* is 1, the pointer is set to its current location plus *n*.

If *type* is 2, the pointer is set to the size of the file plus *n*.

The new file offset value is returned.

Seeking in a directory is not allowed. Seeking in a pipe is a no-op.

SOURCE

/sys/src/libc/9syscall

SEE ALSO

intro(2), open(2)

DIAGNOSTICS

Sets errstr.

segattach, segdetach, segfree - map/unmap a segment in virtual memory

SYNOPSIS

#include <u.h>
#include <u.h>
void*segattach(int attr, char *class, void *va, ulong len)
int segdetach(void *addr)
int segfree(void *va, ulong len)

DESCRIPTION

Segattach creates a new memory segment, adds it to the calling process's address space, and returns its lowest address. Segments belong to system-dependent classes. Segment classes memory (plain memory) and shared (shared memory) are available on all systems.

Shared segments are inherited by the children of the attaching process and remain untouched across a fork(2). An exec(2) will release a shared segment if it overlaps the segments in the file being *exec'ed*; otherwise the segment will be inherited.

Some machines provide a segment class lock. Lock segments allow access to special lock hardware provided by some multiprocessors, in particular the SGI Power Series machines.

Systems may also provide interfaces to special hardware devices like frame buffers through the *segattach* interface. Device memory mapped by this method is typically uncached by default.

If the specified *class* is unknown, *segattach* draws an error.

Attr specifies the new segment's attributes. The only attributes implemented on all classes of segment is SG_RONLY, which allows only read access on the segment, and SG_CEXEC, which causes the segment to be detached when the process does an *exec*(2). Specific devices may implement attributes to control caching and allocation, but these will vary between devices.

Va and len specify the position of the segment in the process's address space. Va is rounded down to the nearest page boundary and va+len is rounded up. The system does not permit segments to overlap. If va is zero, the system will choose a suitable address.

Segdetach removes a segment from a process's address space. Memory used by the segment is freed. *Addr* may be any address within the bounds of the segment.

The system will not permit the initial stack segment to be detached from the address space.

Segfree tells the system that it may free any physical memory within the span [*va*, *va+len*), but leaves that portion of the process's address space valid. The system will not free any memory outside that span, and may not free all or even any of the specified memory. If free'd memory is later referenced, it will be initialized as appropriate for the segment type. For example data and text segments will be read from the executable file, and bss segments will be filled with zero bytes.

The MIPS R2000 and R3000 have no hardware instructions to implement locks. The following method can be used to build them from software. First, try to *segattach* a segment of class lock. If this succeeds, the machine is an SGI Power Series and the memory contains hardware locks. Each 4096-byte page has 64 long words at its beginning; each word implements a test-and-set semaphore when read; the low bit of the word is zero on success, one on failure. If the *segattach* fails, there is no hardware support but the operating system helps: Any COP3 instruction will be trapped by the kernel and interpreted as a test-and-set. In the trap, R1 points to a long; on return, R1 is greater or equal zero on success, negative on failure. The following assembly language implements such a test-and-set.

```
/*
 * MIPS test and set
 */
 TEXT tas(SB), $0
 MOVW R1, sema+0(FP) /* save arg on stack */
btas:
    MOVW sema+0(FP), R1
    MOVB R0, 1(R1)
```

```
NOR R0, R0, R0 /* NOP */
WORD $(023<<26) /* MFC3 R0, R0 */
BLTZ R1, btas
RET
```

SOURCE

```
/sys/src/libc/9syscall
```

SEE ALSO

lock(2), segbrk(2), segflush(2)
/proc/*/segment

DIAGNOSTICS

These functions set *errstr*. *Segattach* returns (void*)–1 on error.

BUGS

There is a small fixed limit on the number of segments that may be attached, as well as a maximum segment size.

segbrk - change memory allocation

SYNOPSIS

#include <u.h>
#include <libc.h>

void* segbrk(void *saddr, void *addr)

DESCRIPTION

Segbrk sets the system's idea of the lowest unused location of a segment to *addr* rounded up to the next multiple of a page size, typically 4096 bytes. The segment is identified by *saddr* which may be any valid address within the segment.

A call to *segbrk* with a zero *addr* argument returns the base address of the segment without altering its size.

The system will prevent segments from overlapping and will not allow the length of the text, data, or stack segment to be altered.

SOURCE

/sys/src/libc/9syscall

SEE ALSO

brk(2), segattach(2), segflush(2)
/proc/*/segment

DIAGNOSTICS

Sets *errstr*. *Segbrk* returns (void*)–1 on error.

BUGS

The *segbrk* system call may go away or be re-implemented to give more general segment control, subsuming the functions of brk(2), segflush(2) and segfree in segattach(2).

segflush - flush instruction and data caches

SYNOPSIS

#include <u.h>
#include <libc.h>
int segflush(void *va, ulong len)

DESCRIPTION

Segflush invalidates any instruction cache and writes back any data cache associated with pages contained in a segment. All subsequent new pages in the segment will also be flushed when first referenced.

Va is an address within the segment to be flushed; it is rounded down to the nearest page boundary. *Len* specifies the length in bytes of the memory to flush; va+len is rounded up to the nearest page boundary. *Segflush* works correctly when the memory straddles multiple segments.

Correct use of *segflush* depends on an understanding of the cache architecture of the specific machine.

SOURCE

/sys/src/libc/9syscall

SEE ALSO

segattach(2), segbrk(2)
/proc/*/segment

DIAGNOSTICS

Sets errstr.

semacquire, tsemacquire, semrelease - user level semaphores

SYNOPSIS

#include <u.h>
#include <libc.h>
int semacquire(long *addr, int block);
int tsemacquire(long *addr, ulong ms);

long semrelease(long *addr, long count);

DESCRIPTION

Semacquire, tsemacquire, and semrelease facilitate scheduling between processes sharing memory. Processes arrange to share memory by using *rfork* with the RFMEM flag (see *fork*(2)), *segattach*(2), or *thread*(2).

The semaphore's value is the integer pointed at by *addr*. Semacquire atomically waits until the semaphore has a positive value and then decrements that value. If *block* is zero and the semaphore is not immediately available, *semacquire* returns 0 instead of waiting. Tsemacquire only waits *ms* milliseconds for the semaphore to attain a positive value and, if available in that time, decrements that value. It returns 0 otherwise. Both functions return 1 if the semaphore was acquired and -1 on error (e.g., if they were interrupted). Semrelease adds count to the semaphore's value and returns the new value.

Semacquire (and analogously for *tsemacquire*) and *semrelease* can be thought of as efficient, correct replacements for:

```
int
semacquire(long *addr, int block)
{
     while(*addr == 0){
          if(!block)
                return 0;
          if(interrupted)
               return -1;
     }
     --*addr:
     return 1;
}
int
semrelease(long *addr, int count)
{
     return *addr += count;
}
```

Like *rendezvous*(2), *semacquire*, *tsemacquire*, and *semrelease* are not typically used directly. Instead, they are intended to be used to coordinate scheduling in higher-level abstractions such as locks, rendezvous points, and channels (see *lock*(2) and *thread*(2)). Also like *rendezvous*, *semacquire*, *tsemacquire*, and *semrelease* cannot be used to coordinate between threads in a single process. Use locks, rendezvous points, or channels instead.

SOURCE

SEE ALSO

```
/sys/src/9/port/sysproc.c
```

fork(2), lock(2), rendezvous(2), segattach(2), thread(2)

DIAGNOSTICS

These functions set *errstr*.

setjmp, longjmp, notejmp - non-local goto

SYNOPSIS

#include <u.h>

```
#include <libc.h>
```

int setjmp(jmp_buf env)

```
void longjmp(jmp_buf env, int val)
```

```
void notejmp(void *uregs, jmp_buf env, int val)
```

DESCRIPTION

These routines are useful for dealing with errors and interrupts encountered in a low-level subroutine of a program.

Setjmp saves its stack environment in env for later use by longjmp. It returns value 0.

Longjmp restores the environment saved by the last call of *setjmp*. It then causes execution to continue as if the call of *setjmp* had just returned with value *val*. The invoker of *setjmp* must not itself have returned in the interim. All accessible data have values as of the time *longjmp* was called.

Notejmp is the same as longjmp except that it is to be called from within a note handler (see notify(2)). The uregs argument should be the first argument passed to the note handler.

Setjmp and longjmp can also be used to switch stacks. Several macros are defined in /\$objtype/include/u.h that can be used to build jmp_bufs by hand. The following code establishes a jmp_buf that may be called by longjmp to begin execution in a function f with 1024 bytes of stack:

SOURCE

/sys/src/libc/\$objtype/setjmp.s
/sys/src/libc/\$objtype/notejmp.c

SEE ALSO

notify(2)

BUGS

Notejmp cannot recover from an address trap or bus error (page fault) on the 680x0 architectures.

sin, cos, tan, asin, acos, atan, atan2 - trigonometric functions

SYNOPSIS

```
#include <u.h>
#include <libc.h>
double sin(double x)
double cos(double x)
double tan(double x)
double asin(double x)
double acos(double x)
double atan(double x)
double atan(double x)
```

DESCRIPTION

Sin, cos and *tan* return trigonometric functions of radian arguments. The magnitude of the argument should be checked by the caller to make sure the result is meaningful.

Asin returns the arc sine in the range $-\pi/2$ to $\pi/2$.

Acos returns the arc cosine in the range 0 to π .

Atan returns the arc tangent in the range $-\pi/2$ to $\pi/2$.

Atan2 returns the arc tangent of y/x in the range $-\pi$ to π .

SOURCE

/sys/src/libc/port

SEE ALSO

intro(2)

BUGS

The value of *tan* for arguments greater than about 2^{31} is garbage.

sinh, cosh, tanh - hyperbolic functions

SYNOPSIS

```
#include <u.h>
#include <libc.h>
double sinh(double x)
double cosh(double x)
double tanh(double x)
```

DESCRIPTION

These functions compute the designated hyperbolic functions for real arguments.

SOURCE

```
/sys/src/libc/port
```

SEE ALSO

intro(2)

sleep, alarm - delay, ask for delayed note

SYNOPSIS

#include <u.h>

#include <libc.h>

int sleep(long millisecs)

long alarm(ulong millisecs)

DESCRIPTION

Sleep suspends the current process for the number of milliseconds specified by the argument. The actual suspension time may be a little more or less than the requested time. If *millisecs* is 0, the process gives up the CPU if another process is waiting to run, returning immediately if not. Sleep returns -1 if interrupted, 0 otherwise.

Alarm causes an alarm note (see notify(2)) to be sent to the invoking process after the number of milliseconds given by the argument. Successive calls to *alarm* reset the alarm clock. A zero argument clears the alarm. The return value is the amount of time previously remaining in the alarm clock.

SOURCE

```
/sys/src/libc/9syscall
```

SEE ALSO

intro(2)

DIAGNOSTICS

These functions set errstr.

stat, fstat, wstat, fwstat, dirstat, dirfstat, dirwstat, dirfwstat, nulldir - get and put file status

SYNOPSIS

```
#include <u.h>
#include <u.h>
#include <libc.h>
int stat(char *name, uchar *edir, int nedir)
int fstat(int fd, uchar *edir, int nedir)
int wstat(char *name, uchar *edir, int nedir)
int fwstat(int fd, uchar *edir, int nedir)
Dir* dirstat(char *name)
Dir* dirfstat(int fd)
int dirwstat(char *name, Dir *dir)
int dirfwstat(int fd, Dir *dir)
void nulldir(Dir *d)
```

DESCRIPTION

Given a file's *name*, or an open file descriptor *fd*, these routines retrieve or modify file status information. *Stat*, *fstat*, *wstat*, and *fwstat* are the system calls; they deal with machine-independent *directory entries*. Their format is defined by *stat*(5). *Stat* and *fstat* retrieve information about *name* or *fd* into *edir*, a buffer of length *nedir*, defined in <libc.h>. *Wstat* and *fwstat* write information back, thus changing file attributes according to the contents of *edir*. The data returned from the kernel includes its leading 16-bit length field as described in *intro*(5). For symmetry, this field must also be present when passing data to the kernel in a call to *wstat* and *fwstat*, but its value is ignored.

Dirstat, dirfstat, dirwstat, and dirfwstat are similar to their counterparts, except that they operate on *Dir* structures:

```
typedef
struct Dir {
    /* system-modified data */
    uint type;
                /* server type */
                   /* server subtype */
    uint
          dev;
    /* file data */
    Oid
                   /* unique id from server */
          qid;
    ulong mode;
                   /* permissions */
                   /* last read time */
    ulong atime;
                   /* last write time */
    ulong mtime;
                   /* file length: see <u.h> */
    vlong length;
                   /* last element of path */
    char
          *name;
                   /* owner name */
          *uid:
    char
                   /* group name */
    char
          *gid:
                   /* last modifier name */
    char
          *muid:
} Dir;
```

The returned structure is allocated by *malloc*(2); freeing it also frees the associated strings.

This structure and the Qid structure are defined in <libc.h>. If the file resides on permanent storage and is not a directory, the length returned by *stat* is the number of bytes in the file. For directories, the length returned is zero. For files that are streams (e.g., pipes and network connections), the length is the number of bytes that can be read without blocking.

Each file is the responsibility of some *server*: it could be a file server, a kernel device, or a user process. Type identifies the server type, and dev says which of a group of servers of the same type is the one responsible for this file. Qid is a structure containing path and vers fields: path is guaranteed to be unique among all path names currently on the file server, and vers changes each time the file is modified. The path is a long long (64 bits, vlong) and the vers is an unsigned long (32 bits, ulong). Thus, if two files have the same type, dev,

and qid they are the same file.

The bits in mode are defined by

0x80000000	directory
0x40000000	append only
0x20000000	exclusive use (locked)
0400	read permission by owner
0200	write permission by owner
0100	execute permission (search on directory) by owner
0070	read, write, execute (search) by group
0007	read, write, execute (search) by others

There are constants defined in <libc.h> for these bits: DMDIR, DMAPPEND, and DMEXCL for the first three; and DMREAD, DMWRITE, and DMEXEC for the read, write, and execute bits for others.

The two time fields are measured in seconds since the epoch (Jan 1 00:00 1970 GMT). Mtime is the time of the last change of content. Similarly, atime is set whenever the contents are accessed; also, it is set whenever mtime is set.

Uid and gid are the names of the owner and group of the file; muid is the name of the user that last modified the file (setting mtime). Groups are also users, but each server is free to associate a list of users with any user name g, and that list is the set of users in the group g. When an initial attachment is made to a server, the user string in the process group is communicated to the server. Thus, the server knows, for any given file access, whether the accessing process is the owner of, or in the group of, the file. This selects which sets of three bits in mode is used to check permissions.

Only some of the fields may be changed with the *wstat* calls. The name can be changed by anyone with write permission in the parent directory. The mode and mtime can be changed by the owner or the group leader of the file's current group. The *gid* can be changed: by the owner if also a member of the new group; or by the group leader of the file's current group if also leader of the new group (see *intro*(5) for more information about permissions and *users*(6) for users and groups). The length can be changed by anyone with write permission, provided the operation is implemented by the server. (See *intro*(5) for permission information, and *users*(6) for user and group information).

Special values in the fields of the Dir passed to *wstat* indicate that the field is not intended to be changed by the call. The values are the maximum unsigned integer of appropriate size for integral values (usually ~ 0 , but beware of conversions and size mismatches when comparing values) and the empty or nil string for string values. The routine *nulldir* initializes all the elements of *d* to these "don't care" values. Thus one may change the mode, for example, by using *nulldir* to initialize a Dir, then setting the mode, and then doing *wstat*; it is not necessary to use *stat* to retrieve the initial values first.

SOURCE

/sys/src/libc/9syscall for the non-dir routines
/sys/src/libc/9sys for the routines prefixed dir

SEE ALSO

intro(2), fcall(2), dirread(2), stat(5)

DIAGNOSTICS

The *dir* functions return a pointer to the data for a successful call, or nil on error. The others return the number of bytes copied on success, or -1 on error. All set *errstr*.

If the buffer for *stat* or *fstat* is too short for the returned data, the return value will be BIT16SZ (see *fcall*(2)) and the two bytes returned will contain the initial count field of the returned data; retrying with nedir equal to that value plus BIT16SZ (for the count itself) should succeed.

strcat, strncat, strcmp, strncmp, cistrcmp, cistrncmp, strcpy, strncpy, strecpy, strlen, strchr, strrchr, strpbrk, strspn, strcspn, strtok, strdup, strstr, cistrstr - string operations

SYNOPSIS

```
#include <u.h>
#include <libc.h>
char* strcat(char *s1, char *s2)
char* strncat(char *s1, char *s2, long n)
      strcmp(char *s1, char *s2)
int
      strncmp(char *s1, char *s2, long n)
int
      cistrcmp(char *s1, char *s2)
int
      cistrncmp(char *s1, char *s2, int n)
int
char* strcpy(char *s1, char *s2)
char* strecpy(char *s1, char *es1, char *s2)
char* strncpy(char *s1, char *s2, long n)
long strlen(char *s)
char* strchr(char *s, int c)
char* strrchr(char *s, int c)
char* strpbrk(char *s1, char *s2)
long strspn(char *s1, char *s2)
      strcspn(char *s1, char *s2)
long
char* strtok(char *s1, char *s2)
char* strdup(char *s)
char* strstr(char *s1, char *s2)
char* cistrstr(char *s1, char *s2)
```

DESCRIPTION

The arguments *s1*, *s2* and *s* point to null-terminated strings. The functions *strcat*, *strncat*, *strcpy*, *strecpy*, and *strncpy* all alter *s1*. *Strcat* and *strcpy* do not check for overflow of the array pointed to by *s1*.

Strcat appends a copy of string *s2* to the end of string *s1*. *Strncat* appends at most *n* bytes. Each returns a pointer to the null-terminated result.

Strcmp compares its arguments and returns an integer less than, equal to, or greater than 0, according as *s1* is lexicographically less than, equal to, or greater than *s2*. *Strncmp* makes the same comparison but examines at most *n* bytes. *Cistrcmp* and *cistrncmp* ignore ASCII case distinctions when comparing strings. The comparisons are made with unsigned bytes.

Strcpy copies string s2 to s1, stopping after the null byte has been copied. Strncpy copies exactly n bytes, truncating s2 or adding null bytes to s1 if necessary. The result will not be null-terminated if the length of s2 is n or more. Each function returns s1.

Strecpy copies bytes until a null byte has been copied, but writes no bytes beyond *es1*. If any bytes are copied, *s1* is terminated by a null byte, and a pointer to that byte is returned. Otherwise, the original *s1* is returned.

Strlen returns the number of bytes in s, not including the terminating null byte.

Strchr (strrchr) returns a pointer to the first (last) occurrence of byte c in string s, or 0 if c does not occur in the string. The null byte terminating a string is considered to be part of the string.

Strpbrk returns a pointer to the first occurrence in string s1 of any byte from string s2, 0 if no byte from s2 exists in s1.

Strspn (*strcspn*) returns the length of the initial segment of string *s1* which consists entirely of bytes from (not from) string *s2*.

Strtok considers the string s1 to consist of a sequence of zero or more text tokens separated by spans of one or more bytes from the separator string s2. The first call, with pointer s1 specified, returns a pointer to the first byte of the first token, and will have written a null byte into s1 immediately following the returned token. The function keeps track of its position in the string between separate calls; subsequent calls, signified by s1 being 0, will work through the string s1 immediately following that token. The separator string s2 may be different from call to call. When no token remains in s1, 0 is returned.

Strdup returns a pointer to a distinct copy of the null-terminated string *s* in space obtained from *malloc*(2) or 0 if no space can be obtained.

Strstr returns a pointer to the first occurrence of s2 as a substring of s1, or 0 if there is none. If s2 is the null string, strstr returns s1. Cistrstr operates analogously, but ignores ASCII case differences when comparing strings.

SOURCE

All these routines have portable C implementations in /sys/src/libc/port. Many also have machine-dependent assembly language implementations in /sys/src/libc/\$objtype.

SEE ALSO

memory(2), rune(2), runestrcat(2), string(2)

BUGS

These routines know nothing about UTF. Use the routines in *rune*(2) as appropriate. Note, however, that the definition of UTF guarantees that *strcmp* compares UTF strings correctly.

The outcome of overlapping moves varies among implementations.

s_alloc, s_append, s_array, s_copy, s_error, s_free, s_incref, s_memappend, s_nappend, s_new, s_newalloc, s_parse, s_reset, s_restart, s_terminate, s_tolower, s_putc, s_unique, s_grow, s_read, s_read_line, s_getline - extensible strings

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <String.h>
String*
          s_new(void)
void
          s_free(String *s)
String*
          s_newalloc(int n)
String*
          s_array(char *p, int n)
String*
          s_grow(String *s, int n)
void
          s_putc(String *s, int c)
void
          s_terminate(String *s)
String*
          s_reset(String *s)
String*
          s_restart(String *s)
          s_append(String *s, char *p)
String*
String*
          s_nappend(String *s, char *p, int n)
          s_memappend(String *s, char *p, int n)
String*
String*
          s_copy(char *p)
String*
          s_parse(String *s1, String *s2)
          s_tolower(String *s)
void
String*
          s_incref(String *s)
String*
          s_unique(String *s)
#include <bio.h>
          s_read(Biobuf *b, String *s, int n)
int
          s_read_line(Biobuf *b, String *s)
char*
char*
          s_getline(Biobuf *b, String *s)
```

DESCRIPTION

These routines manipulate extensible strings. The basic type is String, which points to an array of characters. The string maintains pointers to the beginning and end of the allocated array. In addition a finger pointer keeps track of where parsing will start (for *s_parse*) or new characters will be added (for *s_putc*, *s_append*, and *s_nappend*). The structure, and a few useful macros are:

```
typedef struct String {
   Lock;
   char *base; /* base of String */
   char *end; /* end of allocated space+1 */
   char *ptr; /* ptr into String */
   ...
} String;
#define s_to_c(s) ((s)->base)
#define s_len(s) ((s)->ptr-(s)->base)
#define s_clone(s) s_copy((s)->base)
```

 S_{to_c} is used when code needs a reference to the character array. Using s->base directly is frowned upon since it exposes too much of the implementation.

allocation and freeing

A string must be allocated before it can be used. One normally does this using s_new , giving the string an initial allocation of 128 bytes. If you know that the string will need to grow much longer, you can use $s_newalloc$ instead, specifying the number of bytes in the initial allocation.

S_free causes both the string and its character array to be freed.

S_grow grows a string's allocation by a fixed amount. It is useful if you are reading directly into a string's character array but should be avoided if possible.

S_array is used to create a constant array, that is, one whose contents won't change. It points directly to the character array given as an argument. Tread lightly when using this call.

Filling the string

After its initial allocation, the string points to the beginning of an allocated array of characters starting with NUL.

S_putc writes a character into the string at the pointer and advances the pointer to point after it.

S_terminate writes a NUL at the pointer but doesn't advance it.

S_restart resets the pointer to the begining of the string but doesn't change the contents.

S_reset is equivalent to *s_restart* followed by *s_terminate*.

 S_append and $s_nappend$ copy characters into the string at the pointer and advance the pointer. They also write a NUL at the pointer without advancing the pointer beyond it. Both routines stop copying on encountering a NUL. $S_memappend$ is like $s_nappend$ but doesn't stop at a NUL.

If you know the initial character array to be copied into a string, you can allocate a string and copy in the bytes using *s_copy*. This is the equivalent of a *s_new* followed by an *s_append*.

 S_parse copies the next white space terminated token from s1 to the end of s2. White space is defined as space, tab, and newline. Both single and double quoted strings are treated as a single token. The bounding quotes are not copied. There is no escape mechanism.

S_tolower converts all ASCII characters in the string to lower case.

Multithreading

S_incref is used by multithreaded programs to avoid having the string memory released until the last user of the string performs an *s_free*. *S_unique* returns a unique copy of the string: if the reference count it 1 it returns the string, otherwise it returns an *s_clone* of the string.

Bio interaction

S_read reads the requested number of characters through a *Biobuf* into a string. The string is grown as necessary. An eof or error terminates the read. The number of bytes read is returned. The string is null terminated.

S_read_line reads up to and including the next newline and returns a pointer to the beginning of the bytes read. An eof or error terminates the read. The string is null terminated.

S_getline reads up to the next newline and returns a pointer to the beginning of the bytes read. Leading spaces and tabs and the trailing newline are all discarded. *S_getline* will recursively read through files included with #include and discard all other lines beginning with #.

SOURCE

/sys/src/libString

SEE ALSO

bio(2)

stringsize, stringwidth, stringnwidth, runestringsize, runestringwidth, runestringnwidth - graphical size of strings

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <libc.h>
#include <draw.h>
Point stringsize(Font *f, char *s)
int stringwidth(Font *f, char *s, int n)
Point runestringsize(Font *f, Rune *s)
int runestringwidth(Font *f, Rune *s)
int runestringwidth(Font *f, Rune *s, int n)
```

DESCRIPTION

These routines compute the geometrical extent of character strings when drawn on the display. The most straightforward, stringsize, returns a Point representing the vector from upper left to lower right of the NUL-terminated string s drawn in font f. Stringwidth returns just the x component. Stringnwidth returns the width of the first n characters of s.

The routines beginning with rune are analogous, but accept an array of runes rather than UTFencoded bytes.

FILES

/lib/font/bit directory of fonts

SOURCE

/sys/src/libdraw

SEE ALSO

addpt(2), cachechars(2), subfont(2), draw(2), draw(3), image(6), font(6)

DIAGNOSTICS

Because strings are loaded dynamically, these routines may generate I/O to the server and produce calls to the graphics error function.

allocsubfont, freesubfont, installsubfont, lookupsubfont, uninstallsubfont, subfontname, readsubfont, readsubfonti, writesubfont, stringsubfont, strsubfontwidth, mkfont - subfont manipulation

SYNOPSIS

	<u.h> <libc.h> <draw.h></draw.h></libc.h></u.h>
Subfont*	allocsubfont(char *name, int n, int height, int ascent, Fontchar *info, Image *i)
void	<pre>freesubfont(Subfont *f)</pre>
void	<pre>installsubfont(char *name, Subfont *f)</pre>
Subfont*	lookupsubfont(Display *d, char *name)
void	uninstallsubfont(Subfont *f)
Subfont*	<pre>readsubfont(Display *d, char *name, int fd, int dolock)</pre>
Subfont*	<pre>readsubfonti(Display *d, char *name, int fd, Image *im,</pre>
int	<pre>writesubfont(int fd, Subfont *f)</pre>
Point	stringsubfont(Image *dst, Point p, Image *src, Subfont *f, char *str)
Point	<pre>strsubfontwidth(Subfont *f, char *s)</pre>
Font*	<pre>mkfont(Subfont *f, Rune min)</pre>

DESCRIPTION

Subfonts are the components of fonts that hold the character images. A font comprises an array of subfonts; see *cachechars*(2). A new Subfont is allocated and initialized with *allocsubfont*. See *cachechars*(2) for the meaning of *n*, *height*, *ascent*, and *info*, and the arrangement of characters in image *i*. The *name* is used to identify the subfont in the subfont cache; see the descriptions *lookupsubfont* and *installsubfont* (*q.v.*). The appropriate fields of the returned Subfont structure are set to the passed arguments, and the image is registered as a subfont with the graphics device *draw*(3). *Allocsubfont* returns 0 on failure.

Freesubfont frees a subfont and all its associated structure including the associated image. Since *freesbufont* calls *free* on f->info, if f->info was not allocated by *malloc*(2) it should be zeroed before calling *subffree*.

A number of subfonts are kept in external files. The convention for naming subfont files is:

/lib/font/bit/name/class.size.depth

where *size* is approximately the height in pixels of the lower case letters (without ascenders or descenders). If there is only one version of the subfont, the *. depth* extension is elided. *Class* describes the range of runes encoded in the subfont: ascii, latin1, greek, etc.

Subfonts are cached within the program, so a subfont shared between fonts will be loaded only once. *Installsubfont* stores subfont *f* under the given *name*, typically the file name from which it was read. *Uninstallsubfont* removes the subfont from the cache. Finally, *lookupsubfont* searches for a subfont with the given *name* in the cache and returns it, or nil if no such subfont exists.

Subfontname is used to locate subfonts given their names within the fonts. The default version constructs a name given the *cfname*, its name within the font, *fname*, the name of the font, and the maximum depth suitable for this subfont. This interface allows a partially specified name within a font to be resolved at run-time to the name of a file holding a suitable subfont. Although it is principally a routine internal to the library, *subfontname* may be substituted by the application to provide a less file-oriented subfont naming scheme.

The format of a subfont file is described in *font*(6). Briefly, it contains a image with all the characters in it, followed by a subfont header, followed by character information. *Readsubfont* reads a subfont from the file descriptor *fd*. The *name* is used to identify the font in the cache. The *dolock*

argument specifies whether the routine should synchronize use of the *Display* with other processes; for single-threaded applications it may always be zero. *Readsubfonti* does the same for a subfont whose associated image is already in memory; it is passed as the argument *im*. In other words, *readsubfonti* reads only the header and character information from the file descriptor.

Writesubfont writes on *fd* the part of a subfont file that comes after the image. It should be preceded by a call to *writeimage* (see *allocimage*(2)).

Stringsubfont is analogous to string (see draw(2)) for subfonts. Rather than use the underlying font caching primitives, it calls draw for each character. It is intended for stand-alone environments such as operating system kernels. Strsubfontwidth returns the width of the string s in as it would appear if drawn with stringsubfont in Subfont f.

Mkfont takes as argument a Subfont *s* and returns a pointer to a Font that maps the character images in *s* into the Runes *min* to min+s->n-1.

FILES

/lib/font/bit bitmap font file tree

SOURCE

/sys/src/libdraw

SEE ALSO

graphics(2), allocimage(2), draw(2), cachechars(2), image(6), font(6)

DIAGNOSTICS

All of the functions use the graphics error function (see *graphics*(2)).

syminit, getsym, symbase, pc2sp, pc2line, textseg, line2addr, lookup, findlocal, getauto, findsym, localsym, globalsym, textsym, file2pc, fileelem, filesym, fileline, fnbound - symbol table access functions

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <bio.h>
#include <mach.h>
     syminit(int fd, Fhdr *fp)
int
    *getsym(int index)
Sym
    *symbase(long *nsyms)
Svm
int
    fileelem(Sym **fp, uchar *encname, char *buf, int n)
    filesym(int index, char *buf, int n)
int
uvlong pc2sp(uvlong pc)
long pc2line(uvlong pc)
void textseg(uvlong base, Fhdr *fp)
uvlong line2addr(long line, uvlong basepc, uvlong endpc)
    lookup(char *fn, char *var, Symbol *s)
int
    findlocal(Symbol *s1, char *name, Symbol *s2)
int
     getauto(Symbol *s1, int off, int class, Symbol *s2)
int
int
    findsym(uvlong addr, int class, Symbol *s)
    localsym(Symbol *s, int index)
int
int
     globalsym(Symbol *s, int index)
int
    textsym(Symbol *s, int index)
uvlong file2pc(char *file, long line)
long fileline(char *str, int n, uvlong addr)
     fnbound(uvlong addr, uvlong *bounds)
int
```

DESCRIPTION

These functions provide machine-independent access to the symbol table of an executable file or executing process. The latter is accessible by opening the device /proc/pid/text as described in *proc*(3). *Mach*(2) and *object*(2) describe additional library functions for processing executable and object files.

Syminit, getsym, symbase, fileelem, pc2sp, pc2line, and line2addr process the symbol table contained in an executable file or the text image of an executing program. The symbol table is stored internally as an array of Sym data structures as defined in *a.out*(6).

Syminit uses the data in the Fhdr structure filled by crackhdr (see mach(2)) to read the raw symbol tables from the open file descriptor fd. It returns the count of the number of symbols or -1 if an error occurs.

Getsym returns the address of the *i*th Sym structure or zero if *index* is out of range.

Symbase returns the address of the first Sym structure in the symbol table. The number of entries in the symbol table is returned in *nsyms*.

Fileelem converts a file name, encoded as described in *a.out*(6), to a character string. *Fp* is the base of an array of pointers to file path components ordered by path index. *Encname* is the address of an array of encoded file path components in the form of a z symbol table entry. *Buf* and *n* specify the address of a receiving character buffer and its length. *Fileelem* returns the length of the null-terminated string that is at most n-1 bytes long.

Filesym is a higher-level interface to *fileelem*. It fills *buf* with the name of the *i*th file and returns the length of the null-terminated string that is at most n-1 bytes long. File names are retrieved in no particular order, although the order of retrieval does not vary from one pass to the next. A zero is returned when *index* is too large or too small or an error occurs during file name conversion.

Pc2sp returns an offset associated with a given value of the program counter. Adding this offset to the current value of the stack pointer gives the address of the current stack frame. This approach only applies to the 68020 architecture; other architectures use a fixed stack frame offset by a constant contained in a dummy local variable (called .frame) in the symbol table.

Pc2line returns the line number of the statement associated with the instruction address *pc*. The line number is the absolute line number in the source file as seen by the compiler after pre-processing; the original line number in the source file may be derived from this value using the history stacks contained in the symbol table.

Pc2sp and *pc2line* must know the start and end addresses of the text segment for proper operation. These values are calculated from the file header by function *syminit*. If the text segment address is changed, the application program must invoke *textseg* to recalculate the boundaries of the segment. *Base* is the new base address of the text segment and *fp* points to the *Fhdr* data structure filled by *crackhdr*.

Line2addr converts a line number to an instruction address. The first argument is the absolute line number in a file. Since a line number does not uniquely identify an instruction location (e.g., every source file has line 1), a second argument specifies a text address from which the search begins. Usually this is the address of the first function in the file of interest.

Pc2sp, *pc2line*, and *line2addr* return -1 in the case of an error.

Lookup, findlocal, getauto, findsym, localsym, globalsym, textsym, file2pc, and fileline operate on data structures riding above the raw symbol table. These data structures occupy memory and impose a startup penalty but speed retrievals and provide higher-level access to the basic symbol table data. Syminit must be called prior to using these functions. The Symbol data structure:

```
typedef struct {
    void *handle; /* private */
    struct {
        char *name;
        long value;
        char type;
        char class;
    };
} Symbol;
```

describes a symbol table entry. The value field contains the offset of the symbol within its address space: global variables relative to the beginning of the data segment, text beyond the start of the text segment, and automatic variables and parameters relative to the stack frame. The type field contains the type of the symbol as defined in *a.out*(6). The class field assigns the symbol to a general class; CTEXT, CDATA, CAUTO, and CPARAM are the most popular.

Lookup fills a Symbol structure with symbol table information. Global variables and functions are represented by a single name; local variables and parameters are uniquely specified by a function and variable name pair. Arguments fn and var contain the name of a function and variable, respectively. If both are non-zero, the symbol table is searched for a parameter or automatic variable. If only *var* is zero, the text symbol table is searched for function fn. If only fn is zero, the global variable table is searched for *var*.

Findlocal fills *s2* with the symbol table data of the automatic variable or parameter matching *name*. *S1* is a Symbol data structure describing a function or a local variable; the latter resolves to its owning function.

Getauto searches the local symbols associated with function *s1* for an automatic variable or parameter located at stack offset *off*. *Class* selects the class of variable: CAUTO or CPARAM. *S2* is the address of a Symbol data structure to receive the symbol table information of the desired symbol.

Findsym returns the symbol table entry of type *class* stored near *addr*. The selected symbol is a global variable or function with address nearest to and less than or equal to *addr*. Class specification CDATA searches only the global variable symbol table; class CTEXT limits the search to the text symbol table. Class specification CANY searches the text table first, then the global table.

Localsym returns the *i*th local variable in the function associated with s. S may reference a function or a local variable; the latter resolves to its owning function. If the *i*th local symbol exists, s is filled with the data describing it.

Globalsym loads *s* with the symbol table information of the *i*th global variable.

Textsym loads *s* with the symbol table information of the *i*th text symbol. The text symbols are ordered by increasing address.

File2pc returns a text address associated with line in file file, or -1 on an error.

Fileline converts text address *addr* to its equivalent line number in a source file. The result, a null terminated character string of the form file:line, is placed in buffer *str* of *n* bytes.

Fnbound returns the start and end addresses of the function containing the text address supplied as the first argument. The second argument is an array of two unsigned longs; *fnbound* places the bounding addresses of the function in the first and second elements of this array. The start address is the address of the first instruction of the function; the end address is the address of the start of the next function in memory, so it is beyond the end of the target function. *Fnbound* returns 1 if the address is within a text function, or zero if the address selects no function.

Functions *file2pc* and *fileline* may produce inaccurate results when applied to optimized code.

Unless otherwise specified, all functions return 1 on success, or 0 on error. When an error occurs, a message describing it is stored in the system error buffer where it is available via *errstr*.

SOURCE

/sys/src/libmach

SEE ALSO

mach(2), object(2), errstr(2), proc(3), a.out(6)

alt, chanclose, chancreate, chanfree, chanclosing, chanprint, mainstacksize, proccreate, procdata, procexec, procexecl, procrfork, recv, recvp, recvul, send, sendp, sendul, nbrecv, nbrecvul, nbsend, nbsendp, nbsendul, threadcreate, threaddata, threadexits, threadexitsall, threadgetgrp, threadgetname, threadint, threadintgrp, threadkill, threadkillgrp, threadmain, threadnotify, threadid, threadpid, threadsetgrp, threadsetname, threadwaitchan, yield - thread and proc management

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <thread.h>
typedef enum {
  CHANEND,
  CHANSND,
  CHANRCV.
  CHANNOP.
  CHANNOBLK,
} ChanOp;
typedef struct Alt Alt;
struct Alt {
    Channel *c:
                  /* channel */
            *v;
                  /* pointer to value */
    void
            op; /* operation */
*err; /* did the op fail? */
    Chan0p
            op;
    char
    /*
     * the next variables are used internally to alt
     * they need not be initialized
     */
    Channel **tag;
                    /* pointer to rendez-vous tag */
    int
            entryno; /* entry number */
};
void
         threadmain(int argc, char *argv[])
int
         mainstacksize
         proccreate(void (*fn)(void*), void *arg, uint stacksize)
int
         procrfork(void (*fn)(void*), void *arg, uint stacksize,
int
            int rforkflag)
         threadcreate(void (*fn)(void*), void *arg, uint stacksize)
int
         threadexits(char *status)
void
void
         threadexitsall(char *status)
         yield(void)
void
         threadid(void)
int
         threadgetgrp(void)
int
         threadsetgrp(int group)
int
int
         threadpid(int id)
void
         threadint(int id)
void
         threadintgrp(int group)
void
         threadkill(int id)
         threadkillgrp(int group)
void
         threadsetname(char *fmt, ...)
void
char*
         threadgetname(void)
void**
         threaddata(void)
void**
         procdata(void)
Channel* chancreate(int elsize, int nel)
```

```
void
         chanfree(Channel *c)
         alt(Alt *alts)
int
         recv(Channel *c, void *v)
int
void*
         recvp(Channel *c)
ulong
         recvul(Channel *c)
int
         nbrecv(Channel *c. void *v)
         nbrecvp(Channel *c)
void*
         nbrecvul(Channel *c)
ulong
         send(Channel *c, void *v)
int
         sendp(Channel *c, void *v)
int
         sendul(Channel *c, ulong v)
nbsend(Channel *c, void *v)
int
int
         nbsendp(Channel *c, void *v)
int
         nbsendul(Channel *c, ulong v)
int
         chanprint(Channel *c, char *fmt, ...)
int
         chanclose(Channel *c);
int
int
         chanclosing(Channel *c);
void
         procexecl(Channel *cpid, char *file, ...)
         procexec(Channel *cpid, char *file, char *args[])
void
Channel*
         threadwaitchan(void)
int
         threadnotify(int (*f)(void*, char*), int in)
```

DESCRIPTION

The thread library provides parallel programming support similar to that of the languages Alef and Newsqueak. *Threads* and *procs* occupy a shared address space, communicating and synchronizing through *channels* and shared variables.

A *proc* is a Plan 9 process that contains one or more cooperatively-scheduled *threads*. Programs using threads must replace *main* by *threadmain*. The thread library provides a *main* function that sets up a proc with a single thread executing *threadmain* on a stack of size *mainstacksize* (default eight kilobytes). To set *mainstacksize*, declare a global variable initialized to the desired value (*e.g.*, int mainstacksize = 1024).

Creation

Threadcreate creates a new thread in the calling proc, returning a unique integer identifying the thread; the thread executes *fn(arg)* on a stack of size *stacksize*. Thread stacks are allocated in shared memory, making it valid to pass pointers to stack variables between threads and procs. *Procrfork* creates a new proc, and inside that proc creates a single thread as *threadcreate* would, returning the id of the created thread. *Procrfork* creates the new proc by calling rfork (see *fork(2)*) with flags RFPROC | RFMEM | RFNOWAIT | *rforkflag*. (The thread library depends on all its procs running in the same rendezvous group. Do not include RFREND in *rforkflag*.) *Proccreate* is identical to *procrfork* with *rforkflag* set to zero. Be aware that the calling thread may continue execution before the newly created proc and thread are scheduled. Because of this, *arg* should not point to data on the stack of a function that could return before the new process is scheduled.

Threadexits terminates the calling thread. If the thread is the last in its proc, *threadexits* also terminates the proc, using *status* as the exit status. *Threadexitsall* terminates all procs in the program, using *status* as the exit status.

Scheduling

The threads in a proc are coroutines, scheduled non-preemptively in a round-robin fashion. A thread must explicitly relinquish control of the processor before another thread in the same proc is run. Calls that do this are *yield*, *proccreate*, *procexec*, *procexecl*, *threadexits*, *alt*, *send*, and *recv* (and the calls related to *send* and *recv*—see their descriptions further on), plus these from *lock*(2): *qlock*, *rlock*, *wlock*, *rsleep*. Procs are scheduled by the operating system. Therefore, threads in different procs can preempt one another in arbitrary ways and should synchronize their actions using qlocks (see *lock*(2)) or channel communication. System calls such as *read*(2) block the entire proc; all threads in a proc block until the system call finishes.

As mentioned above, each thread has a unique integer thread id. Thread ids are not reused; they are unique across the life of the program. *Threadid* returns the id for the current thread. Each thread also has a thread group id. The initial thread has a group id of zero. Each new thread

inherits the group id of the thread that created it. *Threadgetgrp* returns the group id for the current thread; *threadsetgrp* sets it. *Threadpid* returns the pid of the Plan 9 process containing the thread identified by id, or -1 if no such thread is found.

Threadint interrupts a thread that is blocked in a channel operation or system call. Threadintgrp interrupts all threads with the given group id. Threadkill marks a thread to die when it next relinquishes the processor (via one of the calls listed above). If the thread is blocked in a channel operation or system call, it is also interrupted. Threadkillgrp kills all threads with the given group id. Note that threadkill and threadkillgrp will not terminate a thread that never relinquishes the processor.

Names and per-thread data

Primarily for debugging, threads can have string names associated with them. *Threadgetname* returns the current thread's name; *threadsetname* sets it. The pointer returned by *threadgetname* is only valid until the next call to *threadsetname*.

Threaddata returns a pointer to a per-thread pointer that may be modified by threaded programs for per-thread storage. Similarly, *procdata* returns a pointer to a per-proc pointer.

Executing new programs

Procexecl and *procexec* are threaded analogues of *exec* and *execl* (see *exec*(2)); on success, they replace the calling thread (which must be the only thread in its proc) and invoke the external program, never returning. On error, they return and set *errstr*. If *cpid* is not null, the pid of the invoked program will be sent along *cpid* once the program has been started, or –1 will be sent if an error occurs. *Procexec* and *procexecl* will not access their arguments after sending a result along *cpid*. Thus, programs that malloc the *argv* passed to *procexec* can safely free it once they have received the *cpid* response.

Threadwaitchan returns a channel of pointers to Waitmsg structures (see *wait*(2)). When an exec'ed process exits, a pointer to a Waitmsg is sent to this channel. These Waitmsg structures have been allocated with *malloc*(2) and should be freed after use.

Channels

A Channel is a buffered or unbuffered queue for fixed-size messages. Procs and threads *send* messages into the channel and *recv* messages from the channel. If the channel is unbuffered, a *send* operation blocks until the corresponding *recv* operation occurs and *vice versa*. *Chancreate* allocates a new channel for messages of size *elsize* and with a buffer holding *nel* messages. If *nel* is zero, the channel is unbuffered. *Chanfree* frees a channel that is no longer used. *Chanfree* can be called by either sender or receiver after the last item has been sent or received. Freeing the channel will be delayed if there is a thread blocked on it until that thread unblocks (but *chanfree* returns immediately).

Send sends the element pointed at by v to the channel c. If v is null, zeros are sent. Recv receives an element from c and stores it in v. If v is null, the received value is discarded. Send and recv return 1 on success, -1 if interrupted. Nbsend and nbrecv behave similarly, but return 0 rather than blocking.

Sendp, nbsendp, sendul, and nbsendul send a pointer or an unsigned long; the channel must have been initialized with the appropriate *elsize*. *Recvp*, *nbrecvp*, *recvul*, and *nbrecvul* receive a pointer or an unsigned long; they return zero when a zero is received, when interrupted, or (for *nbrecvp* and *nbrecvul*) when the operation would have blocked. To distinguish between these three cases, use *recv* or *nbrecv*.

Alt can be used to recv from or send to one of a number of channels, as directed by an array of Alt structures, each of which describes a potential send or receive operation. In an Alt structure, c is the channel; v the value pointer (which may be null); and op the operation: CHANSND for a send operation, CHANRCV for a recv operation; CHANNOP for no operation (useful when *alt* is called with a varying set of operations). The array of Alt structures is terminated by an entry with *op* CHANEND or CHANNOBLK. If at least one Alt structure can proceed, one of them is chosen at random to be executed. *Alt* returns the index of the chosen structure. If no operations can proceed and the list is terminated with CHANNOBLK, *alt* returns the index of the terminating CHANNOBLK structure. Otherwise, *alt* blocks until one of the operations can proceed, eventually returning the index of the structure are used internally by *alt* and need not be initialized. They are not used between *alt* calls.

Chanprint formats its arguments in the manner of *print*(2) and sends the result to the channel *c*. The string delivered by *chanprint* is allocated with *malloc*(2) and should be freed upon receipt.

Chanclose prevents further elements being sent to the channel c. After closing a channel, send and recv never block. Send always returns -1. Recv returns -1 if the channel is empty. Alt may choose a CHANSND or CHANRCV that failed because the channel was closed. In this case, the err field of the Alt entry points to an error string stating that the channel was closed and the operation was completed with failure. If all entries have been selected and failed because they were closed, alt returns -1.

Errors, notes and resources

Thread library functions do not return on failure; if errors occur, the entire program is aborted.

Chanclosing returns -1 if no one called *chanclose* on the channel, and otherwise the number of elements still in the channel.

Threaded programs should use *threadnotify* in place of *atnotify* (see *notify*(2)).

It is safe to use sysfatal (see *perror*(2)) in threaded programs. *Sysfatal* will print the error string and call *threadexitsall*.

It is safe to use *rfork* (see *fork*(2)) to manage the namespace, file descriptors, note group, and environment of a single process. That is, it is safe to call *rfork* with the flags RFNAMEG, RFFDG, RFCFDG, RFNOTEG, RFENVG, and RFCENVG. (To create new processes, use *proccreate* and *procrfork*.) As mentioned above, the thread library depends on all procs being in the same rendezvous group; do not change the rendezvous group with *rfork*.

FILES

/sys/lib/acid/thread useful acid(1) functions for debugging threaded programs.
/sys/src/libthread/example.c

a full example program.

SOURCE

/sys/src/libthread

SEE ALSO

intro(2), ioproc(2), lock(2)

time, nsec - time in seconds and nanoseconds since epoch

SYNOPSIS

#include <u.h>

#include <libc.h>

long time(long *tp)

vlong nsec(void)

DESCRIPTION

Both *time* and *nsec* return the time since the epoch 00:00:00 GMT, Jan. 1, 1970. The return value of the former is in seconds and the latter in nanoseconds. For *time*, if tp is not zero then * tp is also set to the answer.

These functions work by reading /dev/bintime.

SOURCE

```
/sys/src/libc/9sys/time.c
/sys/src/libc/9sys/nsec.c
```

SEE ALSO

cputime(2), cons(3)

DIAGNOSTICS

Sets errstr.

```
tmnow, tzload, tmtime, tmparse, tmfmt, tmnorm - convert date and time
```

```
SYNOPSIS
```

```
#include <u.h>
#include <libc.h>
typedef struct Tm Tm;
typedef struct Tmfmt Tmfmt;
typedef struct Tzone Tzone;
struct Tm {
                       /* nanoseconds (range 0..1e9) */
     int
             nsec:
                       /* seconds (range 0..59) */
     int
             sec;
                       /* minutes (0..59) */
     int
             min;
                       /* hours (0..23) */
     int
             hour;
                       /* day of the month (1..31) */
     int
             mday;
                       /* month of the year (0..11) */
     int
             mon;
                       /* C.E year - 1900 */
     int
             vear:
     int
             wday;
                       /* day of week (0..6, Sunday = 0) */
     int
             yday;
                       /* day of year (0..365) */
                      /* time zone name */
     char
             zone[];
                      /* time zone delta from GMT, seconds */
     int
             tzoff;
                       /* the time zone (optional) */
     Tzone
            *tz:
};
Tzone *tzload(char *name);
Τm
      *tmnow(Tm *tm, Tzone *tz);
      *tmtime(Tm *tm, vlong abs, Tzone *tz);
\mathrm{Tm}
      *tmtimens(Tm *tm, vlong abs, int ns, Tzone *tz);
Τm
Τm
      *tmparse(Tm *dst, char *fmt, char *tm, Tzone *zone, char **ep);
       tmnorm(Tm *tm);
vlong
Tmfmt
       tmfmt(Tm *tm, char *fmt);
void
       tmfmtinstall(void);
```

DESCRIPTION

This family of functions handles simple date and time manipulation.

Time zones are loaded by name. They can be specified as the abbreviated timezone name, the full timezone name, the path to a timezone file, or an absolute offset in the HHMM form.

When given as a timezone, any instant-dependent adjustments such as leap seconds and daylight savings time will be applied to the derived fields of struct Tm, but will not affect the absolute time. The time zone name local always refers to the time in /env/timezone. The nil timezone always refers to GMT.

Tzload loads a timezone by name. The returned timezone is cached for the lifetime of the program, and should not be freed. Loading a timezone repeatedly by name loads from the cache, and does not leak.

Tmnow gets the current time of day in the requested time zone.

Tmtime converts the second resolution timestamp 'abs' into a Tm struct in the requested timezone. Tmtimens does the same, but with a nanosecond accuracy.

Tmtimens is identical to tmtime, but accepts a nanosecond argument.

Tmparse parses a time from a string according to the format argument. Leading whitespace is ignored. The point at which the parsing stopped is returned in ep. If ep is nil, trailing garbage is ignored. The result is returned in the timezone requested. If there is a timezone in the date, and a timezone is provided when parsing, then the zone is shifted to the provided timezone. Parsing is case–insensitive

The format argument contains zero or more of the following components:

Y, YY, YYYY

Represents the year. YY prints the year in 2 digit form.

M, MM, MMM, MMMM

The month of the year, in unpadded numeric, padded numeric, short name, or long name, respectively.

D, DD

The day of month in unpadded or padded numeric form, respectively.

W, WW, WWW

The day of week in numeric, short or long name form, respectively.

h, hh

The hour in unpadded or padded form, respectively

m, mm

The minute in unpadded or padded form, respectively

s, ss

The second in unpadded or padded form, respectively

t, tt

The milliseconds in unpadded and padded form, respectively. u, uu, uuu, uuuu The microseconds in unpadded. padded form modulo milliseconds, or unpadded, padded forms of the complete value, respectively. n, nn, nnn, nnnn, nnnnn, nnnnn The nanoseconds in unpadded and padded form modulo milliseconds, the unpadded and padded form modulo milliseconds, and the unpadded and padded complete value, respectively.

Z, ZZ, ZZZ

The timezone in [+-]HHMM and [+-]HH:MM, and named form, respectively. If the named timezone matches the name of the local zone, then the local timezone will be used. Otherwise, we will attempt to use the named zones listed in RFC5322.

a, A Lower and uppercase 'am' and 'pm' specifiers, respectively.

[...]

Quoted text, copied directly to the output.

- When formatting, this inserts padding into the date format. The padded width of a field is the sum of format and specifier characters combined. When For example, __h will format to a width of 3. When parsing, this acts as whitespace.
- ? When parsing, all formats of the following argument are tried from most to least specific. For example, ?*M* will match *January*, *Jan*, *01*, and *1*, in that order. When formatting, ? is ignored.
- When parsing a date, this slackens range enforcement, accepting out of range values such as January 32, which would get normalized to February 1st.

Any characters not specified above are copied directly to output, without modification.

Tmfmt produces a format description structure suitable for passing to *fmtprint*(2). If fmt is nil, we default to the format used in *ctime*(2). The format of the format string is identical to *tmparse*.

When parsing, any amount of whitespace is treated as a single token. All string matches are case insensitive, and zero padding is optional.

Tmnorm takes a manually adjusted Tm structure, and normalizes it, returning the absolute timestamp that the date represents. Normalizing recomputes the *year*, *mon*, *mday*, *hr*, *min*, *sec* and *tzoff* fields. If *tz* is non-nil, then *tzoff* will be recomputed, taking into account daylight savings for the absolute time. The values not used in the computation are recomputed for the resulting absolute time. All out of range values are wrapped. For example, December 32 will roll over to Jan 1 of the following year. Tmfmtinstall installs a time format specifier %T. The time format behaves as in tmfmt

EXAMPLES

All examples assume tmfmtinstall has been called.

Get the current date in the local timezone, UTC, and US_Pacific time. Print it using the default format.

```
Tm t;
Tzone *zl, *zp;
if((zl = tzload("local") == nil)
    sysfatal("load zone: %r");
if((zp = tzload("US_Pacific") == nil)
    sysfatal("load zone: %r");
print("local: %t\n", tmfmt(tmnow(&t, zl), nil));
print("gmt: %t\n", tmfmt(tmnow(&t, nil), nil));
print("eastern: %t\n", tmfmt(tmnow(&t, zp), nil));
```

Compare if two times are the same, regardless of timezone. Done with full, strict error checking.

```
#define Fmt "?WWW, ?MM ?DD hh:mm:ss ?Z YYYY"
Tm a, b;
char *e, *est, *pst;
pst = "Tue Dec 10 12:36:00 PST 2019";
est = "Tue Dec 10 15:36:00 EST 2019";
f(tmparse(&a, Fmt, pst, nil, &e) == nil)
     sysfatal("failed to parse: %r");
if(*e != '\0')
     sysfatal("trailing junk %s", e);
if(tmparse(&b, Fmt, est, nil, &e) == nil)
     sysfatal("failed to parse: %r");
if(*e != '\0')
     sysfatal("trailing junk %s", e);
if(tmnorm(a) == tmnorm(b) && a.nsec == b.nsec)
     print("same\n");
else
     print("different\n");
```

Convert from one timezone to another.

```
Tm here, there;
Tzone *zl, *zp;
if((zl = tzload("local")) == nil)
    sysfatal("load zone: %r");
if((zp = tzload("US_Pacific")) == nil)
    sysfatal("load zone: %r");
if(tmnow(&here, zl) == nil)
    sysfatal("get time: %r");
if(tmtime(&there, tmnorm(&here), zp) == nil)
    sysfatal("shift time: %r");
```

Add a day. Because cross daylight savings, only 23 hours are added.

```
t.day++;
tmnorm(&t);
print("%t", tmfmt(&t, nil)); /* Mon Nov 3 13:11:11 PST 2019 */
```

BUGS

Checking the timezone name against the local timezone is a dirty hack. The same date string may parse differently for people in different timezones.

Tmparse and ctime don't mix. Tmparse preserves timezone names, including names like '+0200'. Ctime expects timezone names to be exactly three characters. Use the %t format character instead of ctime.

The timezone information that we ship is out of date.

The Plan 9 timezone format has no way to express leap seconds.

We provide no way to manipulate timezones.

tmpfile, tmpnam - Stdio temporary files

SYNOPSIS

#include <u.h>

#include <stdio.h>

FILE *tmpfile(void)

char *tmpnam(char *s)

DESCRIPTION

Tmpfile creates a temporary file that will automatically be removed when the file is closed or the program exits. The return value is a Stdio FILE* opened in update mode (see *fopen*(2)).

Tmpnam generates a string that is a valid file name and that is not the same as the name of an existing file. If *s* is zero, it returns a pointer to a string which may be overwritten by subsequent calls to *tmpnam*. If *s* is non-zero, it should point to an array of at least L_tmpnam (defined in <stdio.h>) characters, and the answer will be copied there.

FILES

/tmp/tf0000000000 template for tmpfile file names.
/tmp/tn00000000000 template for tmpnam file names.

SOURCE

/sys/src/libstdio

BUGS

The files created by *tmpfile* are not removed until *exits*(2) is executed; in particular, they are not removed on *fclose* or if the program terminates abnormally.

ttfopen, ttfscale, ttfclose, ttffindchar, ttfenumchar, ttfgetglyph, ttfputglyph, ttfgetcontour, ttfrender, ttfrunerender, ttfnewbitmap, ttffreebitmap, ttfblit - TrueType renderer

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <bio.h>
#include <ttf.h>
struct TTBitmap {
     u8int *bit;
     int width, height, stride;
};
struct TTGlvph {
     TTBitmap;
     int xminpx, xmaxpx, yminpx, ymaxpx, advanceWidthpx;
     /* + internals */
};
struct TTFont {
     int ppem, ascentpx, descentpx;
     /* + internals */
};
TTFont*
          ttfopen(char *filename, int size, int flags);
          ttfscale(TTFont *f, int size, int flags);
TTFont*
void
          ttfclose(TTFont *f);
          ttffindchar(TTFont *f, Rune r);
int
          ttfenumchar(TTFont *f, Rune r, Rune *rp);
int
          ttfgetglyph(TTFont *f, int glyphidx, int render);
TTGlyph*
          ttfputglyph(TTGlyph *g);
void
int
          ttfgetcontour(TTGlyph *g, int idx, float **fp, int *nfp);
TTBitmap* ttfrender(TTFont *f, char *s, char *e, int w, int h,
          int flags, char **pp);
TTBitmap* ttfrunerender(TTFont *f, Rune *s, Rune *e, int w, int h,
          int flags, Rune **pp);
TTBitmap* ttfnewbitmap(int w, int h);
          ttfblit(TTBitmap *dst, int dstx, int dsty, TTBitmap *src,
void
          int srcx, int srcy, int w, int h);
void
          ttffreebitmap(TTBitmap *);
```

DESCRIPTION

Libttf is a parser and renderer of TrueType fonts. Given a ttf font file it can produce the rendered versions of characters at a given size.

Ttfopen opens the font at *filename* and initialises it for rendering at size *size* (specified in pixels per em). *Flags* is reserved for future use and should be zero. If rendering at multiple sizes is desired, *ttfscale* reopens the font at a different size (internally the size-independent data is shared). *TTfclose* closes an opened font. Each instance of a font created by *ttfopen* and *ttfscale* must be closed separately.

A character in a TrueType font is called a glyph. Glyphs are numbered starting from 0 and the glyph indices do not need to follow any established coding scheme. *Ttffindchar* finds the glyph number of a given rune (Unicode codepoint). If the character does not exist in the font, zero is returned. Note that, in TrueType fonts, glyph 0 conventionally contains the "glyph not found" character. *Ttfenumchar* is like *ttffindchar* but will continue searching if the character is not in the font, returning the rune number for which it found a glyph in *rp. It returns character in ascending Unicode order and it can be used to enumerate the characters in a font. Zero is returned if there are no further characters.

Ttfgetglyph interprets the actual data for a glyph specified by its index *glyphidx*. With *render* set to zero, the data is left uninterpreted; currently its only use is *ttfgetcontour*. With *render* set to one, the glyph is also rendered, i.e. a pixel representation is produced and stored in the *TTBitmap* embedded in the *TTGlyph* structure it returns. Although TrueType uses a right handed coordinate system (y increases going up), the bitmap data returns follows Plan 9 conventions (and is compatible with the *draw*(3) mask argument). The bottom left hand corner is at position (*xmin, ymin*) in the TrueType coordinate system. *Ttfputglyph* should be used to return *TTGlyph* structures for cleanup.

Ttfgetcontour can be used to obtain raw contour data for a glyph. Given an index *i* it returns the corresponding contour (counting from zero), storing a pointer to a list of (x, y) pairs in *fp. The array is allocated with *malloc*(2). The (always odd) number of points is stored in *np. The contours correspond to closed quadratic Bézier curves and the points with odd indices are the control points. For an invalid index, zero is returned and *fp and *np are not accessed. For a valid index, the number returned is the number of contours with index $\geq i$.

Ttfrender and *ttfrunerender* typeset a string of text (specified as UTF-8 or raw Unicode, respectively) and return a bitmap of size *w* and *h*. It attempts to typeset text starting from *s* and up to and not including *e*. If *e* is nil, text is typeset until a null byte is encountered. *Flags* specifies the alignment. TTFLALIGN, TTFRALIGN and TTFCENTER specify left-aligned, right-aligned and centered text, respectively. TTFJUSTIFY can be or'ed with these three options to produce text where any "wrapped" line is justified.

For reasons of efficiency and simplicity, *libttf* includes its own format for 1 bpp bitmaps. In these bitmaps, 0 corresponds to transparent and 1 corresponds to opaque. Otherwise, the format is identical to k1 *image*(6) bitmaps. *Ttfnewbitmap* and *ttffreebitmap* allocate and deallocate such bitmaps, respectively. *TTGlyph* structures can be used in place of bitmaps but must be deallocated with *ttfputglyph*, not *ttffreebitmap*. *Ttfblit* copies part of one bitmap onto another. Note that bits are or'ed together — blitting a transparent over an opaque pixel does not produce an transparent pixel.

SOURCE

/sys/src/libttf

SEE ALSO

Apple, "TrueType™ Reference Manual". Microsoft, "OpenType® specification". FreeType, source code (the only accurate source). *ttfrender*(1).

DIAGNOSTICS

Following standard conventions, routines returning pointers return nil on error and return an error message in errstr.

BUGS

Both "standards" are packages of contradictions and lies.

Apple Advanced Typography and Microsoft OpenType extensions are not supported; similarly non-TrueType (Postscript, Bitmap) fonts packaged as .ttf files are not supported.

The library is immature and interfaces are virtually guaranteed to change.

Fonts packaged as .ttc files are not supported.

HISTORY

Libttf first appeared in 9front in June, 2018.

venti - archival storage server

SYNOPSIS

#include <u.h>
#include <libc.h>
#include <venti.h>

DESCRIPTION

The Venti library provides support for writing Venti servers and clients. Other manual pages describe the library functions in detail.

Venti-cache(2) describes a simple in-memory block cache to help clients.

Venti-conn(2) describes routines for manipulating network connections between Venti clients and servers. *Venti-client*(2) and *venti-server*(2) describe routines for writing clients and servers on top of these.

Venti-fcall(2) describes the C representation of Venti protocol messages and data structures. It also describes routines that convert between the C representation and the network and disk representations.

Venti-file(2) describes routines for writing clients that manipulate Venti file trees (see venti(6)).

Venti-log(2) describes routines to access in-memory log buffers as well as the logging that is done automatically by the library.

Venti-mem(2) describes wrappers around the canonical malloc(2) routines that abort on error.

Venti-packet(2) describes routines for manipulating zero-copy chains of data buffers.

Venti-zero(2) describes routines to zero truncate and zero extend blocks (see venti(6)).

SOURCE

/sys/src/libventi

SEE ALSO

venti(1), *venti*-*cache*(2), *venti*-*client*(2), *venti*-*fcall*(2), *venti*-*file*(2) *venti*-*log*(2), *venti*-*mem*(2), *venti*-*packet*(2), *venti*-*server*(2), *venti*-*zero*(2), *venti*(6), *venti*(8)

VtBlock, VtCache, vtblockcopy, vtblockdirty, vtblockduplock, vtblockput, vtblockwrite, vtcachealloc, vtcacheallocblock, vtcacheblocksize, vtcachefree, vtcacheglobal, vtcachelocal, vtcachesetwrite, vtglobaltolocal, vtlocaltoglobal – Venti block cache

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <venti.h>
typedef struct VtBlock
{
     uchar *data;
     uchar type;
     uchar score[VtScoreSize];
    u32int addr;
     . . .
} VtBlock;
VtCache* vtcachealloc(VtConn *z, int blocksize, ulong nblocks);
         vtcachefree(VtCache *c);
void
u32int
         vtcacheblocksize(VtCache *c);
u32int
         vtglobaltolocal(uchar score[VtScoreSize])
void
         vtlocaltoglobal(u32int local, uchar score[VtScoreSize])
VtBlock* vtcacheallocblock(VtCache *c, int type);
VtBlock* vtcachelocal(VtCache *c, u32int addr, int type);
VtBlock* vtcacheglobal(VtCache *c, uchar[VtScoreSize], int type);
void
         vtblockput(VtBlock *b);
void
         vtblockduplock(VtBlock *b);
int
         vtblockwrite(VtBlock *b);
void
         vtcachesetwrite(VtCache *c,
            int (*write)(VtConn*, uchar[VtScoreSize], uint, uchar*, int));
VtBlock* vtblockcopy(VtBlock *b);
         vtblockdirty(VtBlock *b);
int
```

DESCRIPTION

These functions provide access to a simple in-memory cache of blocks already stored on a Venti server and blocks that will eventually be stored on a Venti server.

A VtBlock represents a venti data block. Blocks stored on a venti server, called *global blocks*, are named by the SHA1 hash of their contents. This hash is recorded as the block's *score*. Such blocks are immutable. The cache also stores mutable blocks that have not yet been written to a venti server. These blocks are called *local blocks*, and have special scores that are 16 zero bytes followed by a 4-byte big-endian *address*. The address is an index into the internal set of cache blocks.

The user-visible contents of a VtBlock are data, a pointer to the data; type, the venti block type; score, the block's score; and addr, the block's cache address.

Vtcachealloc allocates a new cache using the client connection z (see *venti–conn*(2) and *venti–client*(2)), with room for *nblocks* of maximum block size *blocksize*.

Vtcachefree frees a cache and all the associated blocks.

Vtcacheblocksize returns the cache's maximum block size.

Vtglobaltolocal returns the local address corresponding to the given local *score*. If passed a global score, vtglobaltolocal returns the special constant NilBlock (~0). Vtlocaltoglobal is the opposite, setting *score* to the local score for the cache address *local*.

Vtcacheallocblock allocates a new local block with the given type.

Vtcachelocal retrieves the local block at address *addr* from the cache. The given *type* must match the type of the block found at *addr*.

Vtcacheglobal retrieves the block with the given *score* and *dtype* from the cache, consulting the Venti server if necessary. If passed a local score, *vtcacheglobal* invokes *vtcachelocal* appropriately.

The block references returned by *vtcacheallocblock*, *vtcachelocal*, and *vtcacheglobal* must be released when no longer needed. *Vtblockput* releases such a reference.

It is occasionally convenient to have multiple variables refer to the same block. *Vtblockduplock* increments the block's reference count so that an extra *vtblockput* will be required in order to release the block.

Vtblockwrite writes a local block to the Venti server, changing the block to a global block. It calls the cache's *write* function to write the block to the server. The default *write* function is *vtwrite* (see *venti-client*(2)); *vtsetcachewrite* sets it. *Vtsetcachewrite* is used by clients to install replacement functions that run writes in the background or perform other additional processing.

Vtblockcopy copies a block in preparation for modifying its contents. The old block may be a local or global block, but the new block will be a local block.

The cache only evicts global blocks. Local blocks can only leave the cache via *vtblockwrite*, which turns them into global blocks, making them candidates for eviction.

If a new cache block must be allocated (for *vtcacheallocblock*, *vtcachelocal*, *vtcacheglobal*, or *vtblockcopy*), but the cache is filled (with local blocks and blocks that have not yet been released with *vtblockput*), the library prints the score and reference count of every block in the cache and then aborts. A full cache indicates either that the cache is too small, or, more commonly, that cache blocks are being leaked.

SOURCE

/sys/src/libventi

SEE ALSO

venti(2), venti-client(2), venti-conn(2), venti-file(2), venti(6)

vtconnect, vthello, vtread, vtwrite, vtreadpacket, vtwritepacket, vtsync, vtping, vtrpc, ventidoublechecksha1 - Venti client

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <venti.h>
Packet* vtrpc(VtConn *z, Packet *p)
        vthello(VtConn *z)
int
int
        vtconnect(VtConn *z)
int
        vtread(VtConn *z, uchar score[VtScoreSize],
                uint type, uchar *buf, int n)
int
        vtwrite(VtConn *z, uchar score[VtScoreSize],
                uint type, uchar *buf, int n)
Packet* vtreadpacket(VtConn *z, uchar score[VtScoreSize],
                uint type, int n)
        vtwritepacket(VtConn *z, uchar score[VtScoreSize],
int
                uint type, Packet *p)
int
        vtsync(VtConn *z)
        vtping(VtConn *z)
int
extern int ventidoublechecksha1; /* default 1 */
```

DESCRIPTION

These routines execute the client side of the *venti*(6) protocol.

Vtrpc executes a single Venti RPC transaction, sending the request packet *p* and then waiting for and returning the response packet. *Vtrpc* will set the tag in the packet. *Vtrpc* frees *p*, even on error. *Vtrpc* is typically called only indirectly, via the functions below.

Vthello executes a hello transaction, setting $z \rightarrow sid$ to the name used by the server. *Vthello* is typically called only indirectly, via *vtconnect*.

Vtconnect calls *vtversion* (see *venti-conn*(2)) and *vthello*, in that order, returning success only if both succeed. This sequence (calling *vtversion* and then *vthello*) must be done before the functions below can be called.

Vtread reads the block with the given score and type from the server, stores the returned data in memory at buf, and returns the number of bytes read. If the server's block has size larger than n, vtread does not modify buf and returns an error.

Vtwrite writes the *n* bytes in *buf* as a block of the given *type*, setting *score*.

Vtreadpacket and *vtwritepacket* are like *vtread* and *vtwrite* but return or accept the block contents in the form of a Packet. They avoid making a copy of the data.

Vtsync causes the server to flush all pending write requests to disk before returning.

Vtping executes a ping transaction with the server.

By default, *vtread* and *vtreadpacket* check that the SHA1 hash of the returned data matches the requested *score*, and *vtwrite* and *vtwritepacket* check that the returned *score* matches the SHA1 hash of the written data. Setting *ventidoublechecksha1* to zero disables these extra checks, mainly for benchmarking purposes. Doing so in production code is not recommended.

These functions can be called from multiple threads or procs simultaneously to issue requests in parallel. Programs that issue requests from multiple threads in the same proc should start separate procs running *vtsendproc* and *vtrecvproc* as described in *venti–conn*(2).

SOURCE

/sys/src/libventi

SEE ALSO

venti(2), venti-conn(2), venti-packet(2), venti(6)

DIAGNOSTICS

Vtrpc and *vtpacket* return nil on error. The other routines return -1 on error. *Vtwrite* returns 0 on success: there are no partial writes.

VtConn, vtconn, vtdial, vtfreeconn, vtsend, vtrecv, vtversion, vtdebug, vthangup - Venti network connections

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <venti.h>
typedef struct VtConn {
    int debug;
    char *version;
    char *uid;
    char *sid:
    char addr[256];
    . . .
} VtConn;
VtConn*
           vtconn(int infd, int outfd)
           vtreconn(VtConn *z, int infd, int outfd)
int
VtConn*
           vtdial(char *addr)
           vtredial(VtConn *z, char *addr)
int
           vtversion(VtConn *z)
int
int
           vtsend(VtConn *z, Packet *p)
Packet*
           vtrecv(VtConn *z)
void
           vtrecvproc(void *z)
void
           vtsendproc(void *z)
void
           vtdebug(VtConn *z, char *fmt, ...)
           vthangup(VtConn *z)
void
           vtfreeconn(VtConn *z)
void
extern int chattyventi;/* default 0 */
```

DESCRIPTION

A VtConn structure represents a connection to a Venti server (when used by a client) or to a client (when used by a server). It contains the following user-visible fields: debug, a flag enabling debugging prints; version, the protocol version in use; uid, the (unverified) name of the client; sid, the (unverified) name of the server; and addr, the network address of the remote side.

Vtconn initializes a new connection structure using file descriptors *infd* and *outfd* (which may be the same) for reading and writing. *Vtdial* dials the given network address (see *dial*(2)) and returns a corresponding connection. It returns nil if the connection cannot be established.

Vtversion exchanges version information with the remote side as described in *venti*(6). The negotiated version is stored in *z*->version.

Vtsend writes a packet (see *venti-packet*(2)) on the connection *z*. The packet *p* should be a formatted Venti message as might be returned by *vtfcallpack*; *vtsend* will add the two-byte length field (see *venti*(6)) at the beginning. *Vtsend* frees *p*, even on error.

Vtrecv reads a packet from the connection *z*. Analogous to *vtsend*, the data read from the connection must start with a two-byte length, but the returned packet will omit them.

By default, *vtsend* and *vtrecv* block until the packet can be written or read from the network. In a threaded program (see *thread*(2)), this may not be desirable. If the caller arranges for *vtsendproc* and *vtrecvproc* to run in their own procs (typically by calling *proccreate*), then *vtsend* and *vtrecv* will yield the proc in which they are run to other threads when waiting on the network. The void * argument to *vtsendproc* and *vtrecvproc* must be the connection structure *z*.

Vtdebug prints the formatted message to standard error when $z \rightarrow debug$ is set. Otherwise it is a no-op.

Vthangup hangs up a connection. It closes the associated file descriptors and shuts down send and receive procs if they have been started. Future calls to *vtrecv* or *vtsend* will return errors. Additional calls to *vthangup* will have no effect.

Vtfreeconn frees the connection structure, hanging it up first if necessary.

If the global variable *chattyventi* is set, the library prints all Venti RPCs to standard error as they are sent or received.

SOURCE

/sys/src/libventi

SEE ALSO

venti(1), venti(2), venti-client(2), venti-packet(2), venti-server(2), venti(6)

DIAGNOSTICS

Routines that return pointers return nil on error. Routines returning integers return 0 on success, -1 on error. All routines set *errstr* on error.

VtEntry, VtFcall, VtRoot, vtentrypack, vtentryunpack, vtfcallclear, vtfcallfmt, vtfcallpack, vtfcallunpack, vtfromdisktype, vttodisktype, vtgetstring, vtputstring, vtrootpack, vtrootunpack, vtparsescore, vtscorefmt – venti data formats

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <venti.h>
enum
{
    VtEntrySize = 40.
    VtRootSize = 300.
    VtScoreSize = 20.
};
typedef struct VtEntry
{
    ulong gen; /* generation number */
ushort psize; /* pointer block size */
ushort dsize; /* data block size */
    uchar type;
    uchar flags;
    uvlong size;
    uchar score[VtScoreSize];
} VtEntry;
typedef struct VtRoot
ł
    char name[128];
    char type[128];
    uchar score[VtScoreSize]; /* to a Dir block */
                                  /* maximum block size */
    ushort blocksize;
    uchar prev[VtScoreSize]; /* previous root block */
} VtRoot:
        vtentrypack(VtEntry *e, uchar *buf, int index)
void
        vtentryunpack(VtEntry *e, uchar *buf, int index)
int
Packet* vtfcallpack(VtFcall *f)
        vtfcallunpack(VtFcall *f, Packet *p)
int
void vtfcallclear(VtFcall *f)
uint
        vttodisktype(uint type)
        vtfromdisktype(uint type)
uint
        vtputstring(Packet *p, char *s)
int
        vtgetstring(Packet *p, char **s)
int
        vtrootpack(VtRoot *r, uchar *buf)
void
        vtrootunpack(VtRoot *r, uchar *buf)
int
        vtparsescore(char *s, char **prefix, uchar score[VtScoreSize])
int
int
        vtfcallfmt(Fmt *fmt)
int
        vtscorefmt(Fmt *fmt)
```

DESCRIPTION

These routines convert between C representations of Venti structures and serialized representations used on disk and on the network.

Vtentrypack converts a VtEntry structure describing a Venti file (see *venti*(6)) into a 40-byte (VtEntrySize) structure at *buf+index**40. Vtentryunpack does the reverse conversion.

Vtfcallpack converts a VtFcall structure describing a Venti protocol message (see *venti*(6)) into a packet. *Vtfcallunpack* does the reverse conversion.

The fields in a VtFcall are named after the protocol fields described in *venti*(6), except that the type field is renamed blocktype. The msgtype field holds the one-byte message type: VtThello, VtRhello, and so on.

Vtfcallclear frees the strings f->error, f->version, f->uid, f->sid, the buffers f->crypto and f->codec, and the packet f->data.

The block type enumeration defined in <venti.h> (presented in venti(6)) differs from the one used on disk and in the network protocol. The disk and network representation uses different constants and does not distinguish between VtDataType+n and VtDirType+n blocks. Vttodisktype converts a <venti.h> enumeration value to the disk value; vtfromdisktype converts a disk value to the enumeration value, always using the VtDirType pointers. The VtFcall field blocktype is an enumeration value (vtfcallpack and vtfcallunpack convert to and from the disk values used in packets automatically), so most programs will not need to call these functions.

Vtputstring appends the Venti protocol representation of the string *s* to the packet *p*. *Vtgetstring* reads a string from the packet, returning a pointer to a copy of the string in * *s*. The copy must be freed by the caller. These functions are used by *vtfcallpack* and *vtfcallunpack*; most programs will not need to call them directly.

Vtrootpack converts a VtRoot structure describing a Venti file tree into the 300-byte (VtRootSize) buffer pointed to by *buf*. Vtrootunpack does the reverse conversion.

Vtparsescore parses the 40-digit hexadecimal string *s*, writing its value into *score*. If the hexadecimal string is prefixed with a text label followed by a colon, a copy of that label is returned in ** prefix*. If *prefix* is nil, the label is ignored.

Vtfcallfmt and *vtscorefmt* are *print*(2) formatters to print VtFcall structures and scores. *Vtfcallfmt* assumes that *vtscorefmt* is installed as %V.

SOURCE

/sys/src/libventi

SEE ALSO

venti(1), venti(2), venti(6)

DIAGNOSTICS

Vtentrypack, vtfcallpack, vtrootpack, and vtfcallclear cannot fail.

Vtentryunpack, vtrootunpack, vtputstring, vtgetstring, and vtparsescore return 0 on success, -1 on error.

Vtfcallpack returns a packet on success, nil on error.

Vttodisktype and *vtfromdisktype* return VtCorruptType (255) when presented with invalid input.

VtFile, vtfileblock, vtfileblockscore, vtfileclose, vtfilecreate, vtfilecreateroot, vtfileflush, vtfileflushbefore, vtfilegetdirsize, vtfilegetentry, vtfilegetsize, vtfileincref, vtfilelock, vtfilelock2, vtfileopen, vtfileopenroot, vtfileread, vtfileremove, vtfilesetdirsize, vtfilesetentry, vtfilesetsize, vtfiletruncate, vtfileunlock, vtfilewrite – Venti files

SYNOPSIS

V+T-1 ~*			
VtFile* type);	vtfilecreateroot(VtCache *c, int psize, int dsize, int		
VtFile*	<pre>vtfileopenroot(VtCache *c, VtEntry *e);</pre>		
VtFile*	vtfileopen(VtFile *f, u32int n, int mode);		
VtFile*	vtfilecreate(VtFile *f, int psize, int dsize, int type);		
void	<pre>vtfileincref(VtFile *f);</pre>		
void	<pre>vtfileclose(VtFile *f);</pre>		
int	<pre>vtfileremove(VtFile *f);</pre>		
VtBlock*	<pre>vtfileblock(VtFile *f, u32int n, int mode);</pre>		
long	<pre>vtfileread(VtFile *f, void *buf, long n, vlong offset);</pre>		
long	<pre>vtfilewrite(VtFile *f, void *buf, long n, vlong offset);</pre>		
int	<pre>vtfileflush(VtFile *f);</pre>		
int	<pre>vtfileflushbefore(VtFile *f, vlong offset);</pre>		
int	<pre>vtfiletruncate(VtFile *f);</pre>		
uvlong	<pre>vtfilegetsize(VtFile *f);</pre>		
int	<pre>vtfilesetsize(VtFile *f, vlong size);</pre>		
u32int	<pre>vtfilegetdirsize(VtFile *f);</pre>		
int	<pre>vtfilesetdirsize(VtFile *f, u32int size);</pre>		
int	<pre>vtfilegetentry(VtFile *f, VtEntry *e);</pre>		
int	<pre>vtfilesetentry(VtFile *f, VtEntry *e);</pre>		
int score[VtScor	<pre>vtfileblockscore(VtFile *f, u32int n, uchar eSize]);</pre>		
int	<pre>vtfilelock(VtFile *f, int mode);</pre>		
int	<pre>vtfilelock2(VtFile *f, VtFile *f, int mode);</pre>		
void	<pre>vtfileunlock(VtFile *f);</pre>		

DESCRIPTION

These routines provide a simple interface to create and manipulate Venti file trees (see *venti*(6)).

Vtfilecreateroot creates a new Venti file. *Type* must be either VtDataType or VtDirType, specifying a data or directory file. *Dsize* is the block size to use for leaf (data or directory) blocks in the hash tree; *psize* is the block size to use for internal (pointer) blocks.

Vtfileopenroot opens an existing Venti file described by e.

Vtfileopen opens the Venti file described by the *n*th entry in the directory *f*. *Mode* should be one of VtOREAD, VtOWRITE, or VtORDWR, indicating how the returned file is to be used. The VtOWRITE and VtORDWR modes can only be used if *f* is open with mode VtORDWR.

Vtfilecreate creates a new file in the directory *f* with block type *type* and block sizes *dsize* and *psize* (see *vtfilecreateroot* above).

Each file has an associated reference count and holds a reference to its parent in the file tree. *Vtfileincref* increments this reference count. *Vtfileclose* decrements the reference count. If there are no other references, *vtfileclose* releases the reference to f's parent and then frees the inmemory structure f. The data stored in f is still accessible by reopening it.

Vtfileremove removes the file f from its parent directory. It also acts as vtfileclose, releasing the reference to f and potentially freeing the structure.

Vtfileblock returns the *n*th block in the file f. If there are not *n* blocks in the file and *mode* is VtOREAD, *vtfileblock* returns nil. If the mode is VtOWRITE or VtORDWR, *vtfileblock* grows the file as needed and then returns the block.

Vtfileread reads at most n bytes at offset offset from f into memory at buf. It returns the number of bytes read.

Vtfilewrite writes the *n* bytes in memory at *buf* into the file *f* at offset *n*. It returns the number of bytes written, or -1 on error. Writing fewer bytes than requested will only happen if an error is encountered.

Vtfilewrite writes to an in-memory copy of the data blocks (see venti-cache(2)) instead of writing directly to Venti. Vtfileflush writes all copied blocks associated with f to the Venti server. Vtfileflushbefore flushes only those blocks corresponding to data in the file before byte offset. Loops that vtfilewrite should call vtfileflushbefore regularly to avoid filling the block cache with unwritten blocks.

Vtfiletruncate changes the file *f* to have zero length.

Vtfilegetsize returns the length (in bytes) of file *f*.

Vtfilesetsize sets the length (in bytes) of file *f*.

Vtfilegetdirsize returns the length (in directory entries) of the directory *f*.

Vtfilesetdirsize sets the length (in directory entries) of the directory *f*.

Vtfilegetentry fills *e* with an entry that can be passed to *vtfileopenroot* to reopen *f* at a later time.

Vtfilesetentry sets the entry associated with *f* to be *e*.

Vtfileblockscore returns in *score* the score of the *n*th block in the file *f*.

Venti files are locked and unlocked via *vtfilelock* and *vtfileunlock* to moderate concurrent access. Only one thread at a time—the one that has the file locked—can read or modify the file. The functions that return files (*vtfilecreateroot*, *vtfileopenroot*, *vtfilecreate*, and *vtfileopen*) return them unlocked. When files are passed to any of the functions documented in this manual page, it is the caller's responsibility to ensure that they are already locked.

Internally, a file is locked by locking the block that contains its directory entry. When two files in the same directory both need to be locked, *vtfilelock2* must be used. It locks both its arguments, taking special care not to deadlock if their entries are stored in the same directory block.

SOURCE

/sys/src/libventi/file.c

SEE ALSO

venti-cache(2), venti-conn(2), venti-client(2), venti(6)

VtLog, VtLogChunk, vtlog, vtlogclose, vtlogdump, vtlognames, vtlogopen, vtlogprint, vtlogremove, vtlogopen, ventilogging - Venti logs

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <venti.h>
VtLog* vtlogopen(char *name, uint size);
void
       vtlogprint(VtLog *log, char *fmt, ...);
void
       vtlogclose(VtLog *log);
void
       vtlog(char *name, char *fmt, ...);
void
       vtlogremove(char *name);
char** vtlognames(int *n);
       vtlogdump(int fd, VtLog *log);
void
                            /* default 0 */
extern int ventilogging;
                             /* "libventi/server" */
extern char *VtServerLog;
```

DESCRIPTION

These routines provide an in-memory circular log structure used by the Venti library and the Venti server to record events for debugging purposes. The logs are named by UTF strings.

Vtlogopen returns a reference to the log with the given *name*. If a log with that name does not exist and *size* is non-zero, *vtlogopen* creates a new log capable of holding at least *size* bytes and returns it. *Vtlogclose* releases the reference returned by *vtlogopen*.

Vtlogprint writes to log, which must be open.

Vtlog is a convenient packaging of vtlogopen followed by vtlogprint and vtlogclose.

Vtlogremove removes the log with the given name, freeing any associated storage.

Vtlognames returns a list of the names of all the logs. The length of the list is returned in *n. The list should be freed by calling *vtfree* on the returned pointer. The strings in the list will be freed by this call as well. (It is an error to call *vtfree* on any of the strings in the list.)

Vtlogdump prints log, which must be open, to the file descriptor fd.

If *ventilogging* is set to zero (the default), *vtlognames* and *vtlogdump* can inspect existing logs, but *vtlogopen* always returns nil and *vtlog* is a no-op. The other functions are no-ops when passed nil log structures.

The server library (see *venti-conn*(2) and *venti-server*(2)) writes debugging information to the log named *VtServerLog*, which defaults to the string 'libventi/server'.

SOURCE

/sys/src/libventi

SEE ALSO

venti(2), venti(8)

vtbrk, vtmalloc, vtmallocz, vtrealloc, vtstrdup, vtfree - error-checking memory allocators

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <libc.h>
#include <venti.h>
void* vtbrk(int size)
void* vtmalloc(int size)
void* vtmallocz(int size)
void* vtmallocz(void *ptr, int size)
char* vtstrdup(char *s)
void vtfree(void *ptr)
```

DESCRIPTION

These routines allocate and free memory. On failure, they print an error message and call *sysfatal* (from *perror*(2)). They do not return.

Vtbrk returns a pointer to a new, permanently allocated block of at least *size* bytes.

Vtmalloc, vtrealloc, and *vtstrdup* are like *malloc, realloc,* and *strdup,* but, as noted above, do not return on error. *Vtmallocz* is like *vtmalloc* but zeros the block before returning it. Memory allocated with all four should be freed with *vtfree* when no longer needed.

SOURCE

/sys/src/libventi

SEE ALSO

venti(2)

Packet, packetalloc, packetappend, packetasize, packetcmp, packetconcat, packetconsume, packetcopy, packetdup, packetforeign, packetfragments, packetfree, packetheader, packetpeek, packetprefix, packetsha1, packetsize, packetsplit, packetstats, packettrailer, packettrim – zero-copy network buffers

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <venti.h>
Packet* packetalloc(void);
void
        packetappend(Packet *p, uchar *buf, int n)
        packetasize(Packet *p)
uint
int
        packetcmp(Packet *p, Packet *q)
void
        packetconcat(Packet *p, Packet *q)
int
        packetconsume(Packet *p, uchar *buf, int n)
        packetcopy(Packet *p, uchar *buf, int offset, int n)
int
Packet* packetdup(Packet *p, int offset, int n)
Packet* packetforeign(uchar *buf, int n,
            void (*free)(void *a), void *a)
        packetfragments(Packet *p, IOchunk *io, int nio,
int
            int offset)
void
        packetfree(Packet *p)
uchar*
        packetheader(Packet *p, int n)
uchar*
        packetpeek(Packet *p, uchar *buf, int offset, int n)
void
        packetprefix(Packet *p, uchar *buf, int n)
void
        packetsha1(Packet *p, uchar sha1[20])
uint
        packetsize(Packet *p)
Packet* packetsplit(Packet *p, int n)
void
        packetstats(void)
uchar*
        packettrailer(Packet *p, int n)
int
        packettrim(Packet *p, int offset, int n)
```

DESCRIPTION

A Packet is a chain of blocks of data. Each block, called a fragment, is contiguous in memory, but the entire packet may not be. This representation helps avoid unnecessary memory copies.

Packetalloc allocates an empty packet.

Packetappend appends the *n* bytes at *buf* to the end of *p*.

Packetasize returns the number of data bytes allocated to p. This may be larger than the number of bytes stored in p because fragments may not be filled completely.

Packetcmp compares the data sections of two packets as memcmp (see memory(2)) would.

Packetconcat removes all data from *q*, appending it to *p*.

Packetconsume removes *n* bytes from the beginning of *p*, storing them into *buf*.

Packetcopy copies n bytes at offset in p to buf.

Packetdup creates a new packet initialized with *n* bytes from *offset* in *p*.

Packetforeign allocates a packet containing 'foreign' data: the *n* bytes pointed to by *buf*. Once the bytes are no longer needed, they are freed by calling *free*(a).

Packetfragments initializes up to *nio* of the *io* structures with pointers to the data in p, starting at *offset*. It returns the total number of bytes represented by the returned structures. *Packetfragments* initializes any unused *io* structures with nil pointer and zero length.

Packetfree frees the packet *p*.

Packetheader returns a pointer to the first *n* bytes of *p*, making them contiguous in memory if necessary.

Packetpeek returns a pointer to the n bytes at offset in p. If the requested bytes are already stored contiguously in memory, the returned pointer points at the internal data storage for p. Otherwise, the bytes are copied into buf, and packetpeek returns buf.

Packetprefix inserts a copy of the *n* bytes at *buf* at the beginning of *p*.

Packetsha1 computes the SHA1 hash of the data contained in *p*.

Packetsize returns the length, in bytes, of the data contained in *p*.

Packetsplit returns a new packet initialized with n bytes removed from the beginning of p.

Packetstats prints run-time statistics to standard output.

Packettrailer returns a pointer to the last n bytes of p, making them contiguous in memory if necessary.

Packettrim deletes all bytes from the packet *p* except the *n* bytes at offset.

SOURCE

/sys/src/libventi

SEE ALSO

venti(2)

DIAGNOSTICS

These functions return errors only when passed invalid inputs, *e.g.*, requests for data at negative offsets or beyond the end of a packet.

Functions returning pointers return nil on error; functions returning integers return -1 on error. Most functions returning integers return 0 on success. The exceptions are *packetfragments* and *packetcmp*, whose return values are described above.

When these functions run out of memory, they print error messages and call sysfatal.

vtsrvhello, vtlisten, vtgetreq, vtrespond - Venti server

SYNOPSIS

DESCRIPTION

These routines execute the server side of the *venti*(6) protocol.

Vtsrvhello executes the server side of the initial hello transaction. It sets $z \rightarrow uid$ with the user name claimed by the other side. Each new connection must be initialized by running *vtversion* and then *vtsrvhello*. The framework below takes care of this detail automatically; *vtsrvhello* is provided for programs that do not use the functions below.

Vtlisten, vtgetreq, and vtrespond provide a simple framework for writing Venti servers.

Vtlisten announces at the network address *addr*, returning a fresh VtSrv structure representing the service.

Vtgetreq waits for and returns the next read, write, sync, or ping request from any client connected to the service *srv*. Hello and goodbye messages are handled internally and not returned to the client. The interface does not distinguish between the different clients that may be connected at any given time. The request can be found in the *tx* field of the returned VtReq.

Once a request has been served and a response stored in $r \rightarrow rx$, the server should call *vtrespond* to send the response to the client. *Vtrespond* frees the structure r as well as the packets $r \rightarrow tx.data$ and $r \rightarrow rx.data$.

EXAMPLE

/sys/src/cmd/venti contains two simple Venti servers ro.c and devnull.c written using these routines. *Ro* is a read-only Venti proxy (it rejects write requests). *Devnull* is a dangerous write-only Venti server: it discards all blocks written to it and returns error on all reads.

SOURCE

/sys/src/libventi

SEE ALSO

venti(2), venti-conn(2), venti-packet(2), venti(6), venti(8)

vtzerotruncate, vtzeroextend, vtzeroscore - Venti block truncation

SYNOPSIS

#include <u.h>
#include <libc.h>
#include <venti.h>

uint vtzerotruncate(int type, uchar *buf, uint size)

void vtzeroextend(int type, uchar *buf, uint size, uint newsize)

extern uchar vtzeroscore[VtScoreSize];

DESCRIPTION

These utility functions compute how to truncate or replace trailing zeros (for data blocks) or trailing zero scores (for pointer blocks) to canonicalize the blocks before storing them to Venti.

Vtzerotruncate returns the size of the *size*-byte buffer pointed to by *buf* ignoring trailing zeros or zero scores, according to the given *type*.

Vtzeroextend pads *buf* with zeros or zero scores, according to the given *type*, to grow it from *size* bytes to *newsize* bytes.

Vtzeroscore is the score of the zero-length block.

SOURCE

/sys/src/libventi/zero.c
/sys/src/libventi/zeroscore.c

SEE ALSO

venti(2), venti(6)

await, wait, waitpid - wait for a process to exit

SYNOPSIS

#include <u.h>
#include <libc.h>
Waitmsg* wait(void)
int waitpid(void)
int await(char *s, int n)

DESCRIPTION

Wait causes a process to wait for any child process (see *fork*(2)) to exit. It returns a Waitmsg holding information about the exited child. A Waitmsg has this structure:

```
typedef
struct Waitmsg
{
    int pid;    /* of loved one */
    ulong time[3];    /* of loved one & descendants */
    char *msg;
} Waitmsg;
```

Pid is the child's process id. The time array contains the time the child and its descendants spent in user code, the time spent in system calls, and the child's elapsed real time, all in units of milliseconds. Msg contains the message that the child specified in exits(2). For a normal exit, msg[0] is zero, otherwise msg is the exit string prefixed by the process name, a blank, the process id, and a colon.

If there are no more children to wait for, *wait* returns immediately, with return value nil.

The Waitmsg structure is allocated by *malloc*(2) and should be freed after use. For programs that only need the pid of the exiting program, *waitpid* returns just the pid and discards the rest of the information.

The underlying system call is *await*, which fills in the n-byte buffer *s* with a textual representation of the pid, times, and exit string. There is no terminal NUL. The return value is the length, in bytes, of the data.

The buffer filled in by *await* may be parsed (after appending a NUL) using *tokenize* (see *getfields*(2)); the resulting fields are, in order, pid, the three times, and the exit string, which will be ' for normal exit. If the representation is longer than *n* bytes, it is truncated but, if possible, properly formatted. The information that does not fit in the buffer is discarded, so a subsequent call to *await* will return the information about the next exiting child, not the remainder of the truncated message. In other words, each call to *await* returns the information about one child, blocking if necessary if no child has exited.

If the calling process has no living children, *await* and *waitpid* return -1.

SOURCE

```
/sys/src/libc/9syscall
/sys/src/libc/9sys
```

SEE ALSO

fork(2), exits(2), the wait file in proc(3)

DIAGNOSTICS

These routines set *errstr*.

Screen, allocscreen, publicscreen, freescreen, allocwindow, bottomwindow, bottomnwindows, topwindow, topnwindows, originwindow - window management

SYNOPSIS

```
#include <u.h>
#include <libc.h>
#include <draw.h>
typedef
struct Screen
{
               *display; /* display holding data */
     Display
                         /* id of system-held Screen */
     int
               id:
     Image
               *image;
                         /* unused; for reference only */
                         /* color to paint behind windows */
               *fill;
     Image
} Screen;
Screen* allocscreen(Image *image, Image *fill, int public)
Screen* publicscreen(Display *d, int id, ulong chan)
int
        freescreen(Screen *s)
        allocwindow(Screen *s, Rectangle r, int ref, ulong col)
Image*
void
        bottomwindow(Image *w)
        bottomnwindows(Image **wp, int nw)
void
void
        topwindow(Image *w)
void
        topnwindows(Image **wp, int nw)
int
        originwindow(Image *w, Point log, Point scr)
enum
{
        /* refresh methods */
        Refbackup= 0,
        Refnone= 1,
        Refmesg= 2
}:
```

DESCRIPTION

Windows are represented as Images and may be treated as regular images for all drawing operations. The routines discussed here permit the creation, deletion, and shuffling of windows, facilities that do not apply to regular images.

To create windows, it is first necessary to allocate a Screen data structure to gather them together. A Screen turns an arbitrary image into something that may have windows upon it. It is created by allocscreen, which takes an *image* upon which to place the windows (typically display->image), a *fill* image to paint the background behind all the windows on the image, and a flag specifying whether the result should be publicly visible. If it is public, an arbitrary other program connected to the same display may acquire a pointer to the same screen by calling publicscreen with the Display pointer and the *id* of the published Screen, as well as the expected channel descriptor, as a safety check. It will usually require some out-of-band coordination for programs to share a screen profitably. Freescreen releases a Screen, although it may not actually disappear from view until all the windows upon it have also been deallocated.

Unlike allocwindow, allocscreen does not initialize the appearance of the Screen.

Windows are created by allocwindow, which takes a pointer to the Screen upon which to create the window, a rectangle *r* defining its geometry, an integer pixel value *col* to color the window initially, and a refresh method ref. The refresh methods are Refbackup, which provides backing store and is the method used by *rio*(1) for its clients; Refnone, which provides no refresh and is designed for temporary uses such as sweeping a display rectangle, for windows that are completely covered by other windows, and for windows that are already protected by backing store; and Refmesg, which causes messages to be delivered to the owner of the window when it needs to be repainted. Refmesg is not fully implemented.

The result of allocwindow is an Image pointer that may be treated like any other image. In particular, it is freed by calling freeimage (see *allocimage*(2)). The following functions, however, apply only to windows, not regular images.

Bottomwindow pushes window w to the bottom of the stack of windows on its Screen, perhaps obscuring it. Topwindow pulls window w to the top, making it fully visible on its Screen. (This Screen may itself be within a window that is not fully visible; topwindow will not affect the stacking of this parent window.) Bottomnwindows and Topnwindows are analogous, but push or pull a group of *nw* windows listed in the array *wp*. The order within *wp* is unaffected.

Each window is created as an Image whose Rectangle r corresponds to the rectangle given to allocwindow when it was created. Thus, a newly created window w resides on its Screen->image at w->r and has internal coordinates w->r. Both these may be changed by a call to originwindow. The two Point arguments to originwindow define the upper left corner of the logical coordinate system (*log*) and screen position (*scr*). Their usage is shown in the Examples section.

Rio(1) creates its client windows with backing store, Refbackup. The graphics initialization routine, initdraw (see *graphics*(2)), builds a Screen upon this, and then allocates upon that another window indented to protect the border. That window is created Refnone, since the backing store created by rio protects its contents. That window is the one known in the library by the global name screen (a historic but confusing choice).

EXAMPLES

To move a window to the upper left corner of the display,

originwindow(w, w->r.min, Pt(0, 0));

To leave a window where it is on the screen but change its internal coordinate system so (0, 0) is the upper left corner of the window,

originwindow(w, Pt(0, 0), w->r.min);

After this is done, $w \rightarrow r$ is translated to the origin and there will be no way to discover the actual screen position of the window unless it is recorded separately.

SOURCE

/sys/src/libdraw

SEE ALSO

graphics(2), draw(2), cachechars(2), draw(3)

BUGS

The refresh method Refmesg should be finished.

intro - introduction to the Plan 9 devices

DESCRIPTION

A Plan 9 *device* implements a file tree for client processes. A file name beginning with a pound sign, such as #c, names the root of a file tree implemented by a particular *kernel device driver* identified by the character after the pound sign. Such names are usually bound to conventional locations in the name space. For example, after

bind("#c", "/dev", MREPL)

an ls(1) of /dev will list the files provided by the *console* device.

A kernel device driver is a *server* in the sense of the Plan 9 File Protocol, 9P (see Section 5), but with the messages implemented by local rather than remote procedure calls. Also, several of the messages (*Nop*, *Session*, *Flush*, and *Error*) have no subroutine equivalents.

When a system call is passed a file name beginning with # it looks at the next character, and if that is a valid *device character* it performs an *attach*(5) on the corresponding device to get a channel representing the root of that device's file tree. If there are any characters after the device character but before the next / or end of string, those characters are passed as parameter *aname* to the attach. For example,

#I2

identifies the number 2 IP protocol stack (see ip(3)).

Each kernel device has a conventional place at which to be bound to the name space. The *SYNOPSIS* sections of the following pages includes a *bind* command to put the device in the conventional place. Most of these binds are done automatically by *init*(8) using newns (see *auth*(2)) on the file /lib/namespace (see *namespace*(6)). When typed to rc(1), the *bind* commands will need quotes to protect the # characters.

SEE ALSO

intro(5), intro(2)

aoe - ATA-over-Ethernet (AoE) interface

SYNOPSIS

bind -a #æ /dev
/dev/aoe/ctl
/dev/aoe/log
/dev/aoe/shelf.slot/config
/dev/aoe/shelf.slot/ctl
/dev/aoe/shelf.slot/devlink/0

```
/dev/aoe/shelf.slot/devlink/i
/dev/aoe/shelf.slot/ident
```

DESCRIPTION

The AoE (ATA-over-Ethernet) interface serves a three-level directory providing control and access to AoE targets. The interface provided is primarily intended for low-level control of the AoE initiator. See *sdaoe*(3) for the standard interface.

Top-level files

In order to access AoE targets, one or more Ethernet controllers need to be bound to the AoE initiator. By default, the system starts with no interfaces bound. For automatic binding of interfaces on boot, the aoeif configuration variable is set in *plan9.ini*(8). Ethernet interfaces are specified as ethern, not as #ln. To bind the first and second Ethernet devices on boot, add

aoeif=ether0 ether1

To bind ether1 to a running system:

% echo bind '#l1/ether1' >/dev/aoe/ctl

And to unbind it

% echo unbind '#l1/ether1' >/dev/aoe/ctl

When an interface is unbound, targets depending on that interface are removed.

Each local interface is called a *netlink*. The mapping of AoE targets to netlinks is called a *devlink*. Each devlink may see multiple interfaces per target. For example, if the local machine has one Ethernet address bound and the target has two interfaces on the same Ethernet segment, this will result in one netlink and one devlink with two Ethernet addresses. AoE frames are sent in round-robin fashion. Each successive frame is sent on the next address available on the next available devlink (local interface).

Normally the initiator automatically discovers and adds new device directories on startup. New devices are not added except as new interfaces are bound to the initiator. Several messages can be written to /dev/aoe/ctl which alter this behavior:

autodiscover toggle

If toggle is absent, the state of autodiscover is toggled. If it is the string on, it is turned on. Any other string turns autodisover off. This option is not useful after Ethernet devices have been bound.

discover shelf.slot

Attempt to find the named target on all bound interfaces.

remove shelf.slot

The converse of discover: remove the named target if it exists.

rediscover toggle

Allow or disallow rediscovery. This allows for automatic discovery of new targets. Unfortunately, it also allows automatic modification or loss of existing targets. This option is considered dangerous. Reading /dev/aoe/ctl returns a list of colon-separated lines with keywords and their values:

debug autodiscover	
rediscover	Returns the current state of the variable named by the keyword. Writing the variable's name to the control file toggles the state of that variable.
ifn path	Path to <i>n</i> th bound Ethernet device.
ifn ea	Ethernet address of this device.
ifn flag	A flag of "Up" indicates that this interface is available.
ifn lostjumbo	Number of consecutive lost jumbograms.
ifn datamtu	Incorrect and unused.

Shelf-and-slot subdirectories

Once configured, each AoE target is accessed via files in the directory named for its shelf and slot. For example, shelf 42, slot 0 would be accessed through the path /dev/aoe/42.0. The ident file contains the read-only, verbatim result of the identify unit ATA command. The config file contains the target's AoE configuration string. Writing to this file sets the targets configuration string.

Reading a shelf and slot's ctl file returns a list of colon-separated lines with the following keywords and values:

state	"Up" or "dowr	ı".
State	00 01 0000	

nopen Number of clients using this target.

nout Number of outstanding AoE frames.

nmaxout Maximum number of outstanding frames allowed.

- nframes Maximum number of outstanding frames. *Nframes* is greater than *nmaxout* when the initiator is reducing the number of in-flight frames due to packet loss. It is assumed that packet loss is due to an overwhelmed target and not poor network conditions.
- maxbcount Maximum number of data bytes per AoE frame. Using standard frames, maxbcount is 1024 or two sectors. AoE ATA headers are 36 bytes.

firmware The respective fields from the ATA identify unit command.

flag List of flags useful for debugging. The flag jumbo indicates that jumbo frames are accepted, not that they are being used. *Maxbcount* should be consulted for this purpose.

The data file may be read or written like a normal file except that reads and writes to this file are converted to AoE commands to the target, so transfers should be 512 or 1024 bytes long (or a larger multiple of 512 iff jumbo packets are in use). The size of this file is the usable size of the target.

The devlink directory contains one file for each interface the target was discovered on. The files are numbers from 0 to n and contain a list of colon-separated lines with keywords and their values:

- addr A space-separated list of the target's Ethernet addresses visible from this interface.
- npkt The number of frames sent on this interface.
- resent The number of frames re-sent. Frames are re-sent when they have been outstanding twice the RTT average.
- flag "Up" when the netlink is up.
- rttavg
- mintimer Minimum timer and RTT average as per Congestion Avoidance and Control.

model

serial

- nl path Path of the Ethernet device.
- nl ea Ethernet address of the local Ethernet device.
- nl flag "Up" if the local interface is up.
- nl lostjumbo

Number of consecutive jumbograms lost.

nl datamtu

Unused.

SOURCE

/sys/src/9/port/devaoe.c

SEE ALSO

sd(3), sdaoe(3), vblade(8), snoopy(8)
http://www.coraid.com/documents/AoEr10.txt
Van Jacobson and Michael J. Karels, "Congestion Avoidance and Control", ACM Computer Communication Review; Proceedings of the Sigcomm '88 Symposium in Stanford, CA, August, 1988.

BUGS

There is no raw file for executing arbitrary commands.

This is a fairly primitive interface; *sdaoe*(3) is usually more suitable.

apm - Advanced Power Management 1.2 BIOS interface

SYNOPSIS

bind -a #P /dev

/dev/apm

DESCRIPTION

This device presents a low-level interface to the APM 1.2 bios calls. It is enabled by adding the line "apm0=" to *plan9.ini*. (The value after the equals sign is ignored; the presence of the line at all enables the driver.) It is only available on uniprocessor PCs. Writing a 386 Ureg structure and then reading it back executes an APM call: the written registers are passed to the call, and the read registers are those returned by the call.

This device is intended to enable more user-friendly interfaces such as *apm*(8).

SOURCE

/sys/src/9/pc/apm.c
/sys/src/9/pc/apmjump.s

arch - architecture-specific information and control

SYNOPSIS

```
bind -a #P /dev
/dev/acpitbls
/dev/archctl
/dev/cputype
/dev/ec
/dev/ioalloc
/dev/iob
/dev/iob
/dev/iou
/dev/iow
/dev/irqalloc
/dev/msr
/dev/realmodemem
```

DESCRIPTION

This device presents textual information about PC hardware and allows user-level control of the I/O ports on x86-class machines.

Reads from *cputype* recover the processor type and clock rate in MHz. Reads from *archctl* yield at least data of this form:

```
cpu AMD64 2201 pge
pge on
coherence mfence
cmpswap cmpswap486
i8253set on
cache default uc
cache 0x0 1073741824 wb
cache 0x3ff00000 1048576 uc
```

Where AMD64 is the processor type, 2201 is the processor speed in MHz, and pge is present only if the 'page global extension' capability is present; the next line reflects its setting. coherence is followed by one of mb386, mb586, mfence or nop, showing the form of memory barrier used by the kernel. cmpswap is followed by cmpswap386 or cmpswap486, reflecting the form of 'compare and swap' used by the kernel. i8253set is a flag, indicating the need to explicitly set the Intel 8253 or equivalent timer. There may be lines starting with cache that reflect the state of memory caching via MTRRs (memory-type region registers). The second word on the line is default or a C-style number which is the base physical address of the region; the third is a Cstyle length of the region; and the fourth is one of uc (for uncachable), wb (write-back), wc (write-combining), wp (write-protected), or wt (write-through). A region may be a subset of another region, and the smaller region takes precedence. This may be used to make I/O registers uncachable in the midst of a write-combining region mostly used for a video framebuffer, for example. Control messages may be written to *archctl* and use the same syntax as the data read from *archctl*. Known commands include cache, coherence, i8253set, and pge.

Reads from *ioalloc* return I/O ranges used by each device, one line per range. Each line contains three fields separated by white space: first address in hexadecimal, last address, name of device.

Reads from *irqalloc* return the enabled interrupts, one line per interrupt. Each line contains three fields separated by white space: the trap number, the IRQ it is assigned to, and the name of the device using it.

Reads and writes to *iob*, *iow*, and *iol* cause 8-bit wide, 16-bit wide, and 32-bit wide requests to I/O ports. The port accessed is determined by the byte offset of the file descriptor.

Reads and writes to msr go to the P4/P6/Core/Core2/AMD64 MSRs.

The *realmodemem* file provides access to the first megabyte of memory. This allows reading BIOS data structures and option ROMs. Writing is limited to the VGA framebuffer at [0xA0000-0xBFFFF].

Reads and writes to *ec* transfer bytes from and to the embedded controller.

Reads from *acpitbls* return a concatenation of system ACPI tables. Each table is prefixed with a fixed size header that gives the name sigature and size of the table (see section *5.2.6 System Description Table Header* in the ACPI specification).

EXAMPLE

The following code reads from an x86 byte I/O port.

```
uchar
inportb(unsigned port)
{
    uchar data;
    if(iobfd == -1)
        iobfd = open("#P/iob", ORDWR);
    seek(iobfd, port, 0);
    if(read(iobfd, &data, sizeof(data)) != sizeof(data))
        sysfatal("inportb(0x%4.4ux): %r", port);
    return data;
}
```

SOURCE

/sys/src/9/pc/devarch.c

audio - audio device

SYNOPSIS

bind -a #A /dev
/dev/audio
/dev/audioctl
/dev/audiostat
/dev/volume

DESCRIPTION

The audio device serves a one-level directory, giving access to the stereo audio ports. Audio is the data file, which can be written for audio playback. Audio data is a sequence of stereo samples, left sample first. Each sample is a 16 bit little-endian two's complement integer; the default sampling rate is 44.1 kHz.

The length of the audio file as returned by *stat*(2) represents the number of bytes buffered for output.

Audioctl is driver specific control file and left undocumented here.

Audiostat is a read only status file. The first line has a length of 32 bytes including the newline and starts with the string bufsize followed by the preferred write unit (in bytes) and the string buffered followed by the number of bytes currently queued for output. The numbers are decimal and right-padded with spaces to fit. After this fixed header, the contents of the file is driver specific.

Volume is the control file associated with the audio port. Each source has an associated stereo volume control, ranging from 0 (quiet) to 100 (loud). In addition, there are controls for the sampling rate, latency control and for any tone controls. Reads return lines of the form

source left right

or

source value

Valid sources depend on the particular audio device, though all devices have an audio stereo source, which controls the output volume from the D/A converter. Values for speed set the sampling frequency of the audio device and delay limits the audio data output buffering to a number of samples.

Writes accept the same format except that for stereo sources *left* and *right* can be abbreviated to a single *value* if both should be set the same.

SOURCE

/sys/src/9/port/devaudio.c

SEE ALSO

nusb(4)

bridge – IP Ethernet bridge

SYNOPSIS

bind -a #Bb /net

/net/bridgeb/ctl /net/bridgeb/cache /net/bridgeb/log /net/bridgeb/stats /net/bridgeb/n /net/bridgeb/n/ctl /net/bridgeb/n/local /net/bridgeb/n/status

DESCRIPTION

The *bridge* device bridges packets amongst Ethernet interfaces. The number b in the bind is optional and selects a particular bridge (default 0).

The /net/bridge0 directory contains ctl, cache, log, and stats files, and numbered subdirectories for each physical interface.

Opening the ctl file reserves an interface. The file descriptor returned from the *open*(2) will point to the control file, ctl, of the newly allocated interface. Reading ctl returns a text string representing the number of the interface. Writing ctl alters aspects of the interface. The possible *ctl* messages are:

bind ether name ownhash path

Treat the device mounted at *path* (e.g., /net/ether0) as an Ethernet medium and associate it with this bridge (forward its packets to the other interfaces associated with this bridge). *Ownhash* is an 'owner hash'.

bind tunnel name ownhash path path2

Treat the device mounted at *path* as a network tunnel carrying Ethernet packets, the device mounted at *path2* as an Ethernet and associate them with this bridge (forward its packets to the other interfaces associated with this bridge). Read packets from the *path* interface and write them to the *path2* interface. Such tunnels have an MTU of 1400 bytes.

- unbind type address [ownhash] Disassociate the interface associated with address from this bridge. Type must be ether or tunnel.
- cacheflush Clear the cache of (destination MAC address, port) tuples.

delay delay0 delayn

Set the *delay0* and *delayn* parameters. *delay0* is the constant microsecond delay per packet and *delayn* is the microsecond delay per byte.

- set *option* Set bridge *option*. The only known option is tcpmss, which limits the TCP Maximum Segment Size of TCP packets passing through to 1300 bytes.
- clear option Clear bridge option.

Reading *stats* returns statistics about the bridge.

Reading the *log* file returns data from the bridge's log and will block at end of file awaiting new data.

Reading the cache file prints the cache of (destination MAC address, port) tuples, one entry per line. The format is: the destination MAC (e.g., Ethernet) address in hex, port number, count of packets from this address, count of packets to this address, expiry time in seconds since the epoch, and e for expired entries or v for valid entries.

In a connection subdirectory, ctl and local don't do anything, but status returns a one-line status summary.

EXAMPLES

Set up a network bridge between two Ethernets (#10 and #11).

bind -a '#B' /net bind -a '#l1' /net echo 'bind ether outer 0 /net/ether0' >/net/bridge0/ctl echo 'bind ether inner 0 /net/ether1' >/net/bridge0/ctl

SEE ALSO

ip(3)

SOURCE

/sys/src/9/port/devbridge.c

cap - capabilities for setting the user id of processes

SYNOPSIS

bind #¤ dir

dir/caphash *dir*/capuse

DESCRIPTION

This device enables a trusted process to create a capability that another process may then use to change its user id. The intent is to allow server processes, for example telnetd (see *ipserv*(8)), to change their user id after having proved to a trusted process, such as *factotum*(4), that they are indeed executing on behalf of a user. A trusted process is one running with the user id of the host owner (see /dev/hostowner in *cons*(3)).

A capability is a null terminated string consisting of the concatenation of an old user name, an "@", a new user name, an "@", and a string of randomly generated characters called the key. The trusted process enables the kernel to authenticate capabilities passed to it by writing to *caphash* a secure hash of the capability. The hash is 20 bytes long and generated by the following call:

The kernel maintains a list of hashes, freeing them after the corresponding capability is used or after a minute has passed since the write to *caphash*.

The trusted process may then pass the capability to any process running as the old user. That process may then use the capability to change identity to the new user. A process uses a capability by writing it to *capuse*. The kernel computes the same hash using the supplied capability and searches its list of hashes for a match. If one is found, the kernel sets the process's user id to that in the capability.

SOURCE

```
/sys/src/9/port/devcap.c
```

SEE ALSO

sechash(2)

DIAGNOSTICS

Errors generated by reading and writing *caphash* and *capuse* can be obtained using *errstr*(2). A read of *caphash* with a length of less than 20 or a write to *capuse* that doesn't contain two @ characters generates the error "read or write too small". A write to *capuse* that has no matching hash generates the error "invalid capability".

cmd - interface to host operating system commands

SYNOPSIS

```
bind -a '#C' /
/cmd/clone
/cmd/n/ctl
/cmd/n/data
/cmd/n/stderr
/cmd/n/status
/cmd/n/status
```

DESCRIPTION

Cmd provides a way to run commands in the underlying operating system's command interpreter of drawterm or when Inferno is running hosted. It serves a three-level directory that is conventionally bound behind the root directory. The top of the hierarchy is a directory cmd, that contains a clone file and zero or more numbered directories. Each directory represents a distinct connection to the host's command interpreter. The directory contains five files: ctl, data, stderr, status and wait, used as described below. Opening the clone file reserves a connection: it is equivalent to opening the ctl file of an unused connection directory, creating a new one if necessary.

The file ctl controls a connection. When read, it returns the decimal number n of its connection directory. Thus, opening and reading clone allocates a connection directory and reveals the number of the allocated directory, allowing the other files to be named (eg, /cmd/n/data).

Ctl accepts the following textual commands, allowing quoting as interpreted by *parsecmd*(2):

dir *wdir*

Run the host command in directory *wdir*, which is a directory *on the host system*. Issue this request before starting the command. By default, commands are run in the Inferno root directory on the host system.

exec command args ...

Spawn a host process to run the *command* with arguments as given. The write returns with an error, setting the error string, if anything prevents starting the command. If write returns successfully, the command has started, and its standard input and output may be accessed through data, and its error output accessed through stderr (see below). If arguments containing white space are quoted (following the conventions of rc(1) or *parsecmd*(2)), they are requoted by *cmd* using the host command interpreter's conventions so that *command* sees exactly the same arguments as were written to ctl.

- kill Kill the host command immediately.
- killonclose

Set the device to kill the host command when the ctl file is closed (normally all files must be closed, see below).

nice [*n*]

Run the host command at less than normal scheduling priority. Issue this request before starting the command. The optional value n, in the range 1 to 3, indicates the degree of 'niceness' (default: 1).

The data file provides a connection to the input and output of a previously-started host command. It must be opened separately for reading and for writing. When opened for reading, it returns data that the command writes to its standard output; when closed, further writes by the command will receive the host equivalent of 'write to closed pipe'. When opened for writing, data written to the file can be read by the command on its standard input; when closed, further reads by the command will see the host equivalent of 'end of file'. (Unfortunately there is no way to know when the command needs input.)

The stderr file provides a similar read-only connection to the error output from the command. If the stderr file is not opened, the error output will be discarded.

Once started, a host command runs until it terminates or until it is killed, by using the kill or killonclose requests above, or by closing all ctl, data and wait files for a connection.

The read-only status file provides a single line giving the status of the connection (not the command), of the form:

cmd/n opens state wdir arg0

where the fields are separated by white space. The meaning of each field is:

- *n* The cmd directory number.
- opens The decimal number of open file descriptors for ctl, data and wait.
- *state* The status of the interface in directory *n*:

OpenAllocated for use but not yet running a command.ExecuteRunning a command.DoneCommand terminated: status available in the status file (or via wait).ClosedCommand completed. Available for reallocation via clone.

wdir The command's initial working directory on the host.

arg0 The host command name (without arguments).

The read-only wait file must be opened before starting a command via ctl. When read, it blocks until the command terminates. The read then returns with a single status line, to be parsed using tokenize (see *getfields*(2)). There are five fields: host process ID (or 0 if unknown); time the command spent in user code in milliseconds (or 0); time spent in system code in milliseconds (or 0); real time in milliseconds (or 0); and a string giving the exit status of the command. The exit status is host-dependent, except that an empty string means success, and a non-empty string contains a diagnostic.

Command execution

In all cases, the command runs in the host operating system's own file name space. All file names will be interpreted in that space, not Plan9's. For example, on Unix / refers to the host's file system root, not Plan9's; the effects of mounts and binds will not be visible.

SEE ALSO

os(1)

DIAGNOSTICS

A write to ctl returns with an error and sets the error string if a command cannot be started or killed successfully.

cons - console, clocks, process/process group ids, user, null, reboot, etc.

SYNOPSIS

bind #c /dev

/dev/bintime /dev/config /dev/cons /dev/cputime /dev/drivers /dev/hostdomain /dev/hostowner /dev/kmesg /dev/kprint /dev/mordor /dev/null /dev/osversion /dev/pid /dev/ppid /dev/random /dev/reboot /dev/sysname /dev/sysstat /dev/time /dev/user /dev/zero

DESCRIPTION

The console device serves a one-level directory giving access to the console screen and miscellaneous information.

A *write* (see *read*(2)) to cons causes the characters to be printed on the console screen. Console input is handled by a different program (see kbdfs(8)).

The osversion file contains a textual representation of the operating system's version and parameters. At the moment, it contains one field: the 9P protocol version, currently 2000.

The config file contains a copy of the kernel configuration file used to build the kernel.

The kmesg file holds the last 16 kilobytes of output written to the console by the kernel's print statements or by processes writing to /dev/cons. It is useful for retrieving boot messages once the boot process is over.

The kprint file may be read to receive a copy of the data written to the console by the kernel's print statements or by processes writing to /dev/cons. Only data written after the file is opened is available. If the machine's console is a serial line, the data is sent both to the console and to kprint; if its console is a graphics screen, the data is sent either to the display or to kprint, but not both. (It is advisable not to open kprint on terminals until you have started rio(1).)

The null file throws away anything written to it and always returns zero when read.

The zero file is a read-only file that produces an infinite stream of zero-valued bytes when read.

The drivers file contains, one per line, a listing of the drivers configured in the kernel, in the format

#c cons

The hostdomain file contains the name of the authentication domain that this host belongs to; see *authsrv*(6). Only the user named in /dev/hostowner may write this.

The hostowner file contains the name of the user that owns the console device files. The hostowner also has group permissions for any local devices.

Reads from random return a stream of random bytes produced by the kernels cryptographic random number generator. The rate at which data can be read depends on the implementation and can vary from hundreds of megabytes to just a few hundred bits a second. Therefore, random should be treated as a seed to pseudo-random number generators which can produce a faster rate stream.

Writing the string reboot to reboot causes the system to shutdown and, if possible, restart. Writing the string reboot *kernelpath* loads the named kernel image and restarts, preserving the kernel configuration in #ec, except that the bootfile variable is set to *kernelpath*. Writing the string rdb activates the remote kernel debugger (see *rdbfs*(4)). Only the host owner has the ability to open this file.

Bintime is a binary interface that provides the same information as time (q.v.), in binary form, and also controls clock frequency and clock trim. All integers read or written from bintime are in big endian order. Unlike the other files, reads and writes do not affect the offset. Therefore, there is no need for a seek back to zero between subsequent accesses. A read of bintime returns 24 bytes, three 8 byte numbers, representing nanoseconds since start of epoch, clock ticks, and clock frequency.

A write to bintime is a message with one of 3 formats:

n < 8-byte *time*> set the nanoseconds since epoch to the given *time*.

d<8-byte *delta*><4-byte *period*>

trim the nanoseconds since epoch by *delta* over the next *period* seconds.

f<8-byte *freq*> Set the frequency for interpreting clock ticks to be *freq* ticks per second.

The rest of the files contain (mostly) read-only strings. Each string has a fixed length: a *read*(2) of more than that gives a result of that fixed length (the result does not include a terminating zero byte); a *read* of less than that length leaves the file offset so the rest of the string (but no more) will be read the next time. To reread the file without closing it, *seek* must be used to reset the offset. When the file contains numeric data each number is formatted in decimal. If the binary number fits in 32 bits, it is formatted as an 11 digit decimal number with leading blanks and one trailing blank; totaling 12 bytes. Otherwise, it is formatted as 21 digit decimal numbers with leading blanks; and one trailing blank; totaling 22 bytes.

The cputime file holds six 32-bit numbers, containing the time in milliseconds that the current process has spent in user mode, system calls, real elapsed time, and then the time spent, by exited children and their descendants, in user mode, system calls, and real elapsed time.

The time file holds one 32-bit number representing the seconds since start of epoch and three 64-bit numbers, representing nanoseconds since start of epoch, clock ticks, and clock frequency.

A write of a decimal number to time will set the seconds since epoch.

The sysname file holds the textual name of the machine, e.g. kremvax, if known.

The sysstat file holds 10 numbers: processor number, context switches, interrupts, system calls, page faults, TLB faults, TLB purges, load average, idle time and time spent servicing interrupts. The load average is in units of milli-CPUs and is decayed over time; idle time and interrupt time are percentage units; the others are total counts from boot time. If the machine is a multiprocessor, sysstat holds one line per processor. Writing anything to sysstat resets all of the counts on all processors.

Reads and writes to *mordor* will inevitably cause the front to fall off.

The other files served by the *cons* device are all single numbers:

pid process number

ppid parent's process number

SEE ALSO

draw(3), *kbd*(3), *kbdfs*(8), *keyboard*(6), *authsrv*(6), *utf*(6), *swap*(8)

SOURCE

/sys/src/9/port/devcons.c

draw - screen graphics

SYNOPSIS

bind -a #i /dev

/dev/draw/new

/dev/draw/n/ctl /dev/draw/n/data /dev/draw/n/colormap /dev/draw/n/refresh

#include <u.h>
#include <draw.h>

```
ushort BGSHORT(uchar *p)
ulong BGLONG(uchar *p)
void BPSHORT(uchar *p, ushort v)
void BPLONG(uchar *p, ulong v)
```

DESCRIPTION

The *draw* device serves a three-level file system providing an interface to the graphics facilities of the system. Each client of the device connects by opening /dev/draw/new and reading 12 strings, each 11 characters wide followed by a blank: the connection number (*n*), the image id (*q.v.*) of the display image (always zero), the channel format of the image, the replicate bit, the min.x, min.y, max.x, and max.y of the display image, and the min.x, min.y, max.x, and max.y of the channel format string is described in *image*(6), and the other fields are decimal numbers.

The client can then open the directory /dev/draw/n/ to access the ctl, data, colormap, and refresh files associated with the connection.

Via the ctl and data files, the *draw* device provides access to images and font caches in its private storage, as described in *graphics*(2). Each image is identified by a 4-byte integer, its *id*.

Reading the ctl file yields 12 strings formatted as in /dev/draw/new, but for the current image rather than the display image. The current image may be set by writing a binary image id to the ctl file.

A process can write messages to data to allocate and free images, fonts, and subfonts; read or write portions of the images; and draw line segments and character strings in the images. All graphics requests are clipped to their images. Some messages return a response to be recovered by reading the data file.

The format of messages written to data is a single letter followed by binary parameters; multibyte integers are transmitted with the low order byte first. The BPSHORT and BPLONG macros place correctly formatted two- and four-byte integers into a character buffer. BGSHORT and BGLONG retrieve values from a character buffer. Points are two four-byte numbers: x, y. Rectangles are four four-byte numbers: min x, min y, max x, and max y. Images, screens, and fonts have 32-bit identifiers. In the discussion of the protocol below, the distinction between identifier and actual image, screen, or font is not made, so that "the object *id*" should be interpreted as "the object with identifier *id*". The definitions of constants used in the description below can be found in draw.h.

The following requests are accepted by the data file. The numbers in brackets give the length in bytes of the parameters.

A *id*[4] *imageid*[4] *fillid*[4] *public*[1]

Allocate a new Screen (see *window*(2)) with screen identifier *id* using backing store image *imageid*, filling it initially with data from image *fillid*. If the *public* byte is non-zero, the screen can be accessed from other processes using the publicscreen interface.

b *id*[4] *screenid*[4] *refresh*[1] *chan*[4] *repl*[1] *r*[4*4] *clipr*[4*4] *color*[4]

Allocate an image with a given *id* on the screen named by *screenid*. The image will have rectangle r and clipping rectangle *clipr*. If *repl* is non-zero, the image's replicate bit will be set (see *draw*(2)).

Refresh specifies the method to be used to draw the window when it is uncovered. Refbackup causes the server to maintain a backing store, Refnone does not refresh the image, and Refnesg causes a message to be sent via the refresh file (q.v.).

The image format is described by *chan*, a binary version of the channel format string. Specifically, the image format is the catenation of up to four 8-bit numbers, each describing a particular image channel. Each of these 8-bit numbers contains a channel type in its high nibble and a bit count in its low nibble. The channel type is one of CRed, CGreen, CBlue, CGrey, CAlpha, CMap, and CIgnore. See *image*(6).

Color is the catenation of four 8-bit numbers specifying the red, green, blue, and alpha channels of the color that the new image should be initially filled with. The red channel is in the highest 8 bits, and the alpha in the lowest. Note that color is always in this format, independent of the image format.

c dstid[4] repl[1] clipr[4*4]

Change the replicate bit and clipping rectangle of the image *dstid*. This overrides whatever settings were specified in the allocate message.

d dstid[4] srcid[4] maskid[4] dstr[4*4] srcp[2*4] maskp[2*4]

Use the draw operator to combine the rectangle *dstr* of image *dstid* with a rectangle of image *srcid*, using a rectangle of image *maskid* as an alpha mask to further control blending. The three rectangles are congruent and aligned such that the upper left corner *dstr* in image *dstid* corresponds to the point *srcp* in image *srcid* and the point *maskp* in image *maskid*. See *draw*(2).

D debugon[1]

If *debugon* is non-zero, enable debugging output. If zero, disable it. The meaning of "debugging output" is implementation dependent.

e dstid[4] srcid[4] c[2*4] a[4] b[4] thick[4] sp[2*4] alpha[4] phi[4]

Draw an ellipse in image *dst* centered on the point *c* with horizontal and vertical semiaxes *a* and *b*. The ellipse is drawn using the image *src*, with the point *sp* in *src* aligned with *c* in *dst*. The ellipse is drawn with thickness $1+2 \times thick$.

If the high bit of *alpha* is set, only the arc of the ellipse from degree angles *alpha* to *phi* is drawn. For the purposes of drawing the arc, *alpha* is treated as a signed 31-bit number by ignoring its high bit.

E dstid[4] srcid[4] center[2*4] a[4] b[4] thick[4] sp[2*4] alpha[4] phi[4]

Draws an ellipse or arc as the e message, but rather than outlining it, fills the corresponding sector using the image *srcid*. The *thick* field is ignored, but must be non-negative.

f *id*[4]

Free the resources associated with the image *id*.

F id[4]

Free the screen with the specified *id*. Windows on the screen must be freed separately.

i *id*[4] *n*[4] *ascent*[1]

Treat the image *id* as a font cache of *n* character cells, each with ascent *ascent*.

1 cacheid[4] srcid[4] index[2] r[4*4] sp[2*4] left[1] width[1]

Load a character into the font cache associated with image *cacheid* at cache position *index*. The character data is drawn in rectangle r of the font cache image and is fetched from the congruent rectangle in image *srcid* with upper left corner *sp*. *Width* specifies the width of the character—the spacing from this character to the next—while *left* specifies the horizontal distance from the left side of the character to the left side of the cache image. The dimensions of the image of the character are defined by r.

L dstid[4] p0[2*4] p1[2*4] end0[4] end1[4] thick[4] srcid[4] sp[2*4]

Draw a line of thickness $1+2 \times thick$ in image *dstid* from point *p0* to *p1*. The line is drawn using the image *srcid*, translated so that point *sp* in *srcid* aligns with *p0* in *dstid*. The *end0*

and *end1* fields specify whether the corresponding line end should be a square, a disc, or an arrow head. See *line* in *draw*(2) for more details.

N *id*[4] *in*[1] *j*[1] *name*[*j*]

If *in* is non-zero, associate the image *id* with the string *name*. If *in* is zero and *name* already corresponds to the image *id*, the association is deleted.

n *id*[4] *j*[1] *name*[*j*]

Introduce the identifier *id* to correspond to the image named by the string *name*.

o *id*[4] *r.min*[2*4] *scr*[2*4]

Position the window (layer) *id* so that its upper left corner is at the point *scr* on its screen. Simultaneously change its internal (logical) coordinate system so that the point *r.min* corresponds to the upper left corner of the window, see memlorigin(2).

0 op[1]

Set the compositing operator to *op* for the next draw operation. (The default is SoverD).

p dstid[4] n[2] end0[4] end1[4] thick[4] srcid[4] sp[2*4] dp[2*2*(n+1)]

Draw a polygon of thickness $1+2 \times thick$. It is conceptually equivalent to a series of *n* line-drawing messages (see L above) joining adjacent points in the list of points *dp*. The source image *srcid* is translated so that the point *sp* in *srcid* aligns with the first point in the list *dp*. The polygon need not be closed: *end0* and *end1* specify the line endings for the first and last point on the polygon. All interior lines have rounded ends to make smooth joins.

P dstid[4] n[2] wind[4] ignore[2*4] srcid[4] sp[2*4] dp[2*2*(n+1)]

Draw a polygon as the p message, but fill it rather than outlining it. The winding rule parameter wind resolves ambiguities about what to fill if the polygon is self-intersecting. If wind is ~ 0 , a pixel is inside the polygon if the polygon's winding number about the point is non-zero. If wind is 1, a pixel is inside if the winding number is odd. Complementary values (0 or ~ 1) cause outside pixels to be filled. The meaning of other values is undefined. The polygon is closed with a line if necessary.

r id[4] r[4*4]

Cause the next read of the data file to return the image pixel data corresponding to the rectangle r in image *id*.

s dstid[4] srcid[4] fontid[4] dp[2*4] clipr[4*4] sp[2*4] n[2] n*(index[2])

Draw in the image *dstid* the text string specified by the *n* cache *indices* into font *fontid*, starting with the upper left corner at point *p* in image *dstid*. The image drawn is taken from image *srcid*, translated to align *sp* in *srcid* with *dp* in *dstid*. All drawing is confined to the clipping rectangle *clipr* in *dstid*.

x dstid[4] srcid[4] fontid[4] dp[2*4] clipr[4*4] sp[2*4] n[2] bgid[4] bp[2*4] n*(index[2])

Like the string drawing s command, but fill the background of each character with pixels from image *bgid*. The image *bgid* is translated so that the point *bp* aligns with the point *dp* in *dstid*.

- S *id*[4] *chan*[4] Attach to the public screen with the specified *id*. It is an error if the screen does not exist, is not public, or does not have the channel descriptor *chan* for its associated image.
- t top[1] n[2] n*id[4]

Send n windows to the top (if t is non-zero) or bottom (if t is zero) of the window stack. The window is specified by the list of n image *ids* are moved as a group, maintaining their own order within the stack.

v

Flush changes from a soft screen, if any, to the display buffer.

- y *id*[4] *r*[4*4] *buf*[x*1]
- Y id[4] r[4*4] buf[x*1]

Replace the rectangle r of pixels in image *id* with the pixel data in *buf*. The pixel data must be in the format dictated by *id*'s image channel descriptor (see *image*(6)). The y message uses uncompressed data, while the Y message uses compressed data. In either case, it is an error to include more data than necessary.

Reading the colormap returns the system color map used on 8-bit displays. Each color map entry consists of a single line containing four space-separated decimal strings. The first is an index into the map, and the remaining three are the red, green, and blue values associated with that index. The color map can be changed by writing entries in the above format to the colormap file. Note that changing the system color map does not change the color map used for calculations involving m8 images, which is immutable.

The refresh file is read-only. As windows owned by the client are uncovered, if they cannot be refreshed by the server (such as when they have refresh functions associated with them), a message is made available on the refresh file reporting what needs to be repainted by the client. The message has five decimal integers formatted as in the ctl message: the image id of the window and the coordinates of the rectangle that should be refreshed.

SOURCE

/sys/src/9/port/devdraw.c
/sys/src/libmemdraw

DIAGNOSTICS

Most messages to draw can return errors; these can be detected by a system call error on the write(see read(2)) of the data containing the erroneous message. The most common error is a failure to allocate because of insufficient free resources. Most other errors occur only when the protocol is mishandled by the application. Errstr(2) will report details.

BUGS

The Refmesg refresh method is not fully implemented.

The colormap files only reference the system color map, and as such should be called /dev/colormap rather than /dev/draw/n/colormap.

dup – dups of open files

SYNOPSIS

bind #d /fd

```
/fd/0
/fd/0ctl
/fd/1
/fd/1ctl
```

DESCRIPTION

The *dup* device serves a one-level directory containing files whose names are decimal numbers. Each such file also has an associated control file. A file of name n corresponds to open file descriptor n in the current process.

An *open*(2) of file *n* results in a file descriptor identical to what would be returned from a system call dup(n, -1). Note that the result is no longer a file in the *dup* device.

The *stat* operation returns information about the device file, not the open file it points to. A stat of #d/n will contain *n* for the name, 0 for the length, and 0400, 0200, or 0600 for the mode, depending on whether the dup target is open for reading, writing, or both.

A file of name nctl may be read to discover the properties of the associated file descriptor, in format identical to that of the fd file in proc(3).

SEE ALSO

dup(2)

SOURCE

/sys/src/9/port/devdup.c

env - environment variables

SYNOPSIS

bind #e /env

/env/var1 /env/var2

DESCRIPTION

The *env* device serves a one-level directory containing files with arbitrary names and contents. The intention is that the file name is the name of an *environment variable* (see rc(1)), and the content is the variable's current value.

When a *fork*(2) system call creates a new process, both the parent and the child continue to see exactly the same files in the *env* device: changes made in either process can be noticed by the other. In contrast, an rfork system call with the RFENVG bit set (see *fork*(2)) causes a split: initially both process groups see the same environment files, but any changes made in one process group cannot be noticed by the other. An rfork with RFCENVG splits and then clears the environment.

The special global environment #ec contains kernel configuration variables, such as those set in *plan9.ini*(8). All processes see the same #ec; its contents are writable only by the host owner.

SEE ALSO

rc(1), fork(2), #c/reboot in cons(3), plan9.ini(8)

SOURCE

/sys/src/9/port/devenv.c

BUGS

A write starting at an offset after the current extent of a file yields an error instead of zero filling.

ether - Ethernet device

SYNOPSIS

bind -a #ln /net

```
/net/ethern/clone
/net/ethern/addr
/net/ethern/ifstats
/net/ethern/stats
/net/ethern/[0-7]
/net/ethern/[0-7]/data
/net/ethern/[0-7]/ctl
/net/ethern/[0-7]/ifstats
/net/ethern/[0-7]/stats
/net/ethern/[0-7]/type
```

DESCRIPTION

The Ethernet interface, /net/ethern, is a directory containing subdirectories, one for each distinct Ethernet packet type, and clone, addr, ifstats, and stats files. stats and ifstats are the same as in the subdirectories (see below). Reading addr returns the MAC address of this interface in hex with no punctuation and no trailing newline. The number *n* (optional in the bind) is the device number of the card, permitting multiple cards to be used on a single machine.

Each directory contains files to control the associated connection, receive and send data, and supply statistics. Incoming Ethernet packets are demultiplexed by packet type and passed up the corresponding open connection. Reading from the data file reads packets of that type arriving from the network. A read will terminate at packet boundaries. Each write to the data file causes a packet to be sent. The Ethernet address of the interface is inserted into the packet header as the source address.

A connection is assigned to a packet type by opening its ctl file and writing connect n where n is a decimal integer constant identifying the Ethernet packet type. A type of -1 enables the connection to receive copies of packets of all types. A type of -2 enables the connection to receive copies of the first 64 bytes of packets of all types. If multiple connections are assigned to a given packet type a copy of each packet is passed up each connection.

Some interfaces also accept unique options when written to the *ctl* (or *clone*) file; see the description of *wavelan* in *plan9.ini*(8).

Reading the ctl file returns the decimal index of the associated connection, 0 through 7. Reading the type file returns the decimal value of the assigned Ethernet packet type. Reading the stats file returns status information such as the Ethernet address of the card and general statistics, independent of the interface; ifstats contains device-specific data and statistics about the card.

An interface normally receives only those packets whose destination address is that of the interface or is the broadcast address, ff:ff:ff:ff:ff:ff. The interface can be made to receive all packets on the network by writing the string promiscuous to the ctl file. The interface remains promiscuous until the control file is closed. The extra packets are passed up connections only of types -1 and -2.

Writing packets to the data file automatically fills the source address before sending. To allow implementations of layer 2 bridges like *bridge*(3), connections can be set to bridge mode by writing bridge to the ctl file.

SOURCE

/sys/src/9/*/devether.c

flash - flash memory

SYNOPSIS

bind -a #F[n] /dev
/dev/flash
/dev/flash/part
/dev/flash/partctl

DESCRIPTION

The flash memory device serves a two-level directory, giving access to files representing part or all of a bank of flash memory. A platform might have more than one bank of flash, numbered starting from 0. The attach specifier n is a decimal integer that selects a particular bank of flash (default: 0). Both NOR and NAND flash is supported. For both types of flash, the driver gives a read/write/erase interface to the raw flash device, which can impose constraints on operations beyond those imposed by the driver.

The top level directory contains a single directory named flash for bank 0, and flash*n* for each other bank *n*. It contains two files for each partition: a data file *part* and an associated control file *part*ctl, where *part* is the name of the partition. Each partition represents a region of flash memory that starts and ends on a flash segment (erase unit) boundary. The system initially creates a single standard partition flash representing the whole of flash memory, and the corresponding control file flashctl. Other partitions can be created by writing to flashctl as described below.

The data file *part* provides read and write access to the bytes on the system's flash memory. Bytes can be read and written on any byte boundary: the interface hides any alignment restrictions. A read returns the value of the bytes at the current file offset, where zero is the start of the partition. A write reprograms the flash to the given byte values, at the current file offset (relative to the start of the partition), using the physical device's reprogramming algorithm. An erased flash byte is logically 0xFF (regardless of the conventions of the physical flash device). A write can change a bit with value 1 to a 0, but cannot change a 0 bit to 1; that can only be done by erasing one or more flash segments. NAND flash typically has restrictions on the number of writes allowed to a page before requiring a block erase.

The control file part *ctl* can be read and written. A read returns several lines containing decimal and hexadecimal numbers (separated by white space) revealing the characteristics of memory within the partition. The first line gives the manufacturer ID, the flash device ID, the memory width in bytes, and a string giving the flash type (currently either nor or nand). Subsequent lines give characteristics of each group of erase units within the partition, where the erase units within a group have the same properties. Each line gives the start and end (as byte addresses) of the erase units in the region that lie within the partition, followed by the size in bytes of each erase unit, which is followed for NAND flash by the size in bytes of a page. The sizes for NAND flash include the extra bytes per page typically used to hold an ECC and block status. A write contains one of the following textual commands:

add name start end

Create a new partition that ranges from *start* to *end* within the current partition. Each value must be numeric (decimal, octal or hexadecimal) and a multiple of the erase unit size. *Name* must not be the name of an existing partition. On success, new files *name* and *namectl* will appear in the parent flash directory.

- erase all Erase the whole flash partition, setting all bytes to 0xFF, except those that are hardware write-protected.
- erase offset Erase the segment that begins at the given offset within the partition, setting all bytes to 0xFF, except those that are hardware write-protected. The offset is given in bytes, but must be a multiple of the segment (erase unit) size.
- protectboot[off]

By default the system prevents erase unit 0 of the flash from being erased or written, assuming it contains the primary bootstrap. Writing this command with parameter off removes that protection. Writing protectboot with any other parameter (or none) restores the protection. Note that a manufacturer might also have locked the flash in hardware, and that protection must be removed in a device-dependent way.

sync If the underlying device must buffer or cache (current devices do not), flush the buffer(s).

The syntax of all numbers is that of *strtoul* (in *atof*(2)); the default base is 10.

SOURCE

/sys/src/9/*/devflash.c

SEE ALSO

flashfs(4), paqfs(4)

DIAGNOSTICS

A write will return an error if an attempt is made to change a 0 bit to 1, or if the flash memory fails to be programmed correctly.

BUGS

The flash cannot be written if the kernel is executing directly from flash, because the physical flash cannot be read during programming, and the driver does not copy the programming code to DRAM.

floppy - floppy disk interface

SYNOPSIS

bind -a #f /dev

/dev/fd0disk /dev/fd0ctl /dev/fd1disk /dev/fd1ctl /dev/fd2disk /dev/fd2ctl /dev/fd3disk /dev/fd3ctl

DESCRIPTION

The floppy disk interface serves a one-level directory giving access to up to four floppy disk drives. Each drive is represented by a data and control file. There are no partitions.

Messages accepted by the ctl file include:

eject Eject the floppy, if possible.

reset Reset the drive.

format type

Format the floppy. The *type* sets the density and type of disk to be formatted; see format in *prep*(8).

A read of the ctl file returns a string describing the form factor of the disk, one of 3½DD, 3½HD, 5½DD, or 5¼HD.

SOURCE

/sys/src/9/*/devfloppy.c

fs - file system devices

SYNOPSIS

```
bind -b #k /dev
/dev/fs
/dev/fs/ctl
/dev/fs/...
/dev/new
```

DESCRIPTION

The *fs* driver builds complex disk files out of simpler disk files. Inspired by the Plan 9 file server kernel's configuration strings, it provides device mirroring, partitioning, interleaving, and catenation for disk-based services like *venti*(8).

The device is intended to be bound at /dev and initially contains a directory named fs, which in turn contains a ctl file and one file per configured device.

Most control messages introduce a new device, here named *new*. The *file* arguments are interpreted in the name space of the writing process.

The device name *new* may be a single filename component (containing no slashes); in this case, the device is created under #k/fs. If *new* instead has the format *dir/file*, the device is made available at #k/dir/file. The directory *dir* goes away when the last device on it is removed with the del control message, but #k/fs will never be removed.

cat new files...

The device *new* corresponds to the catenation of *files*.

inter *new files*...

The device *new* corresponds to the block interleaving of *files*; an 8192-byte block size is assumed.

mirror new files...

The device *new* corresponds to a RAID-1-like mirroring of *files*. Writes to new are handled by sequentially writing the same data to the *files* from right to left (the reverse of the order in the control message). A failed write causes an eventual error return but does not prevent the rest of the writes to the other devices of the mirror set. Reads from new are handled by sequentially reading from the *files* from left to right until one succeeds. The length of the mirror device is the minimum of the lengths of the *files*.

- part new file offset length
- part new offset end

In the first form, the device *new* corresponds to the *length* units starting at *offset* in *file*. If *offset*+*length* reaches past the end of *file*, *length* is silently reduced to fit. Units are bytes. In the second form, a previous disk request must have defined the source *file* for further requests and the end of the device is determined by the *end* offset in the source file, and not by the device length. Units are as defined in the previous disk request. This form is accepted for compatibility with *fdisk* (in *prep*(8)) and *sd*(3) devices.

- del old Removes the device named old. The device will still be seen while in use. Further I/O attempts will fail with an error indication stating that the device is gone. When old is dir/*, all devices under dir are removed.
- disk dir [n file]

makes *dir* implicit in new device names (i.e., it makes *new* mean *dir* / *new* by default). Optional argument n specifies the default unit (sector) size in bytes and the default source *file* for further partition devices. Default values are restored when the control file is closed.

crypt new file key

The device *new* corresponds to a AES-encrypted partition *file* encrypted with *key* (see *cryptsetup*(8)).

clear Discard all *fs* device definitions.

If the variable fsconfig is set in *plan9.ini*(8), *fs* will read its configuration from the file \$fsconfig on the first attach. This is useful when the machine boots from a local file server that uses *fs*.

EXAMPLES

Use a previously partitioned disk, /dev/sdC0, making partition files available under /dev/sdC0parts:

{

```
echo disk sdC0parts 512 /dev/sdC0/data
disk/fdisk -p /dev/sdC0/data
# now create plan 9 partitions
echo disk sdC0parts 512 /dev/sdC0parts/plan9
disk/prep -p /dev/sdC0parts/plan9
} > /dev/fs/ctl
```

Mirror the two disks /dev/sdC0/data and /dev/sdD0/data as /dev/fs/m0; similarly, mirror /dev/sdC1/data and /dev/sdD1/data as /dev/fs/m1:

echo mirror m0 /dev/sdC0/data /dev/sdD0/data >/dev/fs/ctl
echo mirror m1 /dev/sdC1/data /dev/sdD1/data >/dev/fs/ctl

Interleave the two mirrored disks to create /dev/fs/data:

echo inter data /dev/fs/m0 /dev/fs/m1 >/dev/fs/ctl

Run *hjfs*(4) on the interleaved device:

hjfs -f /dev/fs/data

Save the configuration:

cp /dev/fs/ctl /dev/fd0disk

To load the configuration automatically at boot time, add this to *plan9.ini*:

fsconfig=/dev/fd0disk

SEE ALSO

read in cat(1), dd(1), sd(3), fs(8), plan9.ini(8), prep(8), venti(8)

SOURCE

/sys/src/9/port/devfs.c

BUGS

Mirrors are RAID-like but not RAID. There is no fancy recovery mechanism and no automatic initial copying from a master drive to its mirror drives.

Each write system call on ctl may transmit at most one command.

i82365 - Personal Computer Memory Card Interface Association (PCMCIA) device

SYNOPSIS

bind -a #y /dev

/dev/pcm0attr /dev/pcm0ctl /dev/pcm0mem /dev/pcm1attr /dev/pcm1ctl /dev/pcm1mem

DESCRIPTION

The *i82365* driver provides an interface to an Intel 82365-compatible PCMCIA interface chip. This chip supports up to 2 PCMCIA slots, 0 and 1. Reading pcm[01]attr returns the contents of attribute memory. Reading or writing pcm[01]mem reads or writes RAM on the card. Reading pcm[01]ctl returns the card's status.

This driver must be included to use PCMCIA devices such as the NE4100 Ethernet card. The individual card drivers make calls to routines in the PCMCIA driver.

SOURCE

/sys/src/9/pc/devi82365.c

SEE ALSO

plan9.ini(8)

BUGS

There is no driver for the Databook PCMCIA interface chip.

ip, esp, gre, icmp, icmpv6, ipmux, rudp, tcp, udp, il - network protocols over IP

SYNOPSIS

515	
<pre>bind -a #Ispec /net /net/ipifc /net/ipifc/clone /net/ipifc/stats /net/ipifc/n /net/ipifc/n/status</pre>	<pre>/net/icmpv6 /net/ipmux /net/rudp /net/tcp /net/udp /net/il</pre>
<pre>/net/ipifc/n/ctl /net/arp /net/bootp /net/iproute /net/ipselftab /net/log /net/ndb /net/esp /net/gre</pre>	<pre>/net/tcp/clone /net/tcp/stats /net/tcp/n /net/tcp/n/data /net/tcp/n/ctl /net/tcp/n/local /net/tcp/n/remote /net/tcp/n/status /net/tcp/n/listen </pre>
/net/icmp	

DESCRIPTION

The *ip* device provides the interface to Internet Protocol stacks. *Spec* is an integer starting from 0 identifying a stack. Each stack implements IPv4 and IPv6. Each stack is independent of all others: the only information transfer between them is via programs that mount multiple stacks. Normally a system uses only one stack. However multiple stacks can be used for debugging new IP networks or implementing firewalls or proxy services.

All addresses used are 16-byte IPv6 addresses. IPv4 addresses are a subset of the IPv6 addresses and both standard ASCII formats are accepted. In binary representation, all v4 addresses start with the 12 bytes, in hex:

00 00 00 00 00 00 00 00 00 00 ff ff

Configuring interfaces

Each stack may have multiple interfaces and each interface may have multiple addresses. The /net/ipifc directory contains a clone file, a stats file, and numbered subdirectories for each physical interface.

Opening the clone file reserves an interface. The file descriptor returned from the open(2) will point to the control file, ctl, of the newly allocated interface. Reading ctl returns a text string representing the number of the interface. Writing ctl alters aspects of the interface. The possible *ctl* messages are those described under Protocol directories below and these:

bind ether *path*

Treat the device mounted at *path* as an Ethernet medium carrying IP and ARP packets and associate it with this interface. The kernel will dial(2) path!0x800, path!0x86DD and path!0x806 and use the three connections for IPv4. IPv6 and ARP respectively.

Treat this interface as a packet interface. Assume a user program will read bind pkt and write the *data* file to receive and transmit IP packets to the kernel. This is used by programs such as ppp(8) to mediate IP packet transfer between the kernel and a PPP encoded device.

bind netdev path

Treat this interface as a packet interface. The kernel will open *path* and read and write the resulting file descriptor to receive and transmit IP packets.

bind loopback Treat this interface as a local loopback. Anything written to it will be looped back.

unbind Disassociate the physical device from an IP interface.

add local mask remote mtu proxy

try local mask remote mtu proxy

Add a local IP address to the interface. *Try* adds the *local* address as a tentative address if it's an IPv6 address. The *mask*, *remote*, *mtu*, and proxy arguments are all optional. The default *mask* is the class mask for the local address. The default *remote* address is *local* ANDed with *mask*. The default *mtu* (maximum transmission unit) is 1514 for Ethernet and 4096 for packet media. The *mtu* is the size in bytes of the largest packet that this interface can send. *Proxy*, if specified, means that this machine should answer ARP requests for the remote address. *Ppp*(8) does this to make remote machines appear to be connected to the local Ethernet. Adding the special null-address 0.0.0.0 or :: in *local* to a interface makes the ip stack accept all incoming connections regardless of the destination IP address. This is used temporarily by *ipconfig*(8) to accept DHCP answers when no IP address has been assigned yet. This can also be used to implement a NAT gateway by accepting all incoming connections and proxying them with *trampoline*(8) to a different ip stack.

remove *local mask*

Remove a local IP address from an interface.

- mtu *n* Set the maximum transfer unit for this device to *n*. The mtu is the maximum size of the packet including any medium-specific headers.
- speed *n* Set the maximum transmit speed in bits per second.
- delay *n* Set the maximum burst delay in milliseconds. (Default is 40ms) When speed has been set and packets in flight exceed the maximum burst delay then packets send on the interface are discarded until the load drops below the maximum.
- iprouting n Allow (n is missing or non-zero) or disallow (n is 0) forwarding packets between this interface and others.
- reflect *n* When forwarding, allow packets from this interface to be echoed back on the same interface.

reassemble *n* Reassemble IP fragments before forwarding to this interface

- bridge Enable bridging (see *bridge*(3)).
- promiscuous Set the interface into promiscuous mode, which makes it accept all incoming packets, whether addressed to it or not.
- connect *type* marks the Ethernet packet *type* as being in use, if not already in use on this interface. A *type* of -1 means 'all' but appears to be a no-op.
- addmulti *Media-addr*

Treat the multicast *Media-addr* on this interface as a local address.

```
remmulti Media-addr
```

Remove the multicast address *Media-addr* from this interface.

- scanbs Make the wireless interface scan for base stations.
- headersonly Set the interface to pass only packet headers, not data too.
- add6 v6addr pfx-len [onlink auto validlt preflt] Add the local IPv6 address v6addr with prefix length pfx-len to this interface.

See RFC 2461 §6.2.1 for more detail. The remaining arguments are optional:

- onlink flag: address is 'on-link'
- *auto* flag: autonomous
- validlt valid life-time in seconds
- preflt preferred life-time in seconds
- remove6 Remove local IPv6 addresses that have expired ther valid life-time.

ra6 keyword value ...

Set IPv6 router advertisement (RA) parameter *keyword*'s *value*. Known *keyword*s and the meanings of their values follow. See RFC 2461 §6.2.1 for more detail. Flags are true iff non-zero.

recvra flag: receive and process RAs. sendra flag: generate and send RAs. flag: "Managed address configuration", goes into RAs. mflag oflag flag: "Other stateful configuration", goes into RAs. "maximum time allowed between sending unsolicited multimaxraint cast" RAs from the interface, in ms. "minimum time allowed between sending unsolicited multiminraint cast" RAs from the interface, in ms. linkmtu "value to be placed in MTU options sent by the router." Zero indicates none. reachtime sets the Reachable Time field in RAs sent by the router. "Zero means unspecified (by this router)." sets the Retrans Timer field in RAs sent by the router. "Zero rxmitra means unspecified (by this router)." ttl default value of the Cur Hop Limit field in RAs sent by the router. Should be set to the "current diameter of the Internet." "Zero means unspecified (by this router)." sets the Router Lifetime field of RAs sent from the interface, in routerlt ms. Zero means the router is not to be used as a default router

Reading the interface's *status* file returns information about the interface. The first line is composed of white-space-separated fields, the first two fields are: device and maxmtu. Subsequent lines list the ip addresses assigned to that inferface. The colums are: ip address, network mask, network address and valid/preferred life times in milliseconds. See *readipifc* in *ip*(2).

Routing

The file *iproute* controls information about IP routing. When read, it returns one line per routing entry. Each line contains eight white-space-separated fields: target address, target mask, address of next hop, flags, tag, interface number, source address, source mask. The entry used for routing an IP packet is the one with the longest destination and source mask for which destination address ANDed with target mask equals the target and also the source ANDed with the source mask equals the source flags are:

- 4 IPv4 route
- 6 IPv6 route
- i local interface
- b broadcast address
- u local unicast address
- m multicast route
- p point-to-point route

The tag is an arbitrary, up to 4 character, string. It is normally used to indicate what routing protocol originated the route.

Writing to /net/iproute changes the route table. The messages are:

flush tag Remove routes of the specified tag, or all routes if tag is omitted.

tag string Associate the tag, string, with all subsequent routes added via this file descriptor.

add target mask nexthop

add target mask nexthop interface

- add target mask nexthop source smask
- add target mask nexthop interface source smask

add target mask nexthop tag interface source smask

add target mask nexthop type tag interface source smask

Add the route to the table. If one already exists with the same target and mask, replace it. The *interface* can be given as either the interface number or a local IP address on the desired interface.

remove target mask

remove target mask nexthop

remove target mask source smask

remove target mask nexthop source smask

remove target mask nexthop interface source smask

remove target mask nexthop tag interface source smask

remove target mask nexthop type tag interface source smask Remove the matching route.

Address resolution

The file /net/arp controls information about address resolution. The kernel automatically updates the v4 ARP and v6 Neighbour Discovery information for Ethernet interfaces. When read, the file returns one line per address containing the type of medium, the status of the entry (OK, WAIT), the IP address, the medium address and the IP address of the interface where the entry is valid. Writing to /net/arp administers the ARP information. The control messages are:

flush Remove all entries.

add type IP-addr Media-addr Interface-IP-addr

Add an entry or replace an existing one for the same IP address. The optional interface IP address specifies the interface where the ARP entry will be valid. This is needed for IPv6 link local addresses.

del *IP-addr* Delete an individual entry.

ARP entries do not time out. The ARP table is a cache with an LRU replacement policy. The IP stack listens for all ARP requests and, if the requester is in the table, the entry is updated. Also, whenever a new address is configured onto an Ethernet, an ARP request is sent to help update the table on other systems.

Currently, the only medium type is ether.

Debugging and stack information

If any process is holding /net/log open, the IP stack queues debugging information to it. This is intended primarily for debugging the IP stack. The information provided is implementation-defined; see the source for details. Generally, what is returned is error messages about bad packets.

Writing to /net/log controls debugging. The control messages are:

- set *arglist* Arglist is a space-separated list of items for which to enable debugging. The possible items are: ppp, ip, fs, tcp, il, icmp, udp, compress, ilmsg, gre, tcpwin, tcprxmt, udpmsg, ipmsg, and esp.
- clear arglist Arglist is a space-separated list of items for which to disable debugging.
- only *addr* If *addr* is non-zero, restrict debugging to only those packets whose source or destination is that address.

The file /net/ndb can be read or written by programs. It is normally used by *ipconfig*(8) to leave configuration information for other programs such as dns and cs (see *ndb*(8)). /net/ndb may contain up to 1024 bytes.

The file /net/ipselftab is a read-only file containing all the IP addresses considered local. Each line in the file contains three white-space-separated fields: IP address, usage count, and flags. The usage count is the number of interfaces to which the address applies. The flags are the same as for routing entries.

Protocol directories

The *ip* device supports IP as well as several protocols that run over it: TCP, UDP, RUDP, ICMP, IL, GRE, and ESP. TCP and UDP provide the standard Internet protocols for reliable stream and unreliable datagram communication. RUDP is a locally-developed reliable datagram protocol based on UDP. ICMP is IP's catch-all control protocol used to send low level error messages and to implement *ping*(8). GRE is a general encapsulation protocol. ESP is the encapsulation protocol for IPsec. IL provides a reliable datagram service for communication between Plan 9 machines but is now deprecated.

Each protocol is a subdirectory of the IP stack. The top level directory of each protocol contains a clone file, a stats file, and subdirectories numbered from zero to the number of connections opened for this protocol.

Opening the clone file reserves a connection. The file descriptor returned from the *open*(2) will point to the control file, ctl, of the newly allocated connection. Reading ctl returns a text string representing the number of the connection. Connections may be used either to listen for incoming calls or to initiate calls to other machines.

A connection is controlled by writing text strings to the associated ctl file. After a connection has been established data may be read from and written to data. A connection can be actively established using the connect message (see also dial(2)). A connection can be established passively by first using an announce message (see dial(2)) to bind to a local port and then opening the listen file (see dial(2)) to receive incoming calls.

The following control messages are supported:

connect ip-address! port!r local

Establish a connection to the remote *ip-address* and *port*. If *local* is specified, it is used as the local port number. If *local* is not specified but !r is, the system will allocate a restricted port number (less than 1024) for the connection to allow communication with Unix login and exec services. Otherwise a free port number starting at 5000 is chosen. The connect fails if the combination of local and remote address/port pairs are already assigned to another port.

- announce X X is a decimal port number or *. Set the local port number to X and accept calls to X. If X is *, accept calls for any port that no process has explicitly announced. The local IP address cannot be set. Announce fails if the connection is already announced or connected.
- bind X X is a decimal port number or *. Set the local port number to X. This exists to support emulation of BSD sockets by the APE libraries (see *pcc*(1)) and is not otherwise used.
- ttl *n* Set the time to live IP field in outgoing packets to *n*.

tos *n* Set the service type IP field in outgoing packets to *n*.

ignoreadvice

Don't break (UDP) connections because of ICMP errors.

addmulti ifc-ip [mcast-ip]

Treat *ifc-ip* on this multicast interface as a local address. If *mcast-ip* is present, use it as the interface's multicast address.

remmulti *ip* Remove the address *ip* from this multicast interface.

Port numbers must be in the range 1 to 32767.

Several files report the status of a connection. The remote and local files contain the IP address and port number for the remote and local side of the connection. The status file contains protocol-dependent information to help debug network connections. On receiving and error or EOF reading or writing the data file, the err file contains the reason for error.

A process may accept incoming connections by *open*(2)ing the listen file. The open will block until a new connection request arrives. Then open will return an open file descriptor which points to the control file of the newly accepted connection. This procedure will accept all calls for the given protocol. See *dial*(2).

ТСР

TCP connections are reliable point-to-point byte streams; there are no message delimiters. A connection is determined by the address and port numbers of the two ends. TCP ctl files support the following additional messages:

hangup close down this TCP connection

close graceful hangup

- keepalive *n* turn on keep alive messages. *N*, if given, is the milliseconds between keepalives (default 30000).
- checksum n emit TCP checksums of zero if n is zero; otherwise, and by default, TCP checksums are computed and sent normally.

tcpporthogdefense *onoff*

onoff of on enables the TCP port-hog defense for all TCP connections; onoff of off disables it. The defense is a solution to hijacked systems staking out ports as a form of denial-of-service attack. To avoid stateless TCP conversation hogs, *ip* picks a TCP sequence number at random for keepalives. If that number gets acked by the other end, *ip* shuts down the connection. Some firewalls, notably ones that perform stateful inspection, discard such out-of-specification keepalives, so connections through such firewalls will be killed after five minutes by the lack of keepalives.

UDP

UDP connections carry unreliable and unordered datagrams. A read from data will return the next datagram, discarding anything that doesn't fit in the read buffer. A write is sent as a single datagram.

By default, a UDP connection is a point-to-point link. Either a connect establishes a local and remote address/port pair or after an announce, each datagram coming from a different remote address/port pair establishes a new incoming connection. However, many-to-one semantics is also possible.

If, after an announce, the message headers is written to ctl, then all messages sent to the announced port are received on the announced connection prefixed with the corresponding structure, declared in <ip.h>:

```
typedef struct Udphdr Udphdr;
struct Udphdr
{
               raddr[16];
                              /* V6 remote address and port */
     uchar
     uchar
               laddr[16];
                              /* V6 local address and port */
     uchar
                              /* V6 interface address (receive only) */
               ifcaddr[16];
     uchar
               rport[2]; /* remote port */
     uchar
               lport[2]: /* local port */
}:
```

Before a write, a user must prefix a similar structure to each message. The system overrides the user specified local port with the announced one. If the user specifies an address that isn't a unicast address in /net/ipselftab, that too is overridden. Since the prefixed structure is the same in read and write, it is relatively easy to write a server that responds to client requests by just copying new data into the message body and then writing back the same buffer that was read.

In this case (writing headers to the *ctl* file), no *listen* nor *accept* is needed; otherwise, the usual sequence of *announce*, *listen*, *accept* must be executed before performing I/O on the corresponding *data* file.

RUDP

RUDP is a reliable datagram protocol based on UDP, currently only for IPv4. Packets are delivered in order. RUDP does not support listen. One must write either connect or announce followed immediately by headers to ctl.

Unlike TCP, the reboot of one end of a connection does not force a closing of the connection. Communications will resume when the rebooted machine resumes talking. Any unacknowledged packets queued before the reboot will be lost. A reboot can be detected by reading the err file.

It will contain the message

hangup address ! port

where *address* and *port* are of the far side of the connection. Retransmitting a datagram more than 10 times is treated like a reboot: all queued messages are dropped, an error is queued to the err file, and the conversation resumes.

RUDP *ctl* files accept the following messages:

headers	Corresponds to the headers format of UDP.	
hangup <i>IP port</i>	Drop the connection to address <i>IP</i> and <i>port</i> .	
<pre>randdrop [percent]</pre>	Randomly drop <i>percent</i> of outgoing packets.	Default is 10%.

ICMP

ICMP is a datagram protocol for IPv4 used to exchange control requests and their responses with other machines' IP implementations. ICMP is primarily a kernel-to-kernel protocol, but it is possible to generate 'echo request' and read 'echo reply' packets from user programs.

ICMPV6

ICMPv6 is the IPv6 equivalent of ICMP. If, after an announce, the message headers is written to ctl, then before a write, a user must prefix each message with a corresponding structure, declared in <ip.h>:

```
/*
 * user level icmpv6 with control message "headers"
 */
typedef struct Icmp6hdr Icmp6hdr;
struct Icmp6hdr {
    uchar unused[8];
    uchar laddr[IPaddrlen]; /* local address */
    uchar raddr[IPaddrlen]; /* remote address */
};
```

In this case (writing headers to the *ctl* file), no *listen* nor *accept* is needed; otherwise, the usual sequence of *announce*, *listen*, *accept* must be executed before performing I/O on the corresponding *data* file.

IL

IL is a reliable point-to-point datagram protocol that runs over IPv4. Like TCP, IL delivers datagrams reliably and in order. Also like TCP, a connection is determined by the address and port numbers of the two ends. Like UDP, each read and write transfers a single datagram.

IL is efficient for LANs but doesn't have the congestion control features needed for use through the Internet. It is no longer necessary, except to communicate with old standalone fs(4) file servers. Its use is now deprecated.

GRE

GRE is the encapsulation protocol used by PPTP. The kernel implements just enough of the protocol to multiplex it. Our implementation encapsulates in IPv4, per RFC 1702. Announce is not allowed in GRE, only connect. Since GRE has no port numbers, the port number in the connect is actually the 16 bit eproto field in the GRE header.

Reads and writes transfer a GRE datagram starting at the GRE header. On write, the kernel fills in the eproto field with the port number specified in the connect message.

ESP

ESP is the Encapsulating Security Payload (RFC 1827, obsoleted by RFC 4303) for IPsec (RFC 4301). We currently implement only tunnel mode, not transport mode. It is used to set up an encrypted tunnel between machines. Like GRE, ESP has no port numbers. Instead, the port number in the connect message is the SPI (Security Association Identifier (sic)). IP packets are written to and read from data. The kernel encrypts any packets written to data, appends a MAC, and prefixes an ESP header before sending to the other end of the tunnel. Received packets are checked against their MAC's, decrypted, and queued for reading from data. In the following, *secret* is the hexadecimal encoding of a key, without a leading 0x. The control messages are:

esp <i>alg secret</i>	Encrypt with the algorithm, <i>alg</i> , using <i>secret</i> as the key. Possible algorithms are: null, des_56_cbc, des3_cbc, and eventually aes_128_cbc, and aes_ctr.
ah <i>alg secret</i>	Use the hash algorithm, <i>alg</i> , with <i>secret</i> as the key for generating the MAC. Possible algorithms are: null, hmac_sha1_96, hmac_md5_96, and eventually aes_xcbc_mac_96.
header	Turn on header mode. Every buffer read from data starts with 4 unused bytes, and the first 4 bytes of every buffer written to data are ignored.
noheader	Turn off header mode.

IP packet filter

The directory /net/ipmux looks like another protocol directory. It is a packet filter built on top of IP. Each numbered subdirectory represents a different filter. The connect messages written to the *ctl* file describe the filter. Packets matching the filter can be read on the data file. Packets written to the data file are routed to an interface and transmitted.

A filter is a semicolon-separated list of relations. Each relation describes a portion of a packet to match. The possible relations are:

ver=n	the IP version must be <i>n</i> .
proto= <i>n</i>	the IP protocol number must be <i>n</i> .
<pre>data[n:m]=expr</pre>	bytes <i>n</i> through <i>m</i> following the IP header must match <i>expr</i> .
<pre>iph[n:m]=expr</pre>	bytes <i>n</i> through <i>m</i> of the IP packet header must match <i>expr</i> .
ifc= <i>expr</i>	the packet must have been received on an interface whose address matches <i>expr</i> .
<pre>src=expr</pre>	The source address in the packet must match <i>expr</i> .
dst= <i>expr</i>	The destination address in the packet must match <i>expr</i> .

Expr is of the form:

value

value | value | ...

value&mask

value | value&mask

If a mask is given, the relevant field is first ANDed with the mask. The result is compared against the value or list of values for a match. In the case of ifc, dst, and src the value is a dot-formatted IP address and the mask is a dot-formatted IP mask. In the case of data, iph and proto, both value and mask are strings of 2 hexadecimal digits representing 8-bit values.

A packet is delivered to only one filter. The filters are merged into a single comparison tree. If two filters match the same packet, the following rules apply in order (here '>' means is preferred to):

- 1) protocol > data > source > destination > interface
- 2) lower data offsets > higher data offsets
- 3) longer matches > shorter matches
- 4) older > younger

So far this has just been used to implement a version of OSPF in Inferno and 6to4 tunnelling.

Statistics

The stats files are read only and contain statistics useful to network monitoring.

Reading /net/ipifc/stats returns a list of 19 tagged and newline-separated fields representing:

forwarding status (0 and 2 mean forwarding off,	output packets
1 means on)	output packets discarded
default TTL	output packets with no route
input packets	timed out fragments in reassembly queue
input header errors	requested reassemblies
input address errors	successful reassemblies
packets forwarded	failed reassemblies
input packets for unknown protocols	successful fragmentations
input packets discarded	unsuccessful fragmentations
input packets delivered to higher level protocols	fragments created

Reading /net/icmp/stats returns a list of 26 tagged and newline-separated fields representing:

messages received bad received messages unreachables received time exceededs received input parameter problems received source quenches received redirects received echo requests received echo replies received timestamps received timestamp replies received address mask requests received messages sent transmission errors unreachables sent time exceededs sent input parameter problems sent source quenches sent redirects sent echo requests sent echo replies sent timestamps sent timestamp replies sent address mask requests sent address mask replies sent

Reading /net/tcp/stats returns a list of 11 tagged and newline-separated fields representing:

maximum number of connections	segments sent
total outgoing calls	segments retransmitted
total incoming calls	retransmit timeouts
number of established connections to be reset number of currently established connections segments received	bad received segments transmission failures
Reading /net/udp/stats returns a list of 4 tagge datagrams received	d and newline-separated fields i malformed datagrams receiv

datagrams received for bad ports

and newline-separated fields representing: malformed datagrams received datagrams sent

Reading /net/il/stats returns a list of 6 tagged and newline-separated fields representing:
checksum errorsretransmitted messagesheader length errorsduplicate messagesout of order messagesduplicate bytes

Reading /net/gre/stats returns a list of 1 tagged number representing: header length errors

SEE ALSO

dial(2), ip(2), bridge(3), ndb(6), listen(8)
/lib/rfc/rfc2460 IPv6
/lib/rfc/rfc4291 IPv6 address architecture
/lib/rfc/rfc4443 ICMPv6

SOURCE

/sys/src/9/ip

BUGS

Ipmux has not been heavily used and should be considered experimental. It may disappear in favor of a more traditional packet filter in the future.

IP(3)

kbd - pc keyboard driver

SYNOPSIS

bind -a #b /dev

/dev/scancode /dev/leds

DESCRIPTION

The *kbd* device serves a one-level directory containing the files scancode and leds.

Reading the scancode file returns the raw scancode stream as it is emitted by the keyboard device without any translation. It is usually *kbdfs*(8) task to interpret the scancodes and provide device independent keyboard input to programs. The scancode file can be only opened once by the hostowner.

Writing a number to the write-only leds file changes the status leds on the keyboard. the value of the number is the addition of 1, 2 and 4 representing activated Scroll, Num and Caps leds.

EXAMPLE

Set the Scroll and Caps leds: echo 5 >/dev/leds

SEE ALSO

kbdfs(8)

SOURCE

/sys/src/9/pc/devkbd.c

kprof – kernel profiling

SYNOPSIS

bind -a #K /dev

/dev/kpctl /dev/kpdata

DESCRIPTION

The *kprof* device provides simple profiling data for the operating system kernel. The data accumulates by recording the program counter of the kernel at each 'tick' of the system clock.

The file kpdata holds the accumulated counts as 4-byte integers in big-endian byte order. The size of the file depends on the size of kernel text. The first count holds the total number of clock ticks during profiling; the second the number of ticks that occurred while the kernel was running. The rest each hold the number of ticks the kernel program counter was within the corresponding 8-byte range of kernel text, starting from the base of kernel text.

The file kpctl controls profiling. Writing the string start to kpctl begins profiling; stop terminates it. The message startclr restarts profiling after zeroing the array of counts.

The program *kprof* (see *prof*(1)) formats the data for presentation.

EXAMPLE

The following rc(1) script runs a test program while profiling the kernel and reports the results.

```
bind -a '#K' /dev
echo start > /dev/kpctl
runtest
echo stop > /dev/kpctl
kprof /386/9pcdisk /dev/kpdata
```

SOURCE

/sys/src/9/port/devkprof.c

SEE ALSO

prof(1)

loopback - network link simulation

SYNOPSIS

bind –a # λ /net

/net/loopbackn/[0-1]
/net/loopbackn/[0-1]/data
/net/loopbackn/[0-1]/ctl
/net/loopbackn/[0-1]/status
/net/loopbackn/[0-1]/stats

DESCRIPTION

The loopback interface, /net/loopback n, is a directory containing two subdirectories, one for each end of a simulated network link. The number n is the device number of the link, permitting multiple links to be used on a single machine.

Each directory contains files to control the associated connection, receive and send data, monitor the simulation parameters, and supply statistics.

The data files for the two directories are cross-connected. Writes to one are divided into packets of at most a certain size, typically 32768 bytes, written to a flow-controlled output queue, transferred across the link, and put into an input queue where it is readable from the other data file.

Options are set by writing to the ctl file for the receiving end of the link, and are reported in the same format by reading status. The following options are supported.

delay latency bytedelay

Control the time a packet takes in the link. A packet n bytes long takes bytedelay * n nanoseconds to exit the output queue and is available for reading *latency* nanoseconds later.

droprate n

Randomly drop approximately one out of n packets. If zero drop no packets.

indrop[01]

Disallow or allow packets to be dropped if the input queue overflows.

limit n

Set the input and output queues to hold at most *n* bytes.

reset

Clear all of the statistics recorded for the link.

Reading stats returns a list of 4 tagged numbers representing:

packets sent to this receiver bytes sent to this receiver packets dropped due to droprate packets dropped due to input queue overflows

SOURCE

/sys/src/9/port/devloopback.c

lpt - parallel port interface for PC's

SYNOPSIS

bind -a #L[123] /dev

/dev/lpt[123]data /dev/lpt[123]dlr /dev/lpt[123]pcr /dev/lpt[123]psr

DESCRIPTION

The *lpt* driver provides an interface to the parallel interface normally used for printers. The specifiers 1, 2, and 3 correspond to the parallel interfaces at PC ports 0x3bc, 0x378, and 0x278 respectively.

Lpt?data is write only. Writing to it sends data to the interface. This file is sufficient for communicating with most printers.

Lpt?dlr, lpt?pcr, and lpt?psr are used for fine control of the parallel port. Reading or writing these files corresponds to reading and writing the data latch register, printer control register, and printer status register. These are used by programs to drive special devices.

SOURCE

/sys/src/9/pc/devlpt.c

mnt - attach to 9P servers

SYNOPSIS

#M

DESCRIPTION

The *mount driver* is used by the mount system call (but not bind; see *bind*(2)) to connect the name space of a process to the service provided by a 9P server over a communications channel. After the mount, system calls involving files in that portion of the name space will be converted by the mount driver into the appropriate 9P messages to the server.

The *mount* system call issues *session* and *attach*(5) messages to the server to identify and validate the user of the connection. Each distinct user of a connection must mount it separately; the mount driver multiplexes the access of the various users and their processes to the service.

File-oriented system calls are converted by the kernel into messages in the 9P protocol. Within the kernel, 9P is implemented by procedure calls to the various kernel device drivers. The mount driver translates these procedure calls into remote procedure calls to be transmitted as messages over the communication channel to the server. Each message is implemented by a write of the corresponding protocol message to the server channel followed by a read on the server channel to get the reply. Errors in the reply message are turned into system call error returns.

A *read*(2) or *write* system call on a file served by the mount driver may be translated into more than one message, since there is a maximum data size for a 9P message. The system call will return when the specified number of bytes have been transferred or a short reply is returned.

The string #M is an illegal file name, so this device can only be accessed directly by the kernel.

SEE ALSO

bind(2)

SOURCE

/sys/src/9/port/devmnt.c

BUGS

When mounting a service through the mount driver, that is, when the channel being multiplexed is itself a file being served by the mount driver, large messages may be broken in two.

mouse, cursor - kernel mouse interface

SYNOPSIS

bind -a #m /dev

/dev/mouse /dev/mousein /dev/mousectl /dev/cursor

DESCRIPTION

The *mouse* device provides an interface to the mouse. There is also a cursor associated with the screen; it is always displayed at the current mouse position.

Reading the mouse file returns the mouse status: its position and button state. The read blocks until the state has changed since the last read. The read returns 49 bytes: the letter m followed by four decimal strings, each 11 characters wide followed by a blank: x and y, coordinates of the mouse position in the screen image; *buttons*, a bitmask with the 1, 2, and 4 bits set when the mouse's left, middle, and right buttons, respectively, are down; and *msec*, a time stamp, in units of milliseconds.

Writing the mouse file, in the same format, causes the mouse cursor to move to the position specified by the x and y coordinates of the message. The *buttons* and *msec* fields are ignored and may be omitted.

Writes to the mousein file are processed as if they were generated by the mouse hardware itself, as extra mouse events to be processed and passed back via the mouse file. The mousein file, which is exclusive-use and may be opened only by the host owner, is intended for controlling devices, such as USB mice, that are managed by user-level software. Each event should consist of the letter m followed by delta x, delta y, and buttons as space-separated decimal numbers.

Writing to the mousectl file configures and controls the mouse. The messages are:

<pre>serial n ps2 intellimouse ps2intellimouse accelerated [n] linear res n hwaccel on/off</pre>	<pre>sets serial port n to be the mouse port. sets the PS2 port to be the mouse port. uses the wheel on a Microsoft Intellimouse as the middle button. is equivalent to a write of ps2 followed by a write of intellimouse. turns on mouse acceleration. N is an optional acceleration factor. turns off mouse acceleration. sets mouse resolution to a setting between 0 and 3 inclusive. sets whether acceleration is done in hardware or software. By default, PS2 mice use hardware and serial mice use software. Some laptops (notably the IBM Thinkpad T23) don't implement hardware acceleration for external mice.</pre>
swap buttonmap <i>xyz</i>	swaps the left and right buttons on the mouse. numbers the left, middle, and right mouse buttons x , y , and z , respec- tively. If xyz is omitted, the default map, 123, is used. Thus in the default state writing buttonmap 321 swaps left and right buttons and writing buttonmap 123 or just buttonmap restores their usual meaning. Note that buttonmap messages are idempotent, unlike
scrollswap	swap. inverts the scroll wheel.
reset	clears the mouse to its default state.
blank	blanks the screen. The screen also blanks after 30 minutes of inactivity.
blanktime <i>minutes</i> twitch	The screen can be unblanked by moving the mouse. sets the timeout before the screen blanks; the default is 30 minutes. If <i>minutes</i> is zero, blanking is disabled. unblanks the screen and resets the idle timeout as if the mouse was twitched.

Not all mice interpret all messages; with some devices, some of the messages may be no-ops.

Cursors are described in *graphics*(2). When read or written from or to the cursor file, they are represented in a 72-byte binary format. The first and second four bytes are little endian 32-bit numbers specifying the x and y coordinates of the cursor *offset*; the next 32 bytes are the clr bit-mask, and the last 32 bytes the set bitmask.

Reading from the cursor file returns the current cursor information. Writing to the cursor file sets the current cursor information. A write of fewer than 72 bytes sets the cursor to the default, an arrow.

The mouse and cursor files are multiplexed by rio(1) to give the illusion of a private mouse to each of its clients. The semantics are otherwise the same except that notification of a window resize is passed to the application using a mouse message beginning with r rather than m; see rio(4) for details.

To cope with pointing devices with only two buttons, when the shift key is pressed, the right mouse button generates middle-button events.

SOURCE

/sys/src/9/port/devmouse.c

SEE ALSO

rio(4)

BUGS

The cursor format is big endian while the rest of the graphics interface is little endian.

pipe - two-way interprocess communication

SYNOPSIS

bind #| dir

*dir/*data *dir/*data1

DESCRIPTION

An attach(5) of this device allocates two new cross-connected I/O streams, dir/data and dir/data1.

Data written to one channel becomes available for reading at the other. Write boundaries are preserved: each read terminates when the read buffer is full or after reading the last byte of a write, whichever comes first.

Writes are atomic up to a certain size, typically 32768 bytes, that is, each write will be delivered in a single read by the recipient, provided the receiving buffer is large enough.

If there are multiple writers, each *write* is guaranteed to be available in a contiguous piece at the other end of the pipe. If there are multiple readers, each read will return data from only one write.

The *pipe*(2) system call performs an *attach* of this device and returns file descriptors to the new pipe's data and data1 files. The files are open with mode ORDWR.

SEE ALSO

pipe(2)

SOURCE

/sys/src/9/port/devpipe.c

pnp - Plug 'n' Play ISA and PCI Interfaces

SYNOPSIS

bind -a '#\$' /dev /dev/pci/bus.dev.fnctl /dev/pci/bus.dev.fnraw /dev/pnp/ctl /dev/pnp/csnnctl /dev/pnp/csnnraw ...

DESCRIPTION

This device provides a limited interface to the PCI bus and Plug 'n' Play ISA devices.

PCI Interface

PCI devices are addressed logically by a bus number, a device number on that bus, and a function number within the device. The set of all such device functions may be enumerated by traversing the /dev/pci directory; the driver serves two files for each function. These are a control file (/dev/pci/bus.dev.fnctl) which may be read for a textual summary of the device function, and a 'raw' file (/dev/pci/bus.dev.fnraw) which may be used to read or write the raw contents of PCI configuration space.

The first field of a PCI control file contains the class, sub-class and programming interface values for the device function, expressed as 2-digit hexadecimal values, and separated by periods. The second field yields the vendor ID and device ID, each as 4-digit hex numbers, separated by a slash. The third field is the associated interrupt line in decimal. The remainder of the line enumerates any valid base address registers for the function, using two fields for each. In the first field, the index of the register is followed by a colon, and then the value of the register itself. The following field gives the associated size of the memory (or I/O space) that is mapped by the register.

Plug 'n' Play

Plug 'n' Play ISA devices are discovered by sending a fixed 'unlock' sequence over an I/O port, and then reading back data from another port. An arbitration algorithm is used to separate out the individual cards and enumerate them in turn. Each card is assigned a unique number, called a CSN, in the range 1–255 as a result of enumeration. Cards also have a fixed 64 bit identification number, set by the manufacturer, which is used by the arbitration algorithm to resolve conflicts. The first 32 bits describe the type of the card, and the second 32 bits form a serial number for the particular instance of that card type. When formatted textually, it appears as 3 upper-case letters (typically representing the manufacturer), followed by 4 hex digits, then a period, then 8 hex digits. The substring before the period is the card type, and the substring after the period is the serial number.

The enumeration algorithm needs to be enabled by specifying the port number to write the unlock sequence out on. This can be configured to take place at boot time by adding a line like the following to *plan9.ini*:

pnp0=port=0x203

Here port should be chosen to not conflict with any existing devices. It must be in the range 0x203-0x3ff. Alternatively, one can use the following command:

echo port 0x203 >/dev/pnp/ctl

Note that a side-effect of PnP enumeration is to reset the configuration state of all such cards; any settings made by a Plug and Play BIOS will be lost. Reading the file /dev/pnp/ctl returns one of the strings enabled *port* or disabled.

For each enumerated card, two files are served in /dev/pnp. A control file (/dev/pnp/csnnctl) may be read to determine the ID of the card, and a raw file (/dev/pnp/csnnraw) may be read to obtain the configuration data associated with the card. It is intended that the control file should take commands which set the various configurable resources of the card, but this has not been implemented yet.

A mechanism is provided for configuring cards via *plan9.ini*(8). A line of the form pnpn=idstring ... will cause the driver to look for the card named by *idstring* and, if found, assign it the CSN *n*. The intention is that any additional text after the idstring is interpreted as if it was written to the card's ctl file, but this is not yet implemented.

EXAMPLES

To list all PCI functions:

cat /dev/pci/*ctl

To find just the PCI video card (class 3):

grep '^03' /dev/pci/*ctl

SOURCE

/sys/src/9/port/devpnp.c

SEE ALSO

pci(8)

BUGS

Access to the I/O and memory regions of a PCI device is not provided.

The ability to set a Plug 'n' Play card's configurable settings has not been implemented. There should be a user program for identifying and configuring Plug 'n' Play cards.

proc – running processes

SYNOPSIS

bind #p /proc /proc/trace /proc/n/args /proc/n/ctl /proc/n/fd /proc/n/fpregs /proc/n/kregs /proc/n/mem /proc/*n*/note /proc/n/noteid /proc/n/notepg /proc/n/ns /proc/n/proc /proc/n/profile /proc/n/regs /proc/n/segment /proc/n/status /proc/n/text /proc/n/wait

...

DESCRIPTION

The *proc* device serves a two-level directory structure. The first level contains the trace file (see below) and numbered directories corresponding to pids of live processes; each such directory contains a set of files representing the corresponding process.

The mem file contains the current memory image of the process. A read or write at offset o, which must be a valid virtual address, accesses bytes from address o up to the end of the memory segment containing o. Kernel virtual memory, including the kernel stack for the process and saved user registers (whose addresses are machine-dependent), can be accessed through mem. Writes are permitted only while the process is in the Stopped state and only to user addresses or registers.

The read-only proc file contains the kernel per-process structure. Its main use is to recover the kernel stack and program counter for kernel debugging.

The files regs, fpregs, and kregs hold representations of the user-level registers, floating-point registers, and kernel registers in machine-dependent form. The kregs file is read-only.

The read-only fd file lists the open file descriptors of the process. The first line of the file is its current directory; subsequent lines list, one per line, the open files, giving the decimal file descriptor number; whether the file is open for read (\mathbf{r}), write, (\mathbf{w}), or both (\mathbf{rw}); the type, device number, and qid of the file; its I/O unit (the amount of data that may be transferred on the file as a contiguous piece; see *iounit*(2)), its I/O offset; and its name at the time it was opened.

The read-only ns file contains a textual representation of the process's file name space, in the format of *namespace*(6) accepted by newns (see *auth*(2)). The last line of the file identifies the current working directory of the process, in the form of a cd command (see rc(1)). The information in this file is based on the names files had when the name space was assembled, so the names it contains may be inaccessible if the files have been subsequently renamed or rearranged.

The read-only segment file contains a textual display of the memory segments attached to the process. Each line has multiple fields: the type of segment (Stack, Text, Data, Bss, etc.); one-letter flags such as R for read-only, if any; starting virtual address, in hexadecimal; ending virtual address, and reference count.

The read-only status file contains a string with twelve fields, each followed by a space. The fields are:

- the process name and user name, each 27 characters left justified
- the process state, 11 characters left justified (see *ps*(1))
- the six 11-character numbers also held in the process's #c/cputime file
- the amount of memory used by the process in units of 1024 bytes
- the base and current scheduling priority, each 11 character numbers

The args file contains the arguments of the program when it was created by exec(2). Writing to the args file will overwrite its contents. If the program was not created by exec, such as by fork(2), its args file will be empty. The format of the file is a list of quoted strings suitable for tokenize; see getfields(2).

The text file is a pseudonym for the file from which the process was executed; its main use is to recover the symbol table of the process.

The wait file may be read to recover records from the exiting children of the process in the format of await (see *wait*(2)). If the process has no extant children, living or exited, a read of wait will block. It is an error for a process to attempt to read its own wait file when it has no children. When a process's wait file is being read, the process will draw an error if it attempts an await system call; similarly, if a process is in an await system call, its wait file cannot be read by any process.

The read-only profile file contains the instruction frequency count information used for multiprocess profiling; see tprof in prof(1). The information is gleaned by sampling the program's user-level program counter at interrupt time.

Strings written to the note file will be posted as a note to the process (see notify(2)). The note should be less than ERRLEN-1 characters long; the last character is reserved for a terminating NUL character. A read of at least ERRLEN characters will retrieve the oldest note posted to the process and prevent its delivery to the process. The notepg file is similar, but the note will be delivered to all the processes in the target process's *note group* (see *fork*(2)). However, if the process doing the write is in the group, it will not receive the note. The notepg file is write-only.

The textual noteid file may be read to recover an integer identifying the note group of the process (see RFNOTEG in fork(2)). The file may be written to cause the process to change to another note group, provided the group exists and is owned by the same user.

The file /proc/trace can be opened once and read to see trace events from processes that have had the string trace written to their ctl file. Each event produces, in native machine format, the *pid*, a *type*, and a *time stamp* (see /sys/include/trace.h and /sys/src/cmd/trace.c).

The watchpt file contains a list of the watchpoints set for the process. If supported by the hardware, watchpoints can be used to trap accesses to specific addresses. Each line in the file has the form "type address length", where type consists of the characters r (read), w (write), x (execute) or – (padding character). The watchpoint triggers on an access to the length bytes starting at address if the type of the access must match one of the characters in the type field.

Writing to the file either replaces (offset zero) or adds to (offset non-zero) the list of watchpoints. Each line written must be terminated by a newline. If and only if all lines written comply with the (usually rather idiosyncratic) hardware restrictions, the list is updated; otherwise all changes are discarded. Watchpoints can also be cleared by opening the file with OTRUNC (see *open*(2)).

A triggered watchpoint will deliver a sys: watchpoint note which includes a commaseparated list of the watchpoints that were triggered, where 0 corresponds to the first line in the watchpt file, 1 to the second and so forth.

Control messages

Textual messages written to the ctl file control the execution of the process. Some require that the process is in a particular state and return an error if it is not.

stop Suspend execution of the process, putting it in the Stopped state.

start Resume execution of a Stopped process.

waitstop

Do not affect the process directly but, like all other messages ending with stop, block

the process writing the ctl file until the target process is in the Stopped state or exits. Also like other stop control messages, if the target process would receive a note while the message is pending, it is instead stopped and the debugging process is resumed.

startstop

Allow a Stopped process to resume, and then do a waitstop action.

- hang Set a bit in the process so that, when it completes an *exec*(2) system call, it will enter the Stopped state before returning to user mode. This bit is inherited across *fork*(2) and *exec*(2).
- nohang Clear the hang bit.
- private

Make it impossible to read the process's user memory. This property is inherited on fork(2), cleared on exec(2), and is not otherwise resettable.

- noswap Don't allow this process to be swapped out. This should be used carefully and sparingly or the system could run out of memory. It is meant for processes that can't be swapped, like the local fileserver implementing the swap device and for processes containing sensitive data. This property is inherited on *fork*(2), cleared on *exec*(2), and is not otherwise resettable.
- kill Kill the process the next time it crosses the user/kernel boundary.

close n

Close file descriptor *n* in the process.

closefiles

Close all open file descriptors in the process.

- pri *n* Set the base priority for the process to the integer *n*.
- wired n

Wire the process to processor *n*.

trace Without an argument, toggle trace event generation for this process into /proc/trace (see below). With a zero argument, tracing for the proc is turned off, with a non-zero numeric argument, it is turned on.

interrupt

Interrupt a blocking system call. If no blocking call was in progress, the interrupt will be pending and the next attempt to block will be interrupted. This is similar to posting a note but, unlike notes, a pending interrupt is not cleared when crossing the user/kernel boundary.

nointerrupt

Clear a pending interrupt.

period nu

Set the real-time scheduling period of the process to nu, where n is an optionally signed number containing an optional decimal point and u is one of s, ms, us, μ s, ns, or empty. The time is interpreted, respectively, as *seconds*, *milliseconds*, *microseconds*, *microseconds*, *nanoseconds*, or, in the case of an absent units specifier, as *nanoseconds*. If the time specifier is signed, it is interpreted as an increment or decrement from a previously set value. See also the admit command below.

deadline nu

Set the real-time deadline interval of the process to *nu*, where *n* and *u* are interpreted as for period above.

cost nu

Set the real-time cost (maximum CPU time per period) of the process to *nu*, where *n* and *u* are interpreted as for period above.

sporadic

Use sporadic scheduling for the real-time process. The description of the admit command below contains further details.

yieldonblock

Make the real-time process yield on blocking I/O. The description of the admit command below contains further details.

admit Given real-time *period*, *deadline* and *cost* are set (an unset *deadline* will set *deadline* to *period*), perform a schedulability test and start scheduling the process as a real-time process if the test succeeds. If the test fails, the write will fail with error set to the reason for failure.

event Add a user event to the /proc/trace file.

Real-time scheduling

Real-time processes are periodically *released*, giving them a higher priority than non-real-time processes until they either give up the processor voluntarily, they exhaust their CPU allocation, or they reach their *deadline*. The moment of release is dictated by the *period* and whether the process is *sporadic* or not. Non-sporadic processes are called *periodic* and they are released precisely at intervals of their period (but periods can be skipped if the process blocks on I/O). Sporadic processes are released whenever they become runnable (after being blocked by *sleep*() or I/O), but always at least an interval of *period* after the previous release.

The *deadline* of a real-time process specifies that the process must complete within the first *deadline* seconds of its *period*. The dealine must be less than or equal to the period. If it is not specified, it is set to the period.

The *cost* of a real-time process describes the maximum CPU time the process may use per period.

A real-time process can give up the CPU before its deadline is reached or its allocation is exhausted. It does this by calling *sleep*(0). If *yieldonblock* is specified, it also does it by executing any blocking system call. *Yieldonblock* is assumed for *sporadic* processes.

Of the released processes, the one with the earliest deadline has the highest priority. Care should be taken using spin locks (see lock(2)) because a real-time process spinning on a lock will not give up the processor until its CPU allocation is exhausted; this is unlikely to be the desired behavior.

When a real-time process reaches its deadline or exhausts its CPU allocation, it remains schedulable, but at a very low priority.

The priority is interpreted by Plan 9's multilevel process scheduler. Priorities run from 0 to 19, with higher numbers representing higher priorities. A process has a base priority and a running priority which is less than or equal to the base priority. As a process uses up more of its allocated time, its priority is lowered. Unless explicitly set, user processes have base priority 10, kernel processes 13. Children inherit the parent's base priority.

FILES

```
/sys/src/9/*/mem.h
/sys/src/9/*/dat.h
/sys/include/trace.h
```

SEE ALSO

trace(1), debugger(2), mach(2), cons(3)

SOURCE

/sys/src/9/port/devproc.c

root - the root file system

SYNOPSIS

/ /boot /dev /env /net /net.alt /proc /root /srv

DESCRIPTION

The syntax #/ is illegal, so this device can only be accessed directly by the kernel.

This device is set up by the kernel to be the root of the name space. The names in the one-level tree are mostly just place-holders, to allow a place to bind(2) to. The exception is /boot, which contains /boot/boot and any files /boot/boot might need. The kernel does an *exec*(2) of /boot/boot when initializing.

SOURCE

/sys/src/9/port/devroot.c

rtc - real-time clock and non-volatile RAM

SYNOPSIS

bind #r /dev

/dev/rtc /dev/nvram

DESCRIPTION

The rtc device supports devices with real-time clocks and non-volatile RAM.

The rtc file behaves just like /dev/time (see *cons*(3)). The real-time clock is maintained on-board; /dev/time is set from the file server. Neither is necessarily more accurate.

The nvram file provides (if permission allows) access to the local non-volatile RAM. For example, boot(8) reads the machine's key from there (see auth(8)).

SEE ALSO

auth(8), boot(8)

SOURCE

/sys/src/9/*/devrtc.c

sd – storage device interface

SYNOPSIS

bind #S /dev

```
/dev/sdctl
/dev/sdCu/ctl
/dev/sdCu/raw
/dev/sdCu/data
```

DESCRIPTION

The storage device interface serves a two-level directory giving access to multiple storage units, typically ATA(PI) or SCSI discs. Each unit is accessed via files in the directory named by the controller to which it is attached, *C*, and by its unit number *u*. The controller naming convention for ATA(PI) units starts with the first controller being named C, the second D, etc. up to a maximum of 4 controllers ([C-F]); legacy controllers are always 'C' and 'D'. There can be a maximum of 2 units per ATA(PI) controller ([01]). The controller naming convention for SCSI units starts with the first controller naming convention for SCSI units starts with the first controller naming convention for SCSI units starts with the first controller being named 0, the second 1, etc. up to a maximum of 16 controllers ([0-9a-f]).

Units are not accessed before the first attach. Units may be individually attached using the attach specifier, for example

bind -a '#SsdD0' /dev

An attach without a specifier will cause the driver to scan for all possible units before processing the rest of the name.

The subdirectory for each unit contains two files, *ctl* and *raw*. In addition, if the unit is a directaccess disc of some type it may be split into partitions and the subdirectory may contain a file per partition. By default, the partition *data* will exist for such media.

Partitions are added and deleted by writing to the ctl file

part name start-sector end-sector
delpart name

The default *data* partition may be deleted. A partition cannot be deleted if a process has it open. If a change of removable media is detected, the new media cannot be opened until all open partitions on the old media are closed.

Partitions are usually created using *fdisk* and *prep*(8); the convention is to name non-Plan 9 partitions after their corresponding operating systems (e.g., /dev/sdC0/dos) and Plan 9 partitions according to their function (e.g., /dev/sdC0/swap). The example in *prep*(8) shows how this is done.

Reading the *ctl* file returns at least one line of textual information about the unit. The first line will always be prefixed by inquiry and will give a manufacturer and model number if possible. A line prefixed by config will be returned for appropriate media, e.g. for ATA(PI) units the remainder of the line contains configuration information from the device's *identify* command (config and capabilities) and also the available I/O transfer options; this is a diagnostic aid. A line prefixed by geometry will be returned for appropriate media; at least two numbers will follow, the first being the number of sectors contained in the unit and the second the sector size in bytes. Any remaining information on the geometry line is unit-dependent, for instance, head, cylinder and sector counts for ATA discs. If any partitions are defined for the media, their name, start-sector and end-sector will be returned, prefixed by part.

```
% cat /dev/sdD0/ctl
inquiry KENWOOD CD-ROM UCR-421 208E10/20/99 7.39 2 M0
config 85C0 capabilities 0F00 dma 00550004 dmactl 00000000
geometry 242725 2352
part data 0 242725
%
```

The use of DMA and multi-sector read/write commands may be enabled and disabled on ATA(PI) units by writing to the ctl file dma and rwm respectively followed by on or off. For example, to enable DMA on a unit that supports it:

% echo 'dma on'>/dev/sd00/ctl

If supported by the unit, the standby timer may be enabled:

% echo 'standby T'>/dev/sdC0/ctl

where T is the standby timer period in seconds. T must be between 30 and 1200, or can be 0 to disable the timer.

The raw file is used to execute an arbitrary command on the unit at a low level. This is used by programs such as *scuzz*(8) to manipulate devices that do not fit the simple storage model or for maintenance purposes. The following steps may be taken to execute a command

- Write the command to the *raw* file;

- Read or write data associated with the command, according to the direction of the transfer.
- Read the *raw* file to retrieve the status of the command, returned as a text integer.

Reading /dev/sdctl yields information about each controller, one line per controller. Writing 'config message' to /dev/sdctl passes message to the legacy configuration machinery, used to set attributes such as IRQ, port and size. Writing 'ctltype message' to /dev/sdctl passes message to ctltype's wtopctl function with a nil sdev argument, where ctltype is a known controller type such as ata or scsi. Writing 'sdctlletter message' to /dev/sdctl passes message to sdctlletter's wtopctl function with an sdev argument corresponding to the named controller, where ctlletter is a known controller letter such as C or 0.

SOURCE

```
/sys/src/9/port/devsd.c
/sys/src/9/*/sd*.[hc]
```

SEE ALSO

scuzz(8)

BUGS

LUNs (logical unit numbers) are not implemented. For (S)ATA drives, LUNs are not merely ignored but are actively prevented from working except for INQUIRY commands.

The 4 controller limit for ATA(PI) is not enforced.

No account is taken of some buggy ATA PCI controllers such as the CMD640.

ATA(PI) units come up with DMA and multi-sector read/write capability disabled.

sdahci - AHCI (Advanced Host Controller Interface) SATA (Serial ATA) storage device drivers

SYNOPSIS

bind -a #S /dev /dev/sdctl /dev/sdEn/ctl /dev/sdEn/raw /dev/sdEn/data

DESCRIPTION

The *sdahci* driver provides access to AHCI devices via the *sd*(3) interface. The AHCI programming interface supports up to 32 hot-swappable ATAPI or hard disk-like devices per controller. The legacy IDE interface provided by sdata.c supports up to four drives which are not hot-swappable. Controller drive letters are assigned from E onward.

AHCI controllers are detected automatically. Currently Intel and AMD controllers are detected. Intel controllers need to have AHCI enabled in the BIOS. For ich parts this typically means enabling enhanced mode and AHCI. For ESB (Enterprise South Bridge) –based parts, only enhanced mode needs to be enabled. Intel ich9-based AHCI does not support hot swapping and drives must be connected to the lowest-numbered free port.

The top level control file, /dev/sdctl, supports the following control messages for *sdahci*:

ahci debug ahci idprint ahci aprint	Toggle debug messages. Default is off. Toggle printing of drive identification messages. Default is on. Prints short messages when a drive is identified or removed. Print verbose ATAPI debugging messages. Default is off.	
The device-level ctl file supports:		
flushcache	Send the ATA/ATAPI FLUSH CACHE command $(0xe7 \text{ or } 0xea)$. This com-	
identify	mand may take up to 60 seconds to complete. Send the ATA/ATAPI IDENTIFY DEVICE command (Oxec). If device infor- mation has changed, the new size, features and serial will be noted. If changed, I/O on existing file descriptors will result in the error string media or partition has changed.	
mode <i>speed</i> nop	Change the connection <i>speed</i> to one of auto, satai or sataii. Send the ATA NOP command (0) if the device supports it. Per standard, the result is always an error.	
smart	Send the ATA/ATAPI SMART RETURN STATUS command (0xda). This will fail unless SMART is enabled on the drive.	
smartdisable smartenable state <i>state</i>	Disable SMART on the drive. SMART is a persistent property of the drive. Enable SMART on the drive. Force a transition to the named <i>state</i> . The states are: null ignored (may only be reached manually); missing not detected; new powered down or newly discovered; ready ready for commands; reset being reset gently; portreset being fully reset; offline device failed portreset (a port reset will be attempted periodically).	

For devices present at boot, the transition is from state new to state ready.

SOURCE

/sys/src/9/pc/sdiahci.c

SEE ALSO

sd(3)
http://download.intel.com/technology/serialata/pdf/rev1_2.pdf.

BUGS

None of enclosure management, LED control and port multipliers are supported. ATAPI devices may not be reset when they have outstanding commands.

sdaoe - ATA-over-Ethernet (AoE) storage device interface

SYNOPSIS

```
bind -a #S /dev
echo config switch on spec / type aoe//dev/aoe/shelf.slot >/dev/sdctl
echo config switch off spec / >/dev/sdctl
/dev/sd/0/ctl
/dev/sd/0/raw
/dev/sd/0/data
...
```

addaoe letter unit

DESCRIPTION

Sdaoe has a few quirks because network-attached storage can't be enumerated as directlyattached storage can. The default first controller letter for AoE devices is e. Each sdaoe device must be configured explicitly.

Addaoe packages up the switch on invocation as an rc script.

To boot from an AoE root, the sd device must be configured on boot by either PXE booting or booting from directly-attached storage and adding two configuration lines to *plan9.ini*(8) for aoeif, listing the names of the Ethernet interface(s) to use, and aoedev=letter!#a/aoe/lun.

EXAMPLES

To configure target (LUN) 42.0 on #S/sde0,

echo config switch on spec e type aoe//dev/aoe/42.0 >/dev/sdctl

To turn this device off,

echo config switch off spec e >/dev/sdctl

To boot using target 42.0 as #S/sde0 and as root, over Ethernet interfaces 0 and 1,

aoeif=ether0 ether1
aoedev=e!42.0

SOURCE

/sys/src/9/port/sdaoe.c

SEE ALSO

aoe(3), sd(3), snoopy(8)

BUGS

It is not currently possible to boot from an AoE target without an external bootstrap like PXE.

sdloop - loopback storage device interface

SYNOPSIS

```
bind -a #S /dev
echo config switch on spec / type loop/path[!sectsize] >/dev/sdctl
```

```
/dev/sd/0/ctl
/dev/sd/0/raw
/dev/sd/0/data
...
```

DESCRIPTION

Sdloop allows a file to be used as a sd device. To configure /tmp/data as sdl0: with a 1024-byte sector size

echo config switch on spec l type loop//tmp/data!1024 >/dev/sdctl To turn this device off.

echo config switch off spec l >/dev/sdctl

The configuration variable loopdev may be specified in plan9.ini(8) to configure a loopback sd device at boot. For example

loopdev=l!/tmp/data!1024

SOURCE

/sys/src/9/port/sdloop.c

SEE ALSO

sd(3), *sdaoe*(3), *partfs*(8)

BUGS

Maybe.

sdp - secure datagram protocol

SYNOPSIS

```
bind -a #Espec /net
/net/sdp/clone
/net/sdp/log
/net/sdp/n
/net/sdp/n/data
/net/sdp/n/control
/net/sdp/n/ctl
/net/sdp/n/rstats
/net/sdp/n/stats
/net/sdp/n/status
```

DESCRIPTION

The *sdp* device provides the interface to the Secure Datagram Protocol (SDP). SDP (un)compresses and (de-)encrypts packets. *Spec* is an integer from 0 to 15 identifying a stack. Each stack is independent of all others: the only information transfer between them is via programs that mount multiple stacks. Normally a system uses only one stack. However multiple stacks can be used for debugging new networks or implementing firewalls or proxy services.

The top level directory contains a clone file, a log file, and subdirectories numbered from zero to the number of connections opened for this protocol.

Opening the clone file reserves a connection. The file descriptor returned from the *open*(2) will point to the control file, ctl, of the newly allocated connection. Reading ctl returns a text string representing the number of the connection. Connections may be used either to listen for incoming calls or to initiate calls to other machines.

A connection is controlled by writing text strings to the associated ctl file. After a connection has been established data may be read from and written to data. A connection can be actively established using the connect message (see also dial(2)). A connection can be established passively by first using an announce message (see dial(2)) to bind to a local port and then opening the listen file (see dial(2)) to receive incoming calls.

The following control messages are supported:

accept file	Accept an incoming encrypted connection on <i>file</i> , typically a data file.
dial file	Initiate a new encrypted connection on <i>file</i> , typically a UDP data file.
drop <i>permil</i>	Randomly drop approximately one of every <i>permil</i> output packets, thus sim- ulating network errors.
cipher algorithm	Use ciphering <i>algorithm</i> ; choices are null, des_56_cbc, rc4_128, and rc4_256.
auth <i>algorithm</i>	Use authentication <i>algorithm</i> ; choices are null, hmac_sha1_96, and hmac_md5_96.
comp <i>algorithm</i>	Use compression <i>algorithm</i> ; choices are null and thwack.
insecret <i>secret</i>	Use <i>secret</i> to decrypt incoming packets.
outsecret secret	Use <i>secret</i> to encrypt outgoing packets.

SEE ALSO

dial(2), ip(3)

Robust Data Compression of Network Packets, Sean Dorward and Sean Quilan, Bell Labs, Lucent Technologies, http://plan9.bell-labs.com/who/seanq/networkcomp.pdf.

SOURCE

/sys/src/9/port/devsdp.c

segment - long lived memory segments

```
SYNOPSIS
```

```
bind -c '#g' /mnt/segment
#g/seg1
#g/seg1/ctl
#g/seg1/data
#g/seq2
#g/seg2/ctl
#g/seg2/data
```

...

DESCRIPTION

The segment device provides a 2-level file system representing long-lived sharable segments that processes may *seqattach*(2). The name of the directory is the *class* argument to *seqattach*.

New segments are created under the top level using create (see open(2)). The DMDIR bit must be set in the permissions. *Remove*(2)'ing the directory makes the segment no longer available for segattach. However, the segment will continue to exist until all processes using it either exit or segdetach it.

Within each segment directory are two files, data and ctl. Reading and writing data affects the contents of the segment. Reading and writing ctl retrieves and sets the segment's properties.

There is only one control message, which sets the segment's virtual address and length in bytes: va address length type

Address is automatically rounded down to a page boundary and *length* is rounded up to end the segment at a page boundary. The segment will reside at the same virtual address in all processes sharing it. Optionally, type can be specified as fixed or sticky. Fixed segments are uncached and physically continuous with a fixed physical base address suitable for hardware DMA access. Sticky segments are like normal shared segments but preallocated at creation time and never swapped out. Only the hostower is allowed to create fixed or sticky segments.

segattach, the address and length arguments are ignored in the call; they are defined only by the va control message. Once the address and length are set, they cannot be reset.

Reading the control file returns a message of the same format with the segment's actual start address and length. For fixed segments, the type and physical base address are appended.

Opening data or reading ctl before setting the virtual address yields the error "segment not yet allocated".

The permissions check when *segattaching* is equivalent to the one performed when opening data with mode ORDWR.

EXAMPLE

```
Create a one megabyte segment at address 0x10000000:
```

```
% bind -c '#g' /mnt/segment
     % mkdir /mnt/segment/example
     % echo 'va 0x1000000 0x100000' > /mnt/segment/example/ctl
Put the string "hi mom" at the start of the segment:
     % echo -n hi mom > /mnt/segment/example/data
Attach the segment to a process:
     ulong va;
     va = segattach(0, "example", 0, 0);
```

```
}
```

```
SEE ALSO
```

{

segattach(2)

SOURCE

/sys/src/9/port/devsegment.c

shr - global mountpoints

SYNOPSIS

bind '# σ ' /shr

#σ/ share1 #σc/ share1/service1 #σc/ share1/service2

DESCRIPTION

...

The *shr* device provides global mountpoints in the form of share directories where *9P* services can be mounted.

Effectively, it is a global mountpoint registry that is separate from private namespaces.

The *shr* device exports a mount tree and a control tree. The directories in the mount tree $\#\sigma$ are the share mountpoints themselves, while the directories in $\#\sigma c$ contain the service files of the share.

To create a new share, create the directory $\#\sigma c/myshare$

To mount a service in that share, create the file $\#\sigma c/myshare/myserv$ and then write a text string (suitable for *strtoul*; see *atof*(2)) giving the file descriptor number of an open *9P* service. Any process with the proper permission may then access $\#\sigma/myshare$ on the mount tree.

The service file can be reopened and passed to *mount* (see *bind*(2)) or added to another share.

Multiple services can be mounted under a share forming a union directory. New services get mounted before old ones. Removing the service file unmounts the service from the share.

Creating shares and mounts requires read-write access in the share directory. The special user none is prohibited from these operations.

EXAMPLES

To mount a 9p service from *srv*(3) to the shr device

```
mkdir '#oc'/myshare
echo 3 > '#oc'/myshare/myserv <>[3]/srv/myserv
```

SOURCE

```
/sys/src/9/port/devshr.c
```

HISTORY

Shr first appeared in 9front (July, 2011).

srv – server registry

SYNOPSIS

bind #s /srv

#s/service1 #s/service2 ...

DESCRIPTION

The *srv* device provides a one-level directory holding already-open channels to services. In effect, *srv* is a bulletin board on which processes may post open file descriptors to make them available to other processes.

To install a channel, create a new file such as /srv/myserv and then write a text string (suitable for *strtoul*; see *atof*(2)) giving the file descriptor number of an open file. Any process may then open /srv/myserv to acquire another reference to the open file that was registered.

An entry in srv holds a reference to the associated file even if no process has the file open. Removing the file from /srv releases that reference.

It is an error to write more than one number into a server file, or to create a file with a name that is already being used.

EXAMPLE

To drop one end of a pipe into /srv, that is, to create a named pipe:

```
int fd, p[2];
char buf[32];
pipe(p);
fd = create("/srv/namedpipe", OWRITE, 0666);
fprint(fd, "%d", p[0]);
close(fd);
close(fd);
close(p[0]);
fprint(p[1], "hello");
```

At this point, any process may open and read /srv/namedpipe to receive the hello string. Data written to /srv/namedpipe can be received by executing

read(p[1], buf, sizeof buf);

in the above process.

SOURCE

/sys/src/9/port/devsrv.c

ssl – SSL record layer

SYNOPSIS

bind -a #D /net

```
/net/ssl/clone
/net/ssl/n
/net/ssl/n/ctl
/net/ssl/n/data
/net/ssl/n/encalgs
/net/ssl/n/hashalgs
/net/ssl/n/secretin
/net/ssl/n/secretout
```

DESCRIPTION

The SSL device provides the interface to the Secure Socket Layer device implementing the record layer protocol of SSLv2 (but not the handshake protocol, which is responsible for mutual authentication and key exchange.) The *ssl* device can be thought of as a filter providing optional encryption and anti-tampering.

The top level directory contains a clone file and subdirectories numbered from zero to the number of connections configured. Opening the clone file reserves a connection. The file descriptor returned from the *open*(2) will point to the control file, ctl, of the newly allocated connection. Reading the ctl file returns a text string representing the number of the connection.

A connection is controlled by writing text strings to the associated ctl file. After a connection has been established data may be read from and written to the data file.

The SSL protocol provides a stream connection that preserves read/write boundaries. As long as reads always specify buffers that are of equal or greater lengths than the writes at the other end of the connection, one write will correspond to one read.

Options are set by writing control messages to the ctl file of the connection.

The following control messages are supported:

fd open-file-descriptor

Run the SSL protocol over the existing file descriptor.

alg cryptoalgs

Connections start in alg clear which means no encryption or digesting. Writing alg sha to the control file turns on SHA-1 digest authentication for the data channel. Similarly, writing alg $rc4_{128}$ enables encryption. Both can be turned on at once by alg sha $rc4_{128}$. The digest mode sha may be replaced by md5. The encryption mode $rc4_{128}$ may be replaced by $rc4_{40}$, $rc4_{128}$, $rc4_{256}$, des_{40} _ecb, des_{40} _cbc, des_{56} _ecb, and des_{56} _cbc. The mode may be changed at any time during the connection.

secretin base64-secret

The secret for decrypting and authenticating incoming messages can be specified either as a base64 encoded string by writing to the control file, or as a binary byte string using the interface below.

secretout base64-secret

The secret for encrypting and hashing outgoing messages can be specified either as a base64 encoded string by writing to the control file, or as a binary byte string using the interface below.

Before enabling digesting or encryption, shared secrets must be agreed upon with the remote side, one for each direction of transmission, and loaded as shown above or by writing to the files *secretin* and *secretout*. If either the incoming or outgoing secret is not specified, the other secret is assumed to work for both directions.

The encryption and hash algoritms actually included in the kernel may be smaller than the set presented here. Reading *encalgs* and *hashalgs* will give the actual space-separated list of algorithms implemented.

SEE ALSO

listen(8), dial(2)

SOURCE

/sys/src/9/port/devssl.c

BUGS

Messages longer than 4096 bytes are truncated.

swap - memory usage statistics and swap file control

SYNOPSIS

bind -a #¶ /dev

/dev/swap

DESCRIPTION

The swap device holds a text block giving memory usage statistics:

```
n memory
n pagesize
n kernel
n/m user
n/m swap
a/n/m kernel malloc
a/n/m kernel draw
a/n/m kernel secret
```

These are total memory (bytes), system page size (bytes), kernel memory (pages), user memory (pages), swap space (pages), kernel malloced data (bytes), kernel graphics data (bytes) and kernel secret data (bytes). The expression n/m indicates n used out of m available. For kernel malloc and kernel draw, a indicates the current allocation in bytes. These numbers are not blank padded.

To turn on swapping, write to swap the textual file descriptor number of a file or device on which to swap.

Only the hostowner is allowed to enable swapping. The pages written to the swap file are transparently encrypted by the kernel using a random key.

SEE ALSO

memory(8), swap(8).

SOURCE

/sys/src/9/port/devswap.c

tls - TLS and SSL3 record layer

SYNOPSIS

bind -a #a /net

```
/net/tls/clone
/net/tls/encalgs
/net/tls/hashalgs
/net/tls/n
/net/tls/n/ctl
/net/tls/n/data
/net/tls/n/hand
/net/tls/n/stats
/net/tls/n/status
```

DESCRIPTION

The TLS device implements the record layer protocols of Transport Layer Security version 1.0–1.2 and Secure Sockets Layer version 3.0. It does not implement the handshake protocols, which are responsible for mutual authentication and key exchange. The *t/s* device can be thought of as filters providing optional encryption and anti-tampering.

The top level directory contains a clone file and subdirectories numbered from zero through at least the last active filter. Opening the clone file reserves a filter. The file descriptor returned from the *open*(2) will point to the control file, ctl, of the newly allocated filter. Reading the ctl file returns a text string containing the number of the filter directory.

The filter initially cannot be used to pass messages and will not encrypt or digest messages. It is configured and controlled by writing commands to ctl.

The following commands are supported:

fd open-fd vers

Pass record messages over the communications channel *open-fd*. Initially, outgoing messages use version *vers* format records, but incoming messages of either version are accepted. Valid versions are 0x300 for SSLv3.0 and 0x301, 0x302 and 0x303 for TLSv1.0 (which could be known as SSLv3.01), TLSv1.1 and TLSv1.2. This command must be issued before any other command and before reading or writing any messages; it may only be executed once.

version vers

Use *vers* format records for all future records, both outgoing and incoming. This command may only be executed once.

secret hashalg encalg isclient secretdata

Set up the digesting and encryption algorithms and secrets. *Hashalg* and *encalg* must be algorithm names returned by the corresponding files. *Secretdata* is the base-64 encoded (see *encode*(2)) secret data used for the algorithms. It must contain at least enough data to populate the secrets for digesting and encrypting. These secrets are divided into three categories: digest secrets, keys, and initialization vectors. The secrets are packed in this order, with no extra padding. Within each category, the secret for data traveling from the client to the server comes first. The incoming and outgoing secrets are automatically selected by devtls based on the *isclient* argument, which must be non-zero for the client of the TLS handshake, and zero for the server.

This command must be issued after version, and may be issued more than once. At least one new *secret* command must be issued before each *changecipher* command; similarly, at least one new *secret command* must precede each incoming changecipher message.

changecipher

Enable outgoing encryption and digesting as configured by the previous *secret* command. This command sends a *changecipher* message.

opened

Enable data messages. This command may be issued any number of times, although only the first is significant. It must follow at least one successful *changecipher* command.

alert *alertno*

Send an alert message. *Alertno* may be a valid alert code for either SSLv3.0 or TLS, and is mapped to an appropriate code for the protocol in use. If it is a fatal alert, the filter is set into an error state.

Application messages and handshake messages are communicated using *data* and *hand*, respectively. Only one *open*(2) of *hand* is allowed at a time.

Any record layer headers and trailers are inserted and stripped automatically, and are not visible from the outside. The device tries to synchronize record boundaries with reads and writes. Each read will return data from exactly one record, and will return all of the data from the record as long as the buffer is big enough. Each write will be converted into an integral number of records, with all but potentially the last being maximal size. The maximum record length supported is 16384 bytes. This behavior is not specified in the protocols, and may not be followed by other implementations.

If a fatal alert message is received, or a fatal *alert* command issued, the filter is set into an error state. All further correspondence is halted, although some pending operations may not be terminated. Operations on *data* will fail with a 'tls error', and operations on *hand* will fail with a 'tls error', and operations on *hand* will fail with a textual decoding of the alert. The current non-fatal alert messages are 'close notify', 'no renegotiation', and 'handshake canceled by user'. Receipt of one of these alerts cause the next read on *hand* to terminate with an error. If the alert is 'close notify', all future reads will terminate with a tls hungup error. A 'close notify' *alert* command will terminate all future writes or reads from *data* with a 'tls hungup' error.

If an error is encountered while reading or writing the underlying communications channel, the error is returned to the offending operation. If the error is not 'interrupted', the filter is set into the error state. In this case, all future operations on *hand* will fail with a 'channel error'.

When all file descriptors for a filter have been closed, the session is terminated and the filter reclaimed for future use. A 'close notify' alert will be sent on the underlying communications channel unless one has already been sent or the filter is in the error state.

Reading *stats* or *status* returns information about the filter. Each datum is returned on a single line of the form *tag*: *data*. *Stats* returns the number of bytes communicated by the data and hand channels. The four lines returned are tagged by, in order, DataIn, DataOut, HandIn, and HandOut. *Status* returns lines following tags: State, Version, EncIn, HashIn, NewEncIn, NewHashIn, EncOut, HashOut, NewEncOut, and NewHashOut. State's value is a string describing the status of the connection, and is one of the following: 'Handshaking', 'Established', 'RemoteClosed', 'LocalClosed', 'Alerting', 'Errored', or 'Closed'. Version's give the hexadecimal record layer version in use. The Enc and Hash fields return name of the current algorithms in use or ready to be used, if any.

Reading *encalgs* and *hashalgs* will give the space-separated list of algorithms implemented. This will always include clear, meaning no encryption or digesting. Currently implemented encryption algorithms for use with TLSv1.0 and TLSv1.1 are: rc4_128, 3des_ede_cbc, aes_128_cbc and aes_256_cbc. For TLSv1.2, which adds support for authenticated encryption with associated data (AEAD), the following ciphers are supported: ccpoly64_aead, ccpoly96_aead, aes_128_gcm_aead and aes_256_gcm_aead. Currently implemented hashing algorithms are: md5, sha1 and sha256. For an AEAD cipher, the hashing algorithm should be set to clear.

SEE ALSO

listen(8), dial(2), pushtls(2)

SOURCE

/sys/src/9/port/devtls.c

twsi - two-wire serial interface (TWSI) and inter-integrated circuit (I²C) interface

SYNOPSIS

bind -a #² /dev

/dev/twsi*

DESCRIPTION

The *twsi* device serves a one-level directory containing one file per TWSI or I^2C bus. Bytes written are transmitted on the bus; bytes received from the bus are queued and delivered by reading. Seeking to a given offset before reading or writing causes the *twsi* device to use that offset as a TWSI slave address for a subsequent *read*(2) or *write* call.

FILES

#²/twsi*

SOURCE

/sys/src/9/*/devtwsi.c

BUGS

10-bit addressed devices are not supported.

No slave mode.

Setting the bus rate is not supported.

uart, eia - serial communication control

SYNOPSIS

```
bind -a #t /dev
```

```
/dev/eia0
/dev/eia0ctl
/dev/eia0status
/dev/eia1
/dev/eia1ctl
/dev/eia1status
```

DESCRIPTION

The serial line devices serve a one-level directory, giving access to the serial ports. Device n is accessed through eian (the data file), eianctl (the control file), and eianstatus (the read-only status file). Reads of the data file will block until at least one byte is available. The control file configures the port. It accepts the following commands:

- b*n* Set the baud rate to *n*.
- c*n* Set hangup on DCD if *n* is non-zero; else clear it.
- d*n* Set DTR if *n* is non-zero; else clear it.
- e *n* Set hangup on DSR if *n* is non-zero; else clear it.
- f Flush output queue.
- h Close input and output queues.
- in Enable/disable the FIFOs. If n is zero the FIFOs are disabled; otherwise n is taken as a trigger level for the FIFOs. The trigger levels supported are device dependant, but usually include 1, 4 and 8. An unrecognised, but non-zero, value of n causes the maximum-supported trigger level to be set.
- k*n* Send a break lasting *n* milliseconds.
- 1*n* Set number of bits per byte to *n*. Legal values are 5, 6, 7, or 8.
- m*n* Obey modem CTS signal if *n* is non-zero; else clear it.
- n Make writes non-blocking.
- pc Set parity to odd if c is o, to even if c is e; else set no parity.
- q*n* Set input and output queue limits to *n*.
- **r***n* Set RTS if *n* is non-zero; else clear it.
- s *n* Set number of stop bits to *n*. Legal values are 1 or 2.
- w*n* Set the uart clock timer to n times 100us.

The status files contain a textual representation of the status of the line, in the format of the commands used on the control file.

SOURCE

/sys/src/9/port/devuart.c
/sys/src/9/*/uart*.c

delim \$\$

NAME

usb - USB Host Controller Interface

SYNOPSIS

```
bind -a #u /dev
/dev/usb
/dev/usb/ctl
/dev/usb/epN.M
/dev/usb/epN.M/data
/dev/usb/epN.M/ctl
```

DESCRIPTION

The Universal Serial Bus is a complex yet popular bus for connecting all kind of devices to a computer. It is a four-wire tree-shaped bus that provides both communication and (limited) power to devices. Branching points in the tree are provided by devices called *hubs*. Hubs provide ports where USB devices (also hubs) can be attached.

Most PCs have one or more USB controllers called *host* controllers. Each one has a built-in hub called a *root hub* providing several ports. In some cases, more hubs are built-in and attached to a root hub port. The topology of the network is a tree with at most 127 nodes, counting both internal and leaf nodes.

Host controllers come in four flavours: UHCI and OHCI for USB 1 (up to 12 Mb/s), EHCI for USB 2 (up to 480 Mb/s) and XHCI for USB 3 (up to 5 Gb/s). We currently support all but XHCI, which is still quite new.

The USB bus is fully controlled by the host; all devices are polled. Hubs are passive in the sense that they do not poll the devices attached to them. The host polls those devices and the hubs merely route the messages.

Devices may be added to or removed from the bus at any time. When a device is attached, the host queries it to determine its type and speed. The querying process is standardized. The first level of querying is the same for all devices, the next is somewhat specialized for particular classes of devices (such as mice, keyboards, or audio devices). Specialization continues as subclasses and subsubclasses are explored.

Enumeration of the bus and initial configuration of devices is done by a user level program, *usbd*. Device drivers are implemented by separate user programs, although some of them may be statically linked into *usbd*.

The kernel device described in this page is responsible for providing I/O for using the devices through so called *endpoints*. Access to the host controller is hidden from user programs, which see just a set of endpoints. After system initialization, some endpoints are created by the device to permit I/O to root hubs. All other devices must be configured by *usbd*.

Devices and Endpoints

A device includes one or more functions (e.g., audio output, volume control buttons, mouse input, etc.) Communication with device functions is performed by some combination of issuing control requests to, sending data to, and receiving data from device *endpoints*. Endpoints can be understood as addresses in the bus. There are several types:

- *Control* Their main use is to configure devices. Writing a message with a specific format (specified in the USB specification) issues a request to the device. If the request implies a reply, a read can be made next to retrieve the requested data (if the write succeeded).
- *Interrupt* Used to send and receive messages to or from a specific device function (e.g., to read events from a mouse).
- *Bulk* Used to send and receive larger amounts of data through streams (e.g., to write blocks to a disk).
- *Isochronous* Used to send and receive data in a timely manner (e.g., to write audio samples to a speaker).

All USB devices include at least a control endpoint to perform device configuration. This is called the *setup* endpoint or *endpoint zero*. After configuring a device, other endpoints may be created as dictated by the device to perform actual I/O.

Operation

Bus enumeration and device configuration is performed by *usbd* and not by this driver. The driver provides an interface to access existing endpoints (initially those for the built-in root hubs), to create and configure other ones, and to perform I/O through them.

Each directory /dev/usb/epN.M represents an endpoint, where N is a number identifying a device and M is a number identifying one of its endpoints.

For each device attached to the bus, and configured by *usbd*, an endpoint zero (a *setup* endpoint) is provided at /dev/usb/epN.0 for configuring the device. This is always a control endpoint and represents the device itself.

The device driver may use the setup endpoint to issue control requests and perhaps to create more endpoints for the device. Each new endpoint created has its own directory as said above. For example, if the driver for the device /dev/usb/epN.0 creates the endpoint number 3 for that device, a directory /dev/usb/epN.3 will be available to access that endpoint.

All endpoint directories contain two files: data and ctl. The former has mode bit DMEXCL set and can be open by only one process at a time.

data

The data file is used to perform actual I/O. In general, reading from it retrieves data from the endpoint and writing into it sends data to the endpoint. For control endpoints, writing to this file issues a control request (which may include data); if the request retrieves data from the device, a following read on the file will provide such data.

USB errors reported by the endpoint upon I/O failures are passed to the user process through the error string. I/O stalls not resulting from an error, usually an indication from the device, are reported by indicating that the number of bytes transferred has been zero. In most cases, the correct course of action after noticing the stall is for the device driver to issue a 'clear halt' request (see *unstall* in *nusb*(2)) to resume I/O. The most common error is crc/timeout indicating problems in communication with the device (eg., a physical detach of the device or a wiring problem).

For control and isochronous transfers, there is an implicit timeout performed by the kernel and it is not necessary for applications to place their own timers. For other transfer types, the kernel will not time out any operation by default (but see the timeout control request).

ctl and status

The ctl file can be read to learn about the endpoint. It contains information that can be used to locate a particular device (or endpoint). It also accepts writes with textual control requests described later.

This may result from the read of an endpoint control file:

(the first line is wrapped to make it fit here)
enabled control rw speed full maxpkt 64 pollival 0
 samplesz 0 hz 0 hub 1 port 3 busy
storage csp 0x500608 vid 0x951 did 0x1613 Kingston 'DT 101 II'

The first line contains status information. The rest is information supplied by *usbd* as an aid to locate devices. The status information includes:

Device state One of config, enabled, and detached. An endpoint starts in the config state, and accepts control commands written to its ctl file to configure the endpoint. When configured, the state is enabled and the data file is used as described above (several control requests can still be issued to its ctl file, but most will not be accepted from now on). Upon severe errors, perhaps a physical detachment from the bus, the endpoint enters the detached state and no further I/O is accepted on it. Files for an endpoint (including its directory) vanish when the device is detached and its files are no longer open. Root hubs may not be detached.

- Endpoint type control, iso, interrupt, or bulk, indicating the type of transfer supported by the endpoint.
- Endpoint mode One of r, w, or rw, depending on the direction of the endpoint (in, out, or inout).
- Speed low (1.5 Mb/s), full (12 Mb/s), or high (480 Mb/s).

Maximum packet size

Used when performing I/O on the data file.

- Polling interval The polling period expressed as a number of µframes (for high-speed endpoints) or frames (for low- and full-speed endpoints). Note that a µframe takes 125 µs while a frame takes 1 ms. This is only of relevance for interrupt and isochronous endpoints. This value determines how often I/O happens. Note that the control request adjusting the polling interval does *not* use these units, to make things easier for USB device drivers.
- Sample size Number of bytes per I/O sample (isochronous endpoints only).
- Frequency Number of samples per second (Hertz).

Hub address Device address of the hub where the device is attached.

- Port number Port number (in the hub) where the device is attached.
- Usage busy while the data file is open and idle otherwise. This is useful to avoid disturbing endpoints already run by a device driver.

The second line contains information describing the device:

- Class name As provided by the device itself.
- CSP Class, Subclass, and Protocol for the device. If the device contains different functions and has more CSPs, all of them will be listed. The first one is that of the device itself. For example, a mouse and keyboard combo may identify itself as a keyboard but then include two CSPs, one for the keyboard and another one for the mouse.
- Vid and Did Vendor and device identifiers.

Device strings Provided by the device and identifying the manufacturer and type of device.

For example, to find a mouse not yet in use by a driver, scan the ctl files for enabled, idle, and csp 0x020103. A mouse belongs to class 3 (in the least significant byte), *human interface device*, subclass 1, *boot*, protocol 2, *mouse* (protocol 1 would be the keyboard). USB class, sub-class and proto codes can be found at http://www.usb.org.

Control requests

Endpoint control files accept the following requests. In most cases the driver does not issue them, leaving the task to either *usbd* or the usb driver library documented in *nusb*(2).

- detach Prevent further I/O on the device (delete the endpoint) and remove its file interface as soon as no process is using their files.
- maxpkt *n* Set the maximum packet size to *n* bytes.
- pollival *n* Only for interrupt and isochronous endpoints. Set the polling interval as a function of the value *n* given by the endpoint descriptor. The interval value used is the period *n* in bus time units for low- and full-speed interrupt endpoints. Otherwise, the actual interval is $2 \sup n$ and not *n*. Bus time units are 1 ms for low- and full-speed endpoints and 125 µs for high-speed endpoints. In most cases, the device driver may ignore all this and issue the control request supplying the polling interval value as found in the endpoint descriptor. The kernel adjusts the value according to the endpoint configuration and converts it into the number of frames or µframes between two consecutive polls.

samplesz n Use n as the number of bytes per sample.

- hz *n* Use *n* as the number of samples per second.
- ntds n Use n as the number of transactions per frame (or μ frame), as reported by the descriptor.
- uframes n If n is set to 1 for an isochronous endpoint, read(2) from the data file will not cross µframe boundaries.

clrhalt Clear the halt condition for an endpoint. Used to recover from a stall caused by a device to signal its driver (usually due to an unknown request or a failure to complete one).

info string Replaces description information in ctl with string. Usbd uses this to add device descriptions.

address Tell this driver that the device has been given an address, which causes the device to enter the *enabled* state.

- name *str* Generates an additional file name, *str*, for the data file of the endpoint. This file name appears in the root directory of the #u tree. For example, this is used by the audio device driver to make the data file also available as /dev/audio.
- debug *n* Enable debugging of the endpoint. *N* is an integer; larger values make diagnostics more verbose. 0 stops debugging diagnostics. 1 causes just problem reports. Bigger values report almost everything.
- timeout n Enable time-outs for the endpoint. Transfers are timed out by the kernel after n ms. This should not be used for control and isochronous endpoints, which are always timed out.

Setup endpoints (those represented by epN.0 directories) also accept the following requests:

new n type mode

Creates a new endpoint with number n of the given *type* (ctl, bulk, intr, or iso). *Mode* may be r, w, or rw, which creates, respectively, an input, output, or input/output endpoint.

speed {low|full|high}

Set the endpoint speed to full, low, or high, respectively.

hub Tell this driver that the endpoint corresponds to a hub device.

Setup endpoints for hub devices also accept his request:

newdev {low|full|high} port

Create a new setup endpoint to represent a new device. The first argument is the device speed. *Port* is the port number where the device is attached (the hub is implied by the endpoint where the control request is issued).

The file /dev/usb/ctl provides all the information provided by the various ctl files when read. It accepts several requests that refer to the entire driver and not to particular endpoints:

debug *n* Sets the global debug flag to *n*.

dump Dumps data structures for inspection.

FILES

#u/usb root of the USB interface

SOURCE

/sys/src/9/port/usb.h
/sys/src/9/port/devusb.c
/sys/src/9/*/usb*.c

SEE ALSO

nusb(2), nusb(4), plan9.ini(8)

BUGS

USB controllers limit the speed of all their ports to that of the slowest device connected to any one of them.

Isochronous input streams are not implemented for OHCI.

Some EHCI controllers drop completion interrupts and so must be polled, which hurts throughput.

vga – VGA controller device

SYNOPSIS

bind #v /dev

/dev/vgactl

DESCRIPTION

The VGA device allows configuration of a graphics controller on a PC. Vgactl allows control over higher-level settings such as display height, width, depth, controller and hardware-cursor type. Along with the I/O-port registers provided by *arch*(3), it is used to implement configuration and setup of VGA controller cards. This is usually performed by vga(8).

Writing strings to vgactl configures the VGA device. The following are valid commands.

size XxYxZ chan

Set the size of the screen image to be X pixels wide and Y pixels high. Each pixel is Z bits as specified by *chan*, whose format is described in *image*(6).

actualsize XxY

Set the physical size of the display to be X pixels wide by Y pixels high. This message is optional; it is used to accommodate displays that require the in-memory screen image to have certain alignment properties. For example, a 1400×1050 screen with a 1408×1050 in-memory image will use size 1408×1050 but actualsize 1400×1050 .

tilt value

Set the tilt of the screen, altering the screen's orientation. The *value* can be one of: none, left, inverted and right.

type ctlr

Set the type of VGA controller being used. *Ctlr* is one of 3dfx, ark200pv, clgd542x, clgd546x, ct65545, cyber938x, et4000, geode, hiqvideo, i81x, igfx, mach64xx, mga2164w, mga4xx, neomagic, nvidia, radeon, s3, t2r4 and vmware.

Note that this list does not indicate the full set of VGA chips supported. For example, s3 includes the 86C801/5, 86C928, Vision864, and Vision964. It is the job of vga(8) to recognize which particular chip is being used and to initialize it appropriately.

hwgc gc

Set the type of hardware graphics cursor being used. *Gc* is one of soft, 3dfxhwgc, ark200pvhwgc, bt485hwgc, clgd542xhwgc, clgd546xhwgc, ct65545hwgc, cyber938xhwgc, et4000hwgc, geodehwgc, hiqvideohwgc, i81xhwgc, igfxhwgc, mga2164whwgc, mach64xxhwgc, neomagichwgc, nvidiahwgc, radeonhwgc, rgb524hwgc, s3hwgc, t2r4hwgc, tvp3020hwgc, tvp3026hwgc and vmwarehwgc. A value of off disables the cursor.

palettedepth d

Set the number of bits of precision used by the VGA palette to d, which must be either 6 or 8.

hwaccel mode

Depending on whether *mode* is on or off, enable or disable whether hardware acceleration (currently for rectangle filling and moving) used by the graphics engine. The default setting is on.

softscreen *mode*

Depending on whether *mode* is on or off, enable or disable shadow framebuffer to reduce slow bus reads. Enabling softscreen disables hardware acceleration. The default setting is off except for the vesa driver.

hwblank *mode*

Depending on whether *mode* is on or off, enable or disable the use of DPMS blanking (see *mouse*(3)).

linear size align

Use a linear screen aperture of size *size* aligned on an *align*-byte boundary.

drawinit

Initialize the graphics hardware. This must be sent after setting the type.

Reading vgactl returns the current settings, one per line.

EXAMPLES

The following disables hardware acceleration.

echo hwaccel off > /dev/vgactl

SOURCE

/sys/src/9/pc/devvga.c

SEE ALSO

arch(3), *vga*(8)

BUGS

The hardware graphics cursor on the et4000 does not work in 2x8-bit mode.

vmx - x86 virtualization interface

SYNOPSIS

#X/clone
#X/n
#X/n/ctl
#X/n/fpregs
#X/n/map
#X/n/regs
#X/n/status
#X/n/wait

DESCRIPTION

The *vmx* device supports "virtual CPUs" using the Intel VT-x extension (a.k.a. VMX instruction set). This is used by vmx(3) to implement virtual machines. Access to the *vmx* device is restricted to the hostowner.

The top level directory contains a clone file and numbered subdirectories representing the allocated virtual CPUs. Opening the clone file allocates a new virtual CPU and returns the file descriptor to its ctl file. The ctl file provides the main control interface. See below for a list of commands. Reading returns the subdirectory number. Removing the ctl file marks the virtual CPU as moribund. The status file contains the current status of the virtual CPU, which is one of

init The virtual CPU is being initialized.

ready The virtual CPU is idle.

running The virtual CPU is executing code.

dead The virtual CPU suffered a fatal error. This state may be followed by an error message. ending The virtual CPU is shutting down.

The map file contains the memory map that the virtual CPU will see. It consists of lines of the form *access cache lowaddr highaddr segment offset*

Lowaddr specifies the lowest address in the region and highaddr one past the highest address. The region is mapped to a region of the same size in the global segment (see *segment*(3)), starting at *offset*. The *access* field specifies the permitted types of access using the characters r (read), w (write), x (execute) and – (padding character). The *cache* field specifies the cacheability of the region, it must be one of uc, wc, wt, wp and wb (as defined in the Intel SDM).

Writes to the map file append lines to the end. Multiple lines can be written at once but all lines written must be newline terminated. Regions can be overlapping, in which case later definitions always override earlier ones. The map can be cleared by opening the file with OTRUNC (see *open* (2)).

The regs file contains the registers of the virtual CPU in the format *name value*. Writes to the file (in the same format) write to the referenced registers (if possible). Multiple lines can be written at once but all lines written must be newline terminated.

Some registers (CRO and CR4) are split into three registers, suffixed real, fake and mask. In this case, real corresponds to the bits that affect actual CPU execution, fake corresponds to the bits read back by the guest and the bits set in mask are those "owned" by the host. The guest is free to modify the bits that it owns (in which case it always has the same value in both real and fake), but attempting to change a host-owned bit from the status in fake causes a VM exit. Certain bits are owned by the kernel, which means they are fixed in both mask and real.

Reading the wait file will stall the reading process until the virtual CPU reaches a point where it cannot continue (a "VM exit"). This may be due to the an access to hardware or a software exception. Each exit is indicated by a single line in a format compatible with *tokenize* (see *getfields*(2)). The first column contains the cause of the exit and the second column contains the "exit qualification" field that may contain more details on the exit (see Intel SDM). The remaining columns come

in pairs and contain further info and the values of relevant registers.

Some notable exit causes are (see kernel source code for a complete list)

#exception	Exception of the specified type (e.g. #gp for general protection fault). Currently only debug exceptions are configured to cause VM exits.
triplef	Triple fault.
eptfault	The virtual CPU attempted a memory access that does not match any entry in the map file.
movcr	Illegal access to a control register (see above).
. instr	The virtual CPU attempted to execute the instruction <i>instr</i> .
*ack	Not an actual exit, but acknowledgement that an interrupt request (IRQ) was posted.

The fpregs file contains the virtual CPU's floating point registers, in the same binary format used by proc(3).

Control messages

quit	Destroy the current virtual CPU.
go [<i>regs</i>]	Launch the virtual CPU. <i>Regs</i> is an optional list of register changes in the for-
	mat <i>name=value</i> ; that will be applied before launching.
stop	Stop the virtual CPU.
step[<i>regs</i>]	Executes a single instruction with the virtual CPU. <i>Regs</i> is optinal, same as go.
exc excep	The exception <i>excep</i> is triggered in the virtual CPU. <i>Excep</i> can either be a
	named exception (such as #gp, in lower case) or an exception number. A num-
	ber may be preeded by # to mark it as an exception, otherwise it is delivered as
ing [avenu]	an interrupt (but always disregarding whether interrupts are enabled).
irq[excep]	An Interrupt is posted, i.e. the exception <i>excep</i> will be triggered the next time
	interrupts are enabled in the virtual CPU, at which point a *ack message is
	sent to wait. Irq cancels any interrupts that have been previously posted
	but not yet delivered and it can be called with no argument to cancel an inter-
	rupt.
ovtran hitman	Changes the exception hitman. Set hits cause a VM exits

extrap *bitmap* Changes the exception bitmap. Set bits cause a VM exits.

SOURCE

/sys/src/9/pc/devvmx.c

SEE ALSO

vmx(1), *cpuid*(8)

Intel 64 and IA-32 Architectures Software Developer's Manual, Volume 3B, Chapters 23-33.

BUGS

Devvmx can and will crash your kernel.

HISTORY

Devvmx first appeared in 9front (June, 2017).

intro – introduction to file servers

DESCRIPTION

A Plan 9 *file server* provides a file tree to processes. This section of the manual describes servers than can be mounted in a name space to give a file-like interface to interesting services. A file server may be a provider of a conventional file system, with files maintained on permanent storage, or it may also be a process that synthesizes files in some manner.

SEE ALSO

bind(1)

acme - control files for text windows

SYNOPSIS

acme [-ab][-c ncol][-f varfont][-F fixfont][-l file | file ...]

DESCRIPTION

The text window system acme(1) serves a variety of files for reading, writing, and controlling windows. Some of them are virtual versions of system files for dealing with the virtual console; others control operations of *acme* itself. When a command is run under *acme*, a directory holding these files is mounted on /mnt/acme (also bound to /mnt/wsys) and also /dev; the files mentioned here appear in both those directories.

Some of these files supply virtual versions of services available from the underlying environment, in particular the character terminal files cons(3). (Unlike in rio(1), each command under *acme* sees the same set of files; there is not a distinct /dev/cons for each window.) Other files are unique to *acme*.

- acme is a subdirectory used by win (see *acme*(1)) as a mount point for the *acme* files associated with the window in which win is running. It has no specific function under *acme* itself.
- cons is the standard and diagnostic output file for all commands run under *acme*. (Input for commands is redirected to /dev/null.) Text written to cons appears in a window labeled *dir*/+Errors, where *dir* is the directory in which the command was run. The window is created if necessary, but not until text is actually written.

consctl

is an empty unwritable file present only for compatibility; there is no way to turn off 'echo', for example, under *acme*.

index

holds a sequence of lines of text, one per window. Each line has 5 decimal numbers, each formatted in 11 characters plus a blank—the window ID; number of characters (runes) in the tag; number of characters in the body; a 1 if the window is a directory, 0 otherwise; and a 1 if the window is modified, 0 otherwise—followed by the tag up to a newline if present. Thus at character position 5×12 starts the name of the window. If a file has multiple zeroxed windows open, only the most recently used will appear in the index file.

is an empty file, writable without effect, present only for compatibility with rio.

- log reports a log of window operations since the opening of the log file. Each line describes a single operation using three fields separated by single spaces: the decimal window ID, the operation, and the window name. Reading from log blocks until there is an operation to report, so reading the file can be used to monitor editor activity and react to changes. The reported operations are new (window creation), zerox (window creation via zerox), get, put, del (window deletion), and focus (window focus change). The window name can be the empty string; in particular it is empty in new log entries corresponding to windows created by external programs.
- new is a directory analogous to the numbered directories (*q.v.*). Accessing any file in new creates a new window. Thus to cause text to appear in a new window, write it to /dev/new/body. For more control, open /dev/new/ctl and use the interface described below.

Each *acme* window has associated a directory numbered by its ID. Window IDs are chosen sequentially and may be discovered by the ID command, by reading the ctl file, or indirectly through the index file. The files in the numbered directories are as follows.

addr may be written with any textual address (line number, regular expression, etc.), in the format understood by button 3 but without the initial colon, including compound addresses, to set the address for text accessed through the data file. When read, it returns the value of the address that would next be read or written through the data file, formatted as 2 decimal numbers *m* and *n*, each formatted in 11 characters plus a blank. *M* and *n* are the character (not byte) offsets of the beginning and end of the address, which would be

label

expressed in *acme* 's input language as #m, #n. Thus a regular expression may be evaluated by writing it to addr and reading it back. The addr address has no effect on the user's selection of text.

- body holds contents of the window body. It may be read at any byte offset. Text written to body is always appended; the file offset is ignored.
- ctl may be read to recover the five numbers as held in the index file, described above, plus three more fields: the width of the window in pixels, the name of the font used in the window, and the width of a tab character in pixels. Text messages may be written to ctl to affect the window. Each message is terminated by a newline and multiple messages may be sent in a single write.

Set the addr address to that of the user's selected text in the window.
Mark the window clean as though it has just been written.
Mark the window dirty, the opposite of clean.
Remove all text in the tag after the vertical bar.
Equivalent to the Del interactive command.
Equivalent to the Delete interactive command.
Set the user's selected text in the window to the text addressed by the
addr address.
Set the command string to recreate the window from a dump file.
ory
Set the directory in which to run the command to recreate the window
from a dump file.
Equivalent to the Get interactive command with no arguments; accepts
no arguments.
When the ctl file is first opened, regular expression context searches in
addr addresses examine the whole file; this message restricts subse-
quent searches to the current addr address.
Cancel nomark, returning the window to the usual state wherein each
modification to the body must be undone individually.
Maintain Undo, Redo, and Put in the left half of the tag. (This is the
default for file windows.)
Set the name of the window to <i>name</i> .
Turn off automatic 'marking' of changes, so a set of related changes may
be undone in a single Undo interactive command.
Do not maintain Undo, Redo, and Put in the left half of the tag. (This
is the default for directory and error windows.)
Turn off automatic 'scrolling' of the window to show text written to the
body.
Equivalent to the Put interactive command with no arguments; accepts
no arguments.
Turn off tracking the 'dirty' status, the window stays clean.
Cancel a noscroll message, returning the window to the default state
wherein each write to the body file causes the window to 'scroll' to dis-
play the new text.
Guarantee at least some of the selected text is visible on the display.

data is used in conjunction with addr for random access to the contents of the body. The file offset is ignored when writing the data file; instead the location of the data to be read or written is determined by the state of the addr file. Text, which must contain only whole characters (no 'partial runes'), written to data replaces the characters addressed by the addr file and sets the address to the null string at the end of the written text. A read from data returns as many whole characters as the read count will permit starting at the beginning of the addr address (the end of the address has no effect) and sets the address to the null string at the end of the returned characters.

errors

Writing to the errors file appends to the body of the *dir*/+Errors window, where *dir* is the directory currently named in the tag. The window is created if necessary, but not until text is actually written.

event

When a window's event file is open, changes to the window occur as always but the actions are also reported as messages to the reader of the file. Also, user actions with buttons 2 and 3 (other than chorded Cut and Paste, which behave normally) have no immediate effect on the window; it is expected that the program reading the event file will interpret them. The messages have a fixed format: a character indicating the origin or cause of the action, a character indicating the type of the action, four free-format blank-terminated decimal numbers, optional text, and a newline. The first and second numbers are the character addresses of the action, the third is a flag, and the final is a count of the characters in the optional text, which may itself contain newlines. The origin characters are E for writes to the body or tag file, F for actions through the window's other files, K for the keyboard, and M for the mouse. The type characters are D for text deleted from the body, d for text deleted from the tag, I for text inserted to the body, i for text inserted to the tag, L for a button 3 action in the body, 1 for a button 3 action in the tag.

If the relevant text has less than 256 characters, it is included in the message; otherwise it is elided, the fourth number is 0, and the program must read it from the data file if needed. No text is sent on a D or d message.

For D, d, I, and i the flag is always zero. For X and x, the flag is a bitwise OR (reported decimally) of the following: 1 if the text indicated is recognized as an *acme* built-in command; 2 if the text indicated is a null string that has a non-null expansion; if so, another complete message will follow describing the expansion exactly as if it had been indicated explicitly (its flag will always be 0); 8 if the command has an extra (chorded) argument; if so, two more complete messages will follow reporting the argument (with all numbers 0 except the character count) and where it originated, in the form of a fully-qualified button 3 style address.

For L and 1, the flag is the bitwise OR of the following: 1 if *acme* can interpret the action without loading a new file; 2 if a second (post-expansion) message follows, analogous to that with X messages; 4 if the text is a file or window name (perhaps with address) rather than plain literal text.

For messages with the 1 bit on in the flag, writing the message back to the event file, but with the flag, count, and text omitted, will cause the action to be applied to the file exactly as it would have been if the event file had not been open.

tag holds contents of the window tag. It may be read at any byte offset. Text written to tag is always appended; the file offset is ignored.

xdata

The xdata file like data except that reads stop at the end address.

SOURCE

/sys/src/cmd/acme

SEE ALSO

rio(1), *acme*(1), *cons*(3).

archfs - mount mkfs-style archive

SYNOPSIS

archfs[-abcC][-m mtpt] archfile

DESCRIPTION

Archfs mounts at *mtpt* (default /mnt/arch) a file system presenting the contents of an archive in the format produced by the -a flag to mkfs(8). The -a, -b, -c, and -C flags control the flag argument to the mount system call (see *bind*(2)) as in the mount command (see *bind*(1)).

SOURCE

/sys/src/cmd/archfs.c

SEE ALSO

mkfs(8)

bzfs - compressed read-write ram filesystem

SYNOPSIS

bzfs[-m *mtpt*][-s][-f *file*]

DESCRIPTION

Bzfs reads a bzip2 (see *gzip*(1)) compressed filesystem archive as produced by *mkfs*(8) and serves it as a writable ram filesystem. The compressed archive file has to be provided with the -f *file* option. The -m option sets the mountpoint *mptp* (default /root). If the -s flag is specified then the 9p channel /srv/ramfs is created to be used later for mounting the filesystem.

SOURCE

/sys/src/cmd/bzfs

SEE ALSO

mkfs(8), *gzip*(1), *ramfs*(4), *paqfs*(4).

cdfs, cddb - optical disc (CD, DVD, BD) track reader and writer file system

SYNOPSIS

cdfs[-d sddev][-m mtpt]
grep aux/cddb /mnt/cd/ctl | rc
aux/cddb[-DTt][-s server] query diskid ntracks trackOid ...

DESCRIPTION

Cdfs serves a one and a half level directory mounted at *mtpt* (default /mnt/cd) that provides access to the tracks on discs placed in the disc reader or writer named by *sddev* (default /dev/sdD0, see *sd*(3)). Any MMC-compliant compact disc (CD), DVD, or Blu-ray disc (BD) drive should work. On DVDs and BDs, access to data tracks only is implemented.

The top level directory contains one file per disc track. The files are named cNNN, where c is a type character (a for audio tracks and d for data tracks) and NNN is the track number.

If the device can write discs and contains a writable disc, the top-level directory also contains an empty directory wd and, for CDs only, an empty directory wa. Files created in these directories appear in the top-level directory as new data or audio tracks, respectively, regardless of name.

At any time, any number of tracks may be open for reading or a single track may be open for writing. Writing a disc track is a quasi-real-time operation: the disc writer should be kept saturated with new data to avoid buffer underruns, but modern drives will be told to cope with underruns transparently. To ensure saturation, copying from a file system stored on local disk or memory is recommended.

To fixate a disc (close a recordable disc by writing its permanent table of contents), simply remove the wa or wd directory. The directory removed selects whether the disc is fixated as an audio or data disc; since each track carries its own type information, very few readers care which fixation type was used. Rewritable discs do not require fixation.

The top level directory also contains a ctl file, into which control messages may be echoed. The current control messages are:

format	Format the rewritable disc ($-RW$ or $-RE$) in the drive before initial use.
blank	Blank the entire rewritable disc in the drive.
quickblank	Blank only the table of contents on the rewritable disc in the drive.
eject	Eject the disc in the drive.
ingest	Ingest a disc into the drive.
speed kbps	Set the reading and writing speed to use, in units of 1,000-bytes-per-second. A value of best requests the optimal speed for the current drive and disc. CD 1x speed is 154; DVD 1x speed is 1350; BD 1x speed is 4608. Drives may round down the speed to one they support. To set reading and writing speeds separately, prefix the speeds with read or write, as in speed write 8192 or speed read 16384 write 8192. Note that most drives reset the reading and writing speed each time a new disc is inserted.

Reading the ctl file yields information about the drive. If the drive contains an audio CD, the first line will be an aux/cddb command that can be run to query an internet CD database to get a table of contents. Subsequent lines contain the current and maximum reading and writing speeds. Additional lines may further describe the current disc.

Aux/cddb takes 4 optional arguments. The -s option makes *aux/cddb* use *server* for the query instead of freedb.freedb.org. The -D option causes the raw database response from the server to be dumped to standard output. The -t option causes the time of each track to be appended to the normal output. -T is like -t but prints a final line with the total time.

EXAMPLES

Backup to a BD-R disc:

9fs boot
cdfs
tar cf /mnt/cd/wd/x /n/boot

Copy the audio tracks from a CD:

cdfs -d /dev/sd05 mkdir /tmp/songs cp /mnt/cd/a* /tmp/songs

Copy the tracks onto a blank CD inserted in the drive, and then fixate the disk as an audio CD.

cp /tmp/songs/* /mnt/cd/wa
rm /mnt/cd/wa

SOURCE

/sys/src/cmd/cdfs

SEE ALSO

sd(3), 9660srv (in dossrv(4)), mk9660(8)
http://www.t10.org optical disc interface standards

BUGS

Fixating a BD-R disc records only the first track in the disc's TOC. Any other tracks are still there and their data accessible via sd(3). There's no need to fixate data discs, except to prevent adding new tracks.

Closing a just-written DVD-R track can take minutes while the drive burns the unused part of the track reservation (for the whole disc). Thus only a single DVD-R track can be written on a DVD-R disc; use other media if you need more than one track per disc.

There are too many combinations of optical media, each with unique quirks, approximately the cross-product of these tuples: (CD DVD- DVD+ BD), (single-layer dual-layer), (-ROM -R -RW).

Only MMC-compliant disc readers and writers are supported, but it would be easy to add support for early CD writers if desired.

cfs - cache file system

SYNOPSIS

cfs -s [-dknrS] [-f partition]

cfs -a netaddr [-dknrS] [-f partition] [mtpt]

cfs -F srvfile [-dknrS] [-f partition] [mtpt]

DESCRIPTION

Cfs is a user-level file server that caches data from remote files onto a local disk. It is normally started by the kernel at boot time, though users may start it manually. *Cfs* is interposed between the kernel and a network connection to a remote file server to improve the efficiency of access across slow network connections such as modem lines. On each open of a file *cfs* checks the consistency of cached information and discards any old information for that file.

Cfs mounts onto *mtpt* (default /mnt/cfs) after connecting to the file server.

The options are:

a netaddr

dial the destination *netaddr* to connect to a remote file server. Exclusive with -F.

- d turn on debugging.
- f partition

use file *partition* as the cache disk partition.

F srvfile

open *srvfile* (often a file under /srv) to connect to a remote file server. Exclusive with -a.

- k keep cache contents even if they might have come from a different server. Cfs will obey -r even if -k is given.
- n mount the remote file server without authentication; often useful with -F.
- r reformat the cache disk partition.
- s the connection to the remote file server is on file descriptors 0 and 1.
- S turn on statistics gathering. A file called cfsctl at the root of the caching file system can be read to get statistics concerning number of calls/bytes on client and server sides and latencies.

All 9P messages except read, clone, and walk (see *intro*(5)) are passed through *cfs* unchanged to the remote server. If possible, a read is satisfied by cached data. Otherwise, the file server is queried for any missing data.

FILES

/dev/sdC0/cache

Default file used for storing cached data.

SOURCE

/sys/src/cmd/cfs

cifs – Microsoft™ Windows network filesystem client

SYNOPSIS

```
cifs [ -bDiv ] [ -d debug ] [ -a auth-method ] [ -s srvname ] [ -n called-name ] [ -k keyparam ] [ -m mntpnt ] [ -t dfs-timeout ] host [ share ... ]
```

DESCRIPTION

Cifs translates between Microsoft's file-sharing protocol (a.k.a. CIFS or SMB) and 9P, allowing Plan9 clients to mount file systems (shares or trees in MS terminology) published by such servers.

The root of the mounted directory contains one subdirectory per share, and a few virtual files give additional information. The arguments are:

-a auth-method Cifs authenticates using ntlmv2 by default, but alternative strategies may be selected using this option. Cifs eschews cleartext authentication, however it may be enabled with the plain auth method. The list of currently-supported methods is printed if no method name is supplied.

Windows server 2003 requires the ntlmv2 method by default, though it can be configured to be more flexible.

- -b Enable file ownership resolution in *stat*(2) calls. This requires an open and close per file and thus will slow *cifs* considerably; its use is not recommended.
- -d *debug* followed by non-whitespace separated list of debug options *debug* writes specific debug output to file descriptor 2. See source for more information.
- -D 9P request debug.
- -i By default *cifs* attempts to enforce case significance file and directory names, though objects which differ only in their case still cannot co-exist in the same directory. The -i option disables this behaveiour.
- -k *keyparam* lists extra parameters which will be passed to *factotum*(4) to select a specific key. The remote servers's domain is always included in the keyspec, under the assumption that all servers in a Windows domain share an authentication domain; thus *cifs* expects keys in *factotum* of the form:

key proto=pass dom=THEIR-DOMAIN service=cifs
 user=MY-USERNAME !password=XYZZY

- -m mntpnt set the mount point for the remote filesystem; the default is /n/host.
- -n called-name The CIFS protocol requires clients to know the NetBios name of the server they are attaching to, the *lcalled-name*. If this is not specified on the command line, *cifs* attempts to discover this name from the remote server. If this fails it will then try *host*, and finally it will try the name *SMBSERVER.
- -s *srvname* post the service as /srv/*srvname*.
- -t *dfs-timeout* sets the timeout in for DFS redirections it defaults to 100ms. This is a reasonable minimum, it should have a value just greater than the RTT to the most distant server being accessed.
- host The address of the remote server to connect to.
- share A list of share names to attach on the remote server; if none is given, *cifs* will attempt to attach all shares published by the remote host.

Synthetic Files

Several synthetic files appear in the root of the mounted filesystem:

- Shares Contains a list of the currently attached shares, with fields giving the share name, the share type, disk free space / capacity, and a descriptive comment from the server.
- Connection Contains the username used for authentication, server's called name, server's domain, server's OS, the time slip between the local host and the server, the

	Maximum Transfer Unit (MTU) the server requested, and optionally a flag indi- cating only guest access has been granted. The second line contains a list of capabilities offered by the server which is mainly of use for debugging <i>cifs</i> .
Users	Each line contains a user's name, the user's full name, and a descriptive com- ment.
Groups	Each line gives a group's name, and a list of the names of the users who are members of that group.
Sessions	Lists the users authenticated, the client machine's NetBios name or IP address, the time since the connection was established, and the time for which the con- nection has been idle.
Domains	One line per domain giving the domain name and a descriptive comment.
Workstations	One line per domain giving the domain name and a descriptive comment, the version number of the OS it is running, and comma-separated list of flags giving the features of that OS.
Dfsroot	Lists the top level DFS domains and the servers that provision them.
Dfscache	Contents of the DFS referal cache, giving the path prefix, the expiry time (or -1 for never), the measured RTT to the server in milliseconds, the server proximity (0 is local), the server name, and the share name on that server.

COMPATIBILITY

Cifs has been tested against aquarela, *cifsd*(8), Windows 95, NT4.0sp6, Windows server 2003, Windows server 2003, WinXP pro, Samba 2.0 (Pluto VideoSpace), and Samba 3.0.

Windows Vista require a hotfix (registry change) to support NTLMv2 without GSSAPI, see http://support.microsoft.com/kb/957441. Alternatively the -a option can be used to force *cifs* to use one of the less secure authentication mechnisms.

Windows 7 has dropped support for RAP, which is used to generate the synthetic files offered by *cifs*. RAP is also used to enumerate the shares offered by the remote host so remote share names must always be specified on the command line.

The NetApp Filer was supported by earlier releases, however recent attempts to mount one have failed. Should a server be available it is likely that this could be easily fixed.

SOURCE

/sys/src/cmd/cifs

SEE ALSO

factotum(4), cifsd(8)

BUGS

DFS support is unfinished, it will not follow referals that span servers.

Kerberos authentication is not supported.

NetBios name resolution is not supported, though it is now rarely used.

HISTORY

Cifs first appeared in Plan 9 from Bell Labs. It was updated to the author's latest revision for 9front (January, 2012).

consolefs, C, clog – file system for console access

SYNOPSIS

aux/consolefs[-m mntpt][-c consoledb]

C system

aux/clog console log system

DESCRIPTION

To ease administration of multiple machines one might attach many serial console lines to a single computer. *Consolefs* is a file system that lets multiple users simultaneously access these console lines. The consoles and permissions to access them are defined in the file *consoledb* (default /lib/ndb/consoledb). The format of *consoledb* is the same as that of other /lib/ndb files, *ndb*(6). Consoles are defined by entries of the form:

```
console=dirty dev=/dev/eia205
    uid=bignose
    gid=support
    speed=56200
    cronly=
```

Each console/dev pair represents the name of a console and the device associated with it. Consolefs presents a single level directory with up to three files per console: console, consolectl, and consolestat. Writes of console are equivalent to writes of dev and reads and writes of consolectl and consolestat are equivalent to reads and writes of devctl and devstat respectively. Consolectl and consolestat will not exist if the underlying dev does not provide them. Consolefs broadcasts anything it reads from dev to all readers of console. Therefore, many users can con(1) to a console, see all output, and enter commands.

The *cronly*= attribute causes newlines typed by the user to be sent to the console as returns. The *speed*=x attribute/value pair specifies a bit rate for the console. The default is 9600 baud. The *openondemand*= attribute causes the console device (*dev*) to be opened only when the corresponding *mntpt/console* file is open.

Access to the console is controlled by the *uid* and *gid* attributes/value pairs. The uid values are user account names. The gid values are the names of groups defined in *consolefs* by entries of the form:

```
group=support
    uid=bob
    uid=carol
    uid=ted
    uid=alice
```

Groups are used to avoid excessive typing. Using gid=x is equivalent to including a uid=y for each user y that is a member of x.

To keep users from inadvertently interfering with one another, notification is broadcast to all readers whenever a user opens or closes *name*. For example, if user boris opens a console that users vlad and barney have already opened, all will read the message:

[+boris, vlad, barney]

If vlad then closes, boris and barney will read:

[-vlad, boris, barney]

Consolefs posts the client end of its 9P channel in /srv/consolefs and mounts this locally in *mntpt* (default /mnt/consoles); remote clients must mount (see *bind*(1)) this file to see the consoles.

The rc(1) script C automates this procedure. It uses *import*(4) to connect to /mnt/consoles on the machine connected to all the consoles, then uses con(1) to connect to the console of the machine *system*. The script must be edited at installation by the local administration to identify the system that holds /mnt/consoles.

Aux/clog opens the file *console* and writes every line read from it, prefixed by the ASCII time to the file *log*.

An example of 2 consoles complete with console logging is:

```
% cat /lib/ndb/consoledb
group=sys
    uid=glenda
console=bootes dev=/dev/eia0 gid=sys
console=fornax dev=/dev/eia1 gid=sys
% aux/consolefs
% ls -p /mnt/consoles
bootes
bootes
bootesctl
fornax
fornaxctl
% clog /mnt/consoles/fornax /sys/log/fornax &
% clog /mnt/consoles/bootes /sys/log/bootes &
```

The console server's default name space must mount the consoles for C to import. This can be arranged by adding

mount /srv/consoles /mnt/consoles

to /lib/namespace.\$sysname.

FILES

/srv/consoles Client end of pipe to server.
/mnt/consoles Default mount point.
/lib/ndb/consoledb Default user database.

SOURCE

/sys/src/cmd/aux/consolefs.c
/rc/bin/C
/sys/src/cmd/aux/clog.c

BUGS

Changing the gid's or uid's while *consolefs* is running is detected by *consolefs*. However, to add new consoles one must restart *consolefs*.

cwfs, cwfs64, cwfs64x, fs64 - cached-worm file server, dump

SYNOPSIS

```
cwfs [-csC][-n service][-a announce-string]...[-m device-map][-f config-device]
```

DESCRIPTION

Cwfs is a cached-worm file server that runs as a user-mode program and can maintain file systems created by fs(4), the original Plan 9 file server that had its own kernel and operated a standalone system with disks and optical-disc jukebox attached. Unlike fs(4), which could only accept 9P connections over IL/IPv4 on Ethernets (or over Datakit and Cyclones, long ago), *cwfs* accepts 9P connections over any network medium and protocol that it can announce on, by default TCP (over IPv4 or IPv6). Given suitable 9P clients, one could even run 9P over *aan*(8) or *tls*(3).

The stock *cwfs* implements a 16K file system block size and 32-bit disk addresses, in order to be compatible with some existing file systems, notably *emelie*'s. These parameters can be changed by recompilation.

Cwfs places its server 9P connection in /srv/*name* and its command pipe in /srv/*name*.cmd, where *name* is the service name.

Options are:

- -f specify *config-device* other than the default /dev/sdC0/cwfs.
- -a announce on *announce-string*, can be specified multiple times.
- -C use a newer, faster, and incompatible cache-device layout. To convert an old file system's cache to the new layout, dump the file system, note the last superblock number, halt *cwfs*, restart *cwfs* with -cC, *recover* the file system, and start *cwfs* with -C thereafter.
- -c enter the file server's configuration mode before starting normal operation.
- -n overrides the *service* name of the file server's configuration.
- -s Post file descriptor zero in /srv/service and read and write protocol messages on file descriptor one.
- -m the file *device-map* contains a simple device name (e.g., w9) and a replacement per line. The device name is in the usual *filsys* notation of *fsconfig*(8). The replacement can be the name of an existing file (which *cwfs* will not grow) or another such device name. For example, the file
 - w0 /tmp/w0
 - h1 w2

would map accesses to device w0 to existing file /tmp/w0 and accesses to device h1 to device w2, if no file named w2 exists.

The file server normally requires all users except none to provide authentication tickets on each *attach*(5). This can be disabled using the noauth configuration command (see *fsconfig*(8)).

The group numbered 9999, normally called noworld, is special on the file server. Any user belonging to that group has attenuated access privileges. Specifically, when checking such a user's access to files, the file's permission bits are first ANDed with 0770 for normal files or 0771 for directories. The effect is to deny world access permissions to noworld users, except when walking directories.

The user none is always allowed to attach to emelie without authentication but has minimal permissions.

Emelie maintains three file systems on a combination of disks and write-once-read-many (WORM) magneto-optical disks.

other

- is a simple disk-based file system not backed by worm.
- main is a worm-based file system with a disk-based look-aside cache. The disk cache holds modified worm blocks to overcome the write-once property of the worm. The cache also holds recently accessed non-modified blocks to speed up the effective access time of the

worm. Occasionally (usually daily at 5AM) the modified blocks in the disk cache are *dumped*. At this time, traffic to the file system is halted and the modified blocks are relabeled to the unwritten portion of the worm. After the dump, the file system traffic is continued and the relabeled blocks are copied to the worm by a background process.

dump Each time the main file system is dumped, its root is appended to a subdirectory of the dump file system. Since the dump file system is not mirrored with a disk cache, it is read-only. The name of the newly added root is created from the date of the dump: /yyyy/mmdds. Here yyyy is the full year, mm is the month number, dd is the day number and s is a sequence number if more than one dump is done in a day. For the first dump, s is null. For the subsequent dumps s is 1, 2, 3, etc.

The root of the main file system that is frozen on the first dump of March 1, 1992 will be named /1992/0301/ in the dump file system.

Changes from fs

fs(4)'s IP configuration is ignored and the underlying system's is used.

Various other fs(4) commands have been omitted since they (or equivalents) can now be executed directly on the underlying CPU server, notably *date* and *passwd* (see *auth/wrkey*).

Files can be used directly as wren devices by giving a file name rooted at / or using double or single quotes. Such a file name can be appended to the w device instead of specifying target and lun numbers.

fs(4)'s device names h for IDE disks and m for Marvell SATA disks are not supported; use -m to map wren devices to appropriate names under $/dev/sd^*$.

The file server kernel seems to have scanned PCI buses in reverse order from the other Plan 9 kernels, so systems with multiple SCSI cards may find controller numbering reversed. -m can be used to compensate for this if you don't want to change *filsys* declarations.

The file server kernel's *config* field in NVRAM was overloaded in recent times to hold a *secstore*(1) key for the CPU hostowner. Since *cwfs* runs on a CPU kernel, the location of its configuration block must be supplied on the command line.

Disk labels are now implemented for 1 devices. At the first access of a side, *cwfs* will attempt to read the label and verify that it has the correct side number and byte order; if either is wrong, it will issue a warning. If the label cannot be read, *cwfs* will attempt to write a new label.

The original file server reserved the rest of the machines RAM for io buffers. Where *cwfs* running under the Plan 9 kernel reserves a settable percentage of the remaining user pages. The percentage is read from the environment variable fsmempercent which when not set is assumed to be 25% (default).

EXAMPLES

Place the root of the dump file system on /n/dump and show the modified times of the MIPS C compiler over all dumps in February, 1992:

cwfs w0 9fs dump 1s -1 /n/dump/1992/02??/mips/bin/vc

To get only one line of output for each version of the compiler:

ls -lp /n/dump/1992/02??/mips/bin/vc | uniq

SOURCE

/sys/src/cmd/cwfs

SEE ALSO

yesterday(1), fs(3), sd(3), fs(4), srv(4), fs(8), fsconfig(8) Sean Quinlan, "A Cached WORM File System", Software – Practice and Experience, December, 1991

Ken Thompson, Geoff Collyer, "The 64-bit Standalone Plan 9 File Server"

BUGS

For the moment, the file server serves both the old (9P1) and new (9P2000) versions of 9P, deciding which to serve by sniffing the first packet on each connection.

File system block size and disk address size (32- or 64-bit) are fixed at compilation time, and this is not easily changed.

dossrv, 9660srv, dosmnt, eject - DOS and ISO9660 file systems

SYNOPSIS

dossrv[-rsv][-f file][service]

9660srv[-9Jsv][-c clusters][-f file][service]

dosmnt *n mtpt*

eject[*n*]

DESCRIPTION

Dossrv is a file server that interprets DOS file systems. A single instance of *dossrv* can provide access to multiple DOS disks simultaneously.

Dossrv posts a file descriptor named *service* (default dos) in the /srv directory. To access the DOS file system on a device, use mount with the *spec* argument (see *bind*(1)) the name of the file holding raw DOS file system, typically the disk. If *spec* is undefined in the mount, *dossrv* will use *file* as the default name for the device holding the DOS system.

Normally *dossrv* creates a pipe to act as the communications channel between itself and its clients. The -s flag instructs *dossrv* to use its standard input and output instead. The kernels use this option if they are booting from a DOS disk. This flag also prevents the creation of an explicit service file in /srv.

The -v flag causes verbose output for debugging, while the -r flag makes the file system read-only.

The file attribute flags used by the DOS file system do not map directly to those used by Plan 9. Since there is no concept of user or group, permission changes via wstat (see *stat*(2)) will fail unless the same (read, write, execute) permissions are specified for user, group, and other. For example, removing write permission in Plan 9 corresponds to setting the read-only attribute in the DOS file system. Most of the other DOS attributes are not accessible.

Setting the exclusive use flag (DMEXCL) in Plan 9 corresponds to setting the system use attribute in the DOS file system. Such files are not actually restricted to exclusive use, but do merit special treatment that helps in the creation of boot disks: when *dossrv* allocates a new block for such a file (caused, say, by a write that fills the file's last allocated block), it succeeds only if it can arrange for the file to be stored contiguously on disk.

Since other operating systems do not guarantee that system files are laid out contiguously, the DMAPPEND mode bit is set in file stat information only when the file is currently contiguous. Attempts to set the DMAPPEND mode bit explicitly will cause *dossrv* to try to make the file contiguous, succeeding only if this is possible.

9660srv is similar to dossrv in specification, except that it interprets ISO9660 CD-ROM file systems instead of DOS file systems. Some CDs contain multiple directory trees describing the same set of files. 9660srv's first choice in such a case is a standard ISO9660 tree with Plan 9 system use fields; the second choice is a Microsoft "Joliet" tree, which allows long file names and Unicode characters; the third choice is a standard ISO9660 or High Sierra tree. The -9 flag causes 9660srv to ignore the Plan 9 system use fields, while the -J flag causes it to ignore the Joliet tree. The -c option sets the size of the RAM cache to clusters clusters of 128KB. The default clusters is 16, but a value of 5600 will cache an entire CD incrementally.

If the floppy drive has an ejection motor, *eject* will spit out the floppy from drive *n*, default 0.

SOURCE

```
/sys/src/cmd/dossrv
/sys/src/cmd/9660srv
/rc/bin/eject
/rc/bin/dosmnt
```

BUGS

The overloading of the semantics of the DMEXCL and DMAPPEND bits can be confusing.

execnet - network interface to program execution

SYNOPSIS

execnet[-n name][netdir]

DESCRIPTION

Execnet presents a network protocol directory (see, for example, ip(3)) called *netdir/name* (default /net/exec).

Once the protocol directory exists, dialing (see *dial*(2)) strings of the form *name* ! *cmd* will connect to a newly executed instance of *cmd*.

SOURCE

/sys/src/cmd/execnet

SEE ALSO

dial(2), ip(3)

exportfs, srvfs - file server plumbing

SYNOPSIS

exportfs[options]

```
srvfs[-dR][-p perm][-P patternfile][-e exportprog] name path
```

DESCRIPTION

Exportfs is a user level file server that allows Plan 9 cpu servers, rather than file servers, to export portions of a name space. It is usually started by other programs such as rcpu(1) after a secure channel has been established. *Exportfs* then acts as a relay file server: operations in the imported file tree are executed on the remote server and the results returned. This gives the appearance of exporting a name space from a remote machine into a local file tree.

The options are:

-d -f dbgfile

Log all 9P traffic to *dbgfile* (default /tmp/exportdb).

-P patternfile

Restrict the set of exported files. *Patternfile* contains one regular expression per line, to be matched against path names relative to the current working directory and starting with /. For a file to be exported, all lines with a prefix + must match and all those with prefix - must not match.

- -R Make the served name space read only.
- -r root

Serve the name space rooted at *root*.

-S service

Serve the result of mounting *service*. A separate mount is used for each attach(5) message, to correctly handle servers in which each mount corresponds to a different client *e.g.*, (rio(4)).

- -s equivalent to -r /; kept for compatibility.
- -m *msize*

Set the maximum message size that *exportfs* should offer to send (see *version*(5)); this helps tunneled 9P connections to avoid unnecessary fragmentation.

Srvfs invokes *exportprog* (default /bin/exportfs) to create a mountable file system from a name space and posts it at /srv/name, which is created with mode *perm* (default 0600). The name space is the directory tree rooted at *path*. The -d, -P, and -R options, if present, are relayed to *exportprog*.

EXAMPLES

To export the archive of one user for one month, except for secrets,

```
cd /n/dump
echo '+ ^/(2003(/10..(/usr(/glenda/?)?)?)?)?' > /tmp/pattern
echo '- \.(aes|pgp)$' >> /tmp/pattern
exportfs -P /tmp/pattern
```

Use *srvfs* to enable mounting of an FTP file system (see *ftpfs*(4)) in several windows, or to publish a /proc (see *proc*(3)) with a broken process so a remote person may debug the program:

srvfs ftp /n/ftp
srvfs broke /mnt/term/proc

Use *srvfs* to obtain a copy of a service to be manipulated directly by a user program like *nfsserver*(8):

srvfs nfs.boot /srv/boot aux/nfsserver -f /srv/nfs.boot

Use *srvfs* to spy on all accesses to a particular subtree:

srvfs -d spy /
tail -f /tmp/exportdb &
mount /srv/spy /n/spy
cd /n/spy; ls

SOURCE

/sys/src/cmd/exportfs /sys/src/cmd/srvfs.c

SEE ALSO

rcpu(1)

ext2srv - ext2 file system

SYNOPSIS

ext2srv[-vrs][-f file][-p passwd][-g group][service]

DESCRIPTION

Ext2srv is a file server that interprets the Linux Second Extended File System. A single instance of *ext2srv* can provide access to multiple ext2 partitions simultaneously.

Ext2srv posts a file descriptor named *service* (default ext2) in the /srv directory. To access an ext2 file system on a device, use mount with the *spec* argument (see *bind*(1)) the name of the file holding the raw ext2 file system, typically the disk or partition. If *spec* is undefined in the mount, *ext2srv* will use *file* as the default name for the device holding the file system.

Normally ext2srv creates a pipe to act as the communications channel between itself and its clients. The -s flag instructs ext2srv to use its standard input and output instead. This flag also prevents the creation of an explicit service file in /srv.

The -v flag causes verbose output for debugging, while the -r flag (recommended) makes the file system read-only. The optional -p and -g flags specify Unix-format password (respectively group) files that give the mapping between the numeric user- and group-ID numbers in the ext2 file system and the strings reported by Plan 9 status inquiries.

There is no authentication or permission checking. Anyone who can access the ext2 file system will have full access to all its files, including write access if ext2srv is not started with the -r flag, irrespective of file ownership and permission flags.

Some file system state is cached in memory, and may be flushed only when the file system is unmounted. Therefore if *ext2srv* is stopped or the machine is rebooted while an ext2 file system is still mounted, the superblock on the device will have been marked 'not valid' (unless the -r flag was used), and a *fsck* will be required before that file system may be mounted again.

BUGS

There is no authentication or permission checking. The implementation has not tracked any changes to the ext2 specification since it was written. There may be other bugs. It is advisable to use *ext2srv* in read-only mode whenever possible.

AUTHOR

Bodet Laurent (bl@mime.univ-paris8.fr), with later updates by Russ Cox and Richard Miller.

factotum, fgui, userpasswd - authentication agent

SYNOPSIS

```
auth/factotum[-DdknpuS][-a asaddr][-s srvname][-m mtpt]
```

auth/factotum -g attribute=value ... attribute? ...

auth/fgui

auth/userpasswd fmt

DESCRIPTION

Factotum is a user-level file system that acts as the authentication agent for a user. It does so by managing a set of *keys*. A key is a collection of information used to authenticate a particular action. Stored as a list of *attribute=value* pairs, a key typically contains a user, an authentication domain, a protocol, and some secret data.

Factotum presents a two level directory. The first level contains a single directory factotum, which in turn contains:

rpc	each open represents a new private channel to <i>factotum</i>
proto	when read lists the protocols available
confirm	for confiming the use of key
needkey	allows external programs to control the addition of new keys
log	a log of actions
ctĺ	for maintaining keys; when read, it returns a list of keys. For secret attributes, only
	the attribute name follow by a ? is returned.

In any authentication, the caller typically acts as a client and the callee as a server. The server determines the authentication domain, sometimes after a negotiation with the client. Authentication always requires the client to prove its identity to the server. Under some protocols, the authentication is mutual. Proof is accomplished using secret information kept by factorum in conjunction with a cryptographic protocol.

Factotum can act in the role of client for any process possessing the same user id as it. For select protocols such as p9sk1 and dp9ik it can also act as a client for other processes provided its user id may speak for the other process' user id (see *authsrv*(6)). *Factotum* can act in the role of server for any process.

Factotum's structure is independent of any particular authentication protocol. *Factotum* supports the following protocols:

p9sk1 legacy Plan 9 shared key protocol described in <i>authsrv</i> (6)'s "Ticket Service" and "P9sk1" sections.	1
dp9ik extended version of p9sk1 that adds password bruteforce resistance and forward secrecy (see <i>authsrv</i> (6)'s "Password authenticated key exchange" and "Dp9ik" sections).	
p9cr legacy Plan 9 protocol that can use either p9sk1 keys or SecureID tokens.	
apop the challenge/response protocol used by POP3 mail servers.	
cram the challenge/response protocol also used by POP3 mail servers.	
chap the challenge/response protocols used by PPP and PPTP.	
mschap a proprietary Microsoft challenge/response protocol also used by PPP, PPTP and CIFS.	ł
mschapv2 version two of Microsofts challenge/response protocol used by WPA.	
mschap2 Microsofts NTLMv2 challenge/response protocol used by CIFS.	
rsa RSA public key decryption, used by SSH and TLS.	
pass passwords in the clear.	
vnc vnc(1)'s challenge/response.	
wpapsk WPA passwords for wireless ethernet cards.	

The options are:

-a supplies the address of the authentication server to use. Without this option, it will attempt to find an authentication server by querying the connection server, the file <mtpt>/ndb,

and finally the network database in /lib/ndb.

- -m specifies the mount point to use, by default /mnt.
- -s specifies the service name to use. Without this option, *factotum* does not create a service file in /srv.
- -D turns on 9P tracing, written to standard error.
- -d turns on debugging, written to standard error.
- -g causes the agent to prompt for the key, write it to the ctl file, and exit. The agent will prompt for values for any of the attributes ending with a question mark (?) and will append all the supplied *attribute = value* pairs. See the section on key templates below.
- -n don't look for a secstore.
- -S indicates that the agent is running on a CPU server. On starting, it will attempt to get p9sk1 and dp9ik keys from NVRAM using readnvram (see *authsrv*(2)), prompting for anything it needs. It will never subsequently prompt for a key that it doesn't have. This option is typically used by the kernel at boot time.
- -k causes the NVRAM to be written. It is only valid with the -S option. This option is typically used by the kernel at boot time.
- -u causes the agent to prompt for user id and writes it to /dev/hostowner. It is mutually exclusive with -k and -S. This option is typically used by the kernel at boot time.
- -p causes the agent not to mark itself 'private' via *proc*(3), so that it can be debugged. It is implied by -d.

Fgui is a graphic user interface for confirming key usage and entering new keys. It hides the window in which it starts and waits reading requests from confirm and needkey. For each requests, it unhides itself and waits for user input. See the sections on key confirmation and key prompting below.

Userpasswd queries and prints a cleartext user/password pair from factotum for the proto=pass key tuple specified in *fmt*. This can be used by shell scripts to do cleartext password authentication.

Key Tuples

A key tuple is a space delimited list of attribute=value pairs. An attribute whose name begins with an exclamation point (!) does not appear when reading the ctl file. The required attributes depend on the authentication protocol.

Dp9ik, p9sk1 and p9cr all require a key with proto=dp9ik or proto=p9sk1, a dom attribute identifying the authentication domain, a user name valid in that domain, and either a !password or !hex attribute specifying the password or hexadecimal secret to be used. Here is an example:

proto=dp9ik dom=9front user=glenda !password=secret

Apop, cram, chap, and mschap, require a key with a proto attribute whose value matches the protocol, in addition to server, user, and !password attributes; e.g.

proto=apop server=mit.edu user=rsc !password=nerdsRus
Vnc is similar but does not require a user attribute.

Pass requires a key with proto=pass in addition to user and !password attributes; e.g.

proto=pass user=tb !password=does.it.matter

Rsa requires a key with proto=rsa in addition to all the hex attributes defining an RSA key: ek, n, !p, !q, !kp, !kq, !c2, and !dk. By convention, programs using the RSA protocol also require a service attribute set to ssh or tls.

All keys can have additional attributes that act either as comments or as selectors to distinguish them in the auth(2) library calls.

The factotum owner can use any key stored by factotum. Any key may have one or more owner attributes listing the users who can use the key as though they were the owner. For example, the TLS and SSH host keys on a server often have an attribute owner=* to allow any user (and in particular, none) to run the TLS or SSH server-side protocol.

Any key may have a role attribute for restricting how it can be used. If this attribute is missing, the key can be used in any role. The possible values are:

client

for authenticating outbound calls

server

for authenticating inbound calls

speakfor

for authenticating processes whose user id does not match *factotum*'s.

If a key has a disabled attribute (with any value), the key is not used during any protocols. Factotum automatically marks keys with disabled=by.factotum when they fail during certain authentication protocols (in particular, the Plan 9 ones).

Whenever *factotum* runs as a server, it must have dp9ik or p9sk1 keys in order to communicate with the authentication server for validating passwords and challenge/responses of other users.

Key Templates

Key templates are used by routines that interface to *factotum* such as auth_proxy and auth_challenge (see *auth*(2)) to specify which key and protocol to use for an authentication. Like a key tuple, a key template is also a list of *attribute=value* pairs. It must specify at least the protocol and enough other attributes to uniquely identify a key, or set of keys, to use. The keys chosen are those that match all the attributes specified in the template. The possible attribute/value formats are:

attr=val The attribute *attr* must exist in the key and its value must exactly match *val*

attr? The attribute *attr* must exist in the key but its value doesn't matter.

attr The attribute *attr* must exist in the key with a null value

Key templates are also used by factotum to request a key either via an RPC error or via the needkey interface. The possible attribute/value formats are:

attr=val	This pair	must remain	unchanged

attr? This attribute needs a value

attr The pair must remain unchanged

Control and Key Management

A number of messages can be written to the control file. The messages are:

key attribute-value-list

add a new key. This will replace any old key whose public, i.e. non ! attributes, match.

delkey attribute-value-list

delete a key whose attributes match those given.

debug

toggle debugging on and off, i.e., the debugging also turned on by the -d option.

By default when factotum starts it looks for a *secstore*(1) account on \$auth for the user and, if one exists, prompts for a secstore password in order to fetch the file *factotum*, which should contain control file commands. An example would be

key dom=x.com proto=p9sk1 user=boyd !hex=26E522ADE2BBB2A229

key proto=rsa service=ssh size=1024 ek=3B !dk=...

where the first line sets a password for challenge/response authentication, strong against dictionary attack by being a long random string, and the second line sets a public/private keypair for ssh authentication.

Confirming key use

The confirm file provides a connection from *factotum* to a confirmation server, normally the program *auth/fgui*. Whenever a key with the confirm attribute is used, *factotum* requires confirmation of its use. If no process has confirm opened, use of the key will be denied. However, if the file is opened a request can be read from it with the following format:

confirm tag=tagno <key template>

The reply, written back to confirm, consists of string:

tag=tagno answer=xxx

If *xxx* is the string yes then the use is confirmed and the authentication will proceed. Otherwise, it fails.

Confirm is exclusive open and can only be opened by a process with the same user id as *factotum*.

Prompting for keys

The needkey file provides a connection from *factotum* to a key server, normally the program *auth/fgui*. Whenever *factotum* needs a new key, it first checks to see if needkey is opened. If it isn't, it returns a error to its client. If the file is opened a request can be read from it with the following format:

needkey tag=tagno <key template>

It is up to the reader to then query the user for any missing fields, write the key tuple into the ctl file, and then reply by writing into the needkey file the string:

tag=*tagno*

Needkey is exclusive open and can only be opened by a process with the same user id as *factotum*.

The RPC Protocol

Authentication is performed by

- 1) opening rpc
- 2) setting up the protocol and key to be used (see the start RPC below),
- 3) shuttling messages back and forth between *factotum* and the other party (see the read and write RPC's) until done
- 4) if successful, reading back an AuthInfo structure (see authsrv(2)).

The RPC protocol is normally embodied by one of the routines in *auth*(2). We describe it here should anyone want to extend the library.

An RPC consists of writing a request message to rpc followed by reading a reply message back. RPC's are strictly ordered; requests and replies of different RPC's cannot be interleaved. Messages consist of a verb, a single space, and data. The data format depends on the verb. The request verbs are:

start attribute-value-list

start a new authentication. Attribute-value-pair-list must include a proto attribute, a role attribute with value client or server, and enough other attributes to uniquely identify a key to use. A start RPC is required before any others. The possible replies are:

- ok start succeeded.
- error *string*

where *string* is the reason.

read get data from *factotum* to send to the other party. The possible replies are:

ok read succeeded, this is zero length message.

ok *data*

read succeeded, the data follows the space and is unformatted.

- done authentication has succeeded, no further RPC's are necessary
- done haveai

authentication has succeeded, an AuthInfo structure (see *auth*(2)) can be retrieved with an authinfo RPC

phase string

its not your turn to read, get some data from the other party and return it with a write RPC.

error *string* authentication failed, *string* is the reason.

protocol not started

a start RPC needs to precede reads and writes

needkey attribute-value-list

a key matching the argument is needed. This argument may be passed as an argument to *factotum* -g in order to prompt for a key. After that, the authentication may proceed, i.e., the read restarted.

write data

send data from the other party to *factotum*. The possible replies are:

ok the write succeeded

needkey *attribute-value-list* see above

toosmall *n*

the write is too short, get more data from the other party and retry the write. n specifies the maximum total number of bytes.

phase string

its not your turn to write, get some data from *factotum* first.

done see above

done haveai see above

authinfo

retrieve the AuthInfo structure. The possible replies are:

ok data

data is a marshaled form of the AuthInfo structure.

error string

where *string* is the reason for the error.

attr retrieve the attributes used in the start RPC. The possible replies are:

ok attribute-value-list

error string

where *string* is the reason for the error.

SOURCE

/sys/src/cmd/auth/factotum

SEE ALSO

authsrv(6)

flashfs - journalling file system for flash memory

SYNOPSIS

```
aux/flashfs[-Dr][-n nsect][-z sectsize][-f file][-m mountpoint]
```

DESCRIPTION

Flashfs interprets the journal-based file system created by *mkflashfs*(8) and stored in *file* (default /dev/flash/fs) so that it can be mounted into a Plan 9 file system. *Flashfs* is typically used to create a stand alone file system from a small persistent storage device, such as an erasable flash memory. It does not authenticate its clients and assumes each group has a single member with the same name.

The -s option causes *flashfs* to post its channel on #s/flashfs. *Flashfs* mounts itself on *mountpoint* (default /n/brzr). The -D option turns on 9P debugging output. The -r option makes the file system read-only.

The files and directory structure are divided into *sectsize* (default 4096) byte blocks. Larger blocks make large files more compact but take longer to access. Supplying the -n option forces *file* to contain exactly *nsect* sectors.

SOURCE

/sys/src/cmd/aux/flashfs

SEE ALSO

paqfs(4), sacfs(4), mkflashfs(8)

fs – file server, dump

SYNOPSIS

none

DESCRIPTION

The file server was the main file system for Plan 9. It was a stand-alone system that ran on a separate computer. It served the Plan 9 protocol via the IL/IP protocols on Ethernets. The name of the main file server at Murray Hill was emelie.

The file server normally requires all users except none to provide authentication tickets on each *attach*(5). This can be disabled using the noauth configuration command (see *fsconfig*(8)).

The group numbered 9999, normally called noworld, is special on the file server. Any user belonging to that group has attenuated access privileges. Specifically, when checking such a user's access to files, the file's permission bits are first ANDed with 0770 for normal files or 0771 for directories. The effect is to deny world access permissions to noworld users, except when walking directories.

The user none is always allowed to attach to emelie without authentication but has minimal permissions.

Emelie maintains three file systems on a combination of disks and write-once-read-many (WORM) magneto-optical disks.

other

is a simple disk-based file system not backed by the worm.

- main is a worm-based file system with a disk-based look-aside cache. The disk cache holds modified worm blocks to overcome the write-once property of the worm. The cache also holds recently accessed non-modified blocks to speed up the effective access time of the worm. Occasionally (usually daily at 5AM) the modified blocks in the disk cache are *dumped*. At this time, traffic to the file system is halted and the modified blocks are relabeled to the unwritten portion of the worm. After the dump, the file system traffic is continued and the relabeled blocks are copied to the worm by a background process.
- dump Each time the main file system is dumped, its root is appended to a subdirectory of the dump file system. Since the dump file system is not mirrored with a disk cache, it is read-only. The name of the newly added root is created from the date of the dump: /yyyy/mmdds. Here yyyy is the full year, mm is the month number, dd is the day number and s is a sequence number if more than one dump is done in a day. For the first dump, s is null. For the subsequent dumps s is 1, 2, 3, etc.

The root of the main file system that is frozen on the first dump of March 1, 1992 will be named /1992/0301/ in the dump file system.

EXAMPLES

Place the root of the dump file system on /n/dump and show the modified times of the MIPS C compiler over all dumps in February, 1992:

9fs dump

ls -l /n/dump/1992/02??/mips/bin/vc

To get only one line of output for each version of the compiler:

ls -lp /n/dump/1992/02??/mips/bin/vc | uniq

Make the other file system available in directory /n/emelieother:

mount -c /srv/boot /n/emelieother other

SOURCE

/sys/src/fs

SEE ALSO

yesterday(1), cwfs(4), srv(4), fs(8)

Sean Quinlan, "A Cached WORM File System", Software - Practice and Experience, December,

1991

BUGS

For the moment, the file server serves both the old (third edition) and new (fourth edition) versions of 9P, deciding which to serve by sniffing the first packet on each connection.

Required IL, thus now deprecated.

ftpfs - file transfer protocol (FTP) file system

SYNOPSIS

```
ftpfs [ -/dqntc ] [ -m mountpoint ] [ -a password ] [ -e ext ] [ -k keyspec ] [ -o os ] [ -r
remoteroot ] system
```

DESCRIPTION

Ftpfs dials the TCP file transfer protocol (FTP) port, 21, on *system* and mounts itself (see *bind*(2)) on *mountpoint* (default /n/ftp) to provide access via FTP to files on the remote machine. *Ftpfs* attempts to use FTP's 'passive' mode but falls back to using 'active' mode if that fails. If required by the remote machine, *ftpfs* will ask *factotum*(4) for a key matching the pattern

proto=pass service=ftp server=system user? !password? keyspec

(If *factotum* does not have such a key, *factotum* will prompt the user for one.)

The user names ftp and anonymous conventionally offer guest/read-only access to machines. Anonymous FTP may be called without using factorum by using the -a option and specifying the *password*.

By default the file seen at the mount point is the user's remote home directory if he has one. The option -/ forces the mount point to correspond to the remote root. The option $-\mathbf{r}$ forces the mount point to correspond to the remote directory *remoteroot*.

To avoid seeing startup messages from the server use option -q. To see all messages from the server use option -d.

By default ftpfs only caches while a file operation is in progress. The -c flag enables caching, increasing performance but allowing outdated file and directory data to persist.

Some systems will hangup an ftp connection that has no activity for a given period. The -K option causes ftp to send a NOP command every 15 seconds to attempt to keep the connection open. This command can cause some servers to hangup, so you'll have to feel your way.

The -t option causes *ftpfs* to negotiate TLS encryption with the server.

To terminate the connection, unmount (see *bind*(1)) the mount point.

Since there is no specified format for metadata retrieved in response to an FTP directory request, *ftpfs* has to apply heuristics to steer the interpretation. Sometimes, though rarely, these heuristics fail. The following options are meant as last resorts to try to steer interpretation.

A major clue to the heuristics is the operating system at the other end. Normally this can be determined automatically using the FTP SYST command. However, in some cases the server doesn't implement the SYST command. The -o option will force the case by specifying the name of the operating system. Known system types are: UNIX, SUN, TOPS, Plan9, VM, VMS, MVS, NetWare, OS/2, TSO, and WINDOWS_NT.

Some systems and/or FTP servers return directory listings that don't include the file extension. The -e option allows the user to specify an extension to append to all remote files (other than directories).

Finally, there are two FTP commands to retrieve the contents of a directory, LIST and NLST. LIST is approximately equivalent to ls -l and NLST to ls. *Ftpfs* normally uses LIST. However, some FTP servers interpret LIST to mean, give a wordy description of the file. *Ftpfs* normally notices this and switches to using NLST. However, in some rare cases, the user must force the use of NLST with the -n option.

EXAMPLE

You want anonymous FTP access to the system export.lcs.mit.edu. The first *import*(4) command is only necessary if your machine does not have access to the desired system, but another, called gateway in this example, does.

import gateway /net
ftpfs -a yourname@yourmachine export.lcs.mit.edu

SOURCE

/sys/src/cmd/ip/ftpfs

SEE ALSO

bind(2)

BUGS

Symbolic links on remote Unix systems will always have mode 0777 and a length of 8.

After connecting to a TOPS-20 system, the mount point will contain only one directory, usually /n/ftp/PS:<ANONYMOUS>. However, walking to any valid directory on that machine will succeed and cause that directory entry to appear under the mount point.

If caching is active, remote changes that have been cached will not be visible. Attempting to walk to *directory* /.flush.ftpfs will flush *directory* from the cache, thus forcing *ftpfs* to re-read it.

There is no way to issue the appropriate commands to handle special synthetic FTP file types such as directories that automatically return a tar of their contents.

Ftpfs makes copies in /tmp of files being transferred, so its effects might not be immediate. If there is enough main memory, you might want to run *ramfs*(4) first.

Filenames containing spaces will confuse *ftpfs* (and other FTP clients).

hgfs – mercurial file system

SYNOPSIS

hgfs [-D][-m mtpt][-s service][dir]

DESCRIPTION

Mercurial is a distributed version control system. It tracks and organizes files and keeps a change history of them. The file revisions are stored as packed deltas in a repository that can be checked out with the hg(1) program.

Hgfs serves a mercurial repository as a read-only filesystem where each file revision and its metadata is accessible as files.

The repository may be specified by passing the working directory *dir* as the final argument. When omitted, *hgfs* locates the repository by walking upwards from the current working directory until the .hg sub-directory is found. If no *mtpt* was specified with -m, then hgfs will mount itself on /mnt/hg (default). When a *service* name is given with the -s flag, the 9p service pipe /srv/service is created and may be mounted from another namespace. The -D flag enables 9p debug messages.

The root of the served filesystem contains directories each corresponding to a specific changeset revision in the repository.

Revision directories are named by a revision id which takes the form [d.]h, where d is the decimal revision number starting from 0 and h is the hexadecimal hash of the changeset. Both the revision number d and the hash h are able to identify a revision uniquely; only one of them needs to be given when walking the root directory. The hexadecimal hash may be shortened so long as the resulting lookup yields a unique result. The special name tip corresponds to the latest revision but does not appear in the directory listing.

In each revision directory the following files can be found:

- rev contains the revision id of the changeset.
- rev1 contains the parent revision id of the changeset.
- rev2 If the changeset was a merge, contains the other parent revision id. Otherwise, a zero size file.
- log The log file contains a list of file names, separated by a newline, that where affected in this changeset. Files that are listed in the log but are not accessible in the files or changes directories have been deleted in this changeset.
- who committer of the changeset.
- why commit message of the changeset.

files

A directory that contains a snapshot of the tree at the time the changeset was committed.

To retrieve the *n*th past version of a file relative to the changeset, one can append *.n* to the filename. Appending *.revn* yields a file that contains its revision id as text. Note that appending *.rev0* or *.rev* yields the file containing the revision id of the changeset when the file was last modified and *.0* yields the same file as when omitting the appendix.

changes

Same as files, but contains only the changed files of the changeset.

SOURCE

/sys/src/cmd/hgfs

SEE ALSO

hg(1)

HISTORY

Hgfs first appeared in 9front (June, 2011).

hjfs – file server

SYNOPSIS

hjfs[-A][-f file][-m mem][-n name][-a announce-string]...[-r][-S][-s]

DESCRIPTION

Hjfs is an experimental file server with support for a cache and an archival dump on a single partition.

The options are:

- -A Require auth.
- -f file Use file as the disk.
- -m *mem* Allocate *mem* megabytes to use for cache.
- -n name Use name as the name of the service.
- -a announce-string
 - will announce and listen on the specified network address.
- $-\mathbf{r}$ Ream the file system, erasing all of the old data.
- -S Ignore permissions.
- -s Read and write protocol messages on standard file descriptors zero and one.

SOURCE

/sys/src/cmd/hjfs

SEE ALSO

history(1), yesterday(1), cwfs(4), hjfs(8), prep(8), sd(3)

BUGS

Hjfs is a work in progress.

httpfile - serve a single web file

SYNOPSIS

ip/httpfile[-9d][-c count][-f file][-m mtpt][-s srvname] url

DESCRIPTION

Httpfile serves the web page specified by the URL *url* as a new file *file* in the directory *mtpt*. The default *file* is the last path element of the URL, and the default *mtpt* is the current directory.

Httpfile does not download large files all at once. Instead, it requests 64-kilobyte blocks as they are needed to satisfy reads, caching a few blocks in memory at a time.

The -D and -d options enable a trace of the 9P traffic and general debugging messages.

The -s option causes *httpfile* to post the 9P service as /srv/srvname and disables the default mount.

The -c option sets the number of file blocks kept cached in memory (default 32).

EXAMPLE

Mount an ISO image on a web server:

ip/httpfile http://www.r-36.net/9front/9front.iso
9660srv
mount /srv/9660 /n/iso 9front.iso

SOURCE

/sys/src/cmd/ip/httpfile.c

SEE ALSO

hget(1), webfs(4)

DIAGNOSTICS

Httpfile requires *webfs*(4) service mounted on /mnt/web to work.

import - import a name space from a remote system

SYNOPSIS

import [options] system file [mountpoint]

import -B [options] mountpoint [cmd [args ...]]

DESCRIPTION

This tool is deprecated and has been replaced by *rimport* (see *rcpu*(1)).

Import allows an arbitrary *file* on a remote *system* to be imported into the local name space. Usually *file* is a directory, so the complete file tree under the directory is made available.

A process is started on the remote machine, with authority of the user of *import*, to perform work for the local machine using the *oexportfs*(4) service. The default port used is TCP 17007. If *mountpoint* is omitted *import* uses the name of the remote *file* as the local mount point.

The options are:

- -a -b -c -C Control the construction of union directories, as in *mount* and *bind*(1). Only valid when *file* is a directory.
- -A Skip the authentication protocol. This is useful for connecting to foreign systems like Inferno.
- -z Bypass the initial protocol request for which remote tree to serve. This is necessary when the remote *oexportfs*(4) is running with the -r or -S options which pre-select a file tree to serve. The exception is if both sides are operating in the -B backwards mode.
- -B Run in ''backwards'' mode, described below.
- -E enc Push an encryption protocol on its network connection. The supported protocols are clear (the default, no protocol) and ssl. There are plans to make tls available.
- -e 'enc hash' Specify the encryption and hash algorithms to use for encrypting and authenticating the wire traffic (see ssl(3)). The defaults are $rc4_256$ and sha1.
- -k keypattern Use keypattern to select a key to authenticate to the remote side (see auth(2)).
- -p Push the *aan*(8) filter onto the connection to protect against temporary network outages.
- -n Specify announce string for *aan*(8) filter when run in "backwards" mode.
- -s *name* Post the connection's mountable file descriptor as /srv/*name*.

The -B option runs *import* in "backwards" mode. In this mode, *import* runs a *p9any* authentication (as server) over its file descriptor 0 (expected to be an incoming network connection from oexportfs -B), mounts the connection onto *mntpt*, and optionally runs *cmd args*.

EXAMPLES

Assume a machine kremvax that has IP interfaces for the company intranet and the global internet mounted on */net* and */net.alt* respectively. Any machine inside the company can get telnet out to the global internet using:

import -a kremvax /net.alt
telnet /net.alt/tcp!ucbvax

Suppose that the machine moscvax has access to a private file server containing public web pages that need to be served by the less-trusted server webvax. Webvax runs the following listener (see *listen*(8)) on TCP port 999:

#!/bin/rc
import -B -s rowebfs /usr/web /bin/restarthttpd

When moscvax boots, it runs

```
oexportfs -R -r /usr/web -B tcp!webvax!999
```

to serve a read-only copy of /usr/web to webvax. When webvax gets the call, import mounts the served tree onto its own /usr/web and then runs /bin/restarthttpd to restart *httpd*(8).

SOURCE

/sys/src/cmd/import.c

SEE ALSO

rcpu(1), bind(1), ssl(3), oexportfs(4), srv(4), aan(8), listen(8), cs in ndb(8)

iostats - file system to measure I/O

SYNOPSIS

iostats[-d][-C][-f dbfile] cmd[args...]

DESCRIPTION

lostats is a user-level 9p filter that interposes itself between a program and the regular file server, which allows it to gather statistics of file system use at the level of the Plan 9 file system protocol, 9P. After a program exits a report is printed on standard error.

The report consists of three sections. The first section reports the amount of user data in read and write messages sent by the program and the average rate at which the data was transferred. The protocol line reports the amount of data sent as message headers, that is, protocol overhead. The rpc line reports the total number of file system transactions.

The second section gives the number of messages, the fastest, slowest, and average turn around time and the amount of data involved with each 9P message type. The final section gives an I/O summary for each file used by the program in terms of opens, reads and writes.

If the -d flag is present, a debugging log including all traffic is written to *dbfile* (default iostats.out).

The -C flag sets the MCACHE flag on the mount which allows the kernel to cache (see *bind*(1)).

EXAMPLE

Display summary of file I/O incurred by Is(1):

iostats ls

Start a new shell, displaying all 9P traffic caused by the shell or its children:

```
iostats -df /fd/1 rc
```

SOURCE

```
/sys/src/cmd/iostats.c
```

SEE ALSO

dup(3), exportfs(4)

BUGS

Poor clock resolution means that large amounts of I/O must be done to get accurate rate figures.

Can be fooled by programs that do fresh mounts outside its purview, or by the use of names of files with content that can vary by process (e.g., #d, /dev/cons).

keyfs, warning - authentication database files

SYNOPSIS

```
auth/keyfs[-p][-w[np]][-mmntpt][-r][keyfile]
```

auth/warning[-n][-p]

DESCRIPTION

Keyfs serves a two-level file tree for manipulating authentication information. It runs on the machine providing authentication service for the local Plan 9 network, which may be a dedicated authentication server or a CPU server. The programs described in *auth*(8) use *keyfs* as their interface to the authentication database.

Keyfs reads and decrypts file keyfile (default /adm/keys) using the DES or AES key, which is by default read from $\#_{\Gamma}/nv_{\Gamma}am$ (see rtc(3)). With option -p, keyfs prompts for a password from which the key is derived. Keyfile holds a 41-byte (57-byte for AES) record for each user in the database. Each record contains the user's name, DES key, status, warning status, expiration date, secret password and AES key. The name is a null-terminated UTF string NAMELEN bytes long. The status is a byte containing binary 0 if the account is enabled, 1 if it is disabled. Warning status is a byte containing the number of user expiration notifications. The expiration date is fourbyte little-endian integer which represents the time in seconds since the epoch (see date(1)) at which the account will expire. The secret password is a null-terminated UTF string SECRETLEN bytes long. If any changes are made to the database that affect the information stored in keyfile, a new version of the file is written.

If the $-\mathbf{r}$ option is given, the database is mounted 'read-only' and no changes are permitted.

There are two authentication databases, one for Plan 9 user information, and one for SecureNet user information. A user need not be installed in both databases but must be installed in the Plan 9 database to connect to a Plan 9 server.

Keyfs serves an interpretation of the *keyfile* in the file tree rooted at *mntpt* (default /mnt/keys). Each user *user* in *keyfile* is represented as the directory *mntpt*/*user*.

Making a new directory in *mntpt* creates a new user entry in the database. Removing a directory removes the user entry, and renaming it changes the name in the entry. Such changes are reflected immediately in *keyfile*. *Keyfs* does not allow duplicate names when creating or renaming user entries.

All files in the user directories except for key and aeskey contain UTF strings with a trailing newline when read, and should be written as UTF strings with or without a trailing newline. Key contains the DESKEYLEN-byte encryption key for the user. Aeskey contains the AESKEYLEN-byte encryption key.

The following files appear in the user directories.

- key The authentication key for the user. If the user's account is disabled or expired, reading this file returns an error. Writing *key* changes the key in the database.
- aeskey The AES encryption key for the user.
- secret The secret password.
- log The number of consecutive failed authentication attempts for the user. Writing the string bad increments this number; writing good resets it to 0. This number is not stored in *keyfile*, and is initialized to 0 when *keyfs* starts. When the number reaches a multiple of ten, *keyfs* temporarily disables the account for that many seconds. Reads from the key or secret files during this time return the error "user in purgatory."
- status The current status of the account, either ok or disabled. Writing ok enables the account; writing disabled disables it.
- expire The expiration time for the account. When read, it contains either the string never or the time in seconds since the epoch that the account will expire. When written with strings of the same form, it sets the expiration date for the user. If the expiration date is reached, the account is not disabled, but *key* cannot be read without an error.

If the -w option is on, *keyfs* runs the command *warning* once every 24 hours to mail people about expiring keys. Warnings are sent 14 days and 7 days prior to expiration. The argument to -w,

either p or n, is passed to *warning* to restrict the warnings to the Plan 9 or SecureNet database. The default for *keyfs* is not to call *warning* at all; *warning's* own default is to warn about both. The files /adm/netkeys.who and /adm/keys.who are used to find the mail addresses to send to. The first word on each line identifies a user. Any subsequent strings on the line delimited '<' and '>' are considered mail addresses to send warnings to. If multiple lines match a user, the last in the file is used. Changeuser (see *auth*(8)) adds lines to these files.

FILES

/adm/keys	Encrypted key file for the Plan 9 database.
/adm/netkeys	Encrypted key file for the SecureNet database.
/adm/keys.who	List of users in the Plan 9 database.
/adm/netkeys.who	List of users in the SecureNet database.
#r/nvram	The non-volatile RAM on the server, which holds the key used to decrypt key files.

SOURCE

/sys/src/cmd/auth/keyfs.c
/sys/src/cmd/auth/warning.c

SEE ALSO

authsrv(6), namespace(6), auth(8)

Infs - long name file system

SYNOPSIS

lnfs[-r][-s srvname] mountpoint
unlnfs mountpoint

DESCRIPTION

Lnfs starts a process that mounts itself (see *bind*(2)) on *mountpoint*. It presents a filtered view of the files under the mount point, allowing users to use long file names on file servers that do not support file names longer than 27 bytes.

The names used in the underlying file system are the base32 encoding of the md5 hash of the longer file name. The user need not know the mapping since *lnfs* does all the work. *Lnfs* maintains a file .longnames in the directory *mountpoint* to record the long file names.

The options are:

- -r allow only read access to the file system
- -s provide a service name, *srvname*, to post in /srv. Without this option, no posting is performed.

UnInfs renames files with shortened names to their actual long names. It is useful once you have moved to a file server with true long name support.

FILES

.longnames

SOURCE

/sys/src/cmd/lnfs.c

/sys/src/cmd/unlnfs.c

BUGS

This exists only to shame us into getting a real long name file server working.

mntgen - automatically generate mount points for file systems

SYNOPSIS

mntgen[-s service][mnt]

DESCRIPTION

Mntgen mounts itself on *mnt* (default /n) after the current contents, creating subdirectories on demand as they are accessed. It is intended to supply mount points automatically.

The -s option causes *mntgen* to post a 9P service file in /srv/service.

SOURCE

/sys/src/cmd/mntgen.c

namespace - structure of conventional file name space

SYNOPSIS

none

DESCRIPTION

After a user's profile has run, the file name space should adhere to a number of conventions if the system is to behave normally. This manual page documents those conventions by traversing the file hierarchy and describing the points of interest. It also serves as a guide to where things reside in the file system proper. The traversal is far from exhaustive.

First, here is the appearance of the file server as it appears before any mounts or bindings.

/adm/timezone/	Time zone description for Eastern Time. Other such files are in this directory too.
/adm/timezone/	Timezone Time zone description for the local time zone; a copy of one of the other files in this directory.
/bin /dev /env /fd /net /proc /srv	in this directory.
/shr /tmp /mnt /n	All empty unwritable directories, place holders for mounted services and directories. A directory containing mount points for applications. A directory containing mount points for file trees imported from remote systems.
/386 /68000 /68020 /alpha /arm /mips /power	
/sparc	Each CPU architecture supported by Plan 9 has a directory in the root containing architecture-specific files, to be selected according to $bjtype$ or $cputype$ (see $2c(1)$ and $init(8)$). Here we list only those for $/386$.
/386/init /386/bin /386/bin/aux /386/bin/ip	The initialization program used during bootstrapping; see <i>init</i> (8). Directory containing binaries for the Intel x86 architecture.
etc.	Subdirectories of /386/bin containing auxiliary tools and collecting related programs.
/386/lib /386/include /386/9*	Directory of object code libraries as used by $\$1$ (see $2l(1)$). Directory of x86-specific C include files. The files in /386 beginning with a 9 are binaries of the operating system or its bootstrap loader.

/386/mkfile	Selected by $mk(1)$ when $bjtype$ is 386, this file configures mk to compile for the Intel x86 architecture.
/rc	Isomorphic to the architecture-dependent directories, this holds executables and libraries for the shell, $rc(1)$.
/rc/bin	Directory of shell executable files.
/rc/lib	Directory of shell libraries.
/rc/lib/rcmain	n
	Startup code for <i>rc</i> (1).
/rc/lib/rcmain	
	Site local startup code for <i>rc</i> (1).
/lib	Collections of data, generally not parts of programs.
/lib/mammals	
/lib/sky	
etc.	Databases.
/lib/ndb	The network database used by the networking software; see $ndb(6)$ and
	ndb(8).
/lib/namespace	
	The file used by newns (see <i>auth</i> (2)) to establish the default name space; see
	namespace(6).
/lib/font/bit	
	TrueType font files.
/lib/rfc	Directory of Internet 'Requests For Comments', ranging from trivia to specifications.
/lib/rfc/grab	
, , , , , , , ,	Maintains RFC collection; usually run from <i>cron</i> (see <i>auth</i> (8)).
/sys	System software.
/sys/include	Directory of machine-independent C include files.
/sys/lib	Pieces of programs not easily held in the various bins.
	Directory of <i>acid</i> (1) load modules.
	Software used to assemble the distribution's installation floppy.
/sys/lib/trof:	f
	Directory of <i>troff</i> (1) font tables and macros.
/sys/lib/yaccj	
	The yacc(1) parser.
/sys/man	The manual.
/sys/doc	Other system documentation.
/sys/log	Log files created by various system services.
/sys/src	Top-level directory of system sources.
/sys/src/cmd	Source to the commands in the bin directories.
/sys/src/9	Source to the operating system for terminals and CPU servers.
/sys/src/fs	Source to the operating system for file servers.
/sys/src/lib*	
/usr	A directory containing home directories of users.
/mail	Directory of electronic mail; see <i>mail</i> (1).
/mail/box	Directory of users' mail box files.
/mail/lib	Directory of alias files, etc.
/acme /cron	Directory of tools for <i>acme</i> (1).
/cfg/system	Directory of files for <i>cron</i> (8). <i>System</i> -specific files, often addenda to their namesakes, notably cpurc,
/ CTB/ SASIGHI	termrc, namespace, and consoledb.
T I () ()	

The following files and directories are modified in the standard name space, as defined by /lib/namespace (see *namespace*(6)).

/	The root of the name space. It is a kernel device, <i>root</i> (3), serving a number of local mount points such as /bin and /dev as well as the bootstrap program (boot Unioned with (is the root of the main file server)
	/boot. Unioned with / is the root of the main file server.
/boot	Compiled into the operating system kernel, this file establishes the connection
	to the main file server and starts init; see <i>boot</i> (8) and <i>init</i> (8).
/bin	Mounted here is a union directory composed of /\$objtype/bin, /rc/bin, \$home/bin/\$objtype, \$home/bin/rc, etc., so /bin is

/dev	always the directory containing the appropriate executables for the current architecture. Mounted here is a union directory containing I/O devices such as the console $(cons(3))$, the interface to the raster display $(draw(3))$, etc. The window system, $rio(1)$, prefixes this directory with its own version, overriding many
/env	device files with its own, multiplexed simulations of them. Mounted here is the environment device, <i>env</i> (3), which holds environment
/ env	variables such as \$cputype.
/net	Mounted here is a union directory formed of all the network devices available.
/net/cs	The communications point for the connection server, ndb/cs (see <i>ndb</i> (8)).
/net/dns	The communications point for the Domain Name Server, ndb/dns (see
/not /ton	ndb(8)).
/net/tcp /net/udp	Directories holding the IP protocol devices (see $ip(3)$).
/proc	Mounted here is the process device, $p(3)$, which provides debugging
/ 2100	access to active processes.
/fd	Mounted here is the dup device, <i>dup</i> (3), which holds pseudonyms for open
)	file descriptors.
/shr	Mounted here is the global mountpoint device, <i>shr</i> (3), which holds mounted
	filesystems visible in all namespaces.
/srv	Mounted here is the service registry, srv(3), which holds connections to file
	servers.
/srv/boot	The communication channel to the main file server for the machine.
/mnt/wsys	Mount point for the window system.
/mnt/term	Mount point for the terminal's name space as seen by the CPU server after a <i>cpu</i> (1) command.
/n/kremvax	A place where machine kremvax's name space may be mounted.
/tmp	Mounted here is each user's private tmp, \$home/tmp.
1.00	

SEE ALSO

intro(1), *namespace*(6)

nfs – Sun network file system client

SYNOPSIS

nfs [-DRv] [-p perm] [-s srvname] [-u passwd group] addr1 [addr2]

aux/portmap[-R] host cmd

aux/nfsmount[-R] host cmd

DESCRIPTION

Nfs translates between the Sun network file system protocol (NFS) and 9P, allowing 9P clients to mount file systems on NFS servers. NFS servers comprise two separate services: a mount service used to obtain the initial file handle, and a file service used to perform actual file system operations. The Sun port mapper service is typically used to find these two services. If one address is given, it is taken to be the address of a port mapper service; *nfs* queries the port mapper to find the addresses of the NFS mount service and file service. If two addresses are given, the port mapper is bypassed; *addr1* is used as the address of the NFS mount service, and *addr2* is used as the address of the file service.

The options are:

- -D print all 9P messages.
- -R print all NFS messages.
- -v print verbose information about session startup.
- -p perm

set the posted service file to have mode *perm*, which is assumed to be octal; the default is 600.

−s srvname

post the service as /srv/srvname; the default is /srv/addr1.

-u passwd group

translate user and group names using the *passwd* and *group* files, which are in the traditional Unix format. The translation is used to present names for user and group in *stat*(5) and *wstat* messages. The translation is also used to choose the user and group credentials to present for a user. Without this option, users and groups are presented as decimal numbers, and everyone attaches as uid -1 (nobody on most Unix systems).

Portmap and *nfsmount* are test programs to perform port mapper and NFS mount RPCs. They are useful mainly to help debug problems with starting *nfs* itself. The -R option causes them to print all RPC messages sent and received.

Portmap queries a Sun RPC portmap server, which maps integer (program, version, protocol) triples to port numbers. Program and version are Sun RPC defined, while protocol is typically TCP (6) or UDP (17). The commands are:

null a no-op

dump print the entire map

- set prog vers proto port add an entry to (or replace an entry in) the map
- unset *prog vers proto port* remove an entry from the map
- getport prog vers proto

look for an entry with *prog*, *vers*, *proto* in the map, and return the corresponding port The default command is dump. For running NFS over UDP, there must be an entry for the NFS v3 mount daemon (100005, 3, 17) and the NFS v3 server itself (100003, 3, 17).

Nfsmount queries a Sun NFS mount server, which authenticates (ha!) connections and hands out file handles naming the root of an exported file system. This handle is used as the basis for a conversation with the NFS service daemon itself. The commands are:

null a no-op

export

dump the export table; each line is a path followed by a list of machines or groups allowed to mount that path

mnt path

attempt to acquire a file handle for *path*. the request has user and group id 1001 and gnot as the system name.

umnt path

notify the mount daemon that a particular path is being unmounted by the requesting system

umntall

notify the mount daemon that all paths mounted by the requesting system are being unmounted

dump should also dump an export table, but typically does nothing

EXAMPLE

We use this in our /rc/bin/9fs script to mount all the home directories served by *bopp*:

SOURCE

/sys/src/cmd/nfs.c
/sys/src/libsunrpc

SEE ALSO

nfsserver(8), srv(4)

BUGS

The authentication employed by NFS is laughable. The server simply trusts the uid, gid, and group list presented by the client.

Nfs speaks only NFS version 3. Older operating systems typically have reasonable NFS version 2 servers but crash when serving version 3.

nntpfs - network news transport protocol (NNTP) file system

SYNOPSIS

nntpfs[-a][-s service][-m mountpoint][system]

DESCRIPTION

Nntpfs dials the TCP network news transport protocol (NNTP) port, 119, on *system* (default '\$nntp') and presents at *mountpoint* (default /mnt/news) a file system corresponding to the news articles stored on *system*.

If the -s option is given, the file system is posted as /srv/service. If the -a option is given, *nntpfs* authenticates to the system with a user name and password obtained from *factotum*(4). The key specifier is

proto=pass service=nntp server=server user? !password?

The file system contains a directory per newsgroup, with dots turned into slashes, e.g., comp/os/plan9 for comp.os.plan9. Each newsgroup directory contains one numbered directory per article. The directories follow the numbering used by the server. Each article directory contains three files: article, header, and body. The article file contains the full text of the article, while header and body contain only the header or body.

Each newsgroup directory contains a write-only post file that may be used to post news articles. RFC1036-compliant articles should be written to it. The post file will only exist in a given newsgroup directory if articles are allowed to be posted to it. Other than that, the post file is *not* tied to its directory's newsgroup. The groups to which articles are eventually posted are determined by the newsgroups: header lines in the posted article, not by the location of the post file in the file system.

The qid version of a newsgroup directory is the largest numbered article directory it contains (~0, if there are no articles).

The modification time on a newsgroup directory is the last time a new article was recorded during this *nntpfs* session. To force a check for new articles, *stat*(2) the newsgroup directory.

To force a check for new newsgroups, *stat*(2) the root directory. Note that this causes the entire list of groups, which can be about a megabyte, to be transferred.

To terminate the connection, unmount the mount point.

Nntpfs makes no effort to send "keepalives" so that servers do not hang up on it. Instead, it redials as necessary when hangups are detected.

EXAMPLE

Authenticate to a private news server:

```
% echo key proto=pass service=nntp server=nose.mit.edu \
    user=rsc !password=secret >/mnt/factotum/ctl
% nntpfs -a nose.mit.edu
```

SOURCE

/sys/src/cmd/nntpfs.c

BUGS

Directories are presented for deleted articles; the files in them cannot be opened.

audio, disk, ether, kb, serial, ptp, usbd – Universal Serial Bus drivers

SYNOPSIS

nusb/audio devid
nusb/disk [-d] devid
nusb/ether [-dD] [-t ethertype] [-a addr] devid
nusb/kb [-d] devid
nusb/serial [-d] devid
nusb/ptp [-dD] devid

nusb/usbd[-dD]

DESCRIPTION

These programs drive USB devices of specific classes via usb(3). Usually they are started by nusbrc(8) upon attachment of the device to the bus. All drivers except usbd take the decimal usb *devid* of the device they should handle as ther last argument. A driver's instance handles only one device at a time.

Drivers that provide file systems make them available as shares under /shr (see shr(3)) or /shr/usb (which is bound after /dev by nusbrc(8)).

Options -d and -D trigger debug diagnostics and file system debugging diagnostics for most drivers. Repeating any one of these may increase verbosity.

Hubs

Usbd enumerates the tree of USB hubs and configures the device on attachment. It provides a filesystem with the file usbevent (usually seen as /dev/usbevent) which, when read, returns a 6 column, space separated line of text, one for each event. The columns are: attach or detach followed by addr vid did csp and hname. The addr is the decimal device address assigned. Vid and did are formatted as 4 digit hexadecimal. Csp is the device class, subclass, protocol indentifier formatted as 6 digit hexadecimal. Usbd assigns a stable device unique name based on the device descriptor for hname. This information is read by nusbrc(8) and the addr and hname are passed to a suitable driver as devid in the form addr:hname

Keyboards and mice

Kb supports USB keyboards and mice either as separate USB devices or as a single combined USB device. Scan codes from the keyboard are sent to /dev/kbin to let *kbdfs*(8) process them. Mouse events are sent to /dev/mousein in the same way.

Disks

Disk configures and manages USB mass storage devices. It provides a file system (usually seen under /dev) that includes one directory per storage device, named sdUN[.M] in correspondence with the usb device unique name and the storage unit number (or LUN). The LUN is omited for single lun devices.

The storage device directory contains the usual files served by *sd*(3): data, raw, and ctl.

The ctl file supplies the device geometry and partitions when read.

Ethernet

Ether handles USB ethernet devices. The file system provided is compatible to *ether*(3) and added to the share usbnet (see *shr*(3)) which is bound after /net by *nusbrc*(8) so the device will appear as /net/etherUN. Without specifying the -t option, the device is assumed to be a CDC compliant ethernet communication device. Other devices might require setting an explicit *ethertype*, such as rndis, smsc, a88772 or a88178 (see *nusbrc*(8)). On devices that support it, the mac address can be set using the -a addr option.

Serial and JTAG ports

Serial provides a file system (usually seen under /dev) that includes one directory per USB serial port, named eiaUN or eiaUN[.M]. In this directory there are two files, eiaU, similar to eiaN in uart(3), and eiaUctl, which admits writes in the same format as eiaNctl in uart(3). Reading from eiaUctl gives the serial port's settings in the same format as eiaNstatus in

uart(3). Options are similar to those of *disk*.

JTAG ports are similar but the files are named jtag and jtagctl.

Audio devices

Audio configures and manages a USB audio device. It implements a file system, (normally seen under /dev) compatible to audio(3).

SOURCE

/sys/src/cmd/nusb

SEE ALSO

audio(3), ether(3), mouse(3), sd(3), uart(3), usb(3), shr(3), nusbrc(8), kbdfs(8)

BUGS

The various device drivers are generic USB drivers and may work only for certain devices of each class.

USB ATA storage devices are not supported.

The serial driver works only for the Prolific chip and Ftdi, and control of the dcd and dsr signals and some of the extra features are not implemented. For Ftdi, only the Sheevaplug and Guruplug have been tried. There is support for the EHCI debug port, but it loses bytes.

oexportfs - legacy exportfs for cpu and import

SYNOPSIS

oexportfs[options]

DESCRIPTION

Oexportfs is older version of the *exportfs*(4) program that handles an initial protocol to establish a root directory for the exported name space. It also provides authentication and encryption using the *ssl*(3) device.

It is used exclusively by the deprecated cpu(1) and import(4) services.

The options are:

−d −f *dbgfile*

Log all 9P traffic to *dbgfile* (default /tmp/exportdb).

–P patternfile

Restrict the set of exported files. *Patternfile* contains one regular expression per line, to be matched against path names relative to the current working directory and starting with /. For a file to be exported, all lines with a prefix + must match and all those with prefix - must not match.

- -R Make the served name space read only.
- -r root

Serve the name space rooted at *root*.

–S service

Serve the result of mounting *service*. A separate mount is used for each attach(5) message, to correctly handle servers in which each mount corresponds to a different client *e.g.*, (rio(4)).

- -s equivalent to -r /; kept for compatibility.
- -m *msize*

Set the maximum message size that *oexportfs* should offer to send (see *version*(5)); this helps tunneled 9P connections to avoid unnecessary fragmentation.

-A address

Use the network *address* to announce *aan*(8) connections, if requested by the initial protocol.

- -a Authenticate the user with the *p9any* protocol before running the regular *oexportfs* session; used when *oexportfs* is invoked to handle an incoming network connection. *Exportfs* creates a new name space for each connection, using /lib/namespace by default (see *namespace*(6)).
- –B address

Dial *address*, authenticate as a *p9any* client, and then serve that network connection. Requires setting the root of the name space with -r or -s. The remote system should run import -B to handle the call. See *import*(4) for an example.

-e 'enc auth'

Set the encryption and authentication algorithms to use for encrypting the wire traffic (see ssl(3)). The defaults are $rc4_{256}$ and sha1.

–N nsfile

Serve the name space described by *nsfile*.

-n Disallow mounts by user none.

SOURCE

/sys/src/cmd/exportfs/oexportfs.c

SEE ALSO

dial(2), exportfs(4), import(4), aan(8), listen(8)

paqfs - compressed read-only file system

SYNOPSIS

paqfs [-disv] [-c cachesize] [-m mtpt] [-M mesgsize] [-S srvname] paqfile

DESCRIPTION

Paqfs interprets the compressed read-only file system created by *mkpaqfs*(8) and stored in *paqfile* so that it can be mounted into a Plan 9 file system. *Paqfs* is typically used to create a stand alone file system for a small persistent storage device, such as a flash ROM. It does not authenticate its clients and assumes each group has a single member with the same name.

Options to *paqfs* are:

–с *cachesize*

The number of file system blocks to cache in memory. The default is 20 blocks.

–M mesgsize

The maximum 9P message size. The default is sufficient for 8K byte read message.

- -d Output various debugging information to *stderr*.
- -i Use file descriptors 0 and 1 as the 9P communication channel rather than create a pipe.
- -q Suppress the output of the archive creation date and fingerprint to *stderr*.

-m *mtpt*

The location to mount the file system. The default is /n/paq.

- -s Post the 9P channel on #s/*srvname*, default #s/paqfs, rather than mounting it on *mtpt*.
- -S The name to post in #s. The default is paqfs.
- -p Both post the 9P channel in #s and mount the *paqfile* in to the filesystem.
- -v Verify the integrity of the *paqfile*. Before mounting the file system, the entire file is parsed and the *sha1* checksum of the file system data is compared to the checksum embedded in the file. This option enables the use of *paqfs* with files that consist of a *paq* file system concatenated with additional data.

SOURCE

/sys/src/cmd/paqfs/paqfs.c

SEE ALSO

mkpaqfs(8)

plumber - file system for interprocess messaging

SYNOPSIS

plumber[-p plumbing]

DESCRIPTION

The *plumber* is a user-level file server that receives, examines, rewrites, and dispatches *plumb*(6) messages between programs. Its behavior is programmed by a *plumbing* file (default /usr/\$user/lib/plumbing) in the format of *plumb*(6).

Its services are mounted on the directory /mnt/plumb (/mnt/term/mnt/plumb on the CPU server) and consist of two pre-defined files, send and rules, and a set of output *ports* for dispatching messages to applications. The service is also published as a *srv*(4) file, named in \$plumbsrv, for mounting elsewhere.

Programs use write (see *read*(2)) to deliver messages to the send file, and *read*(2) to receive them from the corresponding port. For example, *sam*(1)'s plumb menu item or the B command cause a message to be sent to /mnt/plumb/send; sam in turn reads from, by convention, /mnt/plumb/edit to receive messages about files to open.

A copy of each message is sent to each client that has the corresponding port open. If none has it open, and the rule has a plumb client or plumb start rule, that rule is applied. A plumb client rule causes the specified command to be run and the message to be held for delivery when the port is opened. A plumb start rule runs the command but discards the message. If neither start or client is specified and the port is not open, the message is discarded and a write error is returned to the sender.

The set of output ports is determined dynamically by the specification in the plumbing rules file: a port is created for each unique destination of a plumb to rule.

The set of rules currently active may be examined by reading the file /mnt/plumb/rules; appending to this file adds new rules to the set, while creating it (opening it with OTRUNC) clears the rule set. Thus the rule set may be edited dynamically with a traditional text editor. However, ports are never deleted dynamically; if a new set of rules does not include a port that was defined in earlier rules, that port will still exist (although no new messages will be delivered there).

FILES

/usr/\$user/lib/plumbing	default rules file
/sys/lib/plumb	directory to search for files in include statements
/mnt/plumb	mount point for <i>plumber</i> (4).

SOURCE

/sys/src/cmd/plumb

SEE ALSO

plumb(1), plumb(2), plumb(6)

BUGS

Plumber's file name space is fixed, so it is difficult to plumb messages that involve files in newly mounted services.

ptrap – *plumber*(4) filter

SYNOPSIS

ptrap port [!]regexp [+attr [!]regexp ...] ...

DESCRIPTION

Ptrap is a program that mounts itself over a *plumber*(4) service mounted at /mnt/plumb and filters incoming messages according to the rules provided on the command line.

Ptrap accepts an arbitrary number of filters; each filter applies to a port, and may match over both the data and attributes of plumb messages.

A filter is formatted as a port name, a data filter, and a list of attribute filters.

The data filter is a regex(6) that matches the plumbed data. The attribute filter consists of the attribute name prefixed with a '+', followed by a regex(6) that matches the contents of the attribute. Any regex may be prefixed with a '!' in order to negate a match, causing all matches for that regex to be discarded. All parts of a filter must match in order for a plumb message to be forwarded.

EXAMPLES

Start a *sam*(1) instance dedicated to editing kernel source code:

```
ptrap edit '^/sys/src/9/'
sam
```

In another window, start a second *sam*(1) instance for all other editing jobs:

```
ptrap edit '!^/sys/src/9/'
sam
```

Start an *acme*(1) instance instance dedicated to reading plumbed manual pages:

```
ptrap edit '.*' +action '^showdata' +filename '^/man/'
acme -c1
```

SOURCE

```
/sys/src/cmd/ptrap.c
```

SEE ALSO

plumber(4), plumb(6)

BUGS

Multiple filters specified on the same port ignore all but the last one.

Ptrap would be more useful if it could inhibit sending the message to other clients.

As far as *plumber*(4) is concerned, even messages dropped by *ptrap* are "accepted", which means rules that are supposed to apply to messages not accepted by clients are not invoked (e.g. a rule starting an editor if no one is listening to the *edit* port will not work if there is a *ptrap* on that port).

HISTORY

Ptrap first appeared in 9front (February, 2018).

ramfs - memory file system

SYNOPSIS

ramfs[-Dipsu][-m mountpoint][-S srvname]

DESCRIPTION

Ramfs starts a process that mounts itself (see *bind*(2)) on *mountpoint* (default /tmp). The *ramfs* process implements a file tree rooted at *dir*, keeping all files in memory. Initially the file tree is empty.

The -D option enables a trace of general debugging messages.

The -i flag tells *ramfs* to use file descriptors 0 and 1 for its communication channel rather than create a pipe. This makes it possible to use *ramfs* as a file server on a remote machine: the file descriptors 0 and 1 will be the network channel from *ramfs* to the client machine.

The -p flag causes *ramfs* to make its memory 'private' (see *proc*(3)) so that its files are not accessible through the debugging interface.

The -s (-S) flag causes *ramfs* to post its channel on /srv/ramfs (/srv/srvname) rather than mounting it on *mountpoint*, enabling multiple clients to access its files. However, it does not authenticate its clients and its implementation of groups is simplistic, so it should not be used for precious data.

The -u option permits *ramfs* to consume as much memory as needed; without it, *ramfs* will limit its consumption to some arbitrary amount, currently 768MB (enough to hold a CD image).

This program is useful mainly as an example of how to write a user-level file server. It can also be used to provide high-performance temporary files.

SOURCE

/sys/src/cmd/ramfs.c

SEE ALSO

bind(2)

ratfs - mail address ratification file system

SYNOPSIS

ratfs[-d][-c configuration][-f classification][-m mountpoint]

DESCRIPTION

Ratfs starts a process that mounts itself (see *bind*(2)) on *mountpoint* (default /mail/ratify). *Ratfs* is a persistent representation of the local network configuration and spam blocking list. Without it each instance of *smtpd*(6) would need to reread and parse a multimegabyte list of addresses and accounts.

Ratfs serves a control file, ctl, and several top level directories: trusted, deny, dial, block, delay, and allow.

The control file is write only and accepts three possible commands:

reload	rereads classification and configuration
debug <i>file</i>	creates <i>file</i> and sends debugging output to it.
nodebug	closes the debug file and turns off debugging

The directory trusted serves a file for each IP range from which all mail is trusted. The names of the files are CIDR blocks; an IP address or an IP address followed by #n, where n is the number of bits to match. To check if any IP address falls in a trusted range, it is sufficient to open the file whose name is the IP address. For example, if trusted contains only the file 135.104.0.0#16, an attempt to open the file 135.104.9.1 will succeed while opening 10.1.1.1 will fail. To determine the particular range matched, dirfstat (see stat (2)) the open file and the name field will be the matching CIDR range.

The trusted ranges come both from the ournet entries in the file *configuration* (default /mail/lib/blocked) and from creates, typically done by imap4d (see *ipserv*(8)) and pop3 (see *mail*(1)) whenever they are used to read someone's mail.

The remaining directories, allow, block, delay, deny, and dial, represent the contents of the *classification* (default /mail/lib/smtpd.conf.ext). Each contains two directories; ip and account. The ip directory has the same open semantics as the trusted directory, i.e., to check if an IP address falls in that category, try to open a file whose name is the IP address. The account directory is similar but is used for matching strings. Each file in the directory represents a regular expression. To see if one of the strings matches one of the regular expression that matches. To determine the regular expression, fstat the open file. The name field will be the regular expression.

There is a direct mapping from entries in *classification* and files under allow, block, delay, deny, and dial. A configuration file entry of the form:

```
dial 135.104.9.0/24
```

corresponds to the file dial/ip/135.104.9.0#24. An entry of the form *block .*!gre

corresponds to the file block/account/.*!gre.

Both the configuration file and control file formats are described in *smtpd*(6).

SOURCE

/sys/src/cmd/ratfs

SEE ALSO

mail(1) smtpd(6) scanmail(8)

rdbfs - remote kernel debugging file system

SYNOPSIS

rdbfs[-d][-p pid][-s srvname][-t text][device]

DESCRIPTION

Rdbfs presents in /proc/pid (default /proc/1) a set of process files for debugging a kernel over the serial line *device* (default /dev/eia0). If the -s option is given, *rdbfs* will post its channel in /srv/srvname (see *srv*(3)), allowing the session to be shared or reattached later.

The text file presented is just a copy of *text* (default /386/9pc). It can usually be ignored, since the debuggers open kernel files directly rather than using /proc/n/text.

Kernels can be remotely debugged only when they are suspended and serving a textual debugging protocol over their serial lines. (see *cons*(3))

Because the debugging protocol is textual, a console provided by *consolefs*(4) may be substituted for the serial device.

SOURCE

/sys/src/cmd/rdbfs.c
/sys/src/9/port/rdb.c

SEE ALSO

acid(1), db(1), cons(3), consolefs(4)

rio – window system files

SYNOPSIS

rio[-i 'cmd'][-k 'kbdcmd'][-s][-b][-f font]

DESCRIPTION

The window system *rio* serves a variety of files for reading, writing, and controlling windows. Some of them are virtual versions of system files for dealing with the display, keyboard, and mouse; others control operations of the window system itself. *Rio* posts its service in the /srv directory, using a name constructed from a catenation of the user ID and a process id; the environment variable swsys is set to this service name within processes running under the control of each invocation of *rio*. Similarly, *rio* posts a named pipe to access the window creation features (see window in *rio*(1)) from outside its name space; this is named in swct1.

A mount (see bind(1)) of \$wsys causes *rio* to create a new window; the attach specifier in the mount gives the coordinates of the created window. The syntax of the specifier is the same as the arguments to window (see rio(1)). By default, the window is sized and placed automatically. It is always necessary, however, to provide the process id of the process to whom to deliver notes generated by DEL characters and hangups in that window. That pid is specified by including the string -pid pid in the attach specifier. (See the Examples section q.v.)

When a window is created either by the *window* command (see rio(1)) or by using the menu supplied by rio, this server is mounted on /mnt/wsys and also /dev; the files mentioned here appear in both those directories.

Some of these files supply virtual versions of services available from the underlying environment, in particular the character terminal files cons and kbd (see *kbdfs*(8)), and the mouse files *mouse*(3) and *cursor*, each specific to the window. Note that the *draw*(3) device multiplexes itself; *rio* places windows but does not mediate programs' access to the display device.

Other files are unique to *rio*.

- cons a virtual version of the standard terminal file from *kbdfs*(8). *Rio* supplies extra editing features and a scroll bar (see *rio*(1)).
- consctl controls interpretation of console input. Writing strings to it sets these modes: rawon
 turns on raw mode; rawoff turns off raw mode; holdon turns on hold mode;
 holdoff turns off hold mode. Closing the file makes the window revert to default
 state (raw off, hold off).
- kbd represents the raw keyboard events (see *kbdfs*(8)) for the corresponding window. While open, navigation keys and input on the *cons* file is disabled.
- cursor Like mouse (q.v.), a multiplexed version of the underlying device file, in this case representing the appearance of the mouse cursor when the mouse is within the corresponding window.
- label initially contains a string with the process ID of the lead process in the window and the command being executed there. It may be written and is used as a tag when the window is hidden.
- mouse is a virtual version of the standard mouse file (see *mouse*(3)). Opening it turns off scrolling, editing, and *rio*-supplied menus in the associated window. In a standard mouse message, the first character is m, but *rio* will send an otherwise normal message with the first character r if the corresponding window has been resized. The application must then call getwindow (see *graphics*(2)) to re-establish its state in the newly moved or changed window. Reading the mouse file blocks until the mouse moves or a button changes. Mouse movements or button changes are invisible when the mouse cursor is located outside the window, except that if the mouse leaves the window while a button is pressed, it will continue receiving mouse data until the button is released.
- screen is a read-only file reporting the depth, coordinates, and raster image corresponding to the entire underlying display, in the uncompressed format defined in *image*(6).
- snarf returns the string currently in the snarf buffer. Writing this file sets the contents of the snarf buffer. When *rio* is run recursively, the inner instance uses the snarf buffer of the parent, rather than managing its own.

- text returns the full contents of the window. Write appends to the window. Truncating clears the windows contents.
- wctl may be read or written. When read, it returns the location of the window as four decimal integers, padded to 12 characters as described in image(6): upper left x and y, lower right x and y. Following these numbers are strings, also padded to 12 characters, describing the window's state: current or notcurrent; hidden or visible. A subsequent read will block until the window changes size, location, or state. When written to, wctl accepts messages to change the size or placement of the associated window, and to create new windows. The messages are in a command-line like format, with a command name, possibly followed by options introduced by a minus sign. The options must be separated by blanks, for example -dx100 rather than -dx100.

The commands are resize (change the size and position of the window), move (move the window), scroll (enable scrolling in the window), noscroll (disable scrolling), set (change selected properties of the window), top (move the window to the 'top', making it fully visible), bottom (move the window to the 'bottom', perhaps partially or totally obscuring it), hide (hide the window), unhide (restore a hidden window), current (make the window the recipient of keyboard and mouse input), delete (close the window and terminate its associated processes) and new (make a new window). The top and bottom commands do not change whether the window is current or not. Neither top nor bottom has any options.

The resize, move, and new commands accept $-\min n$, $-\min n$, $-\max n$, and $-\max n$ options to set the position of the corresponding edge of the window. They also accept an option $-r \min n$ miny maxx maxy to set all four at once. The resize and new commands accept -dx n and -dy n to set the width and height of the window. By default, *rio* will choose a convenient geometry automatically.

Finally, the new command accepts an optional shell command and argument string, given as plain strings after any standard options, to run in the window instead of the default rc -i (see rc(1)). The -pid *pid* option to new identifies the *pid* of the process whose 'note group' should receive interrupt and hangup notes generated in the window. The initial working directory of the new window may be set by a -cd *directory* option. The -hide option causes the window to be created off-screen, in the hidden state, while -scroll and -noscroll set the initial scrolling state of the window; the default is that of the main program.

The set command accepts a set of parameters in the same style; only -pid pid is implemented.

So programs outside name spaces controlled by *rio* may create windows, wctl new messages may also be written to the named pipe identified by \$wctl.

- wdir is a read/write text file containing *rio*'s idea of the current working directory of the process running in the window. It is used to fill in the wdir field of *plumb*(6) messages *rio* generates from the plumb menu item on button 2. The file is writable so the program may update it; *rio* is otherwise unaware of *chdir*(2) calls its clients make. In particular, *rc*(1) maintains /dev/wdir in default *rio*(1) windows.
- winid returns the unique and unchangeable ID for the window; it is a string of digits.
- window is the virtual version of /dev/screen. It contains the depth, coordinates, and uncompressed raster image corresponding to the associated window.
- wsys is a directory containing a subdirectory for each window, named by the unique ID for that window. Within each subdirectory are entries corresponding to several of the special files associated with that window: cons, consctl, label, mouse, etc.

EXAMPLES

Cause a window to be created in the upper left corner, and the word hi to be printed there.

mount \$wsys /tmp 'new -r 0 0 128 64 -pid '\$pid
echo hi > /tmp/cons

Start *sam*(1) in a large horizontal window.

echo new -dx 800 -dy 200 -cd /sys/src/cmd sam > /dev/wctl Print the screen image of window with id 123. lp /dev/wsys/123/window

SOURCE

/sys/src/cmd/rio

SEE ALSO

rio(1), draw(3), mouse(3), kbdfs(8), event(2), graphics(2).

sacfs - compressed file system

SYNOPSIS

disk/sacfs[-i infd outfd][-s][-m mountpoint] file

DESCRIPTION

Sacfs interprets the compressed, block based file system created by *mksacfs*(8) and stored in *file* so that it can be mounted into a Plan 9 file system. *Sacfs* is typically used to create a stand alone file system from a small persistent storage device, such as a flash rom. It does not authenticate its clients and assumes each group has a single member with the same name.

The -s flag causes *sacfs* to post its channel on #s/sacfs. The -i flag causes *sacfs* to use file descriptors *infd* and *outfd* for its communication channel. If neither -s nor -i are given, *sacfs* mounts itself on *mountpoint* (default /n/c:).

SOURCE

/sys/src/cmd/disk/sacfs/sacfs.c

SEE ALSO

mksacfs(8)

snap, snapfs - create and mount process snapshots

SYNOPSIS

snap [–o file] pid...

snapfs[-a][-m mtpt][-s service] file...

DESCRIPTION

Snap and *snapfs* allow one to save and restore (static) process images, usually for debugging on a different machine or at a different time.

Snap writes a snapshot (see *snap*(6)) of the named processes to *file* (default standard output). If *pid* is a text string rather than a process id, *snap* will save all processes with that name that are owned by the current user. Both memory and text images are saved.

Snapfs is a file server that recreates the /proc directories for the processes in the snapshot. By default, it mounts the new directories into /proc before the current entries. The -m option can be used to specify an alternate mountpoint, while -a will cause it to mount the new directories after the current entries. The -s option causes it to serve requests via /srv/service.

EXAMPLE

Suppose *page* has hung viewing Postscript on your terminal, but the author is gone for the rest of the month and you want to make sure the process is still around for debugging on his return. You can save the errant processes with

```
snap -o page.snap '{psu | awk '$NF ~ /page|gs/ {print $2}'}
```

When the author returns, he can add the process images to his name space by running

```
snapfs page.snap
```

and then use a conventional debugger to debug them.

SOURCE

/sys/src/cmd/snap

SEE ALSO

acid(1), db(1), proc(3), snap(6)

BUGS

The snapshots take up about as much disk space as the processes they contain did memory. Compressing them when not in use is recommended, as is storing them on a rewritable disk.

Pid as a non-numeric string is unimplemented; it has to be a number.

srv, srvtls, 9fs - start network file service

SYNOPSIS

srv[-abcCemnNq][-s seconds][net!]system[!service][srvname[mtpt]]

srvtls [-abcCnq] [-k keyspec] [net!] system[! service] [srvname [mtpt]]

9fs [net!] system [mountpoint]

DESCRIPTION

Srv dials the given machine and initializes the connection to serve the 9P protocol. By default, it connects to the 9fs (9P) service, which for TCP is port 564. It then creates in /srv a file named *srvname*. Users can then mount (see *bind*(1)) the service, typically on a name in /n, to access the files provided by the remote machine. If *srvname* is omitted, the first argument to *srv* is used. Option m directs *srv* to mount the service on /n/*system* or onto *mtpt* if it is given. Option q suppresses complaints if the /srv file already exists. The a, b, c, C, and n, N options are used to control the mount flags as in *mount* (see *bind*(1)). The e option causes *srv* to treat *system* as a shell command to be executed rather than an address to be dialed. The s option causes *srv* to sleep for the specified number of seconds after establishing the connection before posting and mounting it.

The specified *service* must serve 9P. Usually *service* can be omitted; when calling some non-Plan-9 systems, a *service* such as u9fs must be mentioned explicitly.

The 9fs command does the srv and the mount necessary to make available the files of system on network net. The files are mounted on mountpoint, if given; otherwise they are mounted on /n/system. If system contains / characters, only the last element of system is used in the /n name.

9fs recognizes some special names, such as dump to make the dump file system available on /n/dump. 9fs is an rc(1) script; examine it to see what local conventions apply.

Srvtls is an rc(1) command that uses *tlsclient* (see *tlssrv*(8)) to establish an mutual authenticated and encrypted 9P connection to the *t9fs* service which by default listens on tcp port 17020.

EXAMPLES

To see kremvax's and deepthought's files in /n/kremvax and /n/deepthought:

9fs kremvax 9fs hhgttg /n/deepthought

FILES

/srv/* ports to file systems and servers posted by *srv* and *9fs*

SOURCE

/sys/src/cmd/srv.c /rc/bin/9fs /rc/bin/srvtls

SEE ALSO

bind(1), *auth*(2), *dial*(2), *srv*(3), *tlssrv*(8), *exportfs*(4).

BUGS

Srv does not explicitly report failures of *auth_proxy* (see *auth*(2)); *mount* (see *bind*(1)) does.

sshfs - secure file transfer protocol client

SYNOPSIS

sshfs[-abdRUGM][-s service][-m mtpt][-r root][-u uidfile][-g gidfile]

[-- ssh-options] [user@]host | -c cmdline | -p

DESCRIPTION

Sshfs makes the file system on a remote host accessible through the secure file transfer protocol (SFTP). By default *sshfs* launches *ssh*(1) to connect to *host* and log in as *user*. If -c is specified, *sshfs* will instead launch the command specified by *cmdline* and if -p is specified, *sshfs* communicates with an SFTP server via stdin and stdout.

Unless -M is specified, *sshfs* will mount itself at the mountpoint specified by *mtpt*, or at /n/ssh if -m is not specified. The default mount options are equivalent to calling *mount* (see *bind*(1)) with -c. -a and -b have the same function as they do with *mount*.

If -s is specified, it will post itself in srv(3) with service name *service*. If the service file is mounted, the attach name (the third argument to *mount*(1)) can be used to specify which directory on the remote host will be mounted.

By default, relative paths are assumed relative to the user's home directory. The -r option can be used to specify an alternative base for relative paths. The initial mount at -m also uses this directory. If an attach name starts with \sim , the user's home directory is substituted for \sim .

Since the only supported version 3 of the SFTP protocol has no way to look up numeric user and group IDs, *sshfs* will read the files /etc/passwd and /etc/group on the remote host to create a lookup table for them. The location of these files can be changed with -u and -g, whereas -U and -G will inhibit reading them entirely. If these files cannot be accessed for any reason, numeric IDs simply remain untranslated.

Further options:

-R Read access only.

-d Enable debugging output.

SOURCE

/sys/src/cmd/sshfs.c

BUGS

Currently only version 3 of the SFTP protocol is supported (which is the most common version in use and the latest supported by openssh). Unfortunately there are problems with the version 3 specification and the code relies on openssh-specific behaviour in some corner cases. Version 4 and later also handle uid/gid translation at the server end which would remove the ugly dependence on reading remote configuration files.

Some 9P operations that should be atomic are not atomic because they do not map 1:1 to SFTP operations. In particular there is no guarantee that a failed *wstat* (see *stat*(5)) did not change some of the fields.

The code is naive about links and assumes files with distinct names to be distinct, assigning them different QIDs.

File names with null bytes in them will confuse *sshfs*. *Sshfs* should probably escape them, as well as control characters that might confuse other software.

HISTORY

Sshfs first appeared in 9front (Apr, 2017).

SEE ALSO

ssh(1)

sshnet - secure file transfer protocol client

SYNOPSIS

```
sshnet [ -m mtpt ] [ -s service ] [ user@] host
```

```
sshnet [ -m mtpt ] [ -s service ] -- ssh-options [ user@] host
```

DESCRIPTION

The SSH protocol allows clients to make outgoing and incoming TCP calls via the server. Sshnet establishes an SSH connection and, rather than execute a remote command, presents the remote server's TCP stack as a network stack (see the discussion of TCP in ip(3)) mounted at *mtpt* (default /net), optionally posting a 9P service descriptor for the new file system as /srv/service. All other arguments are passed to ssh(1) as is.

SOURCE

/sys/src/cmd/sshnet.c

SEE ALSO

ssh(1), ip(3)

32vfs, cpiofs, tapfs, tarfs, tpfs, v6fs, v10fs, zipfs - mount archival file systems

SYNOPSIS

fs/32vfs[-b blocksize][-m mountpoint][-p passwd][-g group] file
fs/cpiofs
fs/tapfs
fs/tapfs
fs/tpfs
fs/v6fs
fs/v10fs
fs/zipfs

DESCRIPTION

These commands interpret data from traditional tape or file system formats stored in *file*, and mount their contents (read-only) into a Plan 9 file system. The optional -p and -g flags specify Unix-format password (respectively group) files that give the mapping between the numeric userand group-ID numbers on the media and the strings reported by Plan 9 status inquiries. The -m flag introduces the name at which the new file system should be attached; the default is /n/tapefs.

32vfs interprets raw disk images of 32V systems, which are ca. 1978 research Unix systems for the VAX (512 byte block size, the default), and also pre-FFS Berkeley VAX systems (1KB block size).

Cpiofs interprets cpio tape images.

Tarfs interprets tar tape images.

Tpfs interprets *tp* tapes from the Fifth through Seventh Edition research Unix systems.

Tapfs interprets *tap* tapes from the pre–Fifth Edition era.

V6fs interprets disk images from the Fifth and Sixth edition research Unix systems (512B block size).

V10fs interprets disk images from the Tenth Edition research Unix systems (4KB block size).

Zipfs interprets zip archives (see *gzip*(1)).

SOURCE

These commands are constructed in a highly stereotyped way using the files fs.c and util.c in /sys/src/cmd/tapefs, which in turn derive substantially from ramfs(4).

SEE ALSO

intro(5), ramfs(4).

telco, faxreceive, faxsend, fax, telcofax, telcodata - telephone dialer network

SYNOPSIS

telco[-p][-i source-id][-v] dialer-devs

```
aux/faxsend address page1 ...
```

aux/faxreceive[-s spool-dir][-v]

fax [-v] telno recipient [files]

service/telcofax

service/telcodata

DESCRIPTION

Telco is a file server that provides a network interface to Hayes telephone dialers. The interface is the same as that provided by ip(3) and can be used by any program that makes network connections using dial(2). The network addresses used by telco are telephone numbers.

The options are

- -p use pulse dialing
- -v verbose: write to the log file all communications with the dialer.
- -i specify a *source-id* to be used during FAX transfers

Some control of outgoing calls can be encoded in the address. Normally, addresses are of the form *telco*! *number*, where *number* is a decimal telephone number. However, commas in the telephone number can be used to insert pauses in the dialing process. Dialing options can be added to the end of the address, separated by !'s. The dialing options are

compress turn on compression (default off)

baudrate a decimal number representing the highest baud rate with which to make the call fax to make a Class 2 facsimile call (used by programs such as *faxsend*)

Telco also answers incoming calls. Upon receiving a facsimile call, *telco* starts the script /rc/bin/service/telcofax. For data calls it starts /rc/bin/service/telcodata. Each is started with the network connection as both standard input and standard output and with two arguments, the file name of the network connection, e.g., /net/telco/0/data, and the type of modem. Currently, the only modem types supported are:

MT1432	Multitech's 14400 baud modem
MT2834	Multitech's 28800 baud modem
ATT14400	the 14400 baud modem in Safaris
VOCAL	the 14400 baud Vocal modem

All other modems are assumed to be compatible with the standard Hayes command subset.

Faxreceive is normally started by /rc/bin/service/telcofax. It reads and spools a CCITT Group 3 (G3) encoded FAX, and then starts the script /sys/lib/fax/receiverc, passing it four arguments: the spool file name, Y (for success) or N, the number of pages, and the id string passed by the caller. This script sends by *mail*(1) notification to a list of recipients kept in the file /mail/faxqueue/faxrecipients; the script and the list should be edited to match local needs. *Faxreceive's* options are:

- -s specify a different spool directory; the default is /mail/faxqueue.
- -v verbose: write to the log file all communications with the modem.

Faxsend transmits a FAX to *address*. *Page1* and all arguments that follow are names of files containing G3 encoded FAX images, one per page.

Fax is a shell script that converts to G3 format PostScript, G3, text, or other files acceptable to lp(1) and queues the result to be transmitted to a FAX machine. A standard cover sheet, derived from /sys/lib/fax/h.ps, is sent before the message. *Telno* is the destination telephone number. *Recipient* is the name of the recipient to be placed on the cover sheet. If no *files* are specified, standard input is converted and sent. The -v option invokes page(1) on the generated G3 files instead of transmitting them via FAX machine.

EXAMPLE

Start the dialer on a PC, then use *con* to phone out.

telco /dev/eia1
con -l telco!18005551212

The connection will be made at the highest negotiable baud rate. To use the best negotiable compression scheme as well:

con -l telco!18005551212!compress

FILES

```
/mail/faxqueue/*
/rc/bin/service/telcodata
/rc/bin/service/telcofax
/sys/log/telco
/sys/lib/fax/receiverc
/mail/faxqueue/faxrecipients
/sys/lib/fax/h.ps
/sys/log/fax
```

SOURCE

```
/sys/src/cmd/telco/*
/sys/src/cmd/fax/*
```

SEE ALSO

con(1), ip(3)

BUGS

These programs require the Class 2 facsimile interface. This means that *faxsend* and *faxreceive* will not work on most portable computers since they have Class 1 interfaces.

The modem specific information is currently built into the source. This should be in a user modifiable file.

tftpfs - trivial file transfer protocol (TFTP) file system

SYNOPSIS

ip/tftpfs[-D][-s srvname][-m mtpt][-x net][ipaddr]

DESCRIPTION

Tftpfs serves files from a TFTP server as a filesystem. TFTP is mostly used by bootloaders to download kernel images for network bootstrap (see *dhcpd*(8)). As the protocol has no way of distinguishing files from directories, the final path segment needs to conain a dot (.) character to be recognized as a file. To access files that have no dot in the filename, a trailing dot has to be added and will be stripped before it is passed to the server.

The -D option enables 9P debugging messages.

The -s option causes *tftpfs* to post the 9P service as /srv/srvname and disables the default mount.

The default mountpoint /n/tftp can be changed with the -B *mtpt* option.

The -x option specifies an alternate network directory (*e.g.*, /net.alt).

The ip address of the server can be passed in as the last program argument, *ipaddr*, or in the mount spec (see *bind*(1)) on a per mount basis.

EXAMPLE

Boot a kernel from a tftp server (note the final dot in the kernel path).

ip/tftpfs 10.192.254.53
echo reboot /n/tftp/386/9pc. >/dev/reboot

SOURCE

/sys/src/cmd/ip/tftpfs.c

SEE ALSO

dhcpd(8).

truetypefs – TrueType font file system

SYNOPSIS

truetypefs[-F fontpath]

DESCRIPTION

Truetypefs serves a read-only filesystem at /n/ttf that generates fonts and subfonts from True-Type fonts which can be used in the Plan 9 graphics system.

By default, fonts are loaded from /lib/font/ttf/. The -F flag may be used to set the path TrueType fonts are loaded from.

Truetypefs generates subfonts when they are accessed. Fonts are specified via a TrueType font file name followed by a font size. For example, /n/ttf/unifont.ttf.16/font is a *font*(6) file generated for GNU Unifont at a size of 16.

EXAMPLES

Use size 16 GNU Unifont for *acme*(1):

truetypefs
font=/n/ttf/unifont.ttf.16/font
acme -c 1 /lib/glass

SOURCE

/sys/src/cmd/truetypefs.c

SEE ALSO

ttf(2), font(6), subfont(2)

HISTORY

Truetypefs first appeared in 9front (October, 2018).

upasfs – mail file server

SYNOPSIS

```
upas/fs[-DSbdfilnps][-c cachtarg][-f mailbox][-m mntpoint]
```

DESCRIPTION

Fs is a user level file system that caches mailboxes and presents them as a file system. A user normally starts fs in his/her profile after starting *plumber*(4) and before starting a window system, such as rio(1) or acme(1). The file system is used by nedmail(1), acme(1)'s mail reader, and *imap4d* and *pop3* (both *pop3*(8)) to parse messages. Fs also generates plumbing messages used by *biff* and *faces*(1) to provide mail announcements.

The mailbox itself becomes a directory under /mail/fs. Each message in the mailbox becomes a numbered directory in the mailbox directory, and each attachment becomes a numbered directory in the message directory. Since an attachment may itself be a mail message, this structure can recurse ad nauseam.

Each message and attachment directory contains the files:

body cc date digest disposition filename flags ffrom from	the message minus the RFC2822 style headers the address(es) from the CC: header the date in the message, or if none, the time of delivery an SHA1 digest of the message contents inline or file a name to use to file an attachment persistant message flags as per IMAP the parsed name of the sender the from address in the From: header, or if none, the address on the enve- lope.
header	the RFC822 headers
info	described below, essentially a summary of the header info
inreplyto	contents of the in-reply-to: header
lines	the number of lines in the message body
messageid	the parsed RFC2822 MessageID
mimeheader	the mime headers
raw	the undecoded MIME message
rawbody	the undecoded message body
rawheader	the undecoded message header
references	the parsed MessageIDs of each referenced message, one per line
replyto	the address to send any replies to.
subject	the contents of the subject line
to	the address(es) from the To: line.
type	the MIME content type
unixheader	the envelope header from the mailbox
unixdate	the date portion of the Unix From line.
unixdatesec	the mdir filename for mdir messages. The portion before the dot is always the date from the Unix From line in seconds since epoch.

The info file contains the following information, one item per line. Lists of addresses are single space separated.

sender address recipient addresses cc addresses reply address envelope date subject MIME content type MIME disposition filename SHA1 digest bcc addresses in-reply-to: contents RFC822 date message senders message id number of lines in body size of message message flags unixdatesec name from From: header

Deleting message directories causes the message to be removed from the mailbox.

The mailbox is scanned and the structure updated whenever the mailbox changes. Message directories are not renumbered. The results of the scan are recorded in *mailbox*.idx.

The file /mail/fs/ctl is used to direct *fs* to open, close, rename, create or remove new mailboxes, and also to delete or flag groups of messages atomically. The messages that can be written to this file are:

open path mboxname	opens a new mailbox. <i>path</i> is the file to open, and <i>mboxname</i> is the name that appears under /mail/fs.
close <i>mboxname</i>	close <i>mboxname</i> . The close takes affect only after all files open under /mail/fs/ <i>mboxname</i> have been closed.
create <i>mboxname</i>	create a new mailbox, mboxname. The mailbox type must support creation.
rename [-t] <i>old new</i>	rename the mailbox <i>old</i> to <i>new</i> . The t flag truncates rather than removes the old mailbox. The renaming takes effect immedately. While mailboxes of any type may be renamed, it is not possible to use rename to convert folder types.
<pre>remove [-rt] mboxname</pre>	remove mboxname. The <i>r</i> flag removes any subfolders while the <i>t</i> flag truncates, rather than removes.
delete mboxname number	
	Delete the messages with the given numbers from <i>mboxname</i> .
flag mhoxname flags numbe	r

flag mboxname flags number ...

flag the given messages.

The flags file records persistant message flags. These flags are a superset of the standard IMAP message flags. Flags are stored in order. Unset flags are represented by a '-' while set flags are represented by the following ordered characters

- a answered
- D deleted
- d draft
- f flagged
- r recent
- s seen
- S stored

Messages of the form [+-] flags may be written to the flags file. Fs maintains the *r* flag. Mail readers are expected to maintain other flags.

The options are:

-D	Trace 9P protocol messages.
----	-----------------------------

-S	Log to	consol	e in ado	dition to	the standard	l places.			
-b	stands for biffing. Each time new mail is received, a message is printed to standard output containing the sender address, subject, and number of bytes. It is intended for people telnetting in who want mail announcements.								
–с <i>cachetarg</i>	attemp	ot to ke	ep the	cache be	low cachetai	r <i>g</i> bytes.			
-d	loud d	ebuggiı	ıg.						
−£ file	use	file	as	the	mailbox	instead	of	the	default,

/mail/box/username/mbox.

-i -1	chatty index debugging. logging. Turn on logging via syslog (and to the console with -S) to the file /sys/log/fs.				
-m <i>mntpt</i>	mount on <i>mntpt</i> rather than the default /mail/fs.				
-n	Don't open a mailbox initially. Overridden by -f.				
-p	turn off plumbing. Unless this is specified, <i>fs</i> sends a message to the plumb port, seemail, from source mailfs for each message received or deleted. The message contains the attributes <i>sender</i> = <i><contents file="" from="" of=""></contents></i> , <i>filetype</i> =mail, <i>mailtype</i> = <i>deleted or new</i> , and <i>length</i> = <i><message i="" in<="" length=""> <i>bytes></i>. The contents of the message is the full path name of the directory representing the message.</message></i>				
-s	causes fs to put itself in /srv with a name of the form /srv/upasfs.user.				

Fs will exit once all references to its directory have disappeared.

Fs interprets mailbox file names of the form */proto/host/user* to mean access an account on *host* using the given protocol. Authentication is delegated to *factotum*(4). The final */user* may be omitted, in which case the user name is gleaned from the key held by *factotum*. The following protocols are supported:

рор	cleartext POP with password authentication
арор	cleartext POP with challenge-response (APOP) authentication
poptls	TLS-encrypted POP with password authentication
apoptls	TLS-encrypted POP with challenge-response (APOP) authentication
imap	cleartext IMAP with CRAM-MD5 or password authentication
imaps	TLS-encrypted IMAP CRAM-MD5 or password authentication

The two IMAP protocols allow an optional fourth field specifying a mailbox name, for example /imap/server/user/stored.

Poptls and apoptls connect to port 110 in plaintext and start TLS using the POP STLS command. Imaps connects to port 993 and starts TLS before initiating the IMAP conversation. There should probably be pops, apops, and imaptls protocols as well. (Pops and apops would connect to port 995 and start TLS before initiating the POP conversation, and imaptls would connect to port 143 in plaintext and start TLS using the IMAP STARTTLS command. (That's the nice thing about standards—there's so many to choose from.))

FILES

/mail/box/*	mail directories
/mail/box/*/mbox	mailbox files
/mail/box/*/ <i>mbox</i> .idx	mailbox indicies
/mail/box/*/L.mbox	mutual exclusion lock for altering mbox (mbox format only)

SOURCE

/sys/src/cmd/upas/fs

SEE ALSO

aliasmail(8), faces(1), filter(1), mail(1), marshal(1), mdir(6), mlmgr(1), nedmail(1), pop3(8), qer(8), rewrite(6), send(8), upasfs(4),

Erik Quanstrom "Scaling Upas", Proceedings of IWP9, October, 2008.

vacfs - a Venti-based file system

SYNOPSIS

```
vacfs [-dips][-c cachesize][-h host][-m mtpt][-S srvname] vacfile
```

DESCRIPTION

Vacfs interprets the file system created by *vac*(1) so that it can be mounted into a Plan 9 file hierarchy. The data for the file system is stored on *venti*(8) with a root fingerprint specified in *vacfile*. *Vacfs* is currently rather limited: access is read-only, clients are not authenticated, and groups are assumed to contain a single member with the same name. These restrictions should eventually be removed.

Options to *vacfs* are:

- -c cachesize The number of file system blocks to cache in memory. The default is 1000 blocks.
- -d Print debugging information to standard error.
- -h host The network address of the Venti server. The default is taken from the environment variable venti. If this variable does not exist, then the default is the metaname \$venti, which can be configured via ndb(6).
- -i Use file descriptors 0 and 1 as the 9P communication channel rather than create a pipe.
- -m mtpt The location to mount the file system. The default is /n/vac.
- -p Disables permission checking.
- -s Post the 9P channel in /srv/vacfs rather than mounting it on *mtpt*.
- -S *srvname* Post the 9P channel in /srv/*srvname* rather than mounting it on *mtpt*.

SOURCE

/sys/src/cmd/vac

SEE ALSO

vac(1), venti(8)

wadfs - WAD file system

SYNOPSIS

wadfs [-Dr] [-m mtpt] [-S srvname] [WAD]

DESCRIPTION

Wadfs serves a file tree mounted at *mtpt* (default /mnt/wad) that provides access to a *WAD* file's contents.

The command line options are:

-D	Enable 9P debugging messages.
-r	Set read-only file tree.
–S srvname	Post channel on /srv/ <i>srvname</i> .
-m <i>mtpt</i>	Set mountpoint.

A WAD is a concatenation of uncompressed files, referred to as lumps. A lump may contain either data, or be used as a marker to indicate the beginning or end of a section, segregating lumps of the same format.

Wadfs represents section start markers as directories, and regular lumps and end markers as files. For convenience, lump file names are in lower case, and are translated to the upper case internally.

At startup, if the path to a *WAD* file is provided as argument, *wadfs* will attempt to parse it and construct a file tree. Otherwise, *wadfs* starts with a blank tree instead.

Two additional files are provided in the file system's root directory: SIG and WAD. Reading from and writing to SIG allows accessing and changing the *WAD*'s type. The only possible values are PWAD (the default) and IWAD.

WAD returns the new WAD file resulting from the recompilation of the lump tree.

WAD file structure

There are few restrictions on the structure of *WAD* files. Excepting maps, sections can nest and may have no end marker, or one named differently than the section itself. Regular sections typically have one-letter names, and nested sections use the same name appended by a digit. By convention, lump names may only contain visible printing ASCII characters, excepting lower-case letters. Map sections do not end at a marker but at the next non map lump, and use hardcoded names, depending on game version.

Wadfs imposes a number of additional restrictions on structure and naming:

- Lump names may not contain upper-case letters and the / character.
- A map section may only contain map lumps, which use hardcoded names. Ordering is significant, but is handled automatically. Map sections may not nest.
- Regular sections may not nest beyond one level, and may not contain more than one end marker. End markers may not exist outside of a section. Directory names omit the start marker's _START suffix.
- Excepting map lumps, no two lumps, including markers, may have the same name.
- Once created, a lump may not be renamed so as to change its type.

Error recovery

Upon parsing the initial *WAD* file, if one of the restrictions for *WAD* file structure outlined in the sections above is not respected, a warning is issued, and the offending lump is potentially skipped. Some recovery is attempted, but one must systematically recheck the tree. When duplicate non marker lumps are encountered, each will overwrite the previous entry.

EXAMPLES

Open doom2.wad and play a MUS file:

% games/wadfs /sys/games/lib/doom/doom2.wad createfile SW18_7: file already exists % games/mus /mnt/wad/d_romero | games/midi Now create a blank *WAD*, then one section FF; copy a flat from doom2.wad to the directory, then rename the end marker to F_END to have the doom engine find the flat; finally, compile and save the new *WAD* file.

% games/wadfs -m /mnt/wad2 % cd /mnt/wad2 % mkdir ff adding end marker FF_END % cp ../wad/f/f1/f_sky1 ff/ % mv ff/ff_end ff/f_end % cp WAD /sys/games/lib/doom/sky.wad

SOURCE

/sys/src/games/wadfs.c

SEE ALSO

games(1), mus(1)

HISTORY

Wadfs first appeared in 9front (August, 2017).

BUGS

Many WAD files in the wild do not conform to all the rules exposed above, in particular ones using DeHackEd engine modifications. WAD's using end markers outside of a section, typically F_END, will lose them.

Repairing broken WAD files can be a pain.

webcookies - HTTP cookie manager

SYNOPSIS

webcookies [-f cookiefile] [-m mtpt] [-s service]

DESCRIPTION

Webcookies manages a set of HTTP cookies, which are used to associate HTTP requests with persistent state (such as user profiles) on many web servers.

Webcookies reads cookiefile (default \$home/lib/webcookies) and mounts itself at *mtpt* (default /mnt/webcookies). If *service* is specified, *cookiefs* will post a service file descriptor in /srv/service.

The cookie file contains one cookie per line; each cookie comprises some number of attr=value pairs. Cookie attributes are:

name= <i>name</i>	The name of the cookie on the remote server.
value=value	The value associated with that name on the remote server. The actual data
	included when a cookie is sent back to the server is "name=value" (where,
	confusingly, name and value are the values associated with the name and
	value attributes.
domain= <i>domain</i>	The domain within which the cookie can be used. If <i>domain</i> is an IP address, the cookie can only be used when connecting to a web server at that IP
	address. If <i>domain</i> is a pattern beginning with a dot, the cookie can only be used for servers whose name has <i>domain</i> as a suffix. For example, a cookie with domain=.bell-labs.com may be used on the web sites <i>www.bell</i> -
	labs.com and www.research.bell–labs.com.
path= <i>path</i>	The cookie can only be used for URLs with a path (the part after
E b	http://hostname) beginning with path.
version=version	The version of the HTTP cookie specification, specified by the server.
comment=commen	t
	A comment, specified by the server.
expire= <i>expire</i>	The cookie expires at time <i>expire</i> , which is a decimal number of seconds since the epoch.
secure=1	The cookie may only be used over secure (https) connections.
explicitdomain	1=1
-	The domain associated with this cookie was set by the server (rather than inferred from a URL).
explicitpath=1	
	The path associated with this cookie was set by the server (rather than inferred from a URL).
netscapestyle=	
neveupeerjie	The server presented the cookie in "Netscape style," which does not conform
	to the cookie standard, RFC2109. It is assumed that when presenting the cookie to the server, it must be sent back in Netscape style as well.
Webcookies serves a	directory containing two files. The first, cookies, is a textual representa-
tion of the cookie fi ond, http, is inten	le, which can be edited to change the set of cookies currently held. The sec- ded to be used by HTTP clients to access cookies. Upon opening http, the
chent must write a f	full URL to it. After writing the URL, reading from the file will yield any HTTP

client must write a full URL to it. After writing the URL, reading from the file will yield any HTTP Cookie: headers that should be included in the request for this particular URL. Once the request has been made, any Set-Cookie: lines in the HTTP response header should be written to the file to save them for next time. If cookiefs decides not to accept the cookie (as outlined in RFC2109, section 4.3.4), no indication is given.

SOURCE

/sys/src/cmd/webcookies.c

SEE ALSO

webfs(4), hget(1)

webfs - world wide web file system

SYNOPSIS

webfs [-Dd][-A useragent][-T timeout][-m mtpt][-s service]

DESCRIPTION

Webfs presents a file system interface to the parsing and retrieving of URLs. Webfs mounts itself at *mtpt* (default /mnt/web), and, if *service* is specified, will post a service file descriptor in /srv/service. The -d flag enables general debug printing to standard error while the -D flag enables 9P debug prints.

If the environment variable httpproxy is set, all HTTP request initiated by *webfs* will be made through that proxy url.

Webfs presents a three-level file system suggestive of the network protocol hierarchies ip(3) and ether(3).

The top level contains the two files: ctl, and clone.

The top level ctl file is used to maintain parameters global to the instance of *webfs*. Reading the ctl file yields the current values of the parameters. Writing strings of the form "attr value" sets a particular attribute.

The following global parameters can be set:

useragent

Sets the HTTP user agent string.

timeout

Sets the request timeout in milliseconds.

flushauth url

Flushes any associated authentication information for resources under *url* or all resources if no url was given.

preauth url realm

Preauthenticates all resources under *url* with the given *realm* using HTTP Basic authentication. This will cause *webfs* to preemptively send the resulting authorization information not waiting for the server to respond with an HTTP 401 Unauthorized status.

The top-level directory also contains numbered directories corresponding to connections, which may be used to fetch a single URL. To allocate a connection, open the clone file and read a number n from it. After opening, the clone file is equivalent to the file n/ctl. A connection is assumed closed once all files in its directory have been closed, and is then will be reallocated.

Each connection has a URL attribute url associated with it. This URL may be an absolute URL such as *http://www.lucent.com/index.html* or a relative URL such as *../index.html*. The baseurl attribute sets the URL against which relative URLs are interpreted. Once the URL has been set by writing to the ctl file of the connection, its pieces can be retrieved via individual files in the parsed directory:

```
parsed/url
http://pete:secret@www.example.com:8000/cgi/search?q=kittens#results
parsed/scheme
http
parsed/user
pete
parsed/pass
secret
parsed/host
www.example.com
parsed/port
8000
```

parsed/*path* /cgi/search

parsed/query q=kittens parsed/fragment results

If there is associated data to be posted with the request, it can be written to postbody. Opening postbody or body initiates the request. If the request fails, then opening the body or writing to postbody file will fail and return a error string.

When the body file has been opened, response headers appear as files in the connection directory. For example reading the contenttype file yields the MIME content type of the body data. If the request was redirected, the URL represented by the parsed directory will change to the final destination.

The resulting data may be read from body as it arrives.

The following is a list of attributes that can be set to do a connection prior initiating the request:

url,baseurl

See above.

useragent

Sets a custom useragent string to be used with the request.

Adds arbitrary HTTP headers to be send with the request.

contenttype

Sets the MIME content type of the postbody.

request

headers

Usually, the HTTP method used is POST when postbody file is opend first or GET otherwise. This can be overridden with the request attribute so send arbitrary HTTP requests.

EXAMPLE

/rc/bin/hget is a simple client.

SOURCE

/sys/src/cmd/webfs

SEE ALSO

webcookies(4), hget(1)

DIAGNOSTICS

For cookies to work, *webcookies*(4), should be running and mounted on /mnt/webcookies otherwise cookies will be ignored.

HISTORY

Webfs first appeared in Plan 9 from Bell Labs. It was rewritten from scratch for 9front (January, 2012).

wikifs, wikipost – wiki file system

SYNOPSIS

wikifs [-DM][-a announce]... [-m mtpt][-p perm][-s service] dir

ip/httpd/wikipost [-b inbuf] [-d domain] [-r remoteip] [-w webroot] [-N netdir] method
version uri [search]

DESCRIPTION

A *wiki* is a web server that facilitates easy editing of the pages it contains. *Wikifs* presents a wiki in two forms: as web pages to be served via httpd(8) and as text files to be viewed via the *acme*(1) wiki client (see /acme/wiki/guide).

Wikifs presents a file system interface to the wiki data stored in *dir*. By default, *wikifs* mounts itself at /mnt/wiki; the -m flag specifies a different mount point, and the -M flag causes *wikifs* not to mount at all. *Wikifs* also announces 9P network services on the addresses given as arguments to -a options. If the -s option is given, *wikifs* will post a service file descriptor in /srv/service with permission *perm* (default 600). The -D flag causes a transcript of the 9P conversation to be written to standard error.

The wiki holds both the current pages and also all versions of all pages that have ever existed. All pages have time stamps associated with them. When a user wants to edit a page, he reads the current page from the wiki, noting the time stamp on the page. When a user writes changes to a page, he includes the time stamp of the page he started with. If the page has been updated by someone else while he was editing, the write will fail. This is called a "conflicting write." The submission is still saved in the history, so that the user can compare the page he submitted with the changes that were made while he was editing.

Each version of each page is described by a text file containing one or more metadata lines followed by the page contents. The metadata lines begin with a capital letter specifying the type of data. Currently the metadata types are:

- D The date this page was written, in decimal seconds since the epoch.
- A The author of this version of the page. Typically the rest of the line takes the form *name ip-address*.
- X This page's contents were submitted but rejected due to a conflicting write.

After the metadata comes the actual page contents; each line of page contents is prefixed with a # character.

The directory dir/d contains all the wiki data. Typically it is world-writable so that wikifs can run as none. Each page on the wiki has a unique sequence number n; for each page, the d directory contains three files n, n.hist, and L.n. The file n holds the current version of the page: the first line of n is the page title, followed by page metadata and contents as described above. The append-only file n.hist holds the history of the page. The first line of n.hist is the title of the page. The rest of the file is the metadata and contents of every version of the page that has been submitted to the wiki. L.n is a lock file for the page: it must be held while reading or writing n and n.hist. The lock files allow multiple instances of wikifs to coexist peacefully. Finally, the map file (with associated lock L.map) provides a mapping from sequence numbers to page titles. Each map line is a decimal n, a single space, and then the title. Since titles are presented as names by wikifs, they cannot contain slashes.

Wikifs presents a three-level file system. The top level contains per-page directories named by the page titles with spaces turned into underscores. Each page also has a number associated with it (see the discussion of the wiki data files below). The number corresponding to a page may also be used to access it, although directory listings will always present the title. The new file is used to add new or revised pages to the wiki: writes to the file should be in the usual textual format: a title line, metadata lines, and page contents. Once all the contents have been written, a final zero-length message should be written to mark the end of the page. This last write will return an error if a conflicting write has occurred. After writing the file, the client may read from new to obtain the canonical title for the page, as presented by the file system.

The page directories contain subdirectories representing the history of the page, named by the decimal time stamp corresponding to each version. In addition to these history directories, the page directories contain the following files:

current

The current raw data file for the page.

diff.html

A web page listing the contents of every version of the page that has ever appeared on the wiki. The text is grey by default: differences between versions appear in black.

edit.html

A web form for editing the current version of the page.

history.html

A web page listing the time stamps of the historical versions of the page. Each time stamp links to a page showing just that version.

history.txt

A textual formatting of the history. Each time stamp is prefixed with the name of the directory corresponding to that version.

index.html

An HTML formatting of the current version of the page.

index.txt

A textual formatting of the current version of the page.

werror.html

An HTML error page to be returned by *wikipost* on conflicting writes.

The HTML files are generated from the templates with the same names in *dir*, except that index.html and index.txt are generated from the templates page.html and page.txt.

The history directories are similar to the page directories but only contain current, index.html, and index.txt. This index.html and index.txt are generated from the templates oldpage.html and oldpage.txt.

The *httpd*(8) helper program *wikipost* is used to process editing requests posted to the web server by users. It expects the posted form to contain these (usually hidden) fields: TITLE, the title of the page; VERSION, the time stamp of the page that is being edited; service, the service name associated with this wiki (*wikipost* looks for /srv/wiki.*service*); and base, the base for wiki URLs in the response.

After mounting the wiki, *wikipost* writes a page update request to /mnt/wiki/new and then returns the contents of one HTML file in /mnt/wiki/title. If the write succeeds, *wikipost* returns index.html. if the write fails due to a conflicting write, *wikipost* returns werror.html.

EXAMPLE

The Plan 9 wiki at Bell Labs is started by running:

```
wikifs -p 666 -s wiki.plan9 -a tcp!*!wiki /sys/lib/wiki
```

The wiki is mounted for *httpd*(8) by an entry in /lib/namespace.httpd:

wiki

mount -b #s/wiki.plan9 /usr/web/wiki/plan9

Notice that the wiki service was explicitly posted with mode 666 so that *httpd* (running as none) would be able to mount it.

In the Plan 9 distribution, the directory /sys/lib/wiki contains sample files similar to those used to start the current Plan 9 wiki.

SOURCE

/sys/src/cmd/wikifs
/sys/src/cmd/ip/httpd/wikipost.c

SEE ALSO

The original wiki, http://c2.com/cgi/wiki?WikiWikiWeb /acme/wiki/guide

intro - introduction to the Plan 9 File Protocol, 9P

SYNOPSIS

#include <fcall.h>

DESCRIPTION

A Plan 9 *server* is an agent that provides one or more hierarchical file systems — file trees — that may be accessed by Plan 9 processes. A server responds to requests by *clients* to navigate the hierarchy, and to create, remove, read, and write files. The prototypical server is a separate machine that stores large numbers of user files on permanent media; such a machine is called, somewhat confusingly, a *file server*. Another possibility for a server is to synthesize files on demand, perhaps based on information on data structures inside the kernel; the *proc*(3) *kernel device* is a part of the Plan 9 kernel that does this. User programs can also act as servers.

A *connection* to a server is a bidirectional communication path from the client to the server. There may be a single client or multiple clients sharing the same connection. A server's file tree is attached to a process group's name space by bind(2) and mount calls; see intro(2). Processes in the group are then clients of the server: system calls operating on files are translated into requests and responses transmitted on the connection to the appropriate service.

The *Plan 9 File Protocol*, 9P, is used for messages between *clients* and *servers*. A client transmits *requests* (*T-messages*) to a server, which subsequently returns *replies* (*R-messages*) to the client. The combined acts of transmitting (receiving) a request of a particular type, and receiving (transmitting) its reply is called a *transaction* of that type.

Each message consists of a sequence of bytes. Two-, four-, and eight-byte fields hold unsigned integers represented in little-endian order (least significant byte first). Data items of larger or variable lengths are represented by a two-byte field specifying a count, n, followed by n bytes of data. Text strings are represented this way, with the text itself stored as a UTF-8 encoded sequence of Unicode characters (see utf(6)). Text strings in 9P messages are not NUL-terminated: n counts the bytes of UTF-8 data, which include no final zero byte. The NUL character is illegal in all text strings in 9P, and is therefore excluded from file names, user names, and so on.

Each 9P message begins with a four-byte size field specifying the length in bytes of the complete message including the four bytes of the size field itself. The next byte is the message type, one of the constants in the enumeration in the include file <fcall.h>. The next two bytes are an identifying *tag*, described below. The remaining bytes are parameters of different sizes. In the message descriptions, the number of bytes in a field is given in brackets after the field name. The notation *parameter*[*n*] where *n* is not a constant represents a variable-length parameter: *n*[2] followed by *n* bytes of data forming the *parameter*. The notation *string*[*s*] (using a literal *s* character) is shorthand for *s*[2] followed by *s* bytes of UTF-8 text. (Systems may choose to reduce the set of legal characters to reduce syntactic problems, for example to remove slashes from name components, but the protocol has no such restriction. Plan 9 names may contain any printable character (that is, any character outside hexadecimal 00-1F and 80-9F) except slash.) Messages are transported in byte form to allow for machine independence; *fcall*(2) describes routines that convert to and from this form into a machine-dependent C structure.

MESSAGES

size[4] Tversion tag[2] msize[4] version[s] size[4] Rversion tag[2] msize[4] version[s] size[4] Tauth tag[2] afid[4] uname[s] aname[s] size[4] Rauth tag[2] aqid[13] size[4] Rerror tag[2] ename[s] size[4] Tflush tag[2] oldtag[2] size[4] Rflush tag[2] size[4] Tattach tag[2] fid[4] afid[4] uname[s] aname[s] size[4] Rattach tag[2] qid[13]

```
size[4] Twalk tag[2] fid[4] newfid[4] nwname[2] nwname*(wname[s])
size[4] Rwalk tag[2] nwgid[2] nwgid*(wgid[13])
size[4] Topen tag[2] fid[4] mode[1]
size[4] Ropen tag[2] qid[13] iounit[4]
size[4] Tcreate tag[2] fid[4] name[s] perm[4] mode[1]
size[4] Rcreate tag[2] qid[13] iounit[4]
size[4] Tread tag[2] fid[4] offset[8] count[4]
size[4] Rread tag[2] count[4] data[count]
size[4] Twrite tag[2] fid[4] offset[8] count[4] data[count]
size[4] Rwrite tag[2] count[4]
size[4] Tclunk tag[2] fid[4]
size[4] Rclunk tag[2]
size[4] Tremove tag[2] fid[4]
size[4] Rremove tag[2]
size[4] Tstat tag[2] fid[4]
size[4] Rstat tag[2] stat[n]
size[4] Twstat tag[2] fid[4] stat[n]
size[4] Rwstat tag[2]
```

Each T-message has a *tag* field, chosen and used by the client to identify the message. The reply to the message will have the same tag. Clients must arrange that no two outstanding messages on the same connection have the same tag. An exception is the tag NOTAG, defined as $(ushort)\sim0$ in <fcall.h>: the client can use it, when establishing a connection, to override tag matching in version messages.

The type of an R-message will either be one greater than the type of the corresponding T-message or Rerror, indicating that the request failed. In the latter case, the *ename* field contains a string describing the reason for failure.

The version message identifies the version of the protocol and indicates the maximum message size the system is prepared to handle. It also initializes the connection and aborts all outstanding I/O on the connection. The set of messages between version requests is called a *session*.

Most T-messages contain a *fid*, a 32-bit unsigned integer that the client uses to identify a "current file" on the server. Fids are somewhat like file descriptors in a user process, but they are not restricted to files open for I/O: directories being examined, files being accessed by *stat*(2) calls, and so on — all files being manipulated by the operating system — are identified by fids. Fids are chosen by the client. All requests on a connection share the same fid space; when several clients share a connection, the agent managing the sharing must arrange that no two clients choose the same fid.

The fid supplied in an attach message will be taken by the server to refer to the root of the served file tree. The attach identifies the user to the server and may specify a particular file tree served by the server (for those that supply more than one).

Permission to attach to the service is proven by providing a special fid, called afid, in the attach message. This afid is established by exchanging auth messages and subsequently manipulated using read and write messages to exchange authentication information not defined explicitly by 9P. Once the authentication protocol is complete, the afid is presented in the attach to permit the user to access the service.

A walk message causes the server to change the current file associated with a fid to be a file in the directory that is the old current file, or one of its subdirectories. Walk returns a new fid that refers to the resulting file. Usually, a client maintains a fid for the root, and navigates by walks from the root fid.

A client can send multiple T-messages without waiting for the corresponding R-messages, but all outstanding T-messages must specify different tags. The server may delay the response to a request and respond to later ones; this is sometimes necessary, for example when the client reads from a file that the server synthesizes from external events such as keyboard characters.

Replies (R-messages) to auth, attach, walk, open, and create requests convey a *qid* field back to the client. The qid represents the server's unique identification for the file being accessed: two files on the same server hierarchy are the same if and only if their qids are the same. (The client may have multiple fids pointing to a single file on a server and hence having a single qid.) The thirteen-byte qid fields hold a one-byte type, specifying whether the file is a directory, append-only file, etc., and two unsigned integers: first the four-byte qid *version*, then the eight-byte qid *path*. The path is an integer unique among all files in the hierarchy. If a file is deleted and recreated with the same name in the same directory, the old and new path components of the qids should be different. The version is a version number for a file; typically, it is incremented every time the file is modified.

An existing file can be opened, or a new file may be created in the current (directory) file. I/O of a given number of bytes at a given offset on an open file is done by read and write.

A client should clunk any fid that is no longer needed. The remove transaction deletes files.

The stat transaction retrieves information about the file. The *stat* field in the reply includes the file's name, access permissions (read, write and execute for owner, group and public), access and modification times, and owner and group identifications (see *stat*(2)). The owner and group identifications are textual names. The wstat transaction allows some of a file's properties to be changed.

A request can be aborted with a flush request. When a server receives a Tflush, it should not reply to the message with tag *oldtag* (unless it has already replied), and it should immediately send an Rflush. The client must wait until it gets the Rflush (even if the reply to the original message arrives in the interim), at which point *oldtag* may be reused.

Because the message size is negotiable and some elements of the protocol are variable length, it is possible (although unlikely) to have a situation where a valid message is too large to fit within the negotiated size. For example, a very long file name may cause a Rstat of the file or Rread of its directory entry to be too large to send. In most such cases, the server should generate an error rather than modify the data to fit, such as by truncating the file name. The exception is that a long error string in an Rerror message should be truncated if necessary, since the string is only advisory and in some sense arbitrary.

Most programs do not see the 9P protocol directly; instead calls to library routines that access files are translated by the mount driver, *mnt*(3), into 9P messages.

DIRECTORIES

Directories are created by create with DMDIR set in the permissions argument (see stat(5)). The members of a directory can be found with read(5). All directories must support walks to the directory ... (dot-dot) meaning parent directory, although by convention directories contain no explicit entry for .. or . (dot). The parent of the root directory of a server's tree is itself.

ACCESS PERMISSIONS

Each file server maintains a set of user and group names. Each user can be a member of any number of groups. Each group has a *group leader* who has special privileges (see *stat*(5) and *users*(6)). Every file request has an implicit user id (copied from the original attach) and an implicit set of groups (every group of which the user is a member).

Each file has an associated *owner* and *group* id and three sets of permissions: those of the owner, those of the group, and those of "other" users. When the owner attempts to do something to a file, the owner, group, and other permissions are consulted, and if any of them grant the requested permission, the operation is allowed. For someone who is not the owner, but is a member of the file's group, the group and other permissions are consulted. For everyone else, the other permissions are used. Each set of permissions says whether reading is allowed, whether writing is allowed, and whether executing is allowed. A walk in a directory is regarded as executing the directory, not reading it. Permissions are kept in the low-order bits of the file *mode*: owner read/write/execute permissions are in bits 8, 7, and 6 respectively (using 0 to number the low order). The group permissions are in bits 5, 4, and 3, and the other permissions are in bits 2, 1, and 0.

The file *mode* contains some additional attributes besides the permissions. If bit 31 (DMDIR) is set, the file is a directory; if bit 30 (DMAPPEND) is set, the file is append-only (offset is ignored in writes); if bit 29 (DMEXCL) is set, the file is exclusive-use (only one client may have it open at a

time); if bit 27 (DMAUTH) is set, the file is an authentication file established by auth messages; if bit 26 (DMTMP) is set, the contents of the file (or directory) are not included in nightly archives. (Bit 28 is skipped for historical reasons.) These bits are reproduced, from the top bit down, in the type byte of the Qid: QTDIR, QTAPPEND, QTEXCL, (skipping one bit) QTAUTH, and QTTMP. The name QTFILE, defined to be zero, identifies the value of the type for a plain file.

attach, auth - messages to establish a connection

SYNOPSIS

size[4] Tauth tag[2] afid[4] uname[s] aname[s]

size[4] Rauth tag[2] aqid[13]

size[4] Tattach tag[2] fid[4] afid[4] uname[s] aname[s]

size[4] Rattach tag[2] qid[13]

DESCRIPTION

The attach message serves as a fresh introduction from a user on the client machine to the server. The message identifies the user (*uname*) and may select the file tree to access (*aname*). The *afid* argument specifies a fid previously established by an auth message, as described below.

As a result of the attach transaction, the client will have a connection to the root directory of the desired file tree, represented by *fid*. An error is returned if *fid* is already in use. The server's idea of the root of the file tree is represented by the returned *qid*.

If the client does not wish to authenticate the connection, or knows that authentication is not required, the *afid* field in the attach message should be set to NOFID, defined as $(u32int)\sim0$ in <fcall.h>. If the client does wish to authenticate, it must acquire and validate an *afid* using an auth message before doing the attach.

The auth message contains *afid*, a new fid to be established for authentication, and the *uname* and *aname* that will be those of the following attach message. If the server does not require authentication, it returns Rerror to the Tauth message.

If the server does require authentication, it returns *aqid* defining a file of type QTAUTH (see *intro*(5)) that may be read and written (using read and write messages in the usual way) to execute an authentication protocol. That protocol's definition is not part of 9P itself.

Once the protocol is complete, the same *afid* is presented in the attach message for the user, granting entry. The same validated *afid* may be used for multiple attach messages with the same *uname* and *aname*.

ENTRY POINTS

An attach transaction will be generated for kernel devices (see *intro*(3)) when a system call evaluates a file name beginning with #. *Pipe*(2) generates an attach on the kernel device *pipe*(3). The *mount* system call (see *bind*(2)) generates an attach message to the remote file server. When the kernel boots, an *attach* is made to the root device, *root*(3), and then an attach is made to the requested file server machine.

An auth transaction is generated by the *fauth*(2) system call or by the first mount system call on an uninitialized connection.

SEE ALSO

auth(2), fauth(2), version(5), authsrv(6)

clunk - forget about a fid

SYNOPSIS

size[4] Tclunk tag[2] fid[4]
size[4] Rclunk tag[2]

DESCRIPTION

The clunk request informs the file server that the current file represented by *fid* is no longer needed by the client. The actual file is not removed on the server unless the fid had been opened with ORCLOSE.

Once a fid has been clunked, the same fid can be reused in a new walk or attach request.

Even if the clunk returns an error, the *fid* is no longer valid.

ENTRY POINTS

A clunk message is generated by *close* and indirectly by other actions such as failed *open* calls.

error - return an error

SYNOPSIS

size[4] Rerror tag[2] ename[s]

DESCRIPTION

The Rerror message (there is no Terror) is used to return an error string describing the failure of a transaction. It replaces the corresponding reply message that would accompany a successful call; its tag is that of the failing request.

By convention, clients may truncate error messages after ERRMAX-1 bytes; ERRMAX is defined in <libc.h>.

flush - abort a message

SYNOPSIS

size[4] Tflush tag[2] oldtag[2]
size[4] Rflush tag[2]

DESCRIPTION

When the response to a request is no longer needed, such as when a user interrupts a process doing a *read*(2), a Tflush request is sent to the server to purge the pending response. The message being flushed is identified by *oldtag*. The semantics of flush depends on messages arriving in order.

The server should answer the flush message immediately. If it recognizes *oldtag* as the tag of a pending transaction, it should abort any pending response and discard that tag. In either case, it should respond with an Rflush echoing the *tag* (not *oldtag*) of the Tflush message. A Tflush can never be responded to by an Rerror message.

The server may respond to the pending request before responding to the Tflush. It is possible for a client to send multiple Tflush messages for a particular pending request. Each subsequent Tflush must contain as *oldtag* the tag of the pending request (not a previous Tflush). Should multiple Tflushes be received for a pending request, they must be answered in order. A Rflush for any of the multiple Tflushes implies an answer for all previous ones. Therefore, should a server receive a request and then multiple flushes for that request, it need respond only to the last flush.

When the client sends a Tflush, it must wait to receive the corresponding Rflush before reusing *oldtag* for subsequent messages. If a response to the flushed request is received before the Rflush, the client must honor the response as if it had not been flushed, since the completed request may signify a state change in the server. For instance, Tcreate may have created a file and Twalk may have allocated a fid. If no response is received before the Rflush, the flushed transaction is considered to have been canceled, and should be treated as though it had never been sent.

Several exceptional conditions are handled correctly by the above specification: sending multiple flushes for a single tag, flushing after a transaction is completed, flushing a Tflush, and flushing an invalid tag.

open, create - prepare a fid for I/O on an existing or new file

SYNOPSIS

size[4] Topen tag[2] fid[4] mode[1]

size[4] Ropen tag[2] qid[13] iounit[4]

size[4] Tcreate tag[2] fid[4] name[s] perm[4] mode[1]

size[4] Rcreate tag[2] qid[13] iounit[4]

DESCRIPTION

The open request asks the file server to check permissions and prepare a fid for I/O with subsequent read and write messages. The *mode* field determines the type of I/O: 0 (called OREAD in <libc.h>), 1 (OWRITE), 2 (ORDWR), and 3 (OEXEC) mean *read access, write access, read and write access,* and *execute access,* to be checked against the permissions for the file. In addition, if *mode* has the OTRUNC (0x10) bit set, the file is to be truncated, which requires write permission (if the file is append-only, and permission is granted, the open succeeds but the file will not be truncated); if the *mode* has the ORCLOSE (0x40) bit set, the file is to be removed when the fid is clunked, which requires permission to remove the file from its directory. All other bits in *mode* should be zero. It is illegal to write a directory, truncate it, or attempt to remove it on close. If the file is marked for exclusive use (see *stat*(5)), only one client can have the file open at any time. That is, after such a file has been opened, further opens will fail until *fid* has been clunked. All these permissions are checked at the time of the open request; subsequent changes to the permissions of files do not affect the ability to read, write, or remove an open file.

The create request asks the file server to create a new file with the *name* supplied, in the directory (*dir*) represented by *fid*, and requires write permission in the directory. The owner of the file is the implied user id of the request, the group of the file is the same as *dir*, and the permissions are the value of

perm & (~0666 | (dir.perm & 0666))

if a regular file is being created and

perm & (~0777 | (dir.perm & 0777))

if a directory is being created. This means, for example, that if the create allows read permission to others, but the containing directory does not, then the created file will not allow others to read the file.

Finally, the newly created file is opened according to *mode*, and *fid* will represent the newly opened file. *Mode* is not checked against the permissions in *perm*. The *qid* for the new file is returned with the create reply message.

Directories are created by setting the DMDIR bit (0x8000000) in the perm.

The names . and . . are special; it is illegal to create files with these names.

It is an error for either of these messages if the fid is already the product of a successful open or create message.

An attempt to create a file in a directory where the given *name* already exists will be rejected; in this case, the *create* system call (see *open*(2)) uses open with truncation. The algorithm used by the *create* system call is: first walk to the directory to contain the file. If that fails, return an error. Next walk to the specified file. If the walk succeeds, send a request to open and truncate the file and return the result, successful or not. If the walk fails, send a create message. If that fails, it may be because the file was created by another process after the previous walk failed, so (once) try the walk and open again.

For the behavior of *create* on a union directory, see *bind*(2).

The iounit field returned by open and create may be zero. If it is not, it is the maximum number of bytes that are guaranteed to be read from or written to the file without breaking the I/O transfer into multiple 9P messages; see *read*(5).

ENTRY POINTS

Open and *create* both generate open messages; only *create* generates a create message. The iounit associated with an open file may be discovered by calling *iounit*(2).

For programs that need atomic file creation, without the race that exists in the open-create sequence described above, the kernel does the following. If the OEXCL (0x1000) bit is set in the *mode* for a create system call, the open message is not sent; the kernel issues only the create. Thus, if the file exists, create will draw an error, but if it doesn't and the create system call succeeds, the process issuing the create is guaranteed to be the one that created the file.

read, write - transfer data from and to a file

SYNOPSIS

size[4] Tread tag[2] fid[4] offset[8] count[4]

size[4] Rread tag[2] count[4] data[count]

size[4] Twrite tag[2] fid[4] offset[8] count[4] data[count]

size[4] Rwrite tag[2] count[4]

DESCRIPTION

The read request asks for *count* bytes of data from the file identified by *fid*, which must be opened for reading, starting *offset* bytes after the beginning of the file. The bytes are returned with the read reply message.

The *count* field in the reply indicates the number of bytes returned. This may be less than the requested amount. If the *offset* field is greater than or equal to the number of bytes in the file, a count of zero will be returned.

For directories, read returns an integral number of directory entries exactly as in stat (see *stat*(5)), one for each member of the directory. The read request message must have offset equal to zero or the value of offset in the previous read on the directory, plus the number of bytes returned in the previous read. In other words, seeking other than to the beginning is illegal in a directory (see *seek*(2)).

The write request asks that *count* bytes of data be recorded in the file identified by *fid*, which must be opened for writing, starting *offset* bytes after the beginning of the file. If the file is append-only, the data will be placed at the end of the file regardless of *offset*. Directories may not be written.

The write reply records the number of bytes actually written. It is usually an error if this is not the same as requested.

Because 9P implementations may limit the size of individual messages, more than one message may be produced by a single *read* or *write* call. The *iounit* field returned by *open*(5), if non-zero, reports the maximum size that is guaranteed to be transferred atomically.

ENTRY POINTS

Read and write messages are generated by the corresponding calls. Because they include an offset, the *pread* and *pwrite* calls correspond more directly to the 9P messages. Although *seek*(2) affects the offset, it does not generate a message.

remove - remove a file from a server

SYNOPSIS

size[4] Tremove tag[2] fid[4]
size[4] Rremove tag[2]

DESCRIPTION

The remove request asks the file server both to remove the file represented by *fid* and to clunk the *fid*, even if the remove fails. This request will fail if the client does not have write permission in the parent directory.

It is correct to consider remove to be a clunk with the side effect of removing the file if permissions allow.

If a file has been opened as multiple fids, possibly on different connections, and one fid is used to remove the file, whether the other fids continue to provide access to the file is implementation-defined. The Plan 9 file servers (like fs(4)) remove the file immediately: attempts to use the other fids will yield a "phase error." U9fs follows the semantics of the underlying Unix file system, so other fids typically remain usable.

ENTRY POINTS

Remove messages are generated by *remove*.

stat, wstat - inquire or change file attributes

SYNOPSIS

```
size[4] Tstat tag[2] fid[4]
size[4] Rstat tag[2] stat[n]
size[4] Tstat tag[2] stat[n]
```

size[4] Twstat tag[2] fid[4] stat[n]
size[4] Rwstat tag[2]

5/20[1] 1(05 0)

DESCRIPTION

The stat transaction inquires about the file identified by *fid*. The reply will contain a machineindependent *directory entry*, *stat*, laid out as follows:

size[2] total byte count of the following data

type[2]

for kernel use

dev[4] for kernel use

qid.type[1]

the type of the file (directory, etc.), represented as a bit vector corresponding to the high 8 bits of the file's mode word.

qid.vers[4]

version number for given path

qid.path[8]

the file server's unique identification for the file

mode[4]

permissions and flags

atime[4]

last access time

mtime[4]

last modification time

length[8]

length of file in bytes

name[s]

file name; must be / if the file is the root directory of the server

uid[s]

owner name

gid[s]

group name

muid[s]

name of the user who last modified the file

Integers in this encoding are in little-endian order (least significant byte first). The *convM2D* and *convD2M* routines (see *fcall*(2)) convert between directory entries and a C structure called a Dir.

The *mode* contains permission bits as described in *intro*(5) and the following: 0x8000000 (DMDIR, this file is a directory), 0x4000000 (DMAPPEND, append only), 0x20000000 (DMEXCL, exclusive use), 0x04000000 (DMTMP, temporary); these are echoed in Qid.type. Writes to append-only files always place their data at the end of the file; the *offset* in the write message is ignored, as is the OTRUNC bit in an open. Exclusive use files may be open for I/O by only one fid at a time across all clients of the server. If a second open is attempted, it draws an error. Servers may implement a timeout on the lock on an exclusive use file: if the fid holding the file open has been unused for an extended period (of order at least minutes), it is reasonable to break the lock and deny the initial fid further I/O. Temporary files are not included in nightly archives.

The two time fields are measured in seconds since the epoch (Jan 1 00:00 1970 GMT). The *mtime* field reflects the time of the last change of content (except when later changed by wstat). For a plain file, *mtime* is the time of the most recent create, open with truncation, or write; for a directory it is the time of the most recent remove, create, or wstat of a file in the directory. Similarly, the *atime* field records the last read of the contents; also it is set whenever *mtime* is set. In addition, for a directory, it is set by an attach, walk, or create, all whether successful or not.

The *muid* field names the user whose actions most recently changed the *mtime* of the file.

The *length* records the number of bytes in the file. Directories and most files representing devices have a conventional length of 0.

The stat request requires no special permissions.

The wstat request can change some of the file status information. The *name* can be changed by anyone with write permission in the parent directory; it is an error to change the name to that of an existing file. The *length* can be changed (affecting the actual length of the file) by anyone with write permission on the file. It is an error to attempt to set the length of a directory to a non-zero value, and servers may decide to reject length changes for other reasons. The *mode* and *mtime* can be changed by the owner of the file or the group leader of the file's current group. The directory bit cannot be changed by a wstat; the other defined permission and mode bits can. The *gid* can be changed: by the owner if also a member of the new group; or by the group leader of the file's current group if also leader of the new group (see *intro*(5) for more information about permissions and *users*(6) for users and groups). None of the other data can be altered by a wstat and attempts to change them will trigger an error. In particular, it is illegal to attempt to change the owner of a file. (These conditions may be relaxed when establishing the initial state of a file server; see *fsconfig*(8).)

Either all the changes in wstat request happen, or none of them does: if the request succeeds, all changes were made; if it fails, none were.

A wstat request can avoid modifying some properties of the file by providing explicit "don't touch" values in the stat data that is sent: zero-length strings for text values and the maximum unsigned value of appropriate size for integral values. As a special case, if *all* the elements of the directory entry in a Twstat message are "don't touch" values, the server may interpret it as a request to guarantee that the contents of the associated file are committed to stable storage before the Rwstat message is returned. (Consider the message to mean, "make the state of the file exactly what it claims to be.")

A *read* of a directory yields an integral number of directory entries in the machine independent encoding given above (see *read*(5)).

Note that since the stat information is sent as a 9P variable-length datum, it is limited to a maximum of 65535 bytes.

ENTRY POINTS

Stat messages are generated by *fstat* and *stat*.

Wstat messages are generated by *fwstat* and *wstat*.

BUGS

To make the contents of a directory, such as returned by read(5), easy to parse, each directory entry begins with a size field. For consistency, the entries in Twstat and Rstat messages also contain their size, which means the size appears twice. For example, the Rstat message is formatted as "(4+1+2+2+n)[4] Rstat tag[2] n[2] (n-2)[2] type[2] dev[4]...," where n is the value returned by convD2M.

version - negotiate protocol version

SYNOPSIS

size[4] Tversion tag[2] msize[4] version[s]
size[4] Rversion tag[2] msize[4] version[s]

DESCRIPTION

The version request negotiates the protocol version and message size to be used on the connection and initializes the connection for I/O. Tversion must be the first message sent on the 9P connection, and the client cannot issue any further requests until it has received the Rversion reply. The *tag* should be NOTAG (value (ushort)~0) for a version message.

The client suggests a maximum message size, msize, that is the maximum length, in bytes, it will ever generate or expect to receive in a single 9P message. This count includes all 9P protocol data, starting from the size field and extending through the message, but excludes enveloping transport protocols. The server responds with its own maximum, msize, which must be less than or equal to the client's value. Thenceforth, both sides of the connection must honor this limit.

The version string identifies the level of the protocol. The string must always begin with the two characters "9P". If the server does not understand the client's version string, it should respond with an Rversion message (not Rerror) with the version string the 7 characters "unknown".

The server may respond with the client's version string, or a version string identifying an earlier defined protocol version. Currently, the only defined version is the 6 characters "9P2000". Version strings are defined such that, if the client string contains one or more period characters, the initial substring up to but not including any single period in the version string defines a version of the protocol. After stripping any such period–separated suffix, the server is allowed to respond with a string of the form 9Pnnnn, where nnnn is less than or equal to the digits sent by the client.

The client and server will use the protocol version defined by the server's response for all subsequent communication on the connection.

A successful version request initializes the connection. All outstanding I/O on the connection is aborted; all active fids are freed ('clunked') automatically. The set of messages between version requests is called a *session*.

ENTRY POINTS

The version message is generated by the fversion system call. It is also generated automatically, if required, by a mount or fauth system call on an uninitialized connection.

walk - descend a directory hierarchy

SYNOPSIS

size[4] Twalk tag[2] fid[4] newfid[4] nwname[2] nwname*(wname[s])
size[4] Rwalk tag[2] nwqid[2] nwqid*(qid[13])

DESCRIPTION

The walk request carries as arguments an existing *fid* and a proposed *newfid* (which must not be in use unless it is the same as *fid*) that the client wishes to associate with the result of traversing the directory hierarchy by 'walking' the hierarchy using the successive path name elements wname. The *fid* must represent a directory unless zero path name elements are specified.

The *fid* must be valid in the current session and must not have been opened for I/O by an open or create message. If the full sequence of nwname elements is walked successfully, *newfid* will represent the file that results. If not, *newfid* (and fid) will be unaffected. However, if *newfid* is in use or otherwise illegal, an Rerror is returned.

The name "..." (dot-dot) represents the parent directory. The name "." (dot), meaning the current directory, is not used in the protocol.

It is legal for nwname to be zero, in which case *newfid* will represent the same file as *fid* and the walk will usually succeed; this is equivalent to walking to dot. The rest of this discussion assumes nwname is greater than zero.

The nwname path name elements wname are walked in order, "elementwise". For the first elementwise walk to succeed, the file identified by *fid* must be a directory, and the implied user of the request must have permission to search the directory (see *intro*(5)). Subsequent elementwise walks have equivalent restrictions applied to the implicit fid that results from the preceding elementwise walk.

If the first element cannot be walked for any reason, Rerror is returned. Otherwise, the walk will return an Rwalk message containing *nwqid* qids corresponding, in order, to the files that are visited by the *nwqid* successful elementwise walks; *nwqid* is therefore either nwname or the index of the first elementwise walk that failed. The value of *nwqid* cannot be zero unless nwname is zero. Also, *nwqid* will always be less than or equal to nwname. Only if it is equal, however, will *newfid* be affected, in which case *newfid* will represent the file reached by the final elementwise walk requested in the message.

A walk of the name "..." in the root directory of a server is equivalent to a walk with no name elements.

If *newfid* is the same as *fid*, the above discussion applies, with the obvious difference that if the walk changes the state of *newfid*, it also changes the state of *fid*; and if *newfid* is unaffected, then *fid* is also unaffected.

To simplify the implementation of the servers, a maximum of sixteen name elements or qids may be packed in a single message. This constant is called MAXWELEM in *fcall*(2). Despite this restriction, the system imposes no limit on the number of elements in a file name, only the number that may be transmitted in a single message.

ENTRY POINTS

A call to *chdir*(2) causes a walk. One or more walk messages may be generated by any of the following calls, which evaluate file names: *bind*, *create*, *exec*, *mount*, *open*, *remove*, *stat*, *unmount*, *wstat*. The file name element . (dot) is interpreted locally and is not transmitted in walk messages.

intro - introduction to file formats

DESCRIPTION

This section of the manual describes file formats and other miscellany such as *troff* macro packages.

a.out - object file format

SYNOPSIS

#include <a.out.h>

DESCRIPTION

An executable Plan 9 binary file has up to six sections: a header, the program text, the data, a symbol table, a PC/SP offset table (MC68020 only), and finally a PC/line number table. The header, given by a structure in <a.out.h>, contains 4-byte integers in big-endian order:

<pre>typedef } Exec;</pre>	struct Exec long long long long long long long long	<pre>{ magic; text; data; bss; syms; entry; spsz; pcsz;</pre>	<pre>/* magic number */ /* size of text segment */ /* size of initialized data */ /* size of uninitialized data */ /* size of symbol table */ /* entry point */ /* size of pc/sp offset table */ /* size of pc/line number table */</pre>
#define	HDR_MAGIC	0x00008000	
#define	_MAGIC(f, A_MAGIC I_MAGIC	_MAGIC(0, 8	((f) ((((4*(b))+0)*(b))+7))) /* 68020 */ 1) /* intel 386 */

#uer me	A_MAGIC	$\underline{-}$ MAGIC(0, 0)	/ 08020 /
#define	I_MAGIC	_MAGIC(0, 11)	/* intel 386 */
#define	J_MAGIC	_MAGIC(0, 12)	/* intel 960 (retired) */
#define	K_MAGIC	_MAGIC(0, 13)	/* sparc */
#define	V_MAGIC	_MAGIC(0, 16)	/* mips 3000 BE */
#define	X_MAGIC	$_MAGIC(0, 17)$	/* att dsp 3210 (retired) */
#define	M_MAGIC	_MAGIC(0, 18)	/* mips 4000 BE */
#define	D_MAGIC	_MAGIC(0, 19)	/* amd 29000 (retired) */
#define	E_MAGIC	_MAGIC(0, 20)	/* arm */
#define	Q_MAGIC	_MAGIC(0, 21)	/* powerpc */
#define	N_MAGIC	_MAGIC(0, 22)	/* mips 4000 LE */
#define	L_MAGIC	_MAGIC(0, 23)	/* dec alpha (retired) */
#define	P_MAGIC	_MAGIC(0, 24)	/* mips 3000 LE */
#define	U_MAGIC	_MAGIC(0, 25)	/* sparc64 */
#define	S_MAGIC	_MAGIC(HDR_MAGIC,	26) /* amd64 */
#define	T_MAGIC	_MAGIC(HDR_MAGIC,	27) /* powerpc64 */
#define	R_MAGIC	_MAGIC(HDR_MAGIC,	28) /* arm64 */

Sizes are expressed in bytes. The size of the header is not included in any of the other sizes.

When a Plan 9 binary file is executed, a memory image of three segments is set up: the text segment, the data segment, and the stack. The text segment begins at a virtual address which is a multiple of the machine-dependent page size. The text segment consists of the header and the first text bytes of the binary file. The entry field gives the virtual address of the entry point of the program. The data segment starts at the first page-rounded virtual address after the text segment. It consists of the next data bytes of the binary file, followed by bss bytes initialized to zero. The stack occupies the highest possible locations in the core image, automatically growing downwards. The bss segment may be extended by brk(2).

The next syms (possibly zero) bytes of the file contain symbol table entries, each laid out as:

```
uchar value[4];
char type;
char name[n]; /* NUL-terminated */
```

The value is in big-endian order and the size of the name field is not pre-defined: it is a zero-terminated array of variable length.

The type field is one of the following characters with the high bit set:

- T text segment symbol
- t static text segment symbol
- L leaf function text segment symbol
- 1 static leaf function text segment symbol
- D data segment symbol
- d static data segment symbol
- B bss segment symbol
- b static bss segment symbol
- a automatic (local) variable symbol
- p function parameter symbol

A few others are described below. The symbols in the symbol table appear in the same order as the program components they describe.

The Plan 9 compilers implement a virtual stack frame pointer rather than dedicating a register; moreover, on the MC680X0 architectures there is a variable offset between the stack pointer and the frame pointer. Following the symbol table, MC680X0 executable files contain a spsz-byte table encoding the offset of the stack frame pointer as a function of program location; this section is not present for other architectures. The PC/SP table is encoded as a byte stream. By setting the PC to the base of the text segment and the offset to zero and interpreting the stream, the offset can be computed for any PC. A byte value of 0 is followed by four bytes that hold, in big-endian order, a constant to be added to the offset. A byte value of 1 to 64 is multiplied by four and added, without sign extension, to the offset. A byte value of 129 to 255 is reduced by 64, multiplied by four, and subtracted from the offset. A byte value of 129 to 255 is reduced by 129, multiplied by the quantum of instruction size (e.g. two on the MC680X0), and added to the current PC without changing the offset. After any of these operations, the instruction quantum is added to the PC.

A similar table, occupying pcsz-bytes, is the next section in an executable; it is present for all architectures. The same algorithm may be run using this table to recover the absolute source line number from a given program location. The absolute line number (starting from zero) counts the newlines in the C-preprocessed source seen by the compiler. Three symbol types in the main symbol table facilitate conversion of the absolute number to source file and line number:

- f source file name components
- z source file name
- Z source file line offset

The f symbol associates an integer (the value field of the 'symbol') with a unique file path name component (the name of the 'symbol'). These path components are used by the z symbol to represent a file name: the first byte of the name field is always 0; the remaining bytes hold a zeroterminated array of 16-bit values (in big-endian order) that represent file name components from f symbols. These components, when separated by slashes, form a file name. The initial slash of a file name is recorded in the symbol table by an f symbol; when forming file names from z symbols an initial slash is not to be assumed. The z symbols are clustered, one set for each object file in the program, before any text symbols from that object file. The set of z symbols for an object file form a *history stack* of the included source files from which the object file was compiled. The value associated with each z symbol is the absolute line number at which that file was included in the source; if the name associated with the z symbol is null, the symbol represents the end of an included file, that is, a pop of the history stack. If the value of the z symbol is 1 (one), it represents the start of a new history stack. To recover the source file and line number for a program location, find the text symbol containing the location and then the first history stack preceding the text symbol in the symbol table. Next, interpret the PC/line offset table to discover the absolute line number for the program location. Using the line number, scan the history stack to find the set of source files open at that location. The line number within the file can be found using the line numbers in the history stack. The Z symbols correspond to #line directives in the source; they specify an adjustment to the line number to be printed by the above algorithm. The offset is associated with the first previous z symbol in the symbol table.

SEE ALSO

db(1), *acid*(1), *2a*(1), *2l*(1), *nm*(1), *strip*(1), *mach*(2), *symbol*(2)

BUGS

There is no type information in the symbol table; however, the -a flags on the compilers will produce symbols for acid(1).

ar – archive (library) file format

SYNOPSIS

#include <ar.h>

DESCRIPTION

The archive command ar(1) is used to combine several files into one. Archives are used mainly as libraries to be searched by the loaders 2l(1) et al.

A file produced by *ar* has a magic string at the start, followed by the constituent files, each preceded by a file header. The magic number and header layout as described in the include file are:

```
#define ARMAG
                 "!<arch>\n"
#define SARMAG
                 8
                 "'\n"
#define ARFMAG
struct ar_hdr {
        char
                 name[16]:
        char
                 date[12];
                 uid[6];
        char
                 gid[6];
        char
        char
                 mode[8];
        char
                 size[10];
        char
                 fmag[2];
};
```

#define SAR_HDR 60

The name is a blank-padded string. The fmag field contains ARFMAG to help verify the presence of a header. The other fields are left-adjusted, blank-padded numbers. They are decimal except for mode, which is octal. The date is the modification date of the file (see *stat*(2)) at the time of its insertion into the archive. The mode is the low 9 bits of the file permission mode. The length of the header is SAR_HDR. Because the ar_hdr structure is padded in an architecture-dependent manner, the structure should never be read or written as a unit; instead, each field should be read or written independently.

Each file begins on an even (0 mod 2) boundary; a newline is inserted between files if necessary. Nevertheless size reflects the actual size of the file exclusive of padding.

When all members of an archive are object files of the same architecture, ar automatically adds an extra file, named ____. SYMDEF, as the first member of the archive. This file contains an index used by the loaders to locate all externally defined text and data symbols in the archive.

There is no provision for empty areas in an archive file.

SEE ALSO

ar(1), 2l(1), nm(1), stat(2)

BUGS

The uid and gid fields are unused in Plan 9. They provide compatibility with Unix *ar* format.

authsrv, p9any, p9sk1, dp9ik - authentication protocols

DESCRIPTION

This manual page describes the protocols used to authorize connections, confirm the identities of users and machines, and maintain the associated databases. The machine that provides these services is called the *authentication server* (AS). The AS may be a stand-alone machine or a general-use machine such as a CPU server. The network database *ndb*(6) holds for each public machine, such as a CPU server or file server, the name of the authentication server that machine uses.

Each machine contains four values important to authentication; a 56-bit DES key, a 128-bit AES key, a 28-byte authentication ID, and a 48-byte authentication domain name. The ID is a user name and identifies who is currently responsible for the kernel running on that machine. The domain name identifies the machines across which the ID is valid. Together, the ID and domain name identify the owner of a key.

When a terminal boots, *factotum*(4) prompts for user name and password. The user name becomes the terminal's authentication ID. The password is converted using *passtokey* (see *authsrv*(2)) into a 56-bit DES and 128-bit AES keys and saved in memory. The authentication domain is set to the null string. If possible, *factotum* validates the key with the AS before saving it. For Internet machines the correct AS to ask is found using *dhcpd*(8).

When a CPU or file server boots, *factotum* reads the key, ID, and domain name from non-volatile RAM. This allows servers to reboot without operator intervention.

The details of any authentication are mixed with the semantics of the particular service they are authenticating so we describe them one case at a time. The following definitions will be used in the descriptions:

Ks	server's	host ID's	key

Кс	client's host ID's key

Kn a nonce key created for a ticket (key)

K{*m*} message *m* encrypted with key *K*

CHc an 8-byte random challenge from a client (chal)

CHs an 8-byte random challenge from a server (chal)

- IDs server's ID (authid)
- *DN* server's authentication domain name (authdom)
- IDc client's ID (hostid, cuid)
- *IDr* client's desired ID on server (uid, suid)
- YAc client \rightarrow AS DH public key
- *YBc* AS \rightarrow client DH public key
- YAs server \rightarrow AS DH public key
- $YBs \qquad AS \rightarrow server DH public key$
- *RNc* client's 32-byte random string
- *RNs* server's 32-byte random string

The parenthesized names are the ones used in the Ticketreq and Ticket structures in <authsrv.h>.

The message type constants AuthTreq, AuthChal, AuthPass, AuthOK, AuthErr, AuthMod, AuthApop, AuthOKvar, AuthChap, AuthMSchap, AuthCram, AuthVNC, and AuthPAK (type) are defined in <authsrv.h>, as are the encrypted message types AuthTs, AuthAs, AuthAc, AuthTp, and AuthHr (num).

Ticket Service

When a client and server wish to authenticate to each other, they do so using *tickets* issued by the AS. Obtaining tickets from the AS is the client's responsibility.

The protocol to obtain a ticket pair is:

 $C \rightarrow A$: AuthTreq, IDs, DN, CHs, IDc, IDr

 $A \rightarrow C$: AuthOK, Kc{AuthTc, CHs, IDc, IDr, Kn}, Ks{AuthTs, CHs, IDc, IDr, Kn}

The two tickets are identical except for their type fields and the keys with which they are encrypted. The client and server can each decrypt one of the tickets, establishing a shared secret

Kn.

The tickets can be viewed as a statement by the AS that "a client possessing the *Kn* key is allowed to authenticate as *IDr*."

The presence of the server challenge *CHs* in the ticket allows the server to verify the freshness of the ticket pair.

The AS sets the *IDr* in the tickets to the requested *IDr* only if *IDc* is allowed to *speak for* (q.v.) *IDr*. If not, the AS sets *IDr* to the empty string.

If the users *IDc* or *IDs* do not exist, the AS silently generates one-time random keys to use in place of *Kc* or *Ks*, so that clients cannot probe the AS to learn whether a user name is valid.

P9sk1

The Plan 9 shared key protocol p9sk1 allows a client and server to authenticate each other. The protocol is:

 $C \rightarrow S$: CHc

The client starts by sending a random challenge to the server.

S \rightarrow C: AuthTreq, IDs, DN, CHs, -, -The server replies with a ticket request giving its id and authentication domain along with its own random challenge.

 $C \rightarrow S$: Ks{AuthTs, CHs, IDc, IDr, Kn}, Kn{AuthAc, CHs}

The client adds *IDc* and *IDr* to the ticket request and obtains a ticket pair from the AS as described above. The client relays the server's ticket along with an *authenticator*, the *AuthAc* message. The authenticator proves to the server that the client knows *Kn* and is therefore allowed to authenticate as *IDr*. (The inclusion of *CHs* in the authenticator avoids replay attacks.)

 $S \rightarrow C$: $Kn\{AuthAs, CHc\}$ The server replies with its own authenticator, proving to the client that it also knows Kn and therefore Ks.

The 64-bit shared secret *Kn* is used as the session secret.

Password authenticated key exchange

Initially, the server and client keys *Ks* and *Kc* were equivalent to the password derived 56-bit DES keys, which made the encrypted tickets subject to offline dictionary attacks and provided too small a key space against brute force attacks on current hardware.

The AuthPAK protocol is used to establish new 256-bit random keys with the AS for Ks and Kc before each ticket request on the connection.

The protocol is based on SPAKE2EE, where a hash of the user's secret is used to encypt the public keys of a Elliptic–Curve Diffie–Hellman key exchange. The user's *ID* and 128–bit AES key is hashed and mapped (using Elligator2) into two curve points *PM* and *PN*, called the *pakhash*. Both sides generate a random number xa/xb and make the public keys YA/YB as: $YA=xa^*G+PM$, $YB=xb^*G+PN$. After the public keys have been exchanged, each side calculates the shared secret as: $Z=xa^*(YB-PN)=xb^*(YA-PM)$. The shared secret *Z* is then hashed with the transmitted public keys YA|YB producing the 256-bit *pakkey*.

The *pakkey* is then used in place of *Ks* and *Kc* to authenticate and encrypt tickets from the AS using Chacha20/Poly1305 AEAD for the next following request made on the connection.

The protocol (for AuthTreq) to establish keys Ks and Kc with the AS for IDs and IDc is:

 $C \rightarrow A$: AuthPAK, IDs, DN, CHs, IDc, IDr, YAs, YAc

 $A \rightarrow C$: AuthOK, YBs, YBc

The protocol (for AuthApop, AuthChap...) to establish a single server key Ks for IDs:

 $C \rightarrow A$: AuthPAK, -, DN, CHs, IDs, IDc, YAs

 $A \rightarrow C$: AuthOK, YBs

The protocol (for AuthPass) to establish a single client key Kc for IDc:

 $C \rightarrow A$: AuthPAK, -, -, CHc, -, IDc, YAc

$A \rightarrow C$: AuthOK, YBc

Dp9ik

The *dp9ik* protocol is an extended version of *p9sk1* that adds the random strings *RNc* and *RNs* in the *authenticator* messages for the session key derivation and uses the password authenticated key exchange as described above to derive the ticket encryption keys *Ks* and *Kc*:

 $C \rightarrow S$: CHc

The client starts by sending a random challenge to the server.

 $S \rightarrow C$: AuthPAK, IDs, DN, CHs, -, -, YAs

The server generates a new public key YAs and replies with a AuthPAK request giving its IDs and authentication domain DNs along with its own random challenge CHs and its public key YAs.

 $C \rightarrow S$: YBs, Ks{AuthTs, CHs, IDc, IDr, Kn}, Kn{AuthAc, CHs, RNc}

The client generates its own public key YAc and adds it along with *IDc* and *IDr* to the AuthPAK request and obtains the public keys YBs and YBc from the AS response. At this point, client and AS have completed their authenticated key exchange and derive Kc as described above. Then the client requests a ticket pair using the same message but with AuthPAK type changed to AuthTreq. It decrypts his ticket with Kc extracting the shared secret Kn. The client relays the server's YBs and ticket along with an authenticator, the AuthAc message. The server finishes his authenticated key exchange using YBs and derives Ks to decrypt his ticket to extract the shared secret Kn. When the decryption of the clients authenticator using Kn is successfull then this proves to the server that the client knows Kn and is therefore allowed to authenticate as *IDr*. The random string RNc is used in the derivation of the session secret.

 $S \rightarrow C$: Kn{AuthAs, CHc, RNs}

The server replies with its own authenticator, proving to the client that it also knows *Kn* and contributes its random string *RNs* for the session secret.

The 2048-bit session secret is derived with HKDF-SHA256 hashing the concatenated random strings RNc|RNs with the shared secret key Kn.

P9any

P9any is the standard Plan 9 authentication protocol. It consists of a negotiation to determine a common protocol, followed by the agreed-upon protocol.

The negotiation protocol is:

- $S \rightarrow C$: proto@authdom proto@authdom ...
- $C \rightarrow S$: proto dom

Each message is a NUL-terminated UTF string. The server begins by sending a list of *proto*, *authdom* pairs it is willing to use. The client responds with its choice.

A second version of this protocol exists (indicated by the v.2 prefix before the list) where the server sends an explicit confirmation with a OK message before the agreed-upon protocol starts.

 $S \rightarrow C$: v.2 proto@authdom proto@authdom ...

 $C \rightarrow S$: proto dom

S→*C*: OK

The *p9any* protocol is the protocol used by all Plan 9 services. The file server runs it over special authentication files (see *fauth*(2) and *attach*(5)). Other services, such as *cpu*(1), *exportfs*(4) and *tlssrv*(8) run *p9any* over the network and then use the session secret to derive an *ssl*(3) or *tls*(3) key to encrypt the rest of their communications.

Password Change

Users connect directly to the AS to change their passwords. The protocol is:

 $C \rightarrow A$: AuthPass, -, -, CHc, -, IDc The client sends a password change ticket request.

 $A \rightarrow C$: Kc{AuthTp, CHc, IDc, Kn} The server responds with a ticket containing the key Kn encrypted with the client's key Kc $C \rightarrow A$: Kn{AuthPass, old, new, changesecret, secret}

The client decrypts the ticket using the old password and then sends back an encrypted password request (Passwordreq structure) containing the old password and the new password. If *changesecret* is set, the AS also changes the user's *secret*, the password used for non-Plan 9 authentications.

 $A \rightarrow C$: AuthOK or AuthErr, 64-byte error message

The AS responds with simply AuthOK or with AuthErr followed by a 64-byte error message.

Authentication Database

An *ndb*(2) database file /lib/ndb/auth exists for the AS. This database maintains "speaks for" relationships, i.e., it lists which users may speak for other users when authenticating. The attribute types used by the AS are hostid and uid. The value in the hostid is a client host's ID. The values in the uid pairs in the same entry list which users that host ID may speak for. A uid value of * means the host ID may speak for all users. A uid value of ! *user* means the host ID may not speak for *user*. For example:

```
hostid=bootes
```

uid=!sys uid=!adm uid=*

is interpreted as bootes may speak for any user except sys and adm. This property is used heavily on CPU servers.

Foreign Protocols

The AS accepts ticket request messages of types other than *AuthTreq* to allow users to authenticate using non-Plan 9 protocols. In these situations, the server communicates directly with the AS. Some protocols must begin without knowing the client's name. They ignore the client name in the ticket request. All the protocols end with the AS sending an *AuthOK* message containing a server ticket and authenticator.

AuthOK messages always have a fixed but context-dependent size. The occasional variablelength OK message starts with a *AuthOKvar* byte and a five-byte space-padded decimal length of the data that follows.

Anywhere an AuthOK message is expected, a AuthErr message may be substituted.

- $S \rightarrow A$: AuthChal, -, DN, CHs, IDs, IDc
- $A \rightarrow S$: AuthOK, challenge
- $S \rightarrow A$: response
- $A \rightarrow S$: AuthOK, Ks{AuthTs, CHs, IDc, IDc, Kn}, Kn{AuthAc, CHs}

This protocol allows the use of handheld authenticators such as SecureNet keys and SecureID tokens in programs such as *telnetd* and *ftpd* (see *ipserv*(8)).

Challenge and response are text strings, NUL -padded to 16 bytes (NETCHLEN). The challenge is a random five-digit decimal number. When using a SecureNet key or netkey (see passwd(1)), the response is an eight-digit decimal or hexadecimal number that is an encryption of the challenge using the user's DES key.

When using a SecureID token, the challenge is ignored. The response is the user's PIN followed by the six-digit number currently displayed on the token. In this case, the AS queries an external RADIUS server to check the response. Use of a RADIUS server requires an entry in the authentication database. For example:

radius=server-name secret=xyzzy
 uid=howard rid=trickey
 uid=sape rid=smullender

In this example, the secret xyzzy is the hash key used in talking to the RADIUS server. The uid/rid lines map from Plan 9 user ids to RADIUS ids. Users not listed are assumed to have the same id in both places.

- $S \rightarrow A$: AuthApop, -, DN, CHs, IDs, -
- $A \rightarrow S$: AuthOKvar, challenge
- $S \rightarrow A$: AuthApop, -, DN, CHs, IDs, IDc; hexadecimal MD5 checksum

 $A \rightarrow S$: AuthOK, Ks{AuthTs, CHs, IDc, IDc, Kn}, Kn{AuthAc, CHs}

This protocol implements APOP authentication (see *pop3*(8)). After receiving a ticket request of type *AuthApop*, the AS generates a random challenge of the form *<random@domain>*. The client then replies with a new ticket request giving the user name followed by the MD5 checksum of the challenge concatenated with the user's secret. If the response is correct, the authentication server sends back a ticket and authenticator. If the response is incorrect, the client may repeat the ticket request/MD5 checksum message to try again.

The AuthCram protocol runs identically to the AuthApop protocol, except that the expected MD5 checksum is the keyed MD5 hash using the user's secret as the key (see hmac_md5 in sechash(2)).

- $S \rightarrow A$: AuthChap, -, DN, CHs, IDs, -
- $A \rightarrow S$: challenge
- $S \rightarrow A$: pktid, IDc, response
- $A \rightarrow S$: AuthOK, Ks{AuthTs, CHs, IDc, IDc, Kn}, Kn{AuthAc, CHs}

This protocol implements CHAP authentication (see ppp(8)). The *challenge* is eight random bytes. The response is a 16-byte MD5 checksum over the packet id, user's secret, and challenge. The reply packet is defined as OChapreply in <authsrv.h>.

- $S \rightarrow A$: AuthMSchap, -, DN, CHs, IDs, -
- $A \rightarrow S$: challenge
- $S \rightarrow A$: IDc, Im-response, nt-response
- $A \rightarrow S$: AuthOK, Ks{AuthTs, CHs, IDc, IDc, Kn}, Kn{AuthAc, CHs}

This protocol implements Microsoft's MS-CHAP authentication (see ppp(8)). The *challenge* is eight random bytes. The two responses are Microsoft's LM and NT hashes. Only the NT hash may be used to authenticate, as the LM hash is considered too weak. The reply packet is defined as OMSchapreply in <authsrv.h>.

- $S \rightarrow A$: AuthVNC, -, DN, CHs, IDs, IDc
- $A \rightarrow S$: AuthOKvar, challenge
- $S \rightarrow A$: response
- $A \rightarrow S$: AuthOK, Ks{AuthTs, CHs, IDc, IDc, Kn}, Kn{AuthAc, CHs}

This protocol implements VNC authentication (see *vncs* in *vnc*(1)). The challenge is 16 random bytes, and the response is a DES ECB encryption of the challenge. The method by which VNC converts the user's secret into a DES key is weak, considering only the first eight bytes of the secret.

FILES

/lib/ndb/auth database file
/lib/ndb/auth.* hash files for /lib/ndb/auth

SEE ALSO

auth(2), fauth(2), cons(3), attach(5), auth(8)

color - representation of pixels and colors

DESCRIPTION

To address problems of consistency and portability among applications, Plan 9 uses a fixed color map, called rgbv, on 8-bit-per-pixel displays. Although this avoids problems caused by multiplexing color maps between applications, it requires that the color map chosen be suitable for most purposes and usable for all. Other systems that use fixed color maps tend to sample the color cube uniformly, which has advantages—mapping from a (red, green, blue) triple to the color map and back again is easy—but ignores an important property of the human visual system: eyes are much more sensitive to small changes in intensity than to changes in hue. Sampling the color cube uniformly gives a color map with many different hues, but only a few shades of each. Continuous tone images converted into such maps demonstrate conspicuous artifacts.

Rather than dice the color cube into subregions of size $6 \times 6 \times 6$ (as in Netscape Navigator) or $8 \times 8 \times 4$ (as in previous releases of Plan 9), picking 1 color in each, the rgbv color map uses a $4 \times 4 \times 4$ subdivision, with 4 shades in each subcube. The idea is to reduce the color resolution by dicing the color cube into fewer cells, and to use the extra space to increase the intensity resolution. This results in 16 grey shades (4 grey subcubes with 4 samples in each), 13 shades of each primary and secondary color (3 subcubes with 4 samples plus black) and a reasonable selection of colors covering the rest of the color cube. The advantage is better representation of continuous tones.

The following function computes the 256 3-byte entries in the color map:

```
void
setmaprgbv(uchar cmap[256][3])
{
    uchar *c;
    int r, g, b, v;
    int num, den;
    int i, j;
    for(r=0,i=0; r!=4; r++)
      for(v=0; v!=4; v++,i+=16)
        for(g=0,j=v-r; g!=4; g++)
          for(b=0; b!=4; b++,j++){
            c = cmap[i+(j\&15)];
            den = r;
            if(g > den)
                den = g;
            if(b > den)
                den = b:
            if(den == 0) /* would divide check; pick grey shades */
                c[0] = c[1] = c[2] = 17*v;
            else{
                num = 17*(4*den+v);
                c[0] = r*num/den;
                c[1] = g*num/den;
                c[2] = b*num/den;
            }
          }
}
```

There are 4 nested loops to pick the (red,green,blue) coordinates of the subcube, and the value (intensity) within the subcube, indexed by r, g, b, and v, whence the name *rgbv*. The peculiar order in which the color map is indexed is designed to distribute the grey shades uniformly through the map—the *i*'th grey shade, 0 <= i <= 15 has index $i \times 17$, with black going to 0 and white to 255. Therefore, when a call to draw converts a 1, 2 or 4 bit-per-pixel picture to 8 bits per pixel (which it does by replicating the pixels' bits), the converted pixel values are the appropriate grey shades.

The rgbv map is not gamma-corrected, for two reasons. First, photographic film and television are both normally under-corrected, the former by an accident of physics and the latter by NTSC's design. Second, we require extra color resolution at low intensities because of the non-linear response and adaptation of the human visual system. Properly gamma-corrected displays with adequate low-intensity resolution pack the high-intensity parts of the color cube with colors whose differences are almost imperceptible. Either reason suggests concentrating the available intensities at the low end of the range.

On 'true-color' displays with separate values for the red, green, and blue components of a pixel, the values are chosen so 0 represents no intensity (black) and the maximum value (255 for an 8-bit-per-color display) represents full intensity (e.g., full red). Common display depths are 24 bits per pixel, with 8 bits per color in order red, green, blue, and 16 bits per pixel, with 5 bits of red, 6 bits of green, and 5 bits of blue.

Colors may also be created with an opacity factor called alpha, which is scaled so 0 represents fully transparent and 255 represents opaque color. The alpha is *premultiplied* into the other channels, as described in the paper by Porter and Duff cited in *draw*(2). The function setalpha (see *allocimage*(2)) aids the initialization of color values with non-trivial alpha.

The packing of pixels into bytes and words is odd. For compatibility with VGA frame buffers, the bits within a pixel byte are in big-endian order (leftmost pixel is most significant bits in byte), while bytes within a pixel are packed in little-endian order. Pixels are stored in contiguous bytes. This results in unintuitive pixel formats. For example, for the RGB24 format, the byte ordering is blue, green, red.

To maintain a constant external representation, the *draw*(3) interface as well as the various graphics libraries represent colors by 32-bit numbers, as described in *color*(2).

SEE ALSO

color(2), graphics(2), draw(2)

face – face files

DESCRIPTION

The directories /usr/\$user/lib/face and /lib/face contain a hierarchy of images of people. In those directories are subdirectories named by the sizes of the corresponding image files: 48x48x1 (48 by 48 pixels, one bit per pixel); 48x48x2 (48 by 48 pixels, two (grey) bits per pixel); 48x48x4 (48 by 48 pixels, four (grey) bits per pixel); 48x48x8 (48 by 48 pixels, eight (color-mapped) bits per pixel); 512x512x8 (512 by 512 pixels, eight (color-mapped) bits per pixel); 512x512x24 (512 by 512 pixels, twenty-four bits per pixel (3 times 8 bits per color)). The large files serve no special purpose; they are stored as images (see *image*(6)). The small files are the 'icons' displayed by faces and seemail (see *faces*(1)); for depths less than 4, their format is special.

One- and two-bit deep icons are stored as text, one line of the file to one scan line of display. Each line is divided into 8-bit, 16-bit, or 32-bit big-endian words, stored as a list of commaseparated hexadecimal C constants, such as:

0x9200, 0x1bb0, 0x003e,

This odd format is historical and the programs that read it are somewhat forgiving about blanks and the need for commas.

The files lib/face/*/.dict hold a correspondence between users at machines and face files. The format is

machine/user directory/file.ver

The *machine* is the domain name of the machine sending the message, and *user* the name of the user sending it, as recorded in /sys/log/mail. The *directory* is a further subdirectory of (say) /lib/face/48x48x1, named by a single letter corresponding to the first character of the user names. The *file* is the name of the file, typically but not always the user name, and *ver* is a number to distinguish different images, for example to distinguish the image for Bill Gates from the image for Bill Joy, both of which might otherwise be called b/bill. For example, Bill Gates might be represented by the line

microsoft.com/bill b/bill.1

If multiple entries exist for a user in the various .dict files, *faces* chooses the highest pixel size less than or equal to that of the display on which it is running.

Finally, or rather firstly, the file /lib/face/.machinelist contains a list of machine/domain pairs, one per line, to map any of a set of machines to a single domain name to be looked up in the .dict files. The machine name may be a regular expression, so for example the entry

.*research\.bell-labs\.com astro

maps any of the machines in Bell Labs Research into the shorthand name astro, which then appears as a domain name in the .dict files.

SEE ALSO

mail(1), tweak(1), image(6)

font, subfont - external format for fonts and subfonts

SYNOPSIS

#include <draw.h>

DESCRIPTION

Fonts and subfonts are described in *cachechars*(2).

External fonts are described by a plain text file that can be read using *openfont*. The format of the file is a header followed by any number of subfont range specifications. The header contains two numbers: the height and the ascent, both in pixels. The height is the inter-line spacing and the ascent is the distance from the top of the line to the baseline. These numbers are chosen to display consistently all the subfonts of the font. A subfont range specification contains two or three numbers and a file name. The numbers are the inclusive range of characters covered by the subfont, with an optional starting position within the subfont, and the file name names an external file suitable for *readsubfont* (see *graphics*(2)). The minimum number of a covered range is mapped to the specified starting position (default zero) of the corresponding subfont. If the subfont file name does not begin with a slash, it is taken relative to the directory containing the font file. Each field must be followed by some white space. Each numeric field may be C-format decimal, octal, or hexadecimal.

External subfonts are represented in a more rigid format that can be read and written using *readsubfont* and *writesubfont* (see *subfont*(2)). The format for subfont files is: an image containing character glyphs, followed by a subfont header, followed by character information. The image has the format for external image files described in *image*(6). The subfont header has 3 decimal strings: n, height, and ascent. Each number is right-justified and blank padded in 11 characters, followed by a blank. The character info consists of n+1 6-byte entries, each giving the Fontchar x (2 bytes, low order byte first), top, bottom, left, and width. The x field of the last Fontchar is used to calculate the image width of the previous character; the other fields in the last Fontchar are irrelevant.

Note that the convention of using the character with value zero (NUL) to represent characters of zero width (see draw(2)) means that fonts should have, as their zeroth character, one with non-zero width.

FILES

/lib/font/bit/* font directories

SEE ALSO

graphics(2), draw(2), cachechars(2), subfont(2)

galaxy - representations of n-body simulations

DESCRIPTION

Files of this format are interpreted by galaxy(1) as describing the initial condition of n-body simulations or the saved state of simulation in progress. A galaxy file is a UTF stream of instruction lines. The instruction is given by the first space delimited word. The following instructions are accepted.

MKBODY

The rest of the line must contain 5 white space delimited double-precision floating point numbers. They represent a body's x coordinate, y coordinate, x velocity component, y velocity component, and size respectively.

- ORIG The rest of the line must contain 2 white space delimited double-precision floating point numbers. They represent the current location of the origin with respect to the view window of *galaxy*(1).
- DT The rest of the line must contain a double-precision floating point number which determines the time-scale of the simulation.

SCALE

The rest of the line must contain a double-precision floating point number which determines the scale of the view of the simulation.

GRAV The rest of the line must contain a double-precision floating point number which determines the gravitational constant of the simulation.

SEE ALSO

galaxy(1)

htmlroff - HTML formatting and typesetting

DESCRIPTION

Htmlroff(1) accepts *troff* input with a few extensions and changes. This manual describes the changes to the input language, assuming a working knowledge of *troff* itself.

Name lengths

Request, macro, string, and number names can be longer than two letters, as in:

```
.html c <center>
.de footnote
Footnote here.
..
.footnote
.ds string "hello
\*[string]
.nr number 1
\n[number]
```

HTML output

Two new requests:

```
.html id [ <html>]
.ihtml id [ <ihtml>]
```

.html and .ihtml insert HTML into the output. The requests are only for opening new HTML tags. To close previously-opened tags, repeat the request with the same *id*. For example, the input:

```
.html t 
.html td Cell 1
.html td Cell 2
.html td
.html td
```

produces this output:

```
Cell 1Cell 2
```

The .html request is intended for block-level HTML constructs (those that can contain) and maintains the HTML tag stack automatically. Intermediate tags need not be explicitly closed: removing the final .html t line in the example above would produce the same output. The special *id* – closes the HTML tags immediately after printing them.

The .ihtml request is similar to .html but is intended for inline HTML constructs such as or <i> (those that can be contained within). Unlike .html, .ihtml treats the open HTML tags as a set rather than a stack: each must be explicitly closed. Although it treats the tags as a set, .ihtml treats nesting properly in the output, closing and reopening tags as necessary. For example, the input:

```
.ihtml style <b>
.ihtml link <a href="link.html">
Bold
.ihtml style <i>
and italic, still linked.
.ihtml link <a>
Unlinked.
.ihtml style
```

produces this output:

```
<b><a href="link.html">Bold</a></b>
<i><a href="link.html">and italic, still linked.</i></a>
<i>Unlinked.</i>
```

Outside of .html and .ihtml requests, the characters <, >, and & are treated as normal characters, not HTML markers, and are translated to <, >, and & on output. To embed the raw HTML markers, use $\langle , \rangle >$, and $\langle @[sic]$.

Font changes

Htmlroff interprets the usual f, ft, s, and ps requests to change the font and point size. After applying each such change to its internal registers, *htmlroff* invokes the .font macro to emit corresponding HTML. The default definition of .font is:

.de font .ihtml f1 .ihtml f .ihtml f <span style= .if \n(.f==2 .ihtml f1 <i> .if \n(.f==3 .ihtml f1 .if \n(.f==4 .ihtml f1 <i> .if \n(.f==5 .ihtml f1 <tt> .if \n(.f==6 .ihtml f1 <tt><i>

Input files can redefine . font like any other request or macro.

Paragraphs

Htmlroff implements line height, text adjustment, and margins by wrapping all output text in tags. This behavior can be disabled by setting the .paragraph number register to zero. Setting the .margin register to zero eliminates only the margin annotations.

Subscripts and superscripts

Htmlroff interprets the \u, \d, and \v requests to move vertically during output. It emits output vertically offset up the page inside $\langle sup \rangle$ tags and output vertically offset down the page inside $\langle sub \rangle$ tags. This heuristic handles simple equations formatted by *eqn*(1).

Conditional input

To make it easier to write input files that can be formatted by both *troff* and *htmlroff*, *htmlroff* adds a new condition h which evaluates true in .if and .ie requests. The t condition continues to evaluate true, to accomodate input files trying to distinguish between *troff* and *nroff*. To write a conditional matching *troff* alone, use '.if !h .if t'.

Htmlroff 's handling of conditional input does not match troff's exactly. For example,

```
.if 0 \{\
.de xx
..
.\}
```

redefines the xx macro in *troff* but not in *htmlroff*. Do not write files depending on this behavior, as this bug may be fixed in the future. *Htmlroff* also mishandles $\}$ in some cases. To work around them, use . $\}$ on a line by itself, as in the last example.

Diversions

Diversions in *htmlroff* use the alignment in effect at the time of the diversion when output. In particular,

.di xx Line here. .di .nf .ce .xx

produces a centered line in *troff* but not in *htmlroff*. The solution is to center inside the diversion, as in

.di xx .if h .ce 999 Line here .di

Traps

Htmlroff implements traps at vertical position 0, which run when the first character is about to be printed. Other position traps are ignored. Input traps are implemented.

Input pipes

Htmlroff adds a new request .inputpipe *stop cmd* that redirects *htmlroff*'s input into a pipe to *cmd*. The redirection stops on encountering the line *stop*, optionally followed by white space and extra text. This is a dangerous and clumsy request, as *htmlroff* stops interpreting its input during the redirection, so *stop* must be found in the input itself, not in a macro that the input might appear to call. Although clumsy, .inputpipe allows input files to invoke *troff* to handle complicated input. For example, tmac.html redefines the PS macro that marks the beginning of a *pic*(1) picture:

```
.nr png -1 1
.de PS
.ds pngbase "\\*[basename]
.if '\\*[pngbase]'' .ds pngbase \\n(.B
.ds pngfile \\*[pngbase]\\n+[png].png
.html - <center><img src="\\*[pngfile]"></center>
.inputpipe .PE troff2png >\\*[pngfile]
```

This macro invokes the shell script *troff2png* to run troff and convert the Postscript output to a PNG image file. Before starting the program, the macro creates a new file name for the image and prints HTML referring to it. The .B register holds the final path element (the base name) of the current input file.

Unimplemented

Tabs are set every eight spaces and cannot be changed.

Some requests, such as .tl, are unimplemented for lack of a good implementation. Workarounds can be defined as necessary in input files.

SEE ALSO

htmlroff(1), mhtml(6)

image - external format for images

SYNOPSIS

#include <draw.h>

DESCRIPTION

Images are described in *graphics*(2), and the definition of pixel values is in *color*(6). Fonts and images are stored in external files in machine-independent formats.

Image files are read and written using readimage and writeimage (see *allocimage*(2)), or readmemimage and writememimage (see *memdraw*(2)). An uncompressed image file starts with 5 strings: chan, r.min.x, r.min.y, r.max.x, and r.max.y. Each is right-justified and blank padded in 11 characters, followed by a blank. The chan value is a textual string describing the pixel format (see strtochan in *graphics*(2) and the discussion of channel descriptors below), and the rectangle coordinates are decimal strings. The rest of the file contains the r.max.y-r.min.y rows of pixel data. A *row* consists of the byte containing pixel r.min.x and all the bytes up to and including the byte containing pixel r.max.x-1. For images with depth *d* less than eight, a pixel with x-coordinate = x will appear as *d* contiguous bits in a byte, with the pixel's high order bit starting at the byte's bit number $d \times (x \mod (8/d))$, where bits within a byte are numbered 0 to 7 from the high order to the low order bit. Rows contain integral number of bytes, so there may be some unused pixels at either end of a row. If *d* is greater than 8, the definition of images requires that it be a multiple of 8, so pixel values take up an integral number of bytes.

The loadimage and unloadimage functions described in *allocimage*(2) also deal with rows in this format, stored in user memory.

The channel format string is a sequence of two-character channel descriptions, each comprising a letter (\mathbf{r} for red, \mathbf{g} for green, \mathbf{b} for blue, a for alpha, \mathbf{m} for color-mapped, \mathbf{k} for greyscale, and \mathbf{x} for "don't care") followed by a number of bits per pixel. The sum of the channel bits per pixel is the depth of the image, which must be either a divisor or a multiple of eight. It is an error to have more than one of any channel but \mathbf{x} . An image must have either a greyscale channel; a color mapped channel; or red, green, and blue channels. If the alpha channel is present, it must be at least as deep as any other channel.

The channel string defines the format of the pixels in the file, and should not be confused with ordering of bytes in the file. In particular 'r8g8b8' pixels have byte ordering blue, green, and red within the file. See *color*(6) for more details of the pixel format.

A venerable yet deprecated format replaces the channel string with a decimal *ldepth*, which is the base two logarithm of the number of bits per pixel in the image. In this case, *ldepths* 0, 1, 2, and 3 correspond to channel descriptors k1, k2, k4, and m8, respectively.

Compressed image files start with a line of text containing the word compressed, followed by a header as described above, followed by the image data. The data, when uncompressed, is laid out in the usual form.

The data is represented by a string of compression blocks, each encoding a number of rows of the image's pixel data. Compression blocks are at most 6024 bytes long, so that they fit comfortably in a single 9P message. Since a compression block must encode a whole number of rows, there is a limit (about 5825 bytes) to the width of images that may be encoded. Most wide images are in subfonts, which, at 1 bit per pixel (the usual case for fonts), can be 46600 pixels wide.

A compression block begins with two decimal strings of twelve bytes each. The first number is one more than the y coordinate of the last row in the block. The second is the number of bytes of compressed data in the block, not including the two decimal strings. This number must not be larger than 6000.

Pixels are encoded using a version of Lempel & Ziv's sliding window scheme LZ77, best described in J A Storer & T G Szymanski 'Data Compression via Textual Substitution', JACM 29#4, pp. 928-951.

The compression block is a string of variable-length code words encoding substrings of the pixel data. A code word either gives the substring directly or indicates that it is a copy of data occurring

previously in the pixel stream.

In a code word whose first byte has the high-order bit set, the rest of the byte indicates the length of a substring encoded directly. Values from 0 to 127 encode lengths from 1 to 128 bytes. Subsequent bytes are the literal pixel data.

If the high-order bit is zero, the next 5 bits encode the length of a substring copied from previous pixels. Values from 0 to 31 encode lengths from 3 to 34 bytes. The bottom two bits of the first byte and the 8 bits of the next byte encode an offset backward from the current position in the pixel data at which the copy is to be found. Values from 0 to 1023 encode offsets from 1 to 1024. The encoding may be 'prescient', with the length larger than the offset, which works just fine: the new data is identical to the data at the given offset, even though the two strings overlap.

Some small images, in particular 48×48 face files as used by *seemail* (see *faces*(1) and *face*(6)) and 16×16 cursors, can be stored textually, suitable for inclusion in C source. Each line of text represents one scan line as a comma-separated sequence of hexadecimal bytes, shorts, or words in C format. For cursors, each line defines a pair of bytes. (It takes two images to define a cursor; each must be stored separately to be processed by programs such as *tweak*(1).) Face files of one bit per pixel are stored as a sequence of shorts, those of larger pixel sizes as a sequence of longs. Software that reads these files must deduce the image size from the input; there is no header. These formats reflect history rather than design.

SEE ALSO

jpg(1), *tweak*(1), *graphics*(2), *draw*(2), *allocimage*(2), *color*(6), *face*(6), *font*(6)

keyboard - how to type characters

DESCRIPTION

Keyboards are idiosyncratic. It should be obvious how to type ordinary ASCII characters, backspace, tab, escape, and newline. In Plan 9, the key labeled Return or Enter generates a newline (0x0A); if there is a key labeled Line Feed, it generates a carriage return (0x0D); Plan 9 eschews CRLFs. All control characters are typed in the usual way; in particular, control-J is a line feed and control-M a carriage return. On the PC and some other machines, the key labeled Caps Lock acts as an additional control key.

The delete character (0x7F) may be generated by a different key, one near the extreme upper right of the keyboard. On the Next it is the key labeled * (not the asterisk above the 8). On the SLC and Sparcstation 2, delete is labeled Num Lock (the key above Backspace labeled Delete functions as an additional backspace key). On the other keyboards, the key labeled Del or Delete generates the delete character.

The view character (0x80), used by rio(1), acme(1), and sam(1), causes windows to scroll forward. It is generally somewhere near the lower right of the main key area. The scroll character is generated by the VIEW key on the Gnot, the Alt Graph key on the SLC, and the arrow key \downarrow on the other terminals. As a convenience for sloppy typists, some programs interpret \rightarrow and \leftarrow keys, which lie on either side of \downarrow , as view keys as well. The arrow key \uparrow scrolls backward.

Characters in Plan 9 are runes (see *utf*(6)). Any rune can be typed using a compose key followed by several other keys. The compose key is also generally near the lower right of the main key area: the NUM PAD key on the Gnot, the Alternate key on the Next, the Compose key on the SLC, the Option key on the Magnum, and either Alt key on the PC. After typing the compose key, type a lower case x and up to six hexadecimal characters (digits and a to f) followed by a semicolon (if the sequence is less than six digits long) to type a single rune with the value represented by the typed number. There are shorthands for many characters, comprising the compose key followed by a two- or three-character sequence. There are several rules guiding the design of the sequences, as illustrated by the following examples. The full list is too long to repeat here, but is contained in the file /lib/keyboard in a format suitable for *grep*(1) or *look*(1).

A repeated symbol gives a variant of that symbol, e.g., ?? yields ¿.

ASCII digraphs for mathematical operators give the corresponding operator, e.g., <= yields \leq .

Two letters give the corresponding ligature, e.g., AE yields Æ.

Mathematical and other symbols are given by abbreviations for their names, e.g., pg yields $\P.$

Chess pieces are given by a w or b followed by a letter for the piece (k for king, q for queen, r for rook, n for knight, b for bishop, or p for pawn), e.g., wk for a white king.

Greek letters are given by an asterisk followed by a corresponding latin letter, e.g., *d yields $\delta.$

Cyrillic letters are given by an at sign followed by a corresponding latin letter or letters, e.g., @ya yields я.

Script letters are given by a dollar sign followed by the corresponding regular letter, e.g., F yields \mathcal{F} .

A digraph of a symbol followed by a letter gives the letter with an accent that looks like the symbol, e.g., , c yields ç.

Two digits give the fraction with that numerator and denominator, e.g., 12 yields ½.

The letter s followed by a character gives that character as a superscript, e.g., s1 yields ¹. These characters are taken from the Unicode block 0x2070; the 1, 2, and 3 superscripts in the Latin-1 block are available by using a capital S instead of s.

Sometimes a pair of characters give a symbol related to the superimposition of the characters, e.g., cO yields $\mathbb{O}.$

A mnemonic letter followed by \$ gives a currency symbol, e.g., 1\$ yields £. Note the difference between ß (ss) and μ (micron) and the Greek β and μ .

FILES

/lib/keyboard sorted table of characters and keyboard sequences

SEE ALSO

intro(1), *ascii*(1), *tcs*(1), *acme*(1), *rio*(1), *sam*(1), *cons*(3), *utf*(6)

keys.who - biographic information for key holders

DESCRIPTION

When *auth/changeuser* (see *auth*(8)) creates or modifies an account, it writes a line of biographical information to /adm/keys.who. The line contains the following fields, separated by | characters:

name login name

postid company-wide user name

full name

full name of the user

dept department of the user

email...

one or more fields containing email addresses to be notified when the key is about to expire

The program *auth/warning*, which has fallen into disrepair, once read *keys.who* and mailed expiry warnings.

EXAMPLE

rsc|rscox|Russell S Cox|11276|rsc|dmr|rob

SEE ALSO

keyfs(4), auth(8)

man - macros to typeset manual

SYNOPSIS

nroff -man file ...

troff -man file ...

DESCRIPTION

These macros are used to format pages of this manual.

Except in .LR and .RL requests, any text argument denoted t in the request summary may be zero to six words. Quotes "..." may be used to include blanks in a 'word'. If t is empty, the special treatment is applied to the next text input line (the next line that doesn't begin with dot). In this way, for example, .I may be used to italicize a line of more than 6 words, or .SM followed by .B to make small letters in 'bold' font.

A prevailing indent distance is remembered between successive indented paragraphs, and is reset to default value upon reaching a non-indented paragraph. Default units for indents *i* are ens.

The fonts are

- R roman, the main font, preferred for diagnostics
- I italic, preferred for parameters, short names of commands, names of manual pages, and naked function names
- B 'bold', actually the constant width font, preferred for examples, file names, declarations, keywords, names of struct members, and literals (numbers are rarely literals)
- L also the constant width font. In *troff* L=B; in *nroff* arguments of the macros . L, . LR, and . RL are printed in quotes; preferred only where quotes really help (e.g. lower-case literals and punctuation).

Type font and size are reset to default values before each paragraph, and after processing font- or size-setting macros.

The -man macros admit equations and tables in the style of eqn(1) and tbl(1), but do not support arguments on .EQ and .TS macros.

These strings are predefined by -man:

 $\ \ R$ '[®]', '(Reg)' in *nroff*.

 $\ \ S$ Change to default type size.

FILES

/sys/lib/tmac/tmac.an

SEE ALSO

troff(1), man(1)

REQUESTS

Request Cause If no Explanation

Break	Argument
-------	----------

. B t	no	<i>t</i> =n.t.l.*	Text <i>t</i> is 'bold'.
.BI t	no	<i>t</i> =n.t.l.	Join words of <i>t</i> alternating bold and italic.
.BR t	no	<i>t</i> =n.t.l.	Join words of <i>t</i> alternating bold and Roman.
.DT	no		Restore default tabs.
.EE	yes		End displayed example
.EX	yes		Begin displayed example
.HPi	yes	<i>i</i> =p.i.*	Set prevailing indent to <i>i</i> . Begin paragraph with hanging indent.
.It	no	<i>t</i> =n.t.l.	Text <i>t</i> is italic.
.IBt	no	<i>t</i> =n.t.l.	Join words of <i>t</i> alternating italic and bold.
.IP <i>xi</i>	yes	<i>x</i> =""	Same as . TP with tag x.
.IR t	no	<i>t</i> =n.t.l.	Join words of <i>t</i> alternating italic and Roman.
.Lt	no	<i>t</i> =n.t.l.	Text <i>t</i> is literal.
.LP	yes		Same as . PP.
.LR t	no		Join 2 words of <i>t</i> alternating literal and Roman.
.PD d	no	<i>d</i> =.4v	Interparagraph distance is d .

. PP . RE . RI <i>t</i>	yes yes no	<i>t</i> =n.t.l.	Begin paragraph. Set prevailing indent to default. End of relative indent. Set prevailing indent to amount of starting .RS. Join words of <i>t</i> alternating Roman and italic.
.RL <i>t</i>	no		Join 2 or 3 words of <i>t</i> alternating Roman and literal.
.RS <i>i</i>	yes	<i>i</i> =p.i. Start relative indent, move left margin in distance <i>i</i> . Set prevailing indent default for nested indents.	
. SH t	yes	t=""	Subhead; reset paragraph distance.
. SM t	no	<i>t</i> =n.t.l.	Text <i>t</i> is small.
.SS t	no	t=""	Secondary subhead.
.TF s	yes		Prevailing indent is wide as string s in font L; paragraph distance is 0.
.TH n c	X	yes	Begin page named <i>n</i> of chapter <i>c; x</i> is extra commentary, e.g. 'local', for page head. Set prevailing indent and tabs to default.
.TP i	yes	<i>i</i> =p.i.	Set prevailing indent to i . Restore default indent if $i=0$. Begin indented para- graph with hanging tag given by next text line. If tag doesn't fit, place it on separate line.
.1C	yes		Equalize columns and return to 1-column output
.2C	yes		Start 2-column nofill output

* n.t.l. = next text line; p.i. = prevailing indent

BUGS

There's no way to fool *troff* into handling literal double quote marks " in font-alternation macros, such as .BI.

There is no direct way to suppress column widows in 2-column output; the column lengths may be adjusted by inserting .sp requests before the closing .1C.

map – digitized map formats

DESCRIPTION

Files used by *map*(7) are a sequence of structures of the form:

```
struct {
     signed char patchlatitude;
     signed char patchlongitude;
     short n;
     union {
          struct {
               short latitude;
               short longitude;
          } point[n];
          struct {
               short latitude;
               short longitude;
               struct {
                     signed char latdiff;
                     signed char londiff;
               } point[-n];
          } highres;
     } segment;
```

};

where short stands for 16-bit integers and there is no padding within or between structs. Shorts are stored in little-endian order, low byte first. To assure portability, *map* accesses them bytewise.

Fields patchlatitude and patchlongitude tell to what 10-degree by 10-degree patch of the earth's surface a segment belongs. Their values range from -9 to 8 and from -18 to 17, respectively, and indicate the coordinates of the southeast corner of the patch in units of 10 degrees.

Each segment of $|\mathbf{n}|$ points is connected; consecutive segments are not necessarily related. Latitude and longitude are measured in units of 0.0001 radian. If \mathbf{n} is negative, then differences to the first and succeeding points are measured in units of 0.00001 radian. Latitude is counted positive to the north and longitude positive to the west.

The patches are ordered lexicographically by patchlatitude then patchlongitude. A printable index to the first segment of each patch in a file named *data* is kept in an associated file named *data*.x. Each line of an index file contains patchlatitude, patchlongitude and the byte position of the patch in the map file. Both the map file and the index file are ordered by patch latitude and longitude.

SEE ALSO

map(7)

The data comes from the World Data Bank I and II and U.S. Government sources: the Census Bureau, Geological Survey, and CIA.

mdir - mail directory format

SYNOPSIS

The *mdir* format is used by Upas as a replacement for tradition mailbox format. An *mdir* mailbox is a directory containing any number of messages stored one message per file. Individual messages are stored in the same format they would be in a traditional mailbox; each message is a valid mailbox with a single message. The message files are named with the UNIX seconds corresponding to the date on the From line, a "." separator and a two digit sequence starting with 00.

One *mdir* may contain other *mdirs* but (currently) this relationship is in name only. The mail box /mail/box/a does not contain any messages from /mail/box/a/b, according to upasfs(4).

SEE ALSO

splitmbox(8), upasfs(4)

mhtml - macros for formatting HTML

SYNOPSIS

pic | tbl | eqn | htmlroff [-man | -ms] -mhtml file ...

DESCRIPTION

This package of htmlroff(1) macro definitions provides convenient macros for formatting HTML. It is usually used along with troff(1) macro packages such as man(6) and ms(6). Mhtml replaces some macros defined in the other packages, so it should be listed after them on the htmlroff command line.

The following macros are defined:

.HTML title

Print an HTML header marking the output as HTML 4.01 loose transitional encoded in UTF. If given, the *title* is printed inside <title> tags. This macro opens the <html> tag, opens and closes the <head> section, and opens <body>. It invokes the .HEAD macro inside the <head> section. To add arbitrary lines to the header, append to .HEAD before invoking .HTML.

.FS, .FE

Accumulate footnotes and print them at the end of the document under a **Notes** heading. These replace the macros in ms(6). To emit the notes accumulated so far, invoke .NOTES.

.PS, .PE

Replace input bracketed . PS and . PE with a PNG image corresponding to the output of running troff(1) on the input.

.TS, .TE

Identical to . PS and . PE.

.B1 margin width, .B2

Format the input between .B1 and .B2 inside a box, with *margin* (default 10) pixels between the box and the text. The box is set to be *width* (default 60) percent of the current output width.

FILES

/sys/lib/tmac/tmac.html

SEE ALSO

htmlroff(1), htmlroff(6), ms(6)

mnihongo - macros for typesetting Japanese

SYNOPSIS

troff -mnihongo ...

DESCRIPTION

Mnihongo provides a simple *troff*(1) post-processor that formats Unicode characters that might be Japanese text. It looks up the characters in the bitmap font /lib/font/bit/pelm/unicode.9x24.font and generates bitmap images embedded in the output.

During troff processing, widths of the Japanese characters are taken from the troff font Jp, which is at best a simple approximation to the truth.

FILES

/bin/aux/mnihongo
/sys/lib/tmac/tmac.nihongo
/lib/font/bit/pelm/unicode.9x24.font

SOURCE

/sys/src/cmd/aux/mnihongo

SEE ALSO

troff(1)

mpictures - picture inclusion macros

SYNOPSIS

troff -mpictures[options]file...

DESCRIPTION

Mpictures macros insert PostScript pictures into *troff*(1) documents. The macros are:

.BP source height width position offset flags label

Define a frame and place a picture in it. Null arguments, represented by "", are interpreted as defaults. The arguments are:

source Name of a PostScript picture file, optionally suffixed with (n) to select page number n from the file (first page by default).

height Vertical size of the frame, default 3.01.

width Horizontal size of the frame, current line length by default.

position

l (default), c, or r to left-justify, center, or right-justify the frame.

offset Move the frame horizontally from the original *position* by this amount, default 01. *flags* One or more of:

- a *d* Rotate the picture clockwise *d* degrees, default d=90.
- o Outline the picture with a box.
- s Freely scale both picture dimensions.
- w White out the area to be occupied by the picture.

l,r,t,b

Attach the picture to the left right, top, or bottom of the frame.

label Place *label* at distance 1.5v below the frame.

If there's room, .BP fills text around the frame. Everything destined for either side of the frame goes into a diversion to be retrieved when the accumulated text sweeps past the trap set by .BP or when the diversion is explicitly closed by .EP.

. PI source height, width, yoffset, xoffset flags.

This low-level macro, used by .BP, can help do more complex things. The two arguments not already described are:

xoffset

Offset the frame from the left margin by this amount, default 0i.

yoffset

Offset the frame from the current baseline, measuring positive downward, default 0i.

. EP End a picture started by . BP; . EP is usually called implicitly by a trap at frame bottom.

If a PostScript file lacks page-delimiting comments, the entire file is included. If no %BoundingBox comment is present, the picture is assumed to fill an 8.5×11 -inch page. Nothing prevents the picture from being placed off the page.

SEE ALSO

troff(1)

DIAGNOSTICS

A picture file that can't be read by the PostScript postprocessor is replaced by white space.

BUGS

A picture and associated text silently disappear if a diversion trap set by .BP isn't reached. Call .EP at the end of the document to retrieve it.

Macros in other packages may break the adjustments made to the line length and indent when text is being placed around a picture.

A missing or improper %%BoundingBox comment may cause the frame to be filled incorrectly.

ms - macros for formatting manuscripts

SYNOPSIS

nroff -ms [options] file ...
troff -ms [options] file ...

DESCRIPTION

This package of *nroff* and *troff*(1) macro definitions provides a canned formatting facility for technical papers in various formats.

The macro requests are defined below. Many *nroff* and *troff* requests are unsafe in conjunction with this package, but the following requests may be used with impunity after the first .PP: .bp, .br, .sp, .ls, .na.

Output of the eqn(1), tbl(1), pic(1) and grap(1) preprocessors for equations, tables, pictures, and graphs is acceptable as input.

FILES

/sys/lib/tmac/tmac.s

SEE ALSO

M. E. Lesk, "Typing Documents on the UNIX System: Using the -ms Macros with Troff and Nroff", *Unix Research System Programmer's Manual*, Tenth Edition, Volume 2. *eqn*(1), *troff*(1), *tbl*(1), *pic*(1)

REQUESTS

	REQUESTS			
I	Request	Initial	Cause	Explanation
		Value	Break	
	.1C	yes	yes	One column format on a new page.
	.2C	no	yes	Two column format.
	. AB	no	yes	Begin abstract.
	.AE	-	yes	End abstract.
	.AI	no	yes	Author's institution follows. Suppressed in .TM.
	. AT	no	yes	Print 'Attached' and turn off line filling.
	. AU <i>x y</i>	no	yes	Author's name follows. x is location and y is extension, ignored except in TM.
	. B <i>x y z</i>	no	no	Print x in boldface, append roman y and preface with z; if no argument switch to
				boldface.
	.B1	no	yes	Begin text to be enclosed in a box.
	.B2	no	yes	End boxed text.
	.BIxyz	no	no	Print x in bold italic, append roman y and preface with z; if no argument switch
				to bold italic.
	.BT	date	no	Bottom title, automatically invoked at foot of page. May be redefined.
	. BX <i>x</i>	no	no	Print x in a box.
	.CW x y z	no	no	Constant width font for x, append roman y and preface with z; if no argument
				switch to constant width.
	.CT	no	yes	Print 'Copies to' and turn off line filling.
	. DA <i>x</i>	nroff	no	'Date line' at bottom of page is x. Default is today.
	.DE	-	yes	End displayed text. Implies .KE.
	.DS <i>x</i>	no	yes	Start of displayed text, to appear verbatim line-by-line: I indented (default), L
				left-justified, C centered, B (block) centered with straight left margin. Implies
				.KS.
	.EG	no	-	Print document in BTL format for 'Engineer's Notes.' Must be first.
	.EN	-	yes	Space after equation produced by <i>neqn</i> or <i>eqn</i> (1).
	.EQ <i>x y</i>	-	yes	Display equation. Equation number is y . Optional x is I, L, C as in .DS.
	.FE	-	yes	End footnote.
	.FP x	-	no	Set font positions for a family, e.g., .FP lucidasans
	.FS	no	no	Start footnote. The note will be moved to the bottom of the page.
	.HO	-	no	'Bell Laboratories, Holmdel, New Jersey 07733'.
	.I <i>xyz</i>	no	no	Italicize x, append roman y and preface with z; if no argument switch to italic.
	.IH	no	no	'Bell Laboratories, Naperville, Illinois 60540'
	.IM	no	no	Print document in BTL format for an internal memorandum. Must be first.

тр.,,,,			Start indepted near work, with hereins to x , indeptetion is your (default Γ)
.IPxy	no	yes	Start indented paragraph, with hanging tag x . Indentation is y ens (default 5).
.KE	-	yes	End keep. Put kept text on next page if not enough room.
.KF	no	yes	Start floating keep. If the kept text must be moved to the next page, float later
720			text back to this page.
.KS	no	yes	Start keeping following text.
.LG	no	no	Make letters larger.
.LP	yes	yes	Start left-blocked paragraph.
.LT	no	yes	Start a letter; a non-empty first argument produces a full Lucent letterhead, a
			second argument is a room number, a third argument is a telephone number.
.MF	-	-	Print document in BTL format for 'Memorandum for File.' Must be first.
.MH	-	no	'Bell Laboratories, Murray Hill, New Jersey 07974'.
.MR	-	-	Print document in BTL format for 'Memorandum for Record.' Must be first.
.ND date	troff	no	Use date supplied (if any) only in special BTL format positions; omit from page
			footer.
.NH <i>n</i>	-	yes	Same as . SH, with automatic section numbers like '1.2.3'; <i>n</i> is subsection level
			(default 1). If <i>n</i> is 0, reset the numbering.
.NL	yes	no	Make letters normal size.
.P1	-	yes	Begin program display in constant width font.
.P2	-	yes	End program display.
.PE	-	yes	End picture; see <i>pic</i> (1).
.PF	-	yes	End picture; restore vertical position.
.PP	no	yes	Begin paragraph. First line indented.
.PShw	-	yes	Start picture; height and width in inches.
.PY	-	no	'Bell Laboratories, Piscataway, New Jersey 08854'
.QE	-	yes	End quoted material.
.QP	-	yes	Begin quoted paragraph (indent both margins).
.QS	-	yes	Begin quoted material (indent both margins).
.R	yes	no	Roman text follows.
.RE	-	yes	End relative indent level.
.RP	no	-	Cover sheet and first page for released paper. Must precede other requests.
.RS	-	yes	Start level of relative indentation from which subsequent indentation is mea-
			sured.
.SG <i>x</i>	no	yes	Insert signature(s) of author(s), ignored except in .TM and .LT. x is the
			reference line (initials of author and typist)}f
.SH	-	yes	Section head follows, font automatically bold.
.SM	no	no	Make letters smaller.
. TA <i>x</i>	5	no	Set tabs in ens. Default is 5 10 15
.TE	-	yes	End table; see <i>tbl</i> (1).
.TH	-	yes	End heading section of table.
.TL	no	yes	Title follows.
. TM <i>x</i>	no	-	Print document in BTL technical memorandum format. Arguments are TM num-
			ber, (quoted list of) case number(s), and file number. Must precede other
			requests.
.TR x	-	-	Print in BTL technical report format; report number is x. Must be first.
. TS <i>x</i>	-	yes	Begin table; if x is H table heading is repeated on new pages.
.UL x	-	no	Underline argument (even in troff).
.UX y z	-	no	'zUNIXy'; first use gives registered trademark notice.
.WH	-	no	'Bell Laboratories, Whippany, New Jersey 07981'.

namespace - name space description file

DESCRIPTION

Namespace files describe how to construct a name space from scratch, an operation normally performed by the *newns* or *addns* subroutines (see *auth*(2)) which is typically called by *init*(8). Each line specifies one name space operation. Spaces and tabs separate arguments to operations. Blank lines and lines with # as the first non-space character are ignored. Environment variables of the form \$ *name* are expanded within arguments, where *name* is a UTF string terminated by white space, a /, or a \$.

The known operations and their arguments are:

mount [-abcC] servename old [spec]

Mount *servename* on *old*.

bind [-abcC] new old

Bind *new* on *old*.

cd dir

Change the working directory to *dir*.

unmount [*new*] old

Unmount *new* from *old*, or everything mounted on *old* if *new* is missing.

clear

Clear the name space with rfork(RFCNAMEG).

. path

Execute the namespace file *path*. Note that *path* must be present in the name space being built.

The options for *bind* and *mount* are interpreted as in *bind*(1).

SEE ALSO

bind(1), namespace(4), init(8)

ndb - Network database

DESCRIPTION

The network database consists of files describing machines known to the local installation and machines known publicly. The files comprise multi-line tuples made up of attribute/value pairs of the form attr=value or sometimes just attr. Each line starting without white space starts a new tuple. Lines starting with # are comments.

The file /lib/ndb/local is the root of the database. Other files are included in the database if a tuple with an attribute-value pair of attribute database and no value exists in /lib/ndb/local. Within the database tuple, each pair with attribute file identifies a file to be included in the database. The files are searched in the order they appear. For example:

database=
 file=/lib/ndb/common
 file=/lib/ndb/local
 file=/lib/ndb/global

declares the database to be composed of the three files /lib/ndb/common, /lib/ndb/local, and /lib/ndb/global. By default, /lib/ndb/local is searched before the others. However, /lib/ndb/local may be included in the database to redefine its ordering.

Within tuples, pairs on the same line bind tighter than pairs on different lines.

Programs search the database directly using the routines in *ndb*(2) or indirectly using ndb/cs and ndb/dns (see *ndb*(8)). Both ndb/cs and the routine *ndbipinfo* impose structure on the otherwise flat database by using knowledge specific to the network. The internet is made up of networks which can be subnetted multiple times. A network must have an ipnet attribute and is uniquely identified by the values of its ip and ipmask attributes. If the ipmask is missing, the relevant Class A, B or C one is used.

A search for an attribute associated with a network or host starts at the lowest level, the entry for the host or network itself, and works its way up, bit by bit, looking at entries for nets/subnets that include the network or host. The search ends when the attribute is found. For example, consider the following entries:

```
ipnet=murray-hill ip=135.104.0.0 ipmask=255.255.0.0
    dns=135.104.10.1
    ntp=ntp.cs.bell-labs.com
ipnet=plan9 ip=135.104.9.0 ipmask=255.255.255.0
    ntp=oncore.cs.bell-labs.com
    smtp=smtp1.cs.bell-labs.com
ip=135.104.9.6 sys=anna dom=anna.cs.bell-labs.com
    smtp=smtp2.cs.bell-labs.com
```

Here anna is on the subnet plan9 which is in turn on the class B net murray-hill. Assume that we're searching for anna's NTP and SMTP servers. The search starts by looking for an entry with sys=anna. We find the anna entry. Since it has an smtp=smtp2.cs.bell-labs.com pair, we're done looking for that attribute. To fulfill the NTP request, we continue by looking for networks that include anna's IP address. We lop off the right most one bit from anna's address and look for an ipnet= entry with ip=135.104.9.4. Not finding one, we drop another bit and look for an ipnet= entry with ip=135.104.9.0. There is such an entry and it has the pair, ntp=oncore.cs.bell-labs.com

Ndb/cs can be made to perform such network aware searches by using metanames in the dialstring. A metaname is a \$ followed by an attribute name. *Ndb/cs* looks up the attribute relative to the system it is running on. Thus, with the above example, if a program called

dial("tcp!\$smtp!smtp", 0, 0, 0);

the dial would connect to the SMTP port of smtp2.cs.bell-labs.com.

A number of attributes are meaningful to programs and thus reserved. They are:

sys	system name (a short name)
dom	Internet fully-qualified domain name
ip	Internet address, v4 or v6.
ipv6	IPv6 Internet address. For DNS, an AAAA record.
ipnet	Internet network name
ipmask	Internet network mask
ipgw	Internet gateway (ip address)
ether	Ethernet address (must be lower-case hex)
vendor	Specific vendor attribute for dhcp and bootp
bootf	file to download for initial bootstrap; /386/9bootpxe to boot a PC via PXE.
tftp	an TFTP server to use for PXE bootstrap
fs	Plan 9 file server to be used
auth	Plan 9 authentication server to be used
authdom	Plan 9 authentication domain. To specify an authentication server for a particu-
	lar domain, add a tuple containing both auth and authdom attributes and val-
	ues.
rootpath	the NFS root for unix machines
rootserver	the NFS server used with rootpath
dnsdomain	a domain name that <i>ndb/dns</i> adds onto any unrooted names when doing a
	search. There may be multiple dnsdomain pairs.
dns	a DNS server to use (for DNS and DHCP)
ntp	an NTP server to use (for DHCP)
smtp	an SMTP server to use (for DHCP)
time	a time server to use (for DHCP)
wins	a Windows name server (for DHCP)
mx	mail exchanger (for DNS and DHCP); also pref.
srv	service location (for DNS); also pri, weight and port.
soa	start of area (for DNS)
tcp	a TCP service name
udp	a UDP service name
port	a TCP or UDP port number
restricted	a TCP service that can be called only by ports numbered less than 1024
proto	a protocol supported by a host. The pair proto=il was needed by <i>cs</i> (see
	<i>ndb</i> (8)) in tuples for hosts that supported the IL protocol

Cs defers to *dns* to translate dotted names to IP addresses, only consulting the database files if *dns* cannot translate the name.

Cs allows network entries with sys and dom attributes but no ip attribute. Searches for the system name are resolved by looking up the domain name with *dns*.

The file /lib/ndb/auth is used during authentication to decide who has the power to 'speak for' other users; see *authsrv*(6).

EXAMPLES

A tuple for the CPU server, spindle.

```
sys=spindle
    dom=spindle.research.bell-labs.com
    bootf=/mips/9powerboot
    ip=135.104.117.32 ether=080069020677
```

Entries for the network mh-astro-net and its subnets.

```
ipnet=mh-astro-net ip=135.104.0.0 ipmask=255.255.255.0
    ipgw=r70.research.bell-labs.com
    fs=bootes.research.bell-labs.com
    auth=p9auth.research.bell-labs.com
ipnet=unix-room ip=135.104.117.0
    ipgw=135.104.117.1
ipnet=third-floor ip=135.104.51.0
    ipgw=135.104.51.1
```

Mappings between TCP service names and port numbers.

tcp=sysmon	port=401	
tcp=rexec	port=512	restricted
tcp=9fs	port=564	

FILES

/lib/ndb/local first database file searched

SEE ALSO

con(1), dial(2), ndb(2), booting(8), dhcpd(8), ipconfig(8), ndb(8)

plot - graphics interface

DESCRIPTION

Files of this format are interpreted by *plot*(1) to draw graphics on the screen. A *plot* file is a UTF stream of instruction lines. Arguments are delimited by spaces, tabs, or commas. Numbers may be floating point. Punctuation marks (except :), spaces, and tabs at the beginning of lines are ignored. Comments run from : to newline. Extra letters appended to a valid instruction are ignored. Thus ...line, line, li all mean the same thing. Arguments are interpreted as follows:

- 1. If an instruction requires no arguments, the rest of the line is ignored.
- 2. If it requires a string argument, then all the line after the first field separator is passed as argument. Quote marks may be used to preserve leading blanks. Strings may include new-lines represented as n.
- 3. Between numeric arguments alphabetic characters and punctuation marks are ignored. Thus line from 5 6 to 7 8 draws a line from (5, 6) to (7, 8).
- 4. Instructions with numeric arguments remain in effect until a new instruction is read. Such commands may spill over many lines. Thus the following sequence will draw a polygon with vertices (4.5, 6.77), (5.8, 5.6), (7.8, 4.55), and (10.0, 3.6).

move 4.5 6.77 vec 5.8, 5.6 7.8 4.55 10.0, 3.6 4.5, 6.77

The instructions are executed in order. The last designated point in a line, move, rmove, vec, rvec, arc, or point command becomes the 'current point' (X, Y) for the next command.

Open & Close

е

- o string Open plotting device. For troff, string specifies the size of the plot (default is 6i).
- cl Close plotting device.

Basic Plotting Commands

- Start another frame of output.
- m x y (move) Current point becomes x y.
- rm dx dy Current point becomes X+dx Y+dy.
- poi x y Plot the point x y and make it the current point.
- v *x y* Draw a vector from the current point to *x y*.
- rv dx dy Draw vector from current point to X+dx Y+dy
- li x1 y1 x2 y2
 - Draw a line from x1 y1 to x2 y2. Make the current point x2 y2.
- t string Place the string so that its first character is centered on the current point (default). If string begins with C (R), it is centered (right-adjusted) on the current point. A back-slash at the beginning of the string may be escaped with another backslash.
- a x1 y1 x2 y2 xc yc r

Draw a circular arc from x1 y1 to x2 y2 with center xc yc and radius r. If the radius is positive, the arc is drawn counterclockwise; negative, clockwise. The starting point is exact but the ending point is approximate.

ci xc yc r

Draw a circle centered at xc yc with radius r. If the range and frame parameters do not specify a square, the 'circle' will be elliptical.

di xc yc r

Draw a disc centered at *xc yc* with radius *r* using the filling color (see cfill below).

bo x1 y1 x2 y2

Draw a box with lower left corner at x1 y1 and upper right corner at x2 y2.

sb x1 y1 x2 y2

Draw a solid box with lower left corner at $x_1 y_1$ and upper right corner at $x_2 y_2$ using the filling color (see cfill below).

- par x1 y1 x2 y2 xg yg
 - Draw a parabola from x1 y1 to x2 y2 'guided' by xg yg. The parabola passes through the

midpoint of the line joining xg yg with the midpoint of the line joining x1 y1 and x2 y2 and is tangent to the lines from xg yg to the endpoints.

- pol { {x1 y1 ... xn yn} ... {X1 Y1 ... Xm Ym} }
 Draw polygons with vertices x1 y1 ... xn yn and X1 Y1 ... Xm Ym. If only one polygon is
 specified, the inner brackets are not needed.
- fi { {x1 y1 ... xn yn} ... {X1 Y1 ... Xm Ym} }
 Fill a polygon. The arguments are the same as those for pol except that the first vertex
 is automatically repeated to close each polygon. The polygons do not have to be connected. Enclosed polygons appear as holes.
- sp { {*x*1 *y*1 ... *xn yn*} ... {*X*1 *Y*1 ... *Xm Ym*} }

Draw a parabolic spline guided by $x_1 y_1 \dots x_n y_n$ with simple endpoints.

fsp { { x1 y1 ... xn yn } ... { X1 Y1 ... Xm Ym } }

Draw a parabolic spline guided by x1 y1 ... xn yn with double first endpoint.

- lsp { { x1 y1 ... xn yn } ... { X1 Y1 ... Xm Ym } }
- Draw a parabolic spline guided by $x1 y1 \dots xn yn$ with double last endpoint. dsp { $\{x1 y1 \dots xn yn\} \dots \{X1 Y1 \dots Xm Ym\}$ }
- Draw a parabolic spline guided by $x_1 y_1 \dots x_n y_n$ with double endpoints.
- csp { { x1 y1 ... xn yn } ... { X1 Y1 ... Xm Ym } }
- in filename

(include) Take commands from *filename*.

de string { commands }

Define string as commands.

ca string scale

Invoke commands defined as *string* applying *scale* to all coordinates.

Commands Controlling the Environment

co string

Use color given by first character of *string*, one of red, yellow, green, blue, cyan, magenta, white, and kblack.

pe string

Use *string* as the style for drawing lines. The available pen styles are: solid, dott[ed], short, long, dotd[ashed], cdash, ddash

- cf string
 - Color for filling (see co, above).
- ra *x1 y1 x2 y2*

The data will fall between x1 y1 and x2 y2. The plot will be magnified or reduced to fit the device as closely as possible.

Range settings that exactly fill the plotting area with unity scaling appear below for devices supported by the filters of plot(1). The upper limit is just outside the plotting area. In every case the plotting area is taken to be square; points outside may be displayable on devices with nonsquare faces.

fr px1 py1 px2 py2

Plot the data in the fraction of the display specified by px1 py1 for lower left corner and px2 py2 for upper right corner. Thus frame .5 0 1. .5 plots in the lower right quadrant of the display; frame 0. 1. 1. 0. uses the whole display but inverts the y coordinates.

- sa Save the current environment, and move to a new one. The new environment inherits the old one. There are 7 levels.
- re Restore previous environment.

SEE ALSO

plot(1), graph(1)

plumb - format of plumb messages and rules

SYNOPSIS

#include <plumb.h>

DESCRIPTION

Message format

The messages formed by the *plumb*(2) library are formatted for transmission between processes into textual form, using newlines to separate the fields. Only the data field may contain embedded newlines. The fields occur in a specified order, and each has a name, corresponding to the elements of the Plumbmsg structure, that is used in the plumbing rules. The fields, in order, are:

- src application/service generating message
- dst destination 'port' for message
- wdir working directory (used if data is a file name)
- type form of the data, e.g. text
- attr attributes of the message, in *name=value* pairs separated by white space (the value must follow the usual quoting convention if it contains white space or quote characters or equal signs; it cannot contain a newline)
- ndata number of bytes of data
- data the data itself

At the moment, only textual data (type=text) is supported.

All fields are optional, but type should usually be set since it describes the form of the data, and ndata must be an accurate count (possibly zero) of the number of bytes of data. A missing field is represented by an empty line.

Plumbing rules

The plumber (see *plumb*(2)) receives messages on its send port (applications *send* messages there), interprets and reformats them, and (typically) emits them from a destination port. Its behavior is determined by a plumbing rules file, default /usr/\$user/lib/plumbing, which defines a set of pattern/action rules with which to analyze, rewrite, and dispatch received messages.

The file is a sequence of rule sets, each of which is a set of one-line rules called patterns and actions. There must be at least one pattern and one action in each rule set. (The only exception is that a rule set may contain nothing but plumb to rules; such a rule set declares the named ports but has no other effect.) A blank line terminates a rule set. Lines beginning with a # character are commentary and are regarded as blank lines.

A line of the form

include file

substitutes the contents of *file* for the line, much as in a C #include statement. Unlike in C, the file name is not quoted. If *file* is not an absolute path name, or one beginning ./ or ../, *file* is looked for first in the directory in which the plumber is executing, and then in /sys/lib/plumb.

When a message is received by the plumber, the rule sets are examined in order. For each rule set, if the message matches all the patterns in the rule set, the actions associated with the rule set are triggered to dispose of the message. If a rule set is triggered, the rest are ignored for this message. If none is triggered, the message is discarded (giving a write error to the sender) unless it has a dst field that specifies an existing port, in which case the message is emitted, unchanged, from there.

Patterns and actions all consist of three components: an *object*, a *verb*, and arguments. These are separated by white space on the line. The arguments may contain quoted strings and variable substitutions, described below, and in some cases contain multiple words. The object and verb are single words from a pre-defined set.

The object in a pattern is the name of an element of the message, such as src or data, or the special case arg, which refers to the argument component of the current rule. The object in an action is always the word plumb.

The verbs in the pattern rules describe how the objects and arguments are to be interpreted. Within a rule set, the patterns are evaluated in sequence; if one fails, the rule set fails. Some verbs are predicates that check properties of the message; others rewrite components of the message and implicitly always succeed. Such rewritings are permanent, so rules that specify them should be placed after all pattern-matching rules in the rule set.

- add The object must be attr. Append the argument, which must be a sequence of *name=value* pairs, to the list of attributes of the message.
- delete The object must be attr. If the message has an attribute whose name is the argument, delete it from the list of attributes of the message. (Even if the message does not, the rule matches the message.)
- is If the text of the object is identical to the text of the argument, the rule matches.
- isdir If the text of the object is the name of an existing directory, the rule matches and sets the variable \$dir to that directory name.
- isfile If the text of the object is the name of an existing file (not a directory), the rule matches and sets the variable \$file to that file name.
- matches If the entire text of the object matches the regular expression specified in the argument, the rule matches. This verb is described in more detail below.
- set The value of the object is set to the value of the argument.

The matches verb has special properties that enable the rules to select which portion of the data is to be sent to the destination. By default, a data matches rule requires that the entire text matches the regular expression. If, however, the message has an attribute named click, that reports that the message was produced by a mouse click within the text and that the regular expressions in the rule set should be used to identify what portion of the data the user intended. Typically, a program such as an editor will send a white-space delimited block of text containing the mouse click, using the value of the click attribute (a number starting from 0) to indicate where in the textual data the user pointed.

When the message has a click attribute, the data matches rules extract the longest leftmost match to the regular expression that contains or abuts the textual location identified by the click. For a sequence of such rules within a given rule set, each regular expression, evaluated by this specification, must match the same subset of the data for the rule set to match the message. For example, here is a pair of patterns that identify a message whose data contains the name of an existing file with a conventional ending for an encoded picture file:

data matches ' $[a-zA-Z0-9_-./]+$ '

data matches '([a-zA-Z0-9_-./]+).(jpe?g|gif|bit|ps|pdf)'

The first expression extracts the largest subset of the data around the click that contains file name characters; the second sees if it ends with, for example, .jpeg. If only the second pattern were present, a piece of text horse.gift could be misinterpreted as an image file named horse.gif.

If a click attribute is specified in a message, it will be deleted by the plumber before sending the message if the data matches rules expand the selection.

The action rules all have the object plumb. There are only three verbs for action rules:

- to The argument is the name of the port to which the message will be sent. If the message has a destination specified, it must match the to port of the rule set or the entire rule set will be skipped. (This is the only rule that is evaluated out of order.)
- client If no application has the port open, the arguments to a plumb start rule specify a shell program to run in response to the message. The message will be held, with the supposition that the program will eventually open the port to retrieve it.
- start Like client, but the message is discarded. Only one start or client rule should be specified in a rule set.

The arguments to all rules may contain quoted strings, exactly as in rc(1). They may also contain simple string variables, identified by a leading dollar sign . Variables may be set, between rule sets, by assignment statements in the style of rc. Only one variable assignment may appear on a line. The plumber also maintains some built-in variables:

\$0 The text that matched the entire regular expression in a previous data matches rule. \$1, \$2, etc. refer to text matching the first, second, etc. parenthesized subexpression.

- **\$attr** The textual representation of the attributes of the message.
- \$data The contents of the data field of the message.
- \$dir The directory name resulting from a successful isdir rule. If no such rule has been applied, it is the string constructed syntactically by interpreting data as a file name in wdir.
- \$dst The contents of the dst field of the message.
- \$file The file name resulting from a successful isfile rule. If no such rule has been applied, it is the string constructed syntactically by interpreting data as a file name in wdir.
- **\$type** The contents of the type field of the message.
- \$src The contents of the src field of the message.
- \$wdir The contents of the wdir field of the message.

EXAMPLE

The following is a modest, representative file of plumbing rules.

- # these are generally in order from most specific to least,
- # since first rule that fires wins.

```
addr=':(#?[0-9]+)'
protocol='(https?|ftp|file|gopher|mailto|news|nntp|telnet|wais)'
domain='[a-zA-Z0-9_@]+([.:][a-zA-Z0-9_@]+)*/?[a-zA-Z0-9_?,%#~&/\-]+'
file='([:.][a-zA-Z0-9_?,%#~&/\-]+)*'
```

```
# image files go to page
type is text
data matches '[a-zA-Z0-9_\-./]+'
data matches '([a-zA-Z0-9_\-./]+).(jpe?g|gif|bit)'
arg isfile $0
plumb to image
plumb start page -w $file
```

```
# URLs go to web browser
type is text
data matches $protocol://$domain$file
plumb to web
plumb start window webbrowser $0
```

```
# existing files, possibly tagged by line number, go to edit/sam
type is text
data matches '([.a-zA-Z0-9_/-]+[a-zA-Z0-9_/\-])('$addr')?'
arg isfile $1
data set $file
attr add addr=$3
plumb to edit
plumb start window sam $file
```

```
# .h files are looked up in /sys/include and passed to edit/sam
type is text
data matches '([a-zA-ZO-9]+\.h)('$addr')?'
arg isfile /sys/include/$1
data set $file
attr add addr=$3
plumb to edit
plumb start window sam $file
The following simple plumbing rules file is a good beginning set of rules.
# to update: cp /usr/$user/lib/plumbing /mnt/plumb/rules
```

```
editor = acme
# or editor = sam
include basic
```

FILES

/usr/\$user/lib/plumbing /mnt/plumb default rules file. /sys/lib/plumb directory for include files. /sys/lib/plumb/fileaddr /sys/lib/plumb/basic basic rule set.

SEE ALSO

plumb(1), plumb(2), plumber(4), regexp(6)

regexp - regular expression notation

DESCRIPTION

A *regular expression* specifies a set of strings of characters. A member of this set of strings is said to be *matched* by the regular expression. In many applications a delimiter character, commonly /, bounds a regular expression. In the following specification for regular expressions the word 'character' means any character (rune) but newline.

The syntax for a regular expression e0 is

A literal is any non-metacharacter, or a metacharacter (one of .*+?[]() $|^{\$), or the delimiter preceded by $\$.

A charclass is a nonempty string *s* bracketed [s] (or $[\land s]$); it matches any character in (or not in) *s*. A negated character class never matches newline. A substring a-b, with *a* and *b* in ascending order, stands for the inclusive range of characters between *a* and *b*. In *s*, the metacharacters –,], an initial \land , and the regular expression delimiter must be preceded by a \backslash ; other metacharacters have no special meaning and may appear unescaped.

A . matches any character.

A \wedge matches the beginning of a line; \$ matches the end of the line.

The REP operators match zero or more (*), one or more (+), zero or one (?), instances respectively of the preceding regular expression e2.

A concatenated regular expression, e1e2, matches a match to e1 followed by a match to e2.

An alternative regular expression, e0 | e1, matches either a match to e0 or a match to e1.

A match to any part of a regular expression extends as far as possible without preventing a match to the remainder of the regular expression.

SEE ALSO

awk(1), ed(1), grep(1), sam(1), sed(1), regexp(2)

rewrite - mail rewrite rules

SYNOPSIS

/mail/lib/rewrite

DESCRIPTION

Mail(1) uses rewrite rules to convert mail destinations into commands used to dispose of the mail. Each line of the file is a rule. Blank lines and lines beginning with # are ignored.

Each rewriting rule consists of (up to) 4 strings:

- *pattern* A regular expression in the style of *regexp*(6). The *pattern* is applied to mail destination addresses. The pattern match is case-insensitive and must match the entire address.
- *type* The type of rule; see below.
- arg1 An ed(1) style replacement string, with n standing for the text matched by the *n*th parenthesized subpattern.

arg2 Another *ed*(1) style replacement string.

In each of these fields the substring \s is replaced by the login id of the sender and the substring $\1$ is replaced by the name of the local machine.

When delivering a message, *mail* starts with the first rule and continues down the list until a pattern matches the destination address. It then performs one of the following actions depending on the *type* of the rule:

- >> Append the mail to the file indicated by expanding *arg1*, provided that file appears to be a valid mailbox.
- Pipe the mail through the command formed from concatenating the expanded *arg1* and *arg2*.

alias Replace the address by the address(es) specified by expanding *arg1* and recur.

translate

Replace the address by the address(es) output by the command formed by expanding *arg1* and recur.

Mail expands the addresses recursively until each address has matched a >> or | rule or until the recursion depth indicates a rewriting loop (currently 32).

If mail(1) is called with more than one address and several addresses match | rules and result in the same expanded arg1, the message is delivered to all those addresses by a single command, composed by concatenating the common expanded arg1 and each expanded arg2. This mail bundling is performed to reduce the number of times the same message is transmitted across a network. For example, with the following rewrite rule

([^!]*.bell-labs.com)!(.*) | "/mail/lib/qmail '\s' 'net!\1'" "'\2'"

if user presotto runs the command

% mail plan9.bell-labs.com!ken plan9.bell-labs.com!rob

there will follow only one execution of the command

/mail/lib/qmail presotto net!plan9.bell-labs.com ken rob

Here /mail/lib/qmail is an *rc*(1) script used for locally queuing remote mail.

In the event of an error, the disposition of the mail depends on the name of the command executing the rewrite. If the command is called mail and is run by \$user, the command will print an error and deposit the message in /mail/box/\$user/dead.letter. If the command is called rmail, usually because it was invoked to deliver mail arriving over the network, the message will be returned to the sender. The returned message will appear to have been sent by user postmaster.

SEE ALSO

mail(1)

smtpd - SMTP listener configuration

DESCRIPTION

The SMTP daemon of *mail*(1) implements the slave side of the SMTP protocol to accept incoming mail on TCP port 25. In general, *smtpd*'s default parameters are sufficient for internal systems on protected networks, but external or gateway systems require additional security mechanisms. The files /mail/lib/smtpd.conf, containing configuration parameters, and /mail/lib/blocked, containing banished addresses, provide the means to exercise these facilities.

Input Format

In both files input lines consist of a verb followed by one or more parameters. These tokens are separated by white space or commas and all characters following a # are comments. A # cannot be escaped. Continuation lines are not supported, but verbs that take multiple parameters can be restated on many lines and the associated parameters accumulate into a single set. All token processing is case-insensitive.

Many parameters are *addresses*, either numeric IP addresses in CIDR notation or a *sender address* in UUCP-style format.

An IP address in CIDR notation has the form

aaa.bbb.ccc.ddd/mask

consisting of a four octet IP address, a slash, and a *mask length* specifying the number of significant high-order bits. The lower the mask length, the larger the range of addresses covered by the CIDR address; see RFC 1878 for a discussion of mask lengths. Missing low-order octets are assumed to be zero. If a mask length is not given, a mask length of 16, 24, or 32 is assumed for addresses containing two, three, or four octets, respectively. These mask lengths select a class B, class C or Class D address block. Notice that this convention differs from the standard treatment, where the default mask length depends on the allocation class of the network block containing the address.

Sender addresses are specified in UUCP notation as follows:

[domain!]...domain!user

It is seldom necessary to specify more than one domain. When *domain* is missing or *, the address selects the specified user in all domains. A *domain* of the form *.*domain* selects the domain and all of its sub-domains. For example.com!user only matches the account *user* in domain example.com, while *.example.com!user selects that account in example.com and all of its sub-domains. When *user* is omitted or *, the address selects all users in the specified domain. Finally, when * is the last character of the user name it is a wild-card matching all user names beginning with *user*. This limited pattern matching capability should be used with care. For safety, the sender addresses *, !, *!, !* and *!* are ignored.

/mail/lib/smtpd.conf

This file contains configuration options and parameters describing the local domain. Many of the options can also be specified on the command line; command line options always override the values in this file. Configuration options are:

defaultdomain domain

The name of the local domain; it is appended to addresses lacking a domain qualification. This is identical to the -h command line option.

norelay [on|off]

If on is specified, relaying is prohibited from unauthorized networks to external domains. Authorized networks and domains must be specified by the ournets and ourdomains verbs described below. Setting this option on is equivalent to specifying the -f command line flag, but the list of networks and domains can only be specified in this file.

verifysenderdom[on|off]

When on, smtpd verifies that the first domain of the sender's address exists. The test is cursory; it checks only that there is a DNS delegation for the domain. Setting the option on is equivalent to specifying the -r command line option and is useful for detecting

some unreturnable messages as well as messages with randomly generated domain names.

saveblockedmsg[on|off]

When *on*, causes copies of blocked messages to be saved in subdirectories of /mail/queue.dump. Directories are named with the date and file names are random numbers. If this option is *off* blocked messages are discarded. Setting this option on is equivalent to specifying the -s command line option.

ournets IP address [, IP address, ..., IP address]

This option specifies trusted source networks that are allowed to relay mail to external domains. These are usually the internal networks of the local domain, but they can also include friendly external networks. Addresses are in CIDR notation.

ourdomains domain [, domain, ..., domain]

This option specifies destination domains that are allowed to receive relayed mail. These are usually the domains served by a gateway system. Domain specifications conform to the format for sender addresses given above.

When the norelay option is enabled or the -f command line option given, relaying is allowed only if the source IP address is in ournets or the destination domain is specified in ourdomains.

Blocked Addresses

Smtpd consults /mail/ratify (see *ratfs*(4)) for a list of banned addresses. Messages received from these addresses are rejected with a 5*xx*-series SMTP error code. There is no option to turn blocking on or off; if /mail/ratify is mounted, *smtpd* will use it, even for connections from trusted networks.

The command line format and address specifications conform to the notation described above. If the parameters of the verb is sender addresses in UUCP format, the line must begin with an * character; if the parameters are one or more IP addresses, the * must precede the verb. Most verbs cause messages to be rejected; verbs of this class generally select different error messages. The remaining verbs specify addresses that are always accepted, in effect overriding blocked addresses. The file is processed in order, so an override must precede its associated blocked address. Supported verbs are:

dial IP address [,..., IP address]

The parameters are IP addresses associated with dial-up ports. The rejection message states that connections from dial-up ports are not accepted. Copies of messages are never saved.

block address [, ... address]

Messages from addresses matching the parameters are rejected with an error message saying that spam is not accepted. The message is saved if the option is enabled.

relay address [, ... address]

This verb is identical to block, but the error message states that the message is rejected because the sending system is being used as a spam relay.

deny address [, ... address]

The deny command rejects a message when the sender address matches one of its parameters. The rejection message asks the sender to contact postmaster@ *hostdomain* for further information. This verb is usually used to block inadvertently abusive traffic, for example, mail loops and stuck senders. Messages are never saved.

allow address [, ... address]

The allow verb negates the effect of subsequent blocking commands. It is useful when a large range of addresses contains a few legitimate addresses, for example, when a mail server is in a Class C network block of modem ports. Rather than enumerate the dial ports, it is easier to block the entire Class C with a dial command, and precede it with an override for the address of the mail server. Similarly, it is possible to block mail from an entire domain while accepting mail from a few friendly senders in the domain. The verb accept is a synonym for allow.

Scanmail(8) describes spam detection software that works well with the capabilities described here and *mail*(1) defines additional *smtpd* command line arguments applicable to exposed systems.

SEE ALSO

mail(1), *ratfs*(4), *scanmail*(8)

snap - process snapshots

DESCRIPTION

Process snapshots are used to save a process image for debugging on another machine or at another time. They are like old Unix core dumps but can hold multiple process images and are smaller.

The first line of a snapshot begins with the prefix "process snapshot" and often contains other information as well, such as creation time, user name, system name, cpu type, and kernel type. This information is intended for humans, not programs. Programs reading snapshots should only check that this line begins with the specified prefix.

Throughout the rest of the snapshot, decimal strings are always right-justified, blank-padded to at least 11 characters, and followed by a single space character.

The rest of the snapshot is one or more records, each of which begins with a one-line header. This header is a decimal process id followed by an identification string, which denotes the type of data in the record.

Records of type fd, fpregs, kregs, noteid, ns, proc, regs, segment, and status are all formatted as a decimal number n followed by n bytes of data. This data is the contents of the file of the same name found in /proc.

The format of the mem and text sections is not as simple. These sections contain one or more page descriptions. Each describes a one kilobyte page of data. If the section is not a multiple of a kilobyte in size, the last page will be shorter. Each description begins with a one-byte flag. If the flag is r, then it is followed by a page of binary data. If the flag is z, then the data is understood to be zeros, and is omitted. If the flag is m or t, then it is followed by two decimal strings p and o, indicating that this page is the same as the page at offset o of the memory or text segment for process p. This data must have been previously described in the snapshot, and the offset must be a multiple of a kilobyte.

It is not guaranteed that any of the sections described above be in a process snapshot, although the snapshot quickly becomes useless when too much is missing.

Memory and text images may be incomplete. The memory or text file for a given process may be split across multiple disjoint sections in the snapshot.

SEE ALSO

proc(3), snap(4).

style - Plan 9 coding conventions for C

DESCRIPTION

Plan 9 C code has its own conventions. You would do well to follow them. Here are a few:

- don't use // comments; some old Plan 9 code does, but we're converting it as we touch it. We do sometimes use // to comment-out a few lines of code.
- avoid gotos.
- no tabs expanded to spaces.
- surround a binary operator (particular a low precedence one) with spaces; don't try to write the most compact code possible but rather the most readable.
- parenthesize expressions involving arithmetic and bit-wise operators; otherwise don't parenthesize heavily (e.g., as in Pascal).
- no white space before opening braces.
- no white space after the keywords if, for, while, etc.
- no braces around single-line blocks (e.g., if, for, and while bodies).
- integer-valued functions return -1 on error, 0 or positive on success.
- functions that return errors should set *errstr*(2).
- variable and function names are all lowercase, with no underscores.
- enum or #defined constants should be Uppercase (or UPPERCASE).
- struct tags are Uppercase, with matching typedefs.
- automatic variables (local variables inside a function) are never initialized at declaration.
- follow the standard idioms: use x < 0 not 0 > x, etc.
- don't write !strcmp (nor !memcmp, etc.) nor if(memcmp(a, b, c)); always explicitly compare the result of string or memory comparison with zero using a relational operator.

Ultimately, the goal is to write code that fits in with the other code around it and the system as a whole. If the file you are editing already deviates from these guidelines, do what it does. After you edit a file, a reader should not be able to tell just from coding style which parts you worked on.

COMMENTS

If your code is readable, you shouldn't need many comments. A line or two comment above a function explaining what it does is always welcome.

Comment any code you find yourself wondering about for more than 2 seconds, even if it's to say that you don't understand what's going on. Explain why.

Don't use commenting as an excuse for writing confusing code. Rewrite the code to make it clear.

EFFICIENCY

Do the simple thing. Don't optimize unless you've measured the code and it is too slow. Fix the data structures and the algorithms instead of going for little 5% tunings.

SEE ALSO

"Notes on Programming in C", Rob Pike,

http://www.literateprogramming.com/pikestyle.pdf

BUGS

Some programs use very different styles, for example, rc.

Some programs and programmers diverge from the above rules due to habits formed long before these rules. Notably, some programs have a single space after a keyword and before an opening brace, and some initialize automatic variables at declaration.

thumbprint – public key thumbprints

DESCRIPTION

Applications in Plan 9 that use public keys for authentication, for example by calling tlsClient and okThumbprint or okCertificate (see *pushtls*(2)), check the remote side's public key by comparing against thumbprints from a trusted list. The list is maintained by people who set local policies about which servers can be trusted for which applications, thereby playing the role taken by certificate authorities in PKI-based systems. By convention, these lists are stored as files in /sys/lib/tls/ and protected by normal file system permissions.

Such a thumbprint file comprises lines made up of attribute/value pairs of the form attr=value or attr. The first attribute must be the application tag: x509 for tls applications or ssh for ssh server fingerprints. The second attribute must be a hash type of sha1= or sha256= followed by the hex or base64 encoded hash of binary certificate or public key. All other attributes are treated as comments. The file may also contain lines of the form #include file

For example, a web server might have thumbprint

x509 sha1=8fe472d31b360a8303cd29f92bd734813cbd923c cn=*.cs.bell-labs.com

SEE ALSO

pushtls(2)

users - file server user list format

DESCRIPTION

The permanent file servers each maintain a private list of users and groups, in /adm/users by convention. Each line in the file has the format

id : *name* : *leader* : *members*

where *name* and *leader* are printable strings excluding the characters ?, =, +, -, /, and :, and *members* is a comma-separated list of such strings. Such a line defines a user and a group with the given *name*; the group has a group leader given by *leader* and group members given by the user names in *members*. The *leader* field may be empty, in which case any group member is a group leader. The *members* field may be empty.

Lines beginning with # are ignored.

The *id* in a line is an identifier used in the on-disk structures maintained by a file server; there should be no duplicate *id*s in the file. In older Plan 9 file servers, *id*s are small decimal numbers. In those, a negative *id* is special: a user with a negative *id* cannot attach to the file server. The file /adm/users itself is owned by user *adm* and write protected to others, so it can only be changed via console commands.

SEE ALSO

intro(5), *stat*(5),

UTF, Unicode, ASCII, rune - character set and format

DESCRIPTION

The Plan 9 character set and representation are based on the Unicode Standard and on the ISO multibyte UTF-8 encoding (Universal Character Set Transformation Format, 8 bits wide). The Unicode Standard represents its characters in 21 bits; UTF-8 represents such values in an 8-bit byte stream. Throughout this manual, UTF-8 is shortened to UTF.

In Plan 9, a *rune* is a 32-bit quantity representing a Unicode character. Internally, programs may store characters as runes. However, any external manifestation of textual information, in files or at the interface between programs, uses a machine-independent, byte-stream encoding called UTF.

UTF is designed so the 7-bit ASCII set (values hexadecimal 00 to 7F), appear only as themselves in the encoding. Runes with values above 7F appear as sequences of two or more bytes with values only from 80 to FF.

The UTF encoding of the Unicode Standard is backward compatible with ASCII: programs presented only with ASCII work on Plan 9 even if not written to deal with UTF, as do programs that deal with uninterpreted byte streams. However, programs that perform semantic processing on ASCII graphic characters must convert from UTF to runes in order to work properly with non-ASCII input. See *rune*(2).

Letting numbers be binary, a rune x is converted to a multibyte UTF sequence as follows:

- 001. x in [0000000.0000000.0bbbbbbb] → 0bbbbbbb
- 010. x in [0000000.0000bbb.bbbbbbbb] → 110bbbbb, 10bbbbbb

Conversion 001 provides a one-byte sequence that spans the ASCII character set in a compatible way. Conversions 010, 011 and 100 represent higher-valued characters as sequences of two, three or four bytes with the high bit set. Plan 9 does not support the 5 and 6 byte sequences proposed by X-Open. When there are multiple ways to encode a value, for example rune 0, the shortest encoding is used.

In the inverse mapping, any sequence except those described above is incorrect and is converted to rune hexadecimal FFFD.

FILES

/lib/unicode table of characters and descriptions, suitable for *look*(1).

SEE ALSO

ascii(1), tcs(1), rune(2), keyboard(6), The Unicode Standard.

venti - archival storage server

DESCRIPTION

Venti is a block storage server intended for archival data. In a Venti server, the SHA1 hash of a block's contents acts as the block identifier for read and write operations. This approach enforces a write-once policy, preventing accidental or malicious destruction of data. In addition, duplicate copies of a block are coalesced, reducing the consumption of storage and simplifying the implementation of clients.

This manual page documents the basic concepts of block storage using Venti as well as the Venti network protocol.

Venti(1) documents some simple clients. Vac(1) and vacfs(4) are more complex clients.

Venti(2) describes a C library interface for accessing Venti servers and manipulating Venti data structures.

Venti(8) describes the programs used to run a Venti server.

Scores

The SHA1 hash that identifies a block is called its *score*. The score of the zero-length block is called the *zero score*.

Scores may have an optional *label*: prefix, typically used to describe the format of the data. For example, vac(1) uses a vac: prefix, while vbackup uses prefixes corresponding to the file system types: ext2:, ffs:, and so on.

Files and Directories

Venti accepts blocks up to 56 kilobytes in size. By convention, Venti clients use hash trees of blocks to represent arbitrary-size data *files*. The data to be stored is split into fixed-size blocks and written to the server, producing a list of scores. The resulting list of scores is split into fixed-size pointer blocks (using only an integral number of scores per block) and written to the server, producing a smaller list of scores. The process continues, eventually ending with the score for the hash tree's top-most block. Each file stored this way is summarized by a VtEntry structure recording the top-most score, the depth of the tree, the data block size, and the pointer block size. One or more VtEntry structures can be concatenated and stored as a special file called a *directory*. In this manner, arbitrary trees of files can be constructed and stored.

Scores passed between programs conventionally refer to VtRoot blocks, which contain descriptive information as well as the score of a directory block containing a small number of directory entries.

Conventionally, programs do not mix data and directory entries in the same file. Instead, they keep two separate files, one with directory entries and one with metadata referencing those entries by position. Keeping this parallel representation is a minor annoyance but makes it possible for general programs like *venti/copy* (see *venti*(1)) to traverse the block tree without knowing the specific details of any particular program's data.

Block Types

To allow programs to traverse these structures without needing to understand their higher-level meanings, Venti tags each block with a type. The types are:

VtDataType VtDataType+1 VtDataType+2	000 001 002	data scores of VtDataType blocks scores of VtDataType+1 blocks
 VtDirType VtDirType+1 VtDirType+2	010 011 012	VtEntry structures scores of VtDirType blocks scores of VtDirType+1 blocks
 VtRootType	020	VtRoot structure

The octal numbers listed are the type numbers used by the commands below. (For historical reasons, the type numbers used on disk and on the wire are different from the above. They do not distinguish VtDataType+n blocks from VtDirType+n blocks.)

Zero Truncation

To avoid storing the same short data blocks padded with differing numbers of zeros, Venti clients working with fixed-size blocks conventionally 'zero truncate' the blocks before writing them to the server. For example, if a 1024-byte data block contains the 11-byte string 'hello world' followed by 1013 zero bytes, a client would store only the 11-byte block. When the client later read the block from the server, it would append zero bytes to the end as necessary to reach the expected size.

When truncating pointer blocks (VtDataType+n and VtDirType+n blocks), trailing zero scores are removed instead of trailing zero bytes.

Because of the truncation convention, any file consisting entirely of zero bytes, no matter what its length, will be represented by the zero score: the data blocks contain all zeros and are thus truncated to the empty block, and the pointer blocks contain all zero scores and are thus also truncated to the empty block, and so on up the hash tree.

Network Protocol

A Venti session begins when a *client* connects to the network address served by a Venti *server*; the conventional address is tcp! *server*!venti (the venti port is 17034). Both client and server begin by sending a version string of the form venti-*versions*-*comment*\n. The *versions* field is a list of acceptable versions separated by colons. The protocol described here is version 02. The client is responsible for choosing a common version and sending it in the VtThello message, described below.

After the initial version exchange, the client transmits *requests* (T-messages) to the server, which subsequently returns *replies* (R-messages) to the client. The combined act of transmitting (receiving) a request of a particular type, and receiving (transmitting) its reply is called a *transaction* of that type.

Each message consists of a sequence of bytes. Two-byte fields hold unsigned integers represented in big-endian order (most significant byte first). Data items of variable lengths are represented by a one-byte field specifying a count, n, followed by n bytes of data. Text strings are represented similarly, using a two-byte count with the text itself stored as a UTF-encoded sequence of Unicode characters (see *utf*(6)). Text strings are not NUL-terminated: n counts the bytes of UTF data, which include no final zero byte. The NUL character is illegal in text strings in the Venti protocol. The maximum string length in Venti is 1024 bytes.

Each Venti message begins with a two-byte size field specifying the length in bytes of the message, not including the length field itself. The next byte is the message type, one of the constants in the enumeration in the include file <venti.h>. The next byte is an identifying *tag*, used to match responses to requests. The remaining bytes are parameters of different sizes. In the message descriptions, the number of bytes in a field is given in brackets after the field name. The notation *parameter*[*n*] where *n* is not a constant represents a variable-length parameter: *n*[1] followed by *n* bytes of data forming the *parameter*. The notation *string*[*s*] (using a literal *s* character) is shorthand for *s*[2] followed by *s* bytes of UTF-8 text. The notation *parameter*[] where *parameter* is the last field in the message represents a variable-length field that comprises all remaining bytes in the message.

All Venti RPC messages are prefixed with a field *size*[2] giving the length of the message that follows (not including the *size* field itself). The message bodies are:

VtThello tag[1] version[s] uid[s] strength[1] crypto[n] codec[n]
VtRhello tag[1] sid[s] rcrypto[1] rcodec[1]
VtTping tag[1]
VtTping tag[1]
VtTread tag[1] score[20] type[1] pad[1] count[2]
VtRead tag[1] data[]
VtTwrite tag[1] type[1] pad[3] data[]
VtTwrite tag[1] score[20]
VtTsync tag[1]
VtRsync tag[1]

VtRerror tag[1] error[s]

VtTgoodbye *tag*[1]

Each T-message has a one-byte *tag* field, chosen and used by the client to identify the message. The server will echo the request's *tag* field in the reply. Clients should arrange that no two outstanding messages have the same tag field so that responses can be distinguished.

The type of an R-message will either be one greater than the type of the corresponding T-message or Rerror, indicating that the request failed. In the latter case, the *error* field contains a string describing the reason for failure.

Venti connections must begin with a hello transaction. The VtThello message contains the protocol *version* that the client has chosen to use. The fields *strength*, *crypto*, and *codec* could be used to add authentication, encryption, and compression to the Venti session but are currently ignored. The *rcrypto*, and *rcodec* fields in the VtRhello response are similarly ignored. The *uid* and *sid* fields are intended to be the identity of the client and server but, given the lack of authentication, should be treated only as advisory. The initial hello should be the only hello transaction during the session.

The ping message has no effect and is used mainly for debugging. Servers should respond immediately to pings.

The read message requests a block with the given *score* and *type*. Use *vttodisktype* and *vtfromdisktype* (see *venti*(2)) to convert a block type enumeration value (VtDataType, etc.) to the *type* used on disk and in the protocol. The *count* field specifies the maximum expected size of the block. The *data* in the reply is the block's contents.

The write message writes a new block of the given *type* with contents *data* to the server. The response includes the *score* to use to read the block, which should be the SHA1 hash of *data*.

The Venti server may buffer written blocks in memory, waiting until after responding to the write message before writing them to permanent storage. The server will delay the response to a sync message until after all blocks in earlier write messages have been written to permanent storage.

The goodbye message ends a session. There is no VtRgoodbye: upon receiving the VtTgoodbye message, the server terminates up the connection.

SEE ALSO

venti(1), venti(2), venti(8)

Sean Quinlan and Sean Dorward, "Venti: a new approach to archival storage", Usenix Conference on File and Storage Technologies, 2002.

venti.conf - a venti configuration file

DESCRIPTION

A venti configuration file enumerates the various index sections and arenas that constitute a venti system. The components are indicated by the name of the file, typically a disk partition, in which they reside. The configuration file is the only location that file names are used. Internally, venti uses the names assigned when the components were formatted with *fmtarenas* or *fmtisect* (see *venti–fmt*(8)). In particular, by changing the configuration a component can be copied to a different file.

The configuration file consists of lines in the form described below. Lines starting with # are comments.

index name

Names the index for the system.

arenas file File co

File contains a collection of arenas, formatted using *fmtarenas*.

isect file

File contains an index section, formatted using fmtisect.

After formatting a venti system using *fmtindex*, the order of arenas and index sections should not be changed. Additional arenas can be appended to the configuration.

The configuration file optionally holds configuration parameters for the venti server itself. These are:

mem cachesize

bcmem blockcachesize

icmem indexcachesize

addr ventiaddress

httpaddr httpaddress

queuewrites

See *venti*(8) for descriptions of these variables.

EXAMPLE

```
# a sample venti configuration file
     #
     #
       formatted with
     #
          venti/fmtarenas arena. /tmp/disks/arenas
     #
          venti/fmtisect isect0 /tmp/disks/isect0
     #
          venti/fmtisect isect1 /tmp/disks/isect1
     #
          venti/fmtindex venti.conf
     #
     #
      server is started with
     #
          venti/venti
     # the name of the index
     index main
     # the index sections
     isect /tmp/disks/isect0
     isect /tmp/disks/isect1
     # the arenas
     arenas /tmp/disks/arenas
SEE ALSO
     fs(3), venti(8), venti-fmt(8)
```

vgadb - VGA controller and monitor database

DESCRIPTION

The VGA database, /lib/vgadb, consists of two parts, the first describing how to identify and program a VGA controller and the second describing the timing parameters for known monitors to be loaded into a VGA controller to give a particular resolution and refresh rate. Conventionally, at system boot, the program aux/vga (see vga(8)) uses the monitor type in /env/monitor, the display resolution in /env/vgasize, and the VGA controller information in the database to find a matching monitor entry and initialize the VGA controller accordingly.

The file comprises multi-line entries made up of attribute/value pairs of the form attr=value or sometimes just *attr*. Each line starting without white space starts a new entry. Lines starting with *#* are comments.

The first part of the database, the VGA controller identification and programming information, consists of a number of entries with attribute ctlr and no value. Within one of these entries the following attributes are meaningful:

nnnnn an offset into the VGA BIOS area. The value is a string expected to be found there that will identify the controller. For example, 0xC0068="#9GXE64 Pro" would identify a #9GXEpro VGA controller if the string #9GXE64 Pro was found in the BIOS at address 0xC0068. There may be more than one identifier attribute per controller. If a match cannot be found, the first few bytes of the BIOS are printed to help identify the card and create a controller entry.

nnnnn– mmmmm

A range of the VGA BIOS area. The value is a string as above, but the entire range is searched for that string. The string must begin at or after *nnnn* and not contain any characters at or after *mmmmm*. For example, 0xC0000-0xC0200="MACH64LP" identifies a Mach 64 controller with the string MACH64LP occurring anywhere in the first 512 bytes of BIOS memory.

- ctlr VGA controller chip type. This must match one of the VGA controller types known to /dev/vgactl (see vga(3)) and internally to aux/vga. Currently, ark2000pv, clgd542x, ct65540, ct65545, cyber938x, et4000, hiqvideo, ibm8514, mach32, mach64, mach64xx, mga2164w, neomagic, s3801, s3805, s3928, t2r4, trio64, virge, vision864, vision964, vision968, and w30c516 are recognized.
- ramdac RAMDAC controller type. This must match one of the types known internally to aux/vga. Currently att20c490, att20c491, att20c492, att21c498, bt485, rgb524mn, sc15025, stg1702, tvp3020, tvp3025, and tvp3026 are recognized.
- clock clock generator type. This must match one of the types known internally to aux/vga. Currently ch9294, icd2061a, ics2494, ics2494a, s3clock, tvp3025clock, and tvp3026clock are recognized.
- hwgc hardware graphics cursor type. This must match one of the types known to /dev/vgactl and internally to aux/vga. Currently ark200pvhwgc, bt485hwgc, clgd542xhwgc, clgd546xhwgc, ct65545hwgc, cyber938xhwgc, hiqvideohwgc, mach64xxhwgc, mga2164whwgc, neomagichwgc, rgb524hwgc, s3hwgc, t2r4hwgc, tvp3020hwgc, and tvp3026hwgc are recognized.
- membw Memory bandwidth in megabytes per second. *Vga* chooses the highest refresh rate possible within the constraints of the monitor (explained below) and the card's memory bandwidth.
- linear Whether the card supports a large (>64kb) linear memory window. The value is either 1 or 0 (equivalent to unspecified). The current kernel graphics subsystem requires a linear window; entries without linear=1 are of historic value only.
- link This must match one of the types known internally to aux/vga. Currently vga and ibm8514 are recognized. The type vga handles generic VGA functions and should almost always be included. The type Ibm8514 handles basic graphics accelerator initialization on controllers such as the early S3 family of GUI chips.

The clock, ctlr, link, and ramdac values can all take an extension following a '-' that can be used as a speed-grade or subtype; matching is done without the extension. For example, ramdac=stg1702-135 indicates the STG1702 RAMDAC has a maximum clock frequency of 135MHz, and clock=ics2494a-324 indicates that the frequency table numbered 324 should be used for the ICS2494A clock generator.

The functions internal to aux/vga corresponding to the clock, ctlr, link, and ramdac values will be called in the order given for initialization. Sometimes the clock should be set before the RAMDAC is initialized, for example, depending on the components used. In general, link=vga will always be first and, if appropriate, link=ibm8514 will be last.

The entries in the second part of /lib/vgadb have as attribute the name of a monitor type and the value is conventionally a resolution in the form XxY, where X and Y are numbers representing width and height in pixels. The monitor type (i.e. entry) include has special properties, described below and shown in the examples. The remainder of the entry contains timing information for the desired resolution. Within one of these entries the following attributes are meaningful:

clock	the video dot-clock frequency in MHz required for this resolution. The value
	25.175 is known internally to <i>vga</i> (8) as the baseline VGA clock rate.
	defaultclock the default video dot-clock frequency in MHz used for this reso-
	lution when no memory bandwidth is specified for the card or when vga cannot
	determine the maximum clock frequency of the card.
shb	start horizontal blanking, in character clocks.
ehb	end horizontal blanking, in character clocks.
ht	horizontal total, in character clocks.
vrs	vertical refresh start, in character clocks.
vre	vertical refresh end, in character clocks.
vt	vertical total, in character clocks.
hsync	horizontal sync polarity. Value must be + or –.
vsync	vertical sync polarity. Value must be $+$ or $-$.
interlace	interlaced mode. Only value ${f v}$ is recognized.
alias	continue, replacing the alias line by the contents of the entry whose attribute is
	given as <i>value</i> .
include	continue, replacing this include line by the contents of the previously defined
	include monitor type with matching <i>value</i> . (See the examples.) Any non-zero
	attributes already set will not be overwritten. This is used to save duplication of
	timing information. Note that <i>value</i> is not parsed, it is only used as a string to
	identify the previous include=value monitor type entry.

The values given for shb, ehb, ht, vrs, vre, vt, hsync, and vsync are beyond the scope of this manual page. See the book by Ferraro for details.

EXAMPLES

Basic ctlr entry for a laptop with a Chips and Technology 65550 controller:

hwgc=hiqvideohwgc

A more complex entry. Note the extensions on the clock, ctlr, and ramdac attributes. The order here is important: the RAMDAC clock input must be initialized before the RAMDAC itself. The clock frequency is selected by the ET4000 chip.

```
shb=664 ehb=760 ht=800
    vrs=491 vre=493 vt=525
vga = 640x480
                                       # 60Hz, 31.5KHz
    include=640x480@60Hz
Entries for multisync monitors with video bandwidth up to 65MHz.
#
# Multisync monitors with video bandwidth up to 65MHz.
#
                                 # 60Hz, 48.4KHz
multisync65 = 1024x768
    include=1024x768@60Hz
multisync65 = 1024x768i
                                 # 87Hz, 35.5KHz (interlaced)
    include=1024x768i@87Hz
multisync65
    alias=vga
Note how this builds on the existing vga entries.
```

FILES

/lib/vgadb

SEE ALSO

ndb(2), vga(3), ndb(6), vga(8) Richard E. Ferraro, Programming Guide to the EGA, VGA and Super VGA Cards, Third Edition

BUGS

The database should provide a way to use the PCI bus as well as BIOS memory to identify cards.

ADDING A NEW MONITOR

Adding a new monitor is usually fairly straightforward, as most modern monitors are multisync and the only interesting parameter is the maximum video bandwidth. Once the timing parameters are worked out for a particular maximum video bandwidth as in the example above, an entry for a new monitor with that limit is simply

```
#
# Sony CPD-1304
# Horizontal timing:
# Allowable frequency range: 28-50KHz
# Vertical timing:
# Allowable frequency range: 50-87Hz
#
cpd-1304
alias=multisync65
```

Even this is not necessary, as the monitor type could simply be given as multisync65.

ADDING A NEW VGA CONTROLLER

While the use of this database formalizes the steps needed to program a VGA controller, unless you are lucky and all the important components on a new VGA controller card are interconnected in the same way as an existing entry, adding a new entry requires adding new internal types to vga(8). Fortunately, the unit of variety has, for the most part, shifted from individual components to entire video chipsets. Thus in lucky cases all that is necessary is the addition of another 0xNNNN= line to the entry for the controller. This is particularly true in the case of the ATI Mach 64 and the S3 Virge.

If you need to actually add support for a controller with a different chipset, you will need the data sheets for the VGA controller as well as any RAMDAC or clock generator (these are commonly integrated into the controller). You will also need to know how these components interact. For example, a common combination is an S3 86C928 VGA chip with an ICD2061A clock generator. The ICD2061A is usually loaded by clocking a serial bit-stream out of one of the 86C928 registers. Similarly, the RAMDAC may have an internal clock-doubler and/or pixel-multiplexing modes, in which case both the clock generator and VGA chip must be programmed accordingly. Hardware acceleration for rectangle fills and block copies is provided in the kernel; writing code to handle this is necessary to achieve reasonable performance at high pixel depths.

intro - introduction to databases

DESCRIPTION

This manual section describes databases available on Plan 9 and the commands that access them. Some of them involve proprietary data that is not distributed outside Bell Laboratories.

astro - print astronomical information

SYNOPSIS

astro[-dlpsatokm][-c n][-C d][-e obj1 obj2]

DESCRIPTION

Astro reports upcoming celestial events, by default for 24 hours starting now. The options are:

- d Read the starting date. A prompt gives the input format.
- 1 Read the north latitude, west longitude, and elevation of the observation point. A prompt gives the input format. If 1 is missing, the initial position is read from the file /lib/sky/here.
- c Report for *n* (default 1) successive days.
- C Used with -c, set the interval to d days (or fractions of days).
- e Report distance between the centers of objects, in arc seconds, during eclipses or occultations involving *obj1* and *obj2*.
- p Print the positions of objects at the given time rather than searching for interesting conjunctions. For each, the name is followed by the right ascension (hours, minutes, seconds), declination (degrees, minutes, seconds), azimuth (degrees), elevation (degrees), and semidiameter (arc seconds). For the sun and moon, the magnitude is also printed. The first line of output presents the date and time, sidereal time, and the latitude, longitude, and elevation.
- s Print output in English words suitable for speech synthesizers.
- a Include a list of artificial earth satellites for interesting events. (There are no orbital elements for the satellites, so this option is not usable.)
- t Read ΔT from standard input. ΔT is the difference between ephemeris and universal time (seconds) due to the slowing of the earth's rotation. ΔT is normally calculated from an empirical formula. This option is needed only for very accurate timing of occultations, eclipses, etc.
- o Search for stellar occultations.
- k Print times in local time ('kitchen clock') as described in the timezone environment variable.
- m Includes a single comet in the list of objects. This is modified (in the source) to refer to an approaching comet but in steady state usually refers to the last interesting comet (currently Hale-Bopp, C/1995 O1).

FILES

```
/lib/sky/estartab ecliptic star data
/lib/sky/here default latitude (N), longitude (W), and elevation (meters)
```

SOURCE

/sys/src/cmd/astro

SEE ALSO

scat(7)

BUGS

The k option reverts to GMT outside of 1970–2036.

dict - dictionary browser

SYNOPSIS

dict[-k][-d dictname][-c command][pattern]

DESCRIPTION

Dict is a dictionary browser. If a *pattern* is given on the command line, *dict* prints all matching entries; otherwise it repeatedly accepts and executes commands. The options are

-d dictname
 Use the given dictionary. The default is oed, the second edition of the Oxford English Dictionary. A list of available dictionaries is printed by option -d?.
 -c command
 Execute one command and quit. The command syntax is described below.

-k Print a pronunciation key.

Patterns are regular expressions (see regexp(6)), with an implicit leading \land and trailing \$. Patterns are matched against an index of headwords and variants, to form a 'match set'. By default, both patterns and the index are folded: upper case characters are mapped into their lower case equivalents, and Latin accented characters are mapped into their non-accented equivalents. In interactive mode, there is always a 'current match set' and a 'current entry' within the match set. Commands can change either or both, as well as print the entries or information about them.

Commands have an address followed by a command letter. Addresses have the form:

- /*re*/ Set the match set to all entries matching the regular expression *re*, sorted in dictionary order. Set the current entry to the first of the match set.
- ! *re* ! Like / *re* / but use exact matching, i.e., without case and accent folding.
- *n* An integer *n* means change the current entry to the *n*th of the current match set.
- #n The integer n is an absolute byte offset into the raw dictionary. (See the A command, below.)
- *addr*+ After setting the match set and current entry according to *addr*, change the match set and current entry to be the next entry in the dictionary (not necessarily in the match set) after the current entry.
- *addr* Like *addr*+ but go to previous dictionary entry.

The command letters come in pairs: a lower case and the corresponding upper case letter. The lower case version prints something about the current entry only, and advances the current entry to the next in the match set (wrapping around to the beginning after the last). The upper case version prints something about all of the match set and resets the current entry to the beginning of the set.

- p,P Print the whole entry.
- \hat{h} ,H Print only the headword(s) of the entry.
- a,A Print the dictionary byte offset of the entry.
- r,R Print the whole entry in raw format (without translating special characters, etc.).

If no command letter is given for the first command, H is assumed. After an H, the default command is p. Otherwise, the default command is the previous command.

FILES

/lib/dict/oed2
/lib/dict/oed2index
Other files in /lib.

SEE ALSO

regexp(6)

SOURCE

/sys/src/cmd/dict

BUGS

A font with wide coverage of the Unicode Standard should be used for best results. (Try /lib/font/bit/pelm/unicode.9.font.)

If the *pattern* doesn't begin with a few literal characters, matching takes a long time. The dictionaries are not distributed outside Bell Labs.

juke – music jukebox

SYNOPSIS

juke [-t][-w][-h srvhost][-s srvname]

games/jukebox[-t][-w]

games/jukefs[-m mountpoint][-s srvname][mapfile]

DESCRIPTION

Jukebox controls a playlist server (see *playlistfs*(7)) through a graphical user interface. It connects to a music database server which reads a set of *map* files that describe recordings and their location. Currently, there is one set of maps, mostly for classical music, with some jazz and other stuff thrown in. These are served by jukefs, which presents a file system conventionally mounted at /mnt/juke. The playlist, explained below, is managed by a file system implemented by *playlistfs*(7) and normally mounted on /mnt.

Jukebox is most easily started through the *juke* shell script.

Jukebox has four windows, which can be selected by clicking the appropriate tab at the top of the window.

Above the tab are nine buttons and a volume slider. The buttons, shown below, are named, from left to right, *Exit*, *Pause*, *Play*, *Halt*, *Back*, *Forward*, *Root*, *Delete*, and *Help*. The buttons are *active* when they are displayed in dark green (or red). When they are pale blue they are *inactive*. The Exit button is always active; it exits the program (but leaves the playlist and music database servers running).

The *browse* window is for browsing through the music and selecting music to play. Browsing down in the music hierarchy is done by clicking button one on an item. Clicking button three goes back up. Clicking button two recursively adds all files below the selected item to the *play list*.

The selected music is displayed in the *playlist* window. The track currently playing is shown in the *playing* window.

The *Root* button browses back to the root.

The Delete button empties the playlist.

The *Help* displays a minimal on-line manual.

Play starts playing at the beginning of the play list, or at the selected track in the play list.

During play, *Pause*, *Stop*, *Back*, and *Forward* are active. *Back* and *Forward* go back or forward a track at a time. The other buttons do the obvious thing.

The -t flag chooses a tiny font, useful for handhelds.

The -w flag creates the jukebox in a new window. Normally, the jukebox takes over the window in which it is invoked.

The -s flag specifies the name under which the file descriptors of the playlist and databse servers are posted in /srv. This allows two or more play list servers to exist on one platform, e.g., when there are several audio devices. The default value of the flag is *\$user* for a playlist server at /srv/playlistfs.*\$user* and a database server at /srv/jukefs.*\$user*.

Jukefs reads a set of *maps* describing the music data, builds an in-memory database, and provides lookup service to *jukebox*. The default map is /sys/lib/music/map. It consists of a hierarchical set of *objects*. Each object has a type, a value, zero or more attribute-value pairs and zero or more subobjects. An object consists of the type, followed by its contents between curly brackets. Attribute value pairs consist of a single line containing an attribute name, an equals sign, and a value. The value of an object is any text not containing curly brackets or equals signs. Here is an example:

```
category {
    composer = mahler
```

}

```
Gustav Mahler
(1860 - 1911)
work {
      path {classic/mahler}
      class = symphonic
      orchestra = rfo
      conductor = Waart,~Edo~de
      Symphony № 5 in c? (RFO, Vienna)
      performance{
             Radio Filharmonisch Orkest Holland
             Edo de Waart, conductor
             recorded: Musikverein, Vienna, May 6, 1996
      }
      command {number}
      track {
             Trauermarsch (In gemessenem Schritt. Streng. Wie ein Kondukt)
             time {13:55}
             file {034.pac}
      3
      track {
             Stürmisch bewegt, mit größter Vehemenz
             time {15:34}
             file {035.pac}
      3
      track {
             Scherzo (Kräftig, nicht zu schnell)
             time {18:54}
             file {036.pac}
      3
      track {
             Adagietto (Sehr Langsam)
             time {10:01}
             file {037.pac}
      3
      track {
             Rondo-Finale (Allegro)
             time {15:44}
             file {038.pac}
      }
}
```

This example shows a *category* object for the composer Gustav Mahler (the value consists of the two lines 'Gustav Mahler' and '(1860 — 1911)') with one subobject, a *work* object whose value is 'Symphony N° 5 in c? (RFO, Vienna)'. The work object contains six subobjects: one *performance* object and five *track* objects.

Category objects must contain exactly one attribute-value pair. The attribute names a subobject of the root under which this category object will be placed. Gustav Mahler, thus, will be placed in Root-composer. *Work, Recording, Part,* and *Track,* objects all describe named containers for subunits. A *Lyrics, Performance,* or *Soloists* object adds information to a *Work, Recording, Part,* or *Track,* object. It should only contain text. The same is true for a *Time* object; however, it should only be used adjacent to *File* objects and it should contain the running time of that file (this is for future use).

A *File* object specifies a file to be played. When the *Select* button is pressed, all file objects contained hierarchically in the selected object are added to the playlist.

There are a number of pseudo objects: *Command* may contain either *sort* or *number*. The *sort* command sorts the subobjects of the object it appears in by *key* or textual content. The *number* commands prepends numbers to the texts of its subobjects (e.g., for the parts in a symphony)

An Include object is replaced by the contents of the named file.

A Key object specifies a key for sorting subobjects.

Finally, a *Path* object specifies a path to be prepended to the files named in hierarchically contained *File* objects. The attribute-value value pairs arrange for entries to be made of the current object in a *Category* object named by the attribute directly under the root.

The interface to the browsing database is through a file system implemented by jukefs. The file system synthesises a directory per object. Each directory contains a set of files describing the object's attributes:

children

contains a new-line separated list of subobject names. For each name, x the directory /mnt/juke/x describes the subobject.

digest

contains a one-line summary of the object

files

is a new-line separated list of file objects contained in this object. Each line consists of object name and file name.

fulltext

is the fulltextual value of the object.

key contains the key by which objects are sorted

miniparentage

is a one-line summary of the objects and the path leading to it from the root. This is the line displayed in the playlist and bottom browse windows of games/jukebox.

parent

is the object reference to the parent of this object.

parentage

is a full description of the path leading to this object and the object itself. This is the string displayed in the top of the Browse and Playing windows of games/jukebox.

text is the text field of the object.

type is the type of the object

FILES

/sys/lib/music/map: Default map file /mnt/juke: Default mount point for the music database.

SOURCE

/sys/src/games/music

SEE ALSO

playlistfs(7).

map, mapdemo - draw maps on various projections

SYNOPSIS

map projection [option ...]

mapdemo

DESCRIPTION

Map prepares on the standard output a map suitable for display by any plotting filter described in *plot*(1). A menu of projections is produced in response to an unknown *projection*. *Mapdemo* is a short course in mapping.

The default data for *map* are world shorelines. Option -f accesses more detailed data classified by feature.

-f [feature ...]

Features are ranked 1 (default) to 4 from major to minor. Higher-numbered ranks include all lower-numbered ones. Features are

shore[1-4]	seacoasts, lakes, and islands; option $-f$ always shows shore1
ilake[1-2]	intermittent lakes
river[1-4]	rivers
iriver[1-3]	intermittent rivers
canal[1-3]	3=irrigation canals
glacier	
iceshelf[12]	
reef	
saltpan[12]	
country[1-3]	2=disputed boundaries, 3=indefinite boundaries
state	states and provinces (US and Canada only)

In other options coordinates are in degrees, with north latitude and west longitude counted as positive.

-1 S N E W

Set the southern and northern latitude and the eastern and western longitude limits. Missing arguments are filled out from the list -90, 90, -180, 180, or lesser limits suitable to the projection at hand.

 $-\mathbf{k} \ S \ N \ E \ W$

Set the scale as if for a map with limits -1 S N E W. Do not consider any -1 or -w option in setting scale.

–o lat lon rot

Orient the map in a nonstandard position. Imagine a transparent gridded sphere around the globe. Turn the overlay about the North Pole so that the Prime Meridian (longitude 0) of the overlay coincides with meridian *lon* on the globe. Then tilt the North Pole of the overlay along its Prime Meridian to latitude *lat* on the globe. Finally again turn the overlay about its 'North Pole' so that its Prime Meridian coincides with the previous position of meridian *rot*. Project the map in the standard form appropriate to the overlay, but presenting information from the underlying globe. Missing arguments are filled out from the list 90, 0, 0. In the absence of -0, the orientation is 90, 0, *m*, where *m* is the middle of the longitude range.

-w S N E W

Window the map by the specified latitudes and longitudes in the tilted, rotated coordinate system. Missing arguments are filled out from the list -90, 90, -180, 180. (It is wise to give an encompassing -1 option with -w. Otherwise for small windows computing time varies inversely with area!)

- -d n For speed, plot only every *n*th point.
- -r Reverse left and right (good for star charts and inside-out views).

-v Verso. Switch to a normally suppressed sheet of the map, such as the back side of the earth in orthographic projection.

- -s2 Superpose; outputs for a -s1 map (no closing) and a -s2 map (no opening) may be concatenated.
- -g dlat dlon res

Grid spacings are *dlat*, *dlon*. Zero spacing means no grid. Missing *dlat* is taken to be zero. Missing *dlon* is taken the same as *dlat*. Grid lines are drawn to a resolution of *res* (2° or less by default). In the absence of -g, grid spacing is 10°.

-p lat lon extent

Position the point *lat, lon* at the center of the plotting area. Scale the map so that the height (and width) of the nominal plotting area is *extent* times the size of one degree of latitude at the center. By default maps are scaled and positioned to fit within the plotting area. An *extent* overrides option -k.

-с *х у rot*

After all other positioning and scaling operations have been performed, rotate the image *rot* degrees counterclockwise about the center and move the center to position *x*, *y*, where the nominal plotting area is $-1 \le x \le 1$, $-1 \le y \le 1$. Missing arguments are taken to be 0. -x Allow the map to extend outside the nominal plotting area.

-m [file ...]

Use map data from named files. If no files are named, omit map data. Names that do not exist as pathnames are looked up in a standard directory, which contains, in addition to the data for -f,

world World Data Bank I (default) states US map from Census Bureau US map from Census Bureau

The environment variables MAP and MAPDIR change the default map and default directory.

-b [lat0 lon0 lat1 lon1...]

Suppress the drawing of the normal boundary (defined by options -1 and -w). Coordinates, if present, define the vertices of a polygon to which the map is clipped. If only two vertices are given, they are taken to be the diagonal of a rectangle. To draw the polygon, give its vertices as a -u track.

The *files* contain lists of points, given as latitude-longitude pairs in degrees. If the first file is named –, the standard input is taken instead. The points of each list are plotted as connected 'tracks'.

Points in a track file may be followed by label strings. A label breaks the track. A label may be prefixed by ", :, or ! and is terminated by a newline. An unprefixed string or a string prefixed with " is displayed at the designated point. The first word of a : or ! string names a special symbol (see option -y). An optional numerical second word is a scale factor for the size of the symbol, 1 by default. A : symbol is aligned with its top to the north; a ! symbol is aligned vertically on the page.

Same as -t, except the tracks are unbroken lines. (-t tracks appear as dot-dashed lines if the plotting filter supports them.)

-y file

The *file* contains *plot*(6)-style data for : or ! labels in -t or -u files. Each symbol is defined by a comment : *name* then a sequence of m and v commands. Coordinates (0,0) fall on the plotting point. Default scaling is as if the nominal plotting range were ra -1 -1 1 1; ra commands in *file* change the scaling.

Projections

Equatorial projections centered on the Prime Meridian (longitude 0). Parallels are straight horizontal lines.

⁻s1

⁻t file ...

[–]u file ...

mercator	equally spaced straight meridians, conformal, straight compass courses
sinusoidal	equally spaced parallels, equal-area, same as bonne 0.
cylequalarea <i>lat0</i>	equally spaced straight meridians, equal-area, true scale on <i>lat0</i>
cylindrical	central projection on tangent cylinder
rectangular lat0	equally spaced parallels, equally spaced straight meridians, true scale on <i>lat0</i>
gall lat0	parallels spaced stereographically on prime meridian, equally spaced straight meridians, true scale on <i>lat0</i>
mollweide	(homalographic) equal-area, hemisphere is a circle
	gilbert() sphere conformally mapped on hemisphere and viewed orthographically
gilbert	globe mapped conformally on hemisphere, viewed orthographically

Azimuthal projections centered on the North Pole. Parallels are concentric circles. Meridians are equally spaced radial lines.

azequidistant azequalarea	equally spaced parallels, true distances from pole equal-area
gnomonic	central projection on tangent plane, straight great circles
perspective dist	viewed along earth's axis dist earth radii from center of earth
orthographic	viewed from infinity
stereographic	conformal, projected from opposite pole
laue	<i>radius</i> = tan(2× <i>colatitude</i>), used in X-ray crystallography
fisheye <i>n</i>	stereographic seen from just inside medium with refractive index <i>n</i>
newyorker r	$radius = \log(colatitude/r)$: New Yorker map from viewing pedestal of radius r degrees

Polar conic projections symmetric about the Prime Meridian. Parallels are segments of concentric circles. Except in the Bonne projection, meridians are equally spaced radial lines orthogonal to the parallels.

conic <i>lat0</i>	central projection on cone tangent at <i>lat0</i>
	at0 [at1

simpleconic lat0 lat1 equally spaced parallels, true scale on *lat0* and *lat1* lambert *lat0 lat1* conformal, true scale on *lat0* and *lat1* albers *lat0 lat1* equal-area, true scale on *lat0* and *lat1*

albers lato lati	equal-area, true scale on <i>lato</i> and <i>lati</i>
bonne <i>lat0</i>	equally spaced parallels, equal-area, parallel <i>lat0</i> developed from tangent
	cone

Projections with bilateral symmetry about the Prime Meridian and the equator.

polyconic	parallels developed from tangent cones, equally spaced along Prime Meridian
aitoff lagrange	equal-area projection of globe onto 2-to-1 ellipse, based on <i>azequalarea</i> conformal, maps whole sphere into a circle
bicentric lon0	points plotted at true azimuth from two centers on the equator at longi- tudes $\pm lon0$, great circles are straight lines (a stretched <i>gnomonic</i>)
elliptic <i>lon0</i>	points plotted at true distance from two centers on the equator at longi- tudes <i>±lon0</i>
globular	hemisphere is circle, circular arc meridians equally spaced on equator, cir- cular arc parallels equally spaced on 0- and 90-degree meridians
vandergrinten	sphere is circle, meridians as in <i>globular</i> , circular arc parallels resemble <i>mercator</i>

Doubly periodic conformal projections.

guyou square	W and E hemispheres are square world is square with Poles at diagonally opposite corners
tetra	map on tetrahedron with edge tangent to Prime Meridian at S Pole, unfolded into equilateral triangle
hex	world is hexagon centered on N Pole, N and S hemispheres are equilateral triangles

Miscellaneous projections.

harrison *dist angle* oblique perspective from above the North Pole, *dist* earth radii from center of earth, looking along the Date Line *angle* degrees off vertical

trapezoidal lat0 lat1

equally spaced parallels, straight meridians equally spaced along parallels, true scale at *lat0* and *lat1* on Prime Meridian

lune(lat,angle) conformal, polar cap above latitude *lat* maps to convex lune with given *angle* at 90° E and 90° W

Retroazimuthal projections. At every point the angle between vertical and a straight line to 'Mecca', latitude *lat0* on the prime meridian, is the true bearing of Mecca.

mecca lat0equally spaced vertical meridianshoming lat0distances to Mecca are true

Maps based on the spheroid. Of geodetic quality, these projections do not make sense for tilted orientations. For descriptions, see corresponding maps above.

sp_mercator
sp_albers lat0 lat1

EXAMPLES

map perspective 1.025 -o 40.75 74

A view looking down on New York from 100 miles (0.025 of the 4000-mile earth radius) up. The job can be done faster by limiting the map so as not to 'plot' the invisible part of the world: map perspective 1.025 - 0.40.7574 - 1.206030100. A circular border can be forced by adding option -w77.33. (Latitude 77.33° falls just inside a polar cap of opening angle $\arccos(1/1.025) = 12.6804^\circ$.)

map mercator -o 49.25 -106 180

An 'equatorial' map of the earth centered on New York. The pole of the map is placed 90° away (40.75+49.25=90) on the other side of the earth. A 180° twist around the pole of the map arranges that the 'Prime Meridian' of the map runs from the pole of the map over the North Pole to New York instead of down the back side of the earth. The same effect can be had from map mercator -0 130.75 74

map albers 28 45 -1 20 50 60 130 -m states A customary curved-latitude map of the United States.

map harrison 2 30 -1 -90 90 120 240 -0 90 0 0

A fan view covering 60° on either side of the Date Line, as seen from one earth radius above the North Pole gazing at the earth's limb, which is 30° off vertical. The -0 option overrides the default -0 90 0 180, which would rotate the scene to behind the observer.

FILES

/lib/map/[1-4]?? World Data Bank II, for -f /lib/map/* maps for -m /lib/map/*.x map indexes /bin/aux/mapd Map driver program

SOURCE

/sys/src/cmd/map

SEE ALSO

map(6), *plot*(1)

DIAGNOSTICS

'Map seems to be empty'—a coarse survey found zero extent within the -1 and -w bounds; for maps of limited extent the grid resolution, *res*, or the limits may have to be refined.

BUGS

Windows (option -w) cannot cross the Date Line. No borders appear along edges arising from visibility limits. Segments that cross a border are dropped, not clipped. Excessively large scale or -d setting may cause long line segments to be dropped. *Map* tries to draw grid lines dotted and -t tracks dot-dashed. As very few plotting filters properly support curved textured lines, these lines are likely to appear solid. The west-longitude-positive convention betrays Yankee chauvinism. *Gilbert* should be a map from sphere to sphere, independent of the mapping from sphere to plane.

playlistfs – playlist file system

SYNOPSIS

games/playlistfs[-s postname][-m mountpoint][-a]

DESCRIPTION

Playlistfs implements an audio player which plays files from a built-in play list. The player is controlled through three files, usually mounted at /mnt. The files are /playctl for controlling play: start, stop, pause, skip, etc.; /playvol for controlling the playout volume; and /playlist for controlling the play list itself.

All three files can be written to control the player and read to obtain player status information.

When read, the files report the current status of the player, volume and playlist, respectively. End of file is indicated by a read that returns zero bytes, as usual. However, in all three files, subsequent read operations will block until the status of the file changes and then report the changed state. When the changed state has been read, another end-of-file indication is given, after which another read can be issued to wait for state changes.

The /playctl file returns strings of the form '*cmd n*' where *cmd* is one of *stop*, *pause*, or *play* and *n* is an index (or offset) into the playlist; indices start at zero.

The commands that can be written to /playctl take the same form; however, the index is an optional argument. If the index is omitted, the current value is used. The commands are *play*, *stop*, *pause*, *resume*, and *skip*. *Play* starts playing at the index. *Stop* stops playing. If an index is given, the current index is set to it and can be used in future commands. *Pause* and *Resume* interrupt and continue play, respectively. The index argument is always ignored and the whole command is ignored if the state in which they occur does not make sense. *Skip* adds the argument to the current index (adds one if no argument is given) and starts play at that index, stopping current play, if necessary.

Reads of /playvol return strings of the form 'volume *n*', where *n* is a number or, if there is more than one channel, a quoted set of numbers, between 0 (minimum) and 100 (maximum). Writes to /playvol take the same form.

The /playlist file is an append-only file which accepts lines with one or two fields per line (parsed using tokenize). The first, compulsory, field is a file name, the optional second argument may contain a reference to, or a description of, the item, for instance in a graphical user interface. /playlist is append-only, individual lines cannot be removed. However, the playlist can be cleared by opening the file with the OTRUNC flag. A process that has /playlist open while the file is truncated will receive an error on the next read with errstr set to reading past eof. When this error occurs, clients can seek to the beginning of the file and reread its contents.

After starting up, Playlistfs puts itself in the background. When called with the -s flag, it posts a mountable file descriptor in /srv/playlist.*postname*. The -m flag can be used to specify a mount point other than /mnt.

Playlistfs uses the *audio*(1) decoders by running *play*(1) for format detection and conversion to pcm.

FILES

/srv/playlistfs.user: default playlistfs mountable file descriptor used by juke(7). /mnt/playctl: Control file /mnt/playlist: Playlist file /mnt/playvol: Volume control file

SOURCE

/sys/src/games/music/playlistfs

SEE ALSO

play(1), *audio*(1), *juke*(7).

scat - sky catalogue and Digitized Sky Survey

SYNOPSIS

scat

DESCRIPTION

Scat looks up items in catalogues of objects outside the solar system and implements databaselike manipulations on sets of such objects. It also provides an interface to *astro*(7) to plot the locations of solar system objects. Finally, it displays images from the Space Telescope Science Institute's Digitized Sky Survey, keyed to the catalogues.

Items are read, one per line, from the standard input and looked up in the catalogs. Input is case-insensitive. The result of the lookup becomes the set of objects available to the database commands. After each lookup or command, if more than two objects are in the set, *scat* prints how many objects are in the set; otherwise it prints the objects' descriptions or cross-index listings (suitable for input to *scat*). An item is in one of the following formats:

ngc1234

Number 1234 in the New General Catalogue of Nonstellar Objects, NGC2000.0. The output identifies the type (Gx=galaxy, Pl=planetary nebula, OC=open cluster, Gb=globular cluster, Nb=bright nebula, C+N=cluster associated with nebulosity, Ast=asterism, Kt=knot or nebulous region in a galaxy, ***=triple star, D*=double star, ?=uncertain, -=nonexistent, PD=plate defect, and (blank)=unverified or unknown), its position in 2000.0 coordinates, its size in minutes of arc, a brief description, and popular names.

ic1234

Like NGC references, but from the Index Catalog.

sao12345

Number 12345 in the Smithsonian Astrophysical Star Catalogue. Output identifies the visual and photographic magnitudes, 2000.0 coordinates, proper motion, spectral type, multiplicity and variability class, and HD number.

m4 Catalog number 4 in Messier's catalog. The output is the NGC number.

abell1701

Catalog number 1701 in the Abell and Zwicky catalog of clusters of galaxies. Output identifies the magnitude of the tenth brightest member of the cluster, radius of the cluster in degrees, its distance in megaparsecs, 2000.0 coordinates, galactic latitude and longitude, magnitude range of the cluster (the 'distance group'), number of members (the 'richness group'), population per square degree, and popular names.

planetarynebula

The set of NGC objects of the specified type. The type may be a compact NGC code or a full name, as above, with no blank.

"α umi"

Names are provided in double quotes. Known names are the Greek letter designations, proper names such as Betelgeuse, bright variable stars, and some proper names of stars, NGC objects, and Abell clusters. Greek letters may be spelled out, e.g. alpha. Constellation names must be the three-letter abbreviations. The output is the SAO number. For non-Greek names, catalog numbers and names are listed for all objects with names for which the given name is a prefix.

12h34m -16

Coordinates in the sky are translated to the nearest 'patch', approximately one square degree of sky. The output is the coordinates identifying the patch, the constellations touching the patch, and the Abell, NGC, and SAO objects in the patch. The program prints sky positions in several formats corresponding to different precisions; any output format is understood as input.

- umi All the patches in the named constellation.
- mars The planets are identified by their names. The names shadow and comet refer to the earth's penumbra at lunar distance and the comet installed in the current *astro*(7). The

output is the planet's name, right ascension and declination, azimuth and altitude, and phase for the moon and sun, as shown by astro. The positions are current at the start of *scat* 's execution; see the astro command in the next section for more information.

The commands are:

add item Add the named item to the set.

keep class ...

Flatten the set and cull it, keeping only the specified classes. The classes may be specific NGC types, all stars (sao), all NGC objects (ngc), all M objects (m), all Abell clusters (abell), or a specified brightness range. Brightness ranges are specified by a leading > or < followed by a magnitude. Remember that brighter objects have lesser magnitudes.

drop class ...

Complement to keep.

flat Some items such as patches represents sets of items. *Flat* flattens the set so *scat* holds all the information available for the objects in the set.

print Print the contents of the set. If the information seems meager, try flattening the set.

expand *n*

Flatten the set, expand the area of the sky covered by the set to be n degrees wider, and collect all the objects in that area. If n is zero, *expand* collects all objects in the patches that cover the current set.

astro option

Run *astro*(7) with the specified *options* (to which will be appended -p), to discover the positions of the planets. Astro's -d and -l options can be used to set the time and place; by default, it's right now at the coordinates in /lib/sky/here. Running astro does not change the positions of planets already in the display set, so astro may be run multiple times, executing e.g. add mars each time, to plot a series of planetary positions.

plot option

Expand and plot the set in a new window on the screen. Symbols for NGC objects are as in Sky Atlas 2000.0, except that open clusters are shown as stippled disks rather than circles. Abell clusters are plotted as a triangle of ellipses. The planets are drawn as disks of representative color with the first letter of the name in the disk (lower case for inferior planets; upper case for superior); the sun, moon, and earth's shadow are unlabeled disks. Objects larger than a few pixels are plotted to scale; however, *scat* does not have the information necessary to show the correct orientation for galaxies.

The option nogrid suppresses the lines of declination and right ascension. By default, *scat* labels NGC objects, Abell clusters, and bright stars; option nolabel suppresses these while alllabel labels stars with their SAO number as well. The default size is 512×512 ; options dx *n* and dy *n* set the *x* and *y* extent. The option zenithup orients the map so it appears as it would in the sky at the time and location used by the astro command (*q.v.*).

The output is designed to look best on an LCD display. CRTs have trouble with the thin, grey lines and dim stars. The option nogrey uses white instead of grey for these details, improving visibility at the cost of legibility when plotting on CRTs.

plate [[ra dec] rasize [decsize]]

Display the section of the Digitized Sky Survey (plate scale approximately 1.7 arcseconds per pixel) centered on the given right ascension and declination or, if no position is specified, the current set of objects. The maximum area that will be displayed is one degree on a side. The horizontal and vertical sizes may be specified in the usual notation for angles. If the second size is omitted, a square region is displayed. If no size is specified, the size is sufficient to display the centers of all the objects in the current set. If a single object is in the set, the 500×500 pixel block from the survey containing the center of the object is displayed. The survey is stored in the CD-ROM juke box; run 9fs juke before running *scat*.

gamma value

Set the gamma for converting plates to images. Default is -1.0. Negative values display white stars, positive black. The images look best on displays with depth 8 or greater. *Scat* does not change the hardware color map, which should be set externally to a grey scale; try the command getmap gamma (see *colors*(1)) on an 8-bit color-mapped

display.

EXAMPLES

Plot the Messier objects and naked-eye stars in Orion.

ori keep m <6 plot nogrid Draw a finder chart for Uranus: uranus expand 5 plot Show a partial lunar eclipse: astro -d 2000 07 16 12 45 moon add shadow expand 2 plot Draw a map of the Pleiades. "alcyone" expand 1 plot Show a pretty galaxy. ngc1300 plate 10'

FILES

/lib/sky/*.scat

SOURCE

/sys/src/cmd/scat

SEE ALSO

astro(7)

/lib/sky/constelnames the three-letter abbreviations of the constellation names.

The data was provided by the Astronomical Data Center at the NASA Goddard Space Flight Center, except for NGC2000.0, which is Copyright © 1988, Sky Publishing Corporation, used (but not distributed) by permission. The Digitized Sky Survey, 102 CD-ROMs, is not distributed with the system.

intro - introduction to system administration

DESCRIPTION

This manual section describes commands for system administration as well as various utility programs necessary for the system but not routinely invoked by a user.

6in4, ayiya - configure and run automatic or manual tunnel of IPv6 through IPv4

SYNOPSIS

ip/6in4 [-ag][-m mtu][-x netmtpt][-o outnetmtpt] [-i local4][local6[/mask][remote4[remote6]]]

ip/ayiya[-g][-m mtu][-x netmtpt][-k secret]local6[/mask] remote4 remote6

DESCRIPTION

6in4 sets up and maintains a 6to4 tunnel of IPv6 traffic through an IPv4 connection. *Ayiya* is similar, but uses the UDP based Anything In Anything protocol to tunnel IPv6 traffic.

Local6 and *mask* define the IPv6 address and subnet of the near end of the tunnel (*mask* defaults to /128 for a single-host tunnel). If *local6* is missing or –, it defaults to

2002: *aabb*: *ccdd*::1/48

where *aa*, *bb*, *cc* and *dd* are the hexadecimal equivalents of the bytes *a*.*b*.*c*.*d* in this host's primary IPv4 address.

Remote4 is the IPv4 address of the far end of the tunnel (must be given explicitly for a configured tunnel, or defaults to the anycast address 192.88.99.1 for *6to4*).

Remote6 is the IPv6 address of the far end of the tunnel (used as the point-to-point destination for routing, and defaults to a link-local address constructed from *remote4*).

The program forks a pair of background processes to copy packets to and from the tunnel.

Options are:

- -a for *6in4*, permit any remote IPv4 address as the far end of a tunnel. This is likely to be useful for the server side of a tunnel.
- -i for 6in4, define what is the local IPv4 address, otherwise it takes the first non-loopback address of the outside IP stack.
- -g use the tunnel as the default route for global IPv6 addresses
- -m *mtu* specifies the outside MTU in bytes from which the inside tunnel MTU is derived. Deaults to 1500 8 (Ethernet PPPoE).
- -x use the network mounted at *netmtpt* instead of /net for binding the tunnel interface and sending/receiving IPv4 packets.
- -o for *6in4*, use *outnetmtpt* for the IPv4 packets but bind the IPv6 interface on /net or *netmtpt* when specified by a previous -x option.
- -k for *ayiya*, use the shared secret key *secret* to authenticate messages on the tunnel.

EXAMPLES

If your primary IPv4 address is public, you can start a 6to4 tunnel simply with

ip/6in4 -g

Similarly, you can start a server for 6to4 tunnels with

ip/6in4 -ag

If you use a tunnel broker at address 5.6.7.8, configured to give you a /64 subnet with address 2001:1122:3344:5566::, you can start the tunnel with

ip/6in4 -g 2001:1122:3344:5566::/64 5.6.7.8

FILES

/net/ipmux access to IPv6-in-IPv4 packets
/net/ipifc packet interface to IPv6 network

SEE ALSO

bridge(3), ipmux in ip(3), linklocal in ipconfig(8)
/lib/rfc/rfc3056
/lib/rfc/rfc3068
http://tools.ietf.org/id/draft-massar-v6ops-ayiya-02.txt

BUGS

Needs a kernel with an *ipmux* driver.

The tunnel client filters addresses fairly conservatively in both directions. However it's not watertight, and may be flakey in other ways so don't put too much trust in it.

9bootfat, 9bootiso, 9boothyb, 9bootpxe, bootia32.efi, bootx64.efi, efiboot.fat - PC bootloader for FAT, ISO and PXE network booting

SYNOPSIS

Started by PC BIOS/EFI or chainloaded by partition bootsector

DESCRIPTION

9boot is the bootloader used on PCs to start the Plan 9 kernel. Its task is to read and parse the *plan9.ini*(8) configuration file, gather some basic system information like the amount of usable system memory, do some basic system initialization and load the kernel from the boot media into memory.

After reading the configuration, the loader will automatically attempt to boot the kernel that was specified by the bootfile= parameter. If there is no such parameter, a key gets pressed on the keyboard or the kernel file was not found then the loader enters the interactive boot console.

The syntax of the boot console is the same as in the *plan9.ini*(8) file with key=value pairs setting boot parameters. In addition a few command words are recognized that are intended for interactive use:

clear[prefix]

can be used to remove parameters from the configuration. If a *prefix* is specified, the first parameter that matches the prefix is removed. If the *prefix* argument is omitted, the whole configuration will be reset.

- show displays the current configuration in memory.
- wait will return to the console prompt after processing the configuration file preventing automatic boot.
- boot will end the console and attempt booting the kernel.

There are many ways to boot a PC so *9boot* was split into a number of distinct programs, one for each boot method.

FAT BOOTING

When booting Plan 9 from a harddisk or USB pen drive, a FAT16/32 partition (*9fat*) is used to store the kernel and *plan9.ini*(8) configuration. Due to size limitations, instead of loading the kernel directly, the bootsector (*pbs*) of the FAT partition loads a 2nd stage bootloader (*9bootfat*) from the root directory of the filesystem.

CD-ROM BOOTING

Booting from CD-ROM requires only the *9bootiso* bootloader to be included in the ISO-9660 image under /386/9bootiso, set as a non-emulation bootblock (see -B in *mk9660*(8)). Boot parameters are read from /cfg/plan9.ini.

ISO HYBRID BOOTING

With the *9boothyb* loader, an ISO image can be made into a bootable disk by creating a MBR and appending a bootable DOS partition containing *9boothyb* renamed to *9bootfat*. The loader will read the ISO filesystem as if it were stored on a CD-ROM drive.

NETWORK BOOTING

With a PXE capable BIOS and network card one can download *9bootpxe* and boot the kernel from a TFTP server (see *dhcpd*(8) and *ndb*(6) for details). Once started, *9bootpxe* will read the file /cfg/pxe/\$ether or, if this file is not present, /cfg/pxe/default from the tftp server, where \$ether is the MAC address of the client's network card in lower case hex, and uses this as its *plan9.ini*(8) file.

EFI BOOTING

EFI firmware looks for the files *bootia32.efi* (for 386) or *bootx64.efi* (for amd64) in the boot media and executes them. For local disk media, these files are located in the directory /efi/boot of the FAT formatted boot partition. For CD-ROM media, the boot partition is provided as a embedded FAT filesystem image *efiboot.fat* (see -E in *mk9660*(8)). In the network boot case, the

bootia32.efi or *bootx64.efi* files are used as the BSP program instead of *9bootpxe*. Once started, the boot media (PXE, ISO, FAT) is discovered and *plan9.ini*(8) configuration is read from it in the same way as with the BIOS-based *9boot** loaders. If the EFI loader was executed from a FAT partition, it will first search for *plan9.ini*(8) in the same FAT filesystem that it was loaded from, and if not found, will search for *plan9.ini*(8) in any other partition in an implementation-defined order. The kernel is always loaded from the same partition that *plan9.ini*(8) is read from.

FILES

/386/pbs /386/9bootfat /386/9bootiso /386/9boothyb /386/9bootpxe /386/bootia32.efi /386/bootx64.efi /386/efiboot.fat

SOURCE

/sys/src/boot/pc /sys/src/boot/efi

SEE ALSO

plan9.ini(8), mk9660(8), dhcpd(8), ndb(6) https://uefi.org

HISTORY

9boot first appeared in 9front (April, 2011). EFI support first appeared in 9front (Oct, 2014).

9pcon - 9P to text translator

SYNOPSIS

aux/9pcon[-cn][-m msize] service

DESCRIPTION

9pcon provides a textual interface to *service*, a conventional 9P server. By default, *9pcon* interprets *service* as a file to be opened. The -c flag causes *9pcon* to interpret *service* as a command to run which will carry out a (binary) 9P conversation over file descriptors 0 and 1. The -n flag causes *9pcon* to interpret *service* as a network address to dial.

Once the connection is established, *9pcon* prints R-messages as they arrive from the server, and sends T-messages as they are typed on standard input. There is no prompt. Lines beginning with *#* are ignored. The syntax for T-messages is one of:

Tversion msize version Tauth afid uname aname Tattach fid afid uname aname Twalk fid newfid wname... Topen fid mode Tcreate fid name perm mode Tread fid offset count Twrite fid offset data Tclunk fid Tremove fid Tstat fid Twstat fid name uid gid mode mtime length Tflush oldtag

See *intro*(5) for a description of the fields in each message. For the most part, the syntax mirrors the description of the messages in section 5. The exceptions are that the tags on the T-messages are added automatically; Twalk's *nwname* count is inferred from the number of *wnames* given; and Twstat's *dir* is in expanded form rather than being an opaque byte sequence. Note that since commands are parsed with tokenize (see *getfields*(2)), it is easy to pass empty strings for absent *name*, *uid*, and *gid* fields. To ease specifying default integer fields, the Twstat message recognizes ~0 in the *mode*, *mtime*, and *length* arguments. For example,

Twstat 101 '' '' sys ~0 ~0 ~0

sends a *wstat* message that attempts to change the group id associated with fid 101.

SOURCE

/sys/src/cmd/aux/9pcon.c

SEE ALSO

intro(5)

BUGS

There should be a flag to wait for responses, to facilitate scripting.

aan, aanuke - always available network

SYNOPSIS

```
aan -c [ -d ] [ -m maxto ] dialstring
aan [ -d ] [ -m maxto ] netdir
aanuke
```

DESCRIPTION

Aan tunnels traffic between a client and a server through a persistent network connection. If the connection breaks (voluntarily or due to networking problems), the *aan* client re-establishes the connection by redialing the server.

Aan uses a unique protocol to make sure no data is ever lost even when the connection breaks. After a reconnection, *aan* retransmits all unacknowledged data between client and server.

A connection can be broken voluntarily (e.g. by roaming over IP networks), or a connection can break when the IP service is unreliable. In either case, *aan* re-establishes the client's connection automatically.

When the server part has not heard from the client in *maxto* seconds, the server part of *aan* exits. The default *maxto* is one day. The client side (option -c) calls the server by its *dialstring*, while the server side listens for connections in the already-announced network directory *netdir*.

Aan is usually run automatically through the -p option of *import*(4) and *cpu*(1).

Aanuke prints commands that will cause all processes called *aan* that are owned by the current user and do not have an active tcp connection to be terminated. Use the send command of rio(1), or pipe the output of *kill* into rc(1) to execute the commands.

EXAMPLES

Assume the server part of *aan* is encapsulated in *exportfs* on the machine sob and started through aux/listen as follows:

```
netdir='{echo $3 | sed 's;/[0-9]+$;!*!0;'}
exec exportfs -a -A $netdir
```

Then machine astro6's name space can be imported through *aan* using this command:

```
import -p astro6 / /mnt/term
```

Kill idle instances of *aan* left behind by a terminal that has been powered off:

aanuke | rc

FILES

/sys/log/aan Log file

SOURCE

/sys/src/cmd/aan.c
/rc/bin/aanuke

SEE ALSO

import(4), exportfs(4), cpu(1)

HISTORY

Aanuke first appeared in 9front (April, 2014).

acpi - Advanced Configuration and Power Interface

SYNOPSIS

(in plan9.ini) *acpi=

aux/acpi[-m mountpoint][-s service]

DESCRIPTION

Aux/acpi presents at mountpoint (default /mnt/acpi) an interface to the ACPI. If a service is specified, the interface will be posted at /srv/service as well.

The directory contains the following files.

battery

Contains one line for each battery in the system. Each line lists 12 fields: the percent charge remaining, power unit used (mW or mA), remaining capacity, last full charge capacity, design capacity, warning and low capacity values, mV separator, present voltage, design voltage, approximate time of charge left as hh:mm:ss, and the status (a string, one of unknown, critical, discharging or charging).

cputemp

Each line provides a current temperature reading of a specific CPU.

ctl The ctl file currently does not provide any functionality.

SOURCE

/sys/src/cmd/aux/acpi.c

BUGS

ACPI itself.

HISTORY

Acpi first appeared in 9front (October, 2016).

aliasmail - expand system wide mail aliases

SYNOPSIS

upas/aliasmail arg ...

DESCRIPTION

Aliasmail expands mail aliases, its arguments, according to alias files. *Aliasmail* is normally invoked by a rule in the upas rewrite file, *rewrite*(6).

If a line of an alias file begins with #include, the line is replaced by the contents of the file whose name follows. Other lines, beginning with # are ignored as comment.

Otherwise, lines begin with a name. The rest of a name line gives the expansion. The expansion may contain multiple addresses and may be continued to another line by appending a backslash. Items are separated by white space.

The alias files are searched in the order they are listed, one per line, in /mail/lib/namefiles. If the name is not found, the expansion is taken to be local! *name*. Under the -f option, alias files listed in /mail/lib/fromfiles are consulted instead, and the domain part only of the expansion is printed.

FILES

/mail/lib/namefiles names of system alias files

SOURCE

/sys/src/cmd/upas/alias

SEE ALSO

faces(1), filter(1), mail(1), marshal(1), mlmgr(1), nedmail(1), qer(8), rewrite(6), send(8), smtp(8), upasfs(4)

apm - Advanced Power Management 1.2 BIOS interface

SYNOPSIS

(in plan9.ini) apm0=

bind -a '#P' /dev

aux/apm [-d device] [-m mountpoint] [-s service]

DESCRIPTION

Aux/apm presents at mountpoint (default /mnt/apm) an interface to the APM 1.2 BIOS (see apm(3)) device (the default is to try /dev/apm, followed by #P/apm). If a service is specified, the interface will be posted at /srv/service as well.

The directory contains the following files.

battery

Contains one line for each battery in the system. Each line lists three fields: the status (a string, one of unknown, high, low, critical, or charging), the percent charge remaining, and an estimate of the amount of time left in seconds. If either or both of the last two are unknown, the corresponding field will be zero.

ctl The ctl file is used to set power management modes for various parts of the system. Control messages are of the form "*device verb*," where *device* is one of system, display, storage, lpt, eia, network, and pcmcia, and *verb is one of* enable, disable, standby, off and on. Enable and disable control whether power management is active for the device, while standby puts the device into standby mode and on brings it back to full power.

event

Reads from this file will block until an APM event has occurred. A large enough read is guaranteed to return an integral number of textual event descriptions, one per line.

SOURCE

/sys/src/cmd/aux/apm.c
/acme/bin/Battery

BUGS

The verbs suspend and off should be supported but doing so requires nontrivial help from the kernel.

SEE ALSO

acpi(8)

atazz - ATA target control

SYNOPSIS

atazz[-r][*sddev*] atazz –c *cmd*

DESCRIPTION

Atazz is an interactive program for exercising raw ATA devices. Its intended purpose is to support odd and administrative commands without requiring this functionality be implemented by each device driver. It reads commands from standard input and applies them to an ATA target. Communication is in SATA FIS format. Non-ATA devices accessed through the sd(3) interface will not work; ATAPI devices will respond to the commands in the ACS-2 packet feature set. If the -c option is given, the name of the given numeric ATA command is printed. *sddev* is given on the command line, an open (see below) is immediately applied to the target. On completion of a command, any errors are printed followed by the prompt az> . The response FIS may be printed with the command rfis. Some commands like identify device print processed output by default. Redirecting the output to a file will give the raw output as will the -r flag. In addition the following commands are implemented internally

< > <> file	Redirect output, input or both to or from a file. If <i>file</i> is missing, then the redi- rection is closed.
close	Close the currently open device.
dev	Print device path and basic information.
issuetr[<i>comm</i>	<i>and</i>] Toggle command issue tracing. With no arguments, issuetr toggles tracing for all commands. Commands may be specified by number.
open <i>dev</i>	Open the named device.
probe	Print a list of available device paths, size, sector size and WWNs. The first col- umn is a suitable argument for open.
rfis	Print the returned FIS, if any.

For all commands, it is possible to manipulate the sata registers directly by specifying the register name and an 8-bit value. The registers are

type	FIS type
flags	FIS flags
cmd	command register
feat	or features
lba0	or sector
lba8	or cyl0
lba16	or cyl8
lba24	or dh or byte8
lba32	
lba40	
feat8	
sc	sector count
sc8	
r	reserved FIS register

In addition, commands that take an LBA and a number of sectors may be given those arguments directly, for example to read 1 sector starting at Iba 100,

az> read dma ext 100 1

Subcommands are spelled out as in ACS-2. For example, to set the transfer mode to UDMA 6, enable the write cache and to enable and report smart status, one would

az> set features set transfer mode udma 6 az> set features enable write cache az> smart enable operations az> smart return status normal

SCT pseudo-protocol commands are also supported.

az> sct error recovery time set read timer = 5 az> sct error recovery time return read timer 500ms

FILES

/dev/sdXX/raw

SOURCE

/sys/src/cmd/atazz

SEE ALSO

scuzz(8), sd(3), smart(8), T13/2015 ACS-2 published online at http://www.t13.org.

BUGS

Subcommand help doesn't work. ACS-2 commands are tortuously verbose.

changeuser, convkeys, printnetkey, status, enable, disable, authsrv, guard.srv, debug, wrkey, login, newns, none, as - maintain or query authentication databases

SYNOPSIS

auth/changeuser [-np] user

auth/convkeys [-pa] keyfile

auth/printnetkey user

auth/status user

auth/enable user

auth/disable user

auth/authsrv[-N]

auth/guard.srv

auth/debug

auth/wrkey

auth/login[-a authdom] user

auth/newns [-ad] [-n namespace] command arg ...

auth/none [-d] [-n namespace] command arg ...

auth/as [-d][-n namespace] user command arg ...

DESCRIPTION

These administrative commands run only on the authentication server. *Changeuser* manipulates an authentication database file system served by *keyfs*(4) and used by file servers. There are two authentication databases, one holding information about Plan 9 accounts and one holding SecureNet keys. A *user* need not be installed in both databases but must be installed in the Plan 9 database to connect to a Plan 9 service.

Changeuser installs or changes *user* in an authentication database. It does not install a user on a Plan 9 file server; see $f_{S}(8)$ for that.

Option -p installs *user* in the Plan 9 database. *Changeuser* asks twice for a password for the new *user*. If the responses do not match or the password is too easy to guess the *user* is not installed. *Changeuser* also asks for an APOP secret. This secret is used in the APOP (RFC1939), CRAM (RFC2195), and Microsoft challenge/response protocols used for POP3, IMAP, and VPN access.

Option -n installs *user* in the SecureNet database and prints out a key for the SecureNet box. The key is chosen by *changeuser*.

If neither option -p or option -n is given, *changeuser* installs the *user* in the Plan 9 database.

Changeuser prompts for biographical information such as email address, user name, sponsor and department number and appends it to the file /adm/netkeys.who or /adm/keys.who.

Convkeys re-encrypts the key file *keyfile*. Re-encryption is performed in place. Without the -p option *convkeys* uses the key stored in NVRAM to decrypt the file, and encrypts it using the new key. By default, *convkeys* prompts twice for the new password. The -p forces *convkeys* to also prompt for the old password. The -a option converts the file into AES format. The format of *keyfile* is described in *keyfs*(4).

Printnetkey displays the network key as it should be entered into the hand-held Securenet box.

Status is a shell script that prints out everything known about a user and the user's key status.

Enable/disable are shell scripts that enable/disable both the Plan 9 and Netkey keys for individual users.

Authsrv is the program, run only on the authentication server, that handles ticket requests on TCP port 567. It is started by an incoming call to the server requesting a conversation ticket; its standard input and output are the network connection. Authsrv executes the authentication server's end of the appropriate protocol as described in authsrv(6). The -N flag disables legacy

bruteforceable DES-encrypted tickes as used by the p9sk1 protocol, forcing the use of new dp9ik password authenticated key exchange.

Guard.srv is similar. It is called whenever a foreign (e.g. Unix) system wants to do a SecureNet challenge/response authentication.

Anywhere commands

The remaining commands need not be run on an authentication server.

Debug attempts to authenticate using each dp9ik and p9sk1 key found in *factotum* and prints progress reports.

Wrkey prompts for a machine key, host owner, and host domain and stores them in local non-volatile RAM.

Login allows a user to change his authenticated id to user. Login sets up a new namespace from /lib/namespace, starts a *factotum*(4) under the new id and *execs* rc(1) under the new id.

Newns sets up a new namespace from *namespace* (default /lib/namespace) and *execs* its arguments. If there are no arguments, it *execs* /bin/rc. Under -a, *newns* adds to the current namespace instead of constructing a new one. The -d option enables debugging output.

None sets up a new namespace from *namespace* (default /lib/namespace) as the user *none* and *execs* its arguments under the new id. If there are no arguments, it *execs* /bin/rc. It's an easy way to run a command as *none*.

As executes *command* as *user*. *Command* is a single argument to rc, containing an arbitrary rc command. This only works for the hostowner and only if # m/caphash still exists.

FILES

/lib/ndb/auth Speaksfor relationships and mappings for RADIUS server id's. /adm/keys.who List of users in the Plan 9 database. /adm/netkeys.who List of users in the SecureNet database.

SOURCE

```
/sys/src/cmd/auth
```

SEE ALSO

passwd(1), readnvram in authsrv(2), keyfs(4), securenet(8)

BUGS

Only CPU kernels permit changing userid.

backup, tobackup, dumparenas, restore - backup venti arenas to blu-ray discs or restore from them

SYNOPSIS

backup [-n] [-d dev] [-s set]
tobackup [set]
dumparenas dev arena ...
restore arena-# [dev]

DESCRIPTION

These programs reside in /sys/lib/backup and provide a means to backup *venti*(8) storage to Blu-ray (or other large optical) discs, while keeping track of which arenas have been written to which discs. Multiple backup sets are supported, as is (re)loading a *venti* store from a backup thus made.

The first time that *backup* is run, it will dump all sealed *venti* arenas. Thereafter, it will append only those sealed arenas not already written to a disc within the given backup set. The -s option uses a backup *set* other than the default. The -d option uses a disc burner other than the default /dev/sdD0. The -n option goes through the motions but does not burn any tracks on the Bluray disc.

Tobackup prints the names of all the sealed arenas not yet backed up to a disc in the current set.

Dumparenas copies the named *arenas*, one per track, to the device *dev*, which is first mounted via *cdfs*(4). *Venti/rdarena* is used to extract each arena.

Tobackup and dumparenas are invoked internally by backup.

Restore copies each data track (assumed to be a saved arena) on *dev* (by default, /dev/sdC0) into its appropriate place in the *venti* arenas partition (locally, /dev/sde0/arenas), thus adding the arena to the current *venti* store. The arena size of the arena partition must match the size of the arenas on optical disc (except for ~60K of trailing debris on the optical disc arenas).

Arena-# must be the number (starting from zero) of the first arena slot in the arenas partition that you wish to restore into from the current optical disc (*not* necessarily that of the first arena on the disc). *Restore* will prompt for confirmation that the first arena is the correct one, after printing a summary of its arena header. Typing y will proceed normally, n will abort all processing, and skip will cause *restore* to proceed to the next track and ask for confirmation of it.

The arenas partition must be formatted (see *fmtarenas* in *venti–fmt*(8)) before restoring into it. When all the arenas have been restored, it will be necessary to build a new *venti* index, the usual steps being to run *checkarenas*, *fmtisect*, *fmtbloom*, *fmtindex*, and *buildindex –b*, all from *venti–fmt*(8).

FILES

/sys/lib/backup	backup scripts and records
set1	subdirectory containing records for default backup set
/sys/log	source of dump scores

SOURCE

/sys/lib/backup

SEE ALSO

venti(1), cdfs(4), venti(8), venti–fmt(8), venti–backup(8) Venti Backup on Blu–Ray Discs

BUGS

Assumes a single arenas partition named arena0. Assumes that the file server's arenas are accessible on it as /dev/fs/arena0.

boot, bootrc - connect to the root file server

SYNOPSIS

/boot/boot

DESCRIPTION

Boot is the first program run after a kernel has been loaded. It mounts bootfs.paq, a compressed filesystem contained in root(3), sets up the rc(1) environment and executes *bootrc* passing on its arguments. *Bootrc* connects to the file server that will serve the root, performs any authentication needed to connect to that server, and executes the *init*(8) program. Both *boot* and *bootrc* are started by the kernel, never run directly by the user. See *booting*(8) for information about the process of loading the kernel (and *boot*) into memory.

Once loaded, the kernel initializes its data structures and devices. It sets the two environment variables /env/cputype and /env/terminal to describe the processor. It then binds a place-holder file server, *root*(3), onto / and crafts an initial process whose sole function is to *exec*(2) /boot/boot, a binary which is compiled into *root*(3).

The command line passed depends on the information passed from boot ROM to kernel. Machines that boot directly from ROM (that is, most machines other than PCs) pass the boot line given to the ROM directly to *boot*.

On the PC, each line in the file *plan9.ini*(8) of the form *name=value* is passed to the boot program as an environment variable with the same name and value.

After *boot* passed its execution to *bootrc*, it must determine the fileserver to use and a *method* with which to connect to it. Typically *device* will name a local disk partition or ethernet interface. The complete list of methods is given below.

Bootrc must also set a user name to be used as the owner of devices and all console processes and an encryption key to be used when challenged. *Bootrc* will prompt for these.

Method and device are prompted for first. The prompt lists all valid methods, with the default in brackets, for example:

bootargs is (tcp, il, local!device) [local!/dev/sdC0/fscache]

A newline picks the default. Entering !rc breaks into the rc(1) shell. Other possible responses are *method*, *method*! *device* or *method*! *device args*.

The other interactions depend on whether the system is a terminal or a CPU server.

Terminal

A terminal must have a *username* set. If not specified with the user = plan9.ini(8) parameter, *boot* will prompt for one on the console:

user:

The user will also be prompted for a password to be used as an encryption key on each *attach*(5):

password:

Once connected, *boot* mounts the root file system at /root (with the optional mount spec argument from \$rootspec) and makes the connection available as #s/boot for subsequent processes to mount (see *bind*(2)). It then binds /root (or the value specified by \$rootdir) after the / directory. *Boot* completes by *exec*(2)'ing /\$cputype/init-t. If the -m option is given it is also passed as an option to *init*. If the environment variable init is set (via *plan9.ini*(8)), it is used as an argument to *exec*(2) instead.

If the *bootfs.paq* has been built with the cache file system, cfs(4), the local disk partition /dev/sdXX/cache (where XX is a unit specifier) exists, and the root file system is from a remote server, then *bootrc* will insert a user level cache process between the remote server and the local namespace that caches all remote accesses on the local partition.

CPU Servers

The user owning devices and console processes on CPU servers and that user's domain and encryption key are read from NVRAM on all machines except PCs. PCs keep the information in the disk partition /dev/sdXX/nvram.

password: authid: bootes authdom: research.bell-labs.com

The key is used for mutual authentication of the server and its clients. The domain and id identify the owner of the key.

Once connected, *boot* behaves as on the terminal except for exec(2) ing / cputype/init -c.

Booting Methods

The methods available to any system depend on what was compiled into the kernel. The complete list of booting methods are listed below.

- tcp connect via Ethernet using the TCP protocol. The *device* and *args* are passed to *ipconfig*(8) when configuring the IP stack. The *plan9.ini*(8) variables fs and auth override the file server and authentication servers obtained (if any) from DHCP and IPv6 router advertisements during *ipconfig*(8).
- il the same as tcp but uses the IL protocol to connect to the fileserver.
- tls makes an authenticated and encrypted connection to the fileserver via srvtls using t9fs service (see srv(4)). the arguments are the same as tcp.
- local connect to the local file system. The *device* is a disk partition file holding a file system. *Bootrc* inspects the disk partition with *fstype*(1) to determine the file system type and starts the appropriate server with *args*.

reboot

starts another kernel. The *device* is of the form *bootfile* [! *method*] where *bootfile* is the path to the kernel and *method* is any of the above boot methods that connects to the file-server on where the *bootfile* is located.

EXAMPLES

On PCs, the default arguments to boot are constructed using the bootargs variable in *plan9.ini*(8).

Start *cwfs*(4) in config mode:

```
bootargs=local!/dev/sdC0/fscache -c
```

Use an IP stack on an alternate ethernet interface with a static address and fixed file server and authentication server addresses.

(The bootargs line is split only for presentation; it is one line in the file.)

FILES

#s/boot
#//boot/boot
#//boot/bootfs.paq

SOURCE

/sys/src/9/boot

SEE ALSO

root(3), *dhcpd*(8), *init*(8)

BUGS

The use of bootargs in general is odd.

Filenames passed to *9bootfat* must be specified in DOS 8.3 format. *9bootfat* does not support long file names.

HISTORY

Boot first appeared in Plan 9 from Bell Labs. It was rewritten in rc for 9front (April, 2011).

booting - bootstrapping procedures

SYNOPSIS

none

DESCRIPTION

This manual page collects the incantations required to bootstrap Plan 9 machines. Some of the information here is specific to the installation at Bell Labs; some is generic.

If a CPU server is up, BOOTP/DHCP and TFTP will run from there; if not, the necessary files and services must be available on a separate machine, such as a Unix system, to use these protocols for bootstrapping.

Be sure to read *boot*(8) to understand what happens after the kernel is loaded.

Terminals

To bootstrap a diskless terminal or a CPU server, a file server must be running.

PCs

On a PC, the *9boot*(8) program is used to load the kernel /386/9pc into memory.

Once the kernel is booted, it behaves like the others. See *boot*(8) for details.

CPU Servers

The Plan 9 CPU servers are multi-user, so they do not request a user name when booting.

PC CPU Server

Proceed as for the PC terminal, but have service=cpu set in *plan9.ini*(8).

SGI Challenge multiprocessor CPU Server

The Challenge ROM monitor can boot from the Ethernet. To boot from the Ethernet, type

bootp()/mips/9ch

or use the ROM command setenv to set the variable bootfile to that same string and type boot. To load a different file, tell bootp which file to load, and to force the download to come from a particular system, bootp()system:file. Any arguments after bootp()file are passed to /boot. If you are running a Plan 9 BOOTP server (see *dhcpd*(8)), the file name can be omitted and the file specified by the bootf parameter for the machine in /lib/ndb will be downloaded by default.

Once the kernel is loaded, it prompts for the Ethernet protocol to use to reach the root file server; request the default.

ARM CPU Servers

All ARM systems are started by *U-boot* using similar commands. The kernels (and thus *ndb* bootf parameters) are /arm/9gd for the Marvell PXA168-based Guruplug Display, /arm/9plug for all Marvell Kirkwood plugs (Sheevaplug, Guruplug, Openrd, etc.), and /arm/9beagle for TI OMAP3 boards (IGEPv2 from ISEE, Gumstix Overo). In the following, replace *MAC* with your board's MAC address without colons, in lower case (the format of the ether *ndb* attribute).

First, establish a /cfg/pxe (plan9.ini) file for the new CPU server. For Kirkwood plugs,

cd /cfg/pxe; cp example-kw MAC

and edit /cfg/pxe/MAC to taste. For PXA plugs, replace kw with pxa; for OMAP boards, replace kw with omap and be sure to edit the line for ether0 to set

ea=MAC

Second, configure *U*-boot to load the appropriate kernel and /cfg/pxe file at suitable addresses and start the kernel. For Sheevaplugs and Openrd boards, type this at U-boot once:

setenv bootdelay 2
type the next two lines as one
setenv bootcmd 'bootp; bootp; tftp 0x1000 /cfg/pxe/MAC; bootp;
 tftp 0x800000; go 0x800000'
saveenv

For Guruplugs Displays, do the same but type this after setenv bootcmd instead:

'dhcp; tftpboot; tftpboot 0x1000 /cfg/pxe/MAC; bootz 0x500000' For Kirkwood Guruplugs, type this after setenv bootcmd:

'dhcp 0x800000; tftp 0x1000 /cfg/pxe/MAC; go 0x800000' For IGEPv2 boards, type this after setenv bootcmd:

'tftp 0x80300000 /cfg/pxe/MAC; dhcp 0x80310000; go 0x80310000' For Gumstix Overo boards, type this after setenv bootcmd:

'bootp 0x80310000; bootp 0x80300000 /cfg/pxe/MAC; go 0x80310000' Thereafter, the boards will automatically boot via BOOTP and TFTP when reset.

SEE ALSO

ndb(6), 9boot(8), boot(8), init(8), plan9.ini(8)

SOURCE

Sources for the various boot programs are under /sys/src/boot.

cec - Coraid Ethernet Console

SYNOPSIS

cec [-dp][-S srv][-c esc][-e ea][-h host[-s shelf][interface]

DESCRIPTION

Cec uses raw Ethernet packets to connect to a CEC server for console access. All clients share the same session. Coraid appliances and Coraid Plan 9 kernels can currently be CEC servers.

Cec starts by probing the specified network interface for available CEC servers. The default is /net/ether0. Only one *cec* process may be run per Ethernet interface. If the server is specified with the -b, -h, or -s options, communication will proceed immediately upon discovery of the first CEC server with the specified address. Otherwise, a selection prompt will be displayed showing the discovered CEC servers available for communication. Unless the -p option is specified, *cec* exits if no matching servers are found. The selection prompt accepts

number Connect to server number (from the first column),

p Probe the interface again, and

q Quit.

Note the selection number is not the shelf address but the *cec*-generated sequence number printed in the leftmost column.

Once connected to a CEC server, typing the escape character will drop the user into an escape prompt where the user may type q to quit the connection, i to send the escape character across the connection, or . to continue the connection.

Options

- -c Set the escape character to control-*esc*. The default setting is control-\.
- -d Print debugging information.
- -e Connect to the server with Ethernet address *ea*; implies –p.
- -h Connect to the server *host*. Note that this name might not be the same as the contents of /dev/sysname on the target system.
- -p Persist: continue trying to connect even if there are no matching servers. This is useful when connecting to a CPU server before it boots.
- -s Connect to the server at address *shelf*.
- -S Post the CEC connection as /srv/srv to allow sharing.

If the -e, -s, or -h options are given, *cec* will exit upon closing the connection. Otherwise, *cec* will return to the selection prompt upon connection close.

EXAMPLES

SOURCE

/sys/src/cmd/cec

BUGS

The CEC protocol should be integrated with the console server. The arbitration between the keyboard and network is suboptimal.

Early boot information and very late crash information from servers may be lost due to timing quirks.

cifsd - CIFS/SMB network daemon

SYNOPSIS

ip/cifsd[-t][-d][-f debuglog][-w name][-o option]...[conndir]

DESCRIPTION

Cifsd exports filesystems to CIFS or SMB clients like Microsoft [™] Windows.

It is normally started by the network listen process via the /rc/bin/service/tcp445 service script (see *listen*(8)), which passes *conndir* and filedescriptors 0 and 1 to the incoming connection.

Users are authenticated by their Inferno/pop secret held by the auth server. When successful, *cifsd* changes its user id and namespace to the authenticated user. Informative log messages are appended to /sys/log/cifsd if it exists.

By default the share local is offered, which represents the root of the namespace described by /lib/namespace. If a different name is explicitly requested by the client then /bin/9fs (see srv(4)) is invoked to attach that filesystem, which is then exported instead.

The flags are:

- t Run the server in trusted mode, so it will not require authentication from the client and keep running in the callers namespace.
- d Enable or increases debug verbosity for the *debuglog* file. Debug messages are never written to the system logfile.
- f Specify the filename for the *debuglog* file. If not specified no debug messages are generated.
- w Set the workgroup (or primary domain) to *name. The default is* WORKGROUP
- o Enables the following *option* string. This flag can appear multiple times when more than one option has to be enabled. Valid options are:

trspaces

transforms whitespace in filenames to non breaking whitespace. This is useful when exporting filesystems other than fossil.

casesensitive

By default, filename lookups are done case insensitive to match windows filesystem semantics. This option disables case insensitive lookups which can result in a performance improvement, but might break some applications.

FILES

/rc/bin/service/tcp445
/sys/log/cifsd
/lib/namespace

SOURCE

/sys/src/cmd/ip/cifsd

SEE ALSO

listen(8), srv(4)

HISTORY

Cifsd first appeared in 9front (May, 2011).

cpuid, icanhasvmx - print processor information

SYNOPSIS

aux/cpuid[-ar]

aux/icanhasvmx[-r]

DESCRIPTION

Intel and compatible processors since the Pentium[™] (or late 486) provide the CPUID instruction that returns information about the chip. The *cpuid* program enumerates and prints this information in a simple textual format. The output consists of multiple lines prefixed with a keyword describing the information that follows.

With the -r option, the format changes to raw hexadecimal output with the keyword being the AX input register to the CPUID instruction followed by 4 colums with the output registers AX, BX, CX and DX.

The -a option prints enumerated items in raw format if no keyword is known instead of omitting it (default).

The keywords supported so far are:

vendor

Processor vendor string

procmodel, extmodel
 Processor model, hexadecimal model / family id

features, extfeatures Feature bits, a variable list of feature acronyms

procname

Processor name string

physbits, virtbits, guestbits Address lines, decimal in bits

lcanhasvmx queries the virtual machine extension (VMX) capabilities. If $-\mathbf{r}$ is specified, it prints the results in raw hexadecimal; otherwise it produces a human-readable format. In any case it prints a summary on fd 2.

EXAMPLE

term% aux/cpuid vendor GenuineIntel procmodel 000006b4 / 00000006 features fpu vme de pse tsc msr pae mce cx8 sep mtrr pge mca cmov pat pse36 features mmx fxsr sse extmodel 00000000 / 00000000 procname Mobile Intel(R) Pentium(R) III CPU - M 1133MHz

SOURCE

/sys/src/cmd/aux/cpuid.c

cpurc, cpurc.local, termrc, termrc.local - boot scripts

SYNOPSIS

```
cpurc
cpurc.local
termrc
termrc.local
```

DESCRIPTION

After the kernel boots, it execs /boot (see *boot*(8)), which in turn execs /\$cputype/init. *Init*(8) sets the \$service environment variable to cpu or terminal, and then invokes the appropriate rc script to bring the system up.

Based on the values of sysname and terminal these scripts start appropriate network processes and administrative daemons and enable swapping. *Termrc* sets /env/NPROC to a value suitable for parallel compilation in mk(1).

If an executable file /bin/termrc.local exists, *termrc* will execute it. If an executable file /cfg/\$sysname/termrc exists for the machine named \$sysname, *termrc* will execute it next. These files should be edited by local installations to reflect the configuration of their systems.

On CPU servers, read cpurc for termrc in the previous paragraph.

FILES

/cfg/\$sysname/cpurc machine-specific boot script for cpurc /cfg/\$sysname/termrc machine-specific boot script for termrc

SOURCE

```
/rc/bin/*rc
/rc/bin/*rc.local
/cfg/$sysname/*rc
```

SEE ALSO

namespace(6), boot(8) init(8), listen(8)

cron – clock daemon

SYNOPSIS

auth/cron[-c]

DESCRIPTION

Cron executes commands at specified dates and times according to instructions in the files /cron/user/cron. It runs only on an authentication server. Option -c causes *cron* to create /cron/user and /cron/user/cron for the current user; it can be run from any Plan 9 machine.

Blank lines and lines beginning with # in these files are ignored. Entries are lines with fields

minute hour day month weekday host command

Command is a string, which may contain spaces, that is passed to an rc(1) running on *host* for execution. The first five fields are integer patterns for

minute0-59hour0-23day of month1-31month of year1-12day of week0-6; 0=Sunday

The syntax for these patterns is

Each number must be in the appropriate range. Hyphens specify inclusive ranges of valid times; commas specify lists of valid time ranges.

To run the job, *cron* calls *host* and authenticates remote execution, equivalent to running rx *host command* (see *con*(1)). The user's profile is run with \$service set to rx. If *host* is set to local, *cron* will run the command as *user* on the local machine without using rx.

Cron is not a reliable service. It skips commands if it cannot reach *host* within two minutes, or if the *cron* daemon is not running at the appropriate time.

EXAMPLES

Here is the job that mails system news.

% cat /cron/upas/cron
send system news
15 8-17,21 * * * helix /mail/lib/mailnews
%

FILES

/cron/lock lock file to prevent multiple *cron*s running

SOURCE

/sys/src/cmd/auth/cron.c

SEE ALSO

con(1), *rc*(1)

cryptsetup - setup encrypted partition

SYNOPSIS

disk/cryptsetup -f files ... disk/cryptsetup -o files ... disk/cryptsetup -i files ...

DESCRIPTION

Cryptsetup prepares an AES-encrypted partition to be used with the fs(3) device.

The -f flag formats the partition *files*, generating a new encryption key. The user will be prompted for a password that will be used to protect the encryption key.

The flags -i and -o activate a previously formatted encrypted partition. The -o flag outputs the fs(3) ctl activation commands to standard output, whereas -i directly writes them to the '/dev/fs/ctl' file. The user will be prompted for the password that was used to protect the encryption key.

Once activated, the new partition appears under /dev/fs/name where *name* is the last path element of the *files* argument.

SOURCE

/sys/src/cmd/disk/cryptsetup.c

SEE ALSO

aes(2), fs(3)

HISTORY

Cryptsetup first appeared in 9front (May, 2011).

dhcpd, dhcp6d, dhcpleases, rarpd, tftpd - Internet booting

SYNOPSIS

ip/dhcpd [-dmnprsSZ] [-h homedir] [-f ndbfile] [-M secs] [-x netmtpt] [-Z secs] [address n] ...

ip/dhcpleases

ip/dhcp6d [-d] [-f ndbfile] [-x netmtpt]

ip/rarpd [-d] [-e etherdev] [-x netmtpt]

ip/tftpd [-dr] [-h homedir] [-x netmtpt]

DESCRIPTION

These programs support booting over the Internet. They should all be run on the same server to allow other systems to be booted. *Dhcpd*, *dhcp6d* and *tftpd* are used to boot everything; *rarpd* is an extra piece just for Suns.

Dhcpd runs the BOOTP and DHCP protocols. Clients use these protocols to obtain configuration information. This information comes from attribute/value pairs in the network database (see ndb(6) and ndb(8)). DHCP requests are honored both for static addresses found in the NDB and for dynamic addresses listed in the command line. DHCP requests are honored if either:

- there exists an NDB entry containing both the ethernet address of the requester and an IP address on the originating network or subnetwork.

- a free dynamic address exists on the originating network or subnetwork.

A BOOTP request is honored if all of the following are true:

- there exists an NDB entry containing both the ethernet address of the requester and an IP address on the originating network or subnetwork.

- the entry contains a bootf= attribute

- the file in the bootf= attribute is readable.

Dynamic addresses are specified on the command line as a list of addresses and number pairs. For example,

ip/dhcpd 10.1.1.12 10 10.2.1.70 12

directs *dhcpd* to return dynamic addresses 10.1.1.12 through 10.1.1.21 inclusive and 10.2.1.70 through 10.2.1.81 inclusive.

Dhcpd maintains a record of all dynamic addresses in the directory /lib/ndb/dhcp, one file per address. If multiple servers have access to this common directory, they will correctly coordinate their actions.

Attributes come from either the NDB entry for the system, the entry for its subnet, or the entry for its network. The system entry has precedence, then the subnet, then the network. The NDB attributes used are:

ip	the IP address
ipmask	the IP mask
ipgw	the default IP gateway
dom	the domain name of the system
fs	the default Plan 9 file server
auth	the default Plan 9 authentication server
dns	a domain name server
ntp	a network time protocol server
time	a time server
wins	a NETBIOS name server
WWW	a World Wide Web proxy
рор3	a POP3 mail server
smtp	an SMTP mail server
bootf	the default boot file; see <i>ndb</i> (6)
tftp	the TFTP server to fetch <i>bootf</i> from
rootpath	the NFS root for unix machines

rootserver the NFS server used with *rootpath* vendor Specific vendor attribute for dhcp and bootp

Dhcpd will answer BOOTP requests only if it has been specifically targeted or if it has read access to the boot file for the requester. That means that the requester must specify a boot file in the request or one has to exist in NDB for *dhcpd* to answer. *Dhcpd* will answer all DHCP requests for which it can associate an IP address with the requester. The options are:

- d Print debugging to standard output.
- h Change directory to *homedir*. The default is /. This should match the *homedir* setting of *tftpd* so that the existence check of non-rooted file names is consistent.
- f Specify a file other than /lib/ndb/local as the network database.
- m Mute: don't reply to requests, just log them and what *dhcpd* would have done.
- M Use *secs* as the minimum lease time for dynamic addresses.
- n Don't answer BOOTP requests.
- p Answer DHCP requests from PPTP clients only.
- r Mute static addresses: don't reply to requests for static addresses, just log them and what *dhcpd* would have done.
- s Sleep 2 seconds before answering requests for static addresses. This is used to make a server be a backup only.
- S Sleep 2 seconds before answering requests for dynamic addresses.
- x The IP stack to use is mounted at *netmtpt*. The default is /net.
- Z Use *secs* as the minimum lease time for static addresses.

Dhcp6d provides DHCPv6 service for IPv6 clients. Only network boot and DNS parameters are supported.

Dhcpleases prints out the currently valid DHCP leases found in the /lib/ndb/dhcp directory.

Rarpd performs the Reverse Address Resolution Protocol, translating Ethernet addresses into IP addresses. The options are:

- d Print debugging to standard output.
- e Use the Ethernet mounted at /net/etherdev.
- x The IP stack to use is mounted at *netmtpt*. The default is /net.

Tftpd transfers files to systems that are booting. It runs as user none and can only access files with global read permission. The options are:

- d Print debugging to standard output.
- x The IP stack to use is mounted at *netmtpt*. The default is /net.
- h Change directory to *homedir*. The default is /. All requests for files with non-rooted file names are served starting at this directory. This needs to be consistent with the *homedir* setting of *dhcpd*. *Tftpd* supports only octet mode.
- r Restricts access to only those files rooted in the *homedir*.

FILES

/lib/ndb/dhcp directory of dynamic address files

SOURCE

/sys/src/cmd/ip

SEE ALSO

ndb(6), booting(8)

diskparts - prepare disks for use

SYNOPSIS

diskparts

DESCRIPTION

Diskparts configures EFI, FDISK and Plan 9 partitions on any disks named $/dev/sd^*$, then configures fs(3) by copying /cfg/\$sysname/fsconfig, if present, to /dev/fs/ctl, if present, one line at a time. If #S or #k are not bound to /dev yet, they are first bound after the current contents.

FILES

/dev/sd[C-H]?/ctl storage interface control files for IDE devices

SOURCE

/rc/bin/diskparts

SEE ALSO

sd(3), partfs(8)

disksim – disk simulator

SYNOPSIS

```
aux/disksim[-r][-f file][-s srvname][-m mtpt][diskname]
```

DESCRIPTION

Disksim presents an in-memory disk in the manner of the sd(3) device on mtpt/diskname (default /dev/sdXX). The disk is initialized to zeros; non-zeroed blocks written to the disk are kept in memory.

When setting disk geometry with the geometry control message, the arguments are sectors, sector size, cylinders, heads, and sectors per track. The last three may be zero for LBA disk simulations, but must be present.

The -f option causes *disksim* to use *file* as the initial contents of the disk rather than a zeroed image. Changes made to the disk are written back to *file* unless the -r option is given.

The -s option causes *disksim* to post its 9P service at /srv/service.

EXAMPLES

Disksim can be used to test programs such as fdisk and prep(8) that expect sd(3) disks:

```
aux/disksim
echo geometry 40000 512 0 0 0 >/dev/sdXX/ctl # 20MB
disk/mbr /dev/sdXX/data
disk/fdisk -baw /dev/sdXX/data
disk/prep /dev/sdXX/plan9
```

Disksim is useful for creating very large but mostly zeroed files for testing other programs. Test *tar*(1)'s handling of large files:

```
for(i in sdXX sdYY sdZZ) aux/disksim $i
echo geometry 40000000 512 0 0 0 >/dev/sdXX/ctl # 20GB
echo geometry 10000000 512 0 0 0 >/dev/sdYY/ctl # 5GB
echo geometry 20000000 512 0 0 0 >/dev/sdZZ/ctl # 10GB
tar cf /dev/sdXX/data /dev/sdYY/data /dev/sdZZ/data
tar tvf /dev/sdXX/data
```

SOURCE

/sys/src/cmd/aux/disksim.c

SEE ALSO

sd(3), prep(8)

NAME fs, exsort - file server maintenance **SYNOPSIS** help[command...] allow [uid] arp subcommand cfs filesystem check [options] clean file [bno [addr]] clri[file...] cpu [*proc*] create path uid gid perm [lad] cwcmd subcommand date [[+-] seconds] disallow duallow [uid] dump [filesystem] files flag flag [channel] fstat [files] halt hangup *channel* newuser name [options] noattach passwd printconf profile[01] remove [files...] route *subcommand* sntp kick stat[admiesw] stats [[-] flags...] sync time command trace [number] users [file] version who [user...] wormeject[tunit] wormingest[tunit] wormoffline *drive* wormonline *drive* wormreset disk/exsort [-w] [file]

DESCRIPTION

Except for *exsort*, these commands are available only on the console of an fs(4) file server.

Help prints a 'usage string' for the named *commands*, by default all commands. Also, many commands print menus of their options if given incorrect or incomplete parameters.

Allow disables permission checking and allows wstat for the specified *uid* or for any user if omitted. This may help in initializing a file system. Use this with caution.

Arp has two subcommands: print prints the contents of the ARP cache and flush flushes it.

Cfs changes the current file system, that is, the file tree to which commands (check, clean, clri, create, cwcmd, dump, newuser, profile, remove, and users) apply. The initial *filesystem* is main.

Check verifies the consistency of the current file system. With no options it checks and reports the status. It suspends service while running. Options are:

- rdall Read every block in the file system (can take a *long* time). Normally, *check* will stop short of the actual contents of a file and just verify the block addresses.
- tag Fix bad *tags*; each block has a tag that acts as a backwards pointer for consistency checking.
- ream Fix bad tags and also clear the contents of blocks that have bad tags.
- pfile Print every file name.
- pdir Print every directory name.
- free Rebuild the list of free blocks with all blocks that are not referenced. This option is only useful on non-cache/WORM file systems. If the filesystem was modified, the summary printed at the conclusion of the check may not reflect the true state of the freelist and may also print a list of *missing* blocks. These *missing* blocks are actually on the free list and the true state of the filesystem can be determined by running *check* with no arguments.
- bad Each block address that is out of range or duplicate is cleared. Note that only the second and subsequent use of a block is cleared. Often the problems in a file system are caused by one bad file that has a lot of garbage block addresses. In such a case, it is wiser to use *check* to find the bad file (by number of diagnostic messages) and then use *clri* to clear the addresses in that file. After that, *check* can be used to reclaim the free list.
- touch Cause every directory and indirect block not on the current WORM disk to be advanced to the current WORM on the next dump. This is a discredited idea to try to keep operating on the knee of the cache working set. Buy more cache disk.
- trim reduces the file system's *fsize* to fit the device containing the file system. This is useful after copying a partially-full file system into a slightly smaller device. Running check free afterward will construct a new free list that contains no blocks outside the new, smaller file system.
- rtmp Removes temporary files after a recovery from worm. After a cache ream and recover, temporary files and directories refer to invalid data blocks producing checktag errors on access. To get rid of these errors, the *rtmp* flag can be used with the *check* command which will truncate temporary directories and remove temporary files.

Clean prints the block numbers in *file*'s directory entry (direct, indirect and doubly indirect) and checks the tags of the blocks cited. If *bno* is supplied, the *bno*'th block number (using zero origin) is set to *addr* (defaults to zero). Note that only the block numbers in the directory entry itself are examined; *clean* does not recurse through indirect blocks.

Clri clears the internal directory entry and abandons storage associated with *files*. It ignores the usual rules for sanity, such as checking against removing a non-empty directory. A subsequent check free will place the abandoned storage in the free list.

Cpu prints the CPU utilization and state of the processes in the file server. If the name of a process type argument is given, then CPU utilization for only those processes is printed.

Create creates a file on the current file system. *Uid* and *gid* are names or numbers from /adm/users. *Perm* is the low 9 bits of the permission mode of the file, in octal. An optional final 1, a, or d creates a locked file, append-only file, or directory.

Cwcmd controls the cached WORM file systems, specifically the current file system. The subcommands are:

mvstate state1 state2 [platter]

States are none, dirty, dump, dump1, error, read, and write. A mvstate dump1 dump will cause I/O errors in the last dump to be retried. A mvstate dump1 write will cause I/O errors in the last dump to be retried in reallocated slots in the next dump. A mvstate read none will flush the cache associated with the WORM. A mvstate dump write aborts the background process dumping to WORM; as a consequence it leaves holes in the dump file system. Other uses are possible but arcane. The

optional *platter* limits affected blocks to those on that platter.

prchain [start] [back-flag]

Print the chain of superblocks for the directory containing the roots of the dumped file systems, starting at block number *start* (default 0) going forward (backwards if *back-flag* is supplied and is non-zero).

searchtag [start] [tag] [blocks]

Reads the WORM device starting at block *start* and proceeding for *blocks* blocks (default 1000) until it finds a block with numeric tag *tag*.

savecache [percent]

Copy the block numbers, in native endian longwords, of blocks in the read state to the file /adm/cache for use by disk/exsort. If an argument is given, then that percent (most recently used) of each cache bucket is copied.

loadcache [dskno]

Read /adm/cache and for every block there on WORM disk side *dskno* (zero-origin), read the block from WORM to the cache. If *dskno* is not supplied, all blocks in /adm/cache are read.

morecache dskno [count]

Read *count* blocks from the beginning of WORM disk side *dskno* to the cache. If no count is given, read all of side *dskno* into the cache.

startdump[01]

Suspend (0) or restart (1) the background dump process.

touchsb

Verify that the superblock on the WORM is readable, ignoring the cached copy.

blockcmp [wbno] [cbno]

Compares the WORM block *wbno* with the cache block *cbno* and prints the first 10 differences, if any.

- acct Prints how many times each user has caused the system to allocate new space on the WORM; the units are megabytes.
- clearacct

Clears the accounting records for acct.

Date prints the current date. It may be adjusted using +-seconds. With no sign, it sets the date to the absolute number of seconds since 00:00 Jan 1, 1970 GMT; with a sign it trims the current time.

Disallow restores permission checking back to normal after a file system has been initialized.

Duallow sets permissions such that the named user can read and search any directories. This is the permission necessary to do a du(1) command anywhere in the file system to discover disk usage.

Dump starts a dump to WORM immediately for the named filesystem, or the current filesystem if none is named. File service is suspended while the cache is scanned; service resumes when the copy to WORM starts.

Files prints for every connection the number of allocated fids.

Fstat prints the current status of each named *file*, including uid, gid, wuid (uid of the last user to modify the file), size, qid, and disk addresses.

Flag toggles flags, initially all off:

allchans	Print channels in <i>who</i> output.
arp	Report ARP activity.
attach	Report as connections are made to the file server.
authdebug	Report authentications.
authdisable	Disable authentication.
chat	(Very noisy.) Print all 9P messages to and from the server.
error	Report 9P errors.
il	Report IL errors.

route	Report received RIP packets.
ro	Report I/O on the WORM device.
sntp	Report SNTP activity.

If given a second numeric *channel* argument, as reported by *who*, the flag is altered only on that connection.

Halt does a sync and halts the machine, returning to the boot ROM.

Hangup clunks all the fids on the named *channel*, which has the same format as in the output of the *who* command.

Newuser requires a *name* argument. With no options it adds user *name*, with group leader *name*, to /adm/users and makes the directory /usr/name owned by user and group *name*. The options are

?	Print the entry for <i>name</i> .
:	Add a group: add the name to /adm/users but don't create the directory. By
	convention, groups are numbered starting from 10000, users from 0.
newname	Rename existing user <i>name</i> to <i>newname</i> .
=leader	Change the leader of <i>name</i> to <i>leader</i> . If <i>leader</i> is missing, remove the existing
	leader.
+member	Add <i>member</i> to the member list of <i>name</i> .
– member	Remove existing <i>member</i> from the member list of <i>name</i> .

After a successful *newuser* command the file server overwrites /adm/users to reflect the internal state of the user table.

Noattach disables *attach*(5) messages, in particular for system maintenance. Previously attached connections are unaffected. Another *noattach* will enable normal behavior.

Passwd sets the machine's password and writes it in non-volatile RAM.

Printconf prints the system configuration information.

Profile 1 clears the profiling buffer and enables profiling; *profile* 0 stops profiling and writes the data to /adm/kprofdata for use by kprof (see *prof*(1)). If a number is not specified, the profiling state toggles.

Remove removes *files*.

Route maintains an IP routing table. The *subcommands* are:

add dest gate [mask]	Add a static route from IP address <i>dest</i> using gateway <i>gate</i> with an optional subnet <i>mask</i> .
delete <i>dest</i>	Delete an entry from the routing table.
print	Display the contents of the routing table.
ripon	Enables the table to be filled from RIP packets.
ripoff	Disables the table from being updated by RIP packets.

Sntp kick queries the SNTP server (see *fsconfig*(8)) and sets the time with its response.

The *stat* commands are connected with a service or device identified by the last character of the name: d, SCSI targets; e, Ethernet controllers; i, IDE/ATA targets; m, Marvell SATA targets; w, cached WORM. The *stata* command prints overall statistics about the file system. The *stats* command takes an optional argument identifying the characters of *stat* commands to run. The option is remembered and becomes the default for subsequent *stats* commands if it begins with a minus sign.

Sync writes dirty blocks in memory to the magnetic disk cache.

Time reports the time required to execute the *command*.

Trace with no options prints the set of queue-locks held by each process in the file server. If things are quiescent, there should be no output. With an argument *number* it prints a stack trace-back of that process.

Users uses the contents of *file* (default /adm/users) to initialize the file server's internal representation of the users structure. Incorrectly formatted entries in *file* will be ignored. If file is explicitly default, the system builds a minimal functional users table internally; this can help recover from disasters. If the *file* cannot be read, you *must* run

users default

for the system to function. The default table looks like this:

-1:adm:adm: 0:none:adm: 1:tor:tor: 10000:sys:: 10001:map:map: 10002:doc:: 10003:upas:upas: 10004:font:: 10005:bootes:bootes:

Version reports when the file server was last compiled and last rebooted.

Who reports, one per line, the names of users connected to the file server and the status of their connections. The first number printed on each line is the channel number of the connection. If *users* are given the output selects connections owned by those users.

Wormeject moves the WORM disk in slot tunit of the first jukebox to the output shelf.

Wormingest moves the WORM disk from the input shelf of the first jukebox to slot tunit.

Wormoffline takes drive of the first jukebox out of service; wormonline puts it back in service.

Wormreset put discs back where the jukebox thinks they belong, and does this for all jukeboxes.

When the file server boots, it prints the message

for config mode hit a key within 5 seconds

If a character is typed within 5 seconds of the message appearing, the server will enter config mode. See *fsconfig*(8) for the commands available in config mode. The system also enters config mode if, at boot time, the non-volatile RAM does not appear to contain a valid configuration.

Exsort is a regular command to be run on a CPU server, not on the file server console. It reads the named *file* (default /adm/cache) and sorts the cache disk block numbers contained therein. It assumes the numbers are 4-byte integers and guesses the endianness by looking at the data. It then prints statistics about the cache. With option -w it writes the sorted data back to *file*.

SEE ALSO

fs(4) Ken Thompson, ''The Plan 9 File Server''.

SOURCE

/sys/src/fs /sys/src/cmd/disk/exsort.c

BUGS

The worm* commands should accept an argument identifying a jukebox.

fsconfig - configuring a file server

SYNOPSIS

service name

config *device* nvram *device*

filsys name device

1110yo nume uen

ip ipaddr

ipgw *ipaddr*

ipmask *ipaddr*

ipauth *ipaddr*

ipsntp ipaddr ream name

recover name

allow

readonly

noauth

noattach

copyworm

copydev from-dev to-dev

halt

end

DESCRIPTION

When an fs(4) file server's configuration has not been set, or by explicit request early in the server's initialization (see fs(8)), the server enters 'config mode'. The commands described here apply only in that mode. They establish configuration constants that are typically valid for the life of the server, and therefore need be run only once. If the non-volatile RAM on the server gets erased, it will be necessary to recreate the configuration.

Syntax

In these commands, *ipaddr* is an IP address in the form 111.103.94.19 and *name* is a text string without white space. The syntax of a *device* is more complicated:

wn1.n2.n3

Defines a SCSI disk on target (unit) id n2, controller (host adapter) n1, and LUN (logical unit number) n3. A single number specifies a target, while two numbers specify target. lun, with the missing numbers defaulting to zero. Any one of the numbers may be replaced by $\langle m-n \rangle$ to represent the values m through n inclusive. M may be greater than n. For example, (w<1-4>) is the concatenation of SCSI targets 1 through 4.

hn1.n2.n3

H is similar to *w*, but for IDE or ATA disks, and the controllers must be specified in plan9.ini. *Lun* is ignored. *Target* 0 is an IDE master and 1 is a slave. Instead of specifying *controller* and *target* separately, one may omit the *controller* and specify a target of *controller*-number*2 + *target*-number, thus h2 is equivalent to h1.0.0 (second IDE controller, master drive).

m*n*1.*n*2.*n*3

M is similar to *h*, but for SATA drives connected to Marvell 88SX[56]0[48][01] controllers. There is no need to specify the controllers in plan9.ini as they are autodiscovered. Hot-swapping drives is not currently supported. Similar target naming rules apply as for IDE controllers. However the controller-number is multiplied by the number of drives the

controller supports rather than 2. Thus m9 is equivalent to m1.1.0 (second controller, second drive), if the first controller supports 8 drives.

ln1.n2.n3

rn1.n2.n3

The same as w, but leaving a single block at the beginning for a label (1), or not. Only n2 is really of interest, and refers to a side of a WORM disc. These are only really relevant when used as *device3* in the j device (see below).

(device...)

A pseudo-device formed from the concatenation of the *devices* in the list. The devices are *not* blank- or comma-separated.

[device...]

A pseudo-device formed from the block-wise interleaving of the *devices* in the list. The size of the result is the number of devices times the size of the smallest device.

{ device... }

A pseudo-device formed from the mirroring of the first *device* in the list onto all the others. The size of the result is the size of the smallest device. One might think of this as RAID 1, and [] as RAID 0, though neither includes any fancy recovery mechanisms. Each block is written to all the devices, starting with the rightmost in the list and working leftward. A block is read from the first device that provides it without error, starting with the leftmost in the list and working rightward.

pdevice.n1.n2

A partition starting at n1% from the beginning of *device* with a length n2% of the size of the device. Parenthesize *device* if it contains periods.

x device

A pseudo-device that contains the byte-swapped contents of *device*. Since the file server writes integers to disk in its native byte order, it can be necessary to use this device to read file systems written by processors of the other byte order.

j(device1 device2...)device3

Device1 is the SCSI juke box interface. The *device2*s are the SCSI drives in the jukebox and *device3* represents the demountable platters in the juke box.

f device

A pseudo-WORM disk: blocks on *device* can be written only once and may not be read unless written.

c device1 device2

A cached WORM. The first *device* is the cache, the second the WORM.

o (Letter o) The read-only (dump) file system of the most-recently defined cached WORM file system.

Configuration

The service command sets the textual name of the server as known in the network databases.

The configuration information is stored in block zero on a device whose device string is written in non-volatile RAM. The config and nvram commands identify the *device* on which the information is recorded. The config command also erases any previous configuration.

The *filsys* command configures a file system on *device* and calls it *name*. *Name* is used as the specifier in attach messages to connect to that file system. (The file system main is the one attached to if the specifier is null; see *attach*(5)).

The rest of the configuration commands record IP addresses: the file server's address (*ip*), the local gateway's (*ipgw*), the local authentication server's (*ipauth*), the local subnet mask (*ipmask*), and the address of a system running an SNTP server (*ipsntp*). *Ipauth* is no longer used. If the server has more than one network interface, a digit may be appended to the keywords ip, ipgw and ipmask to indicate the interface number; zero is the default.

One-time actions

The *ream* command initializes the named file system. It overwrites any previous file system on the same device and creates an empty root directory on the device. If *name* is main, the file server,

until the next reboot, will accept wstat messages (see stat(5)) that change the owner and group of files, to enable initializing a fresh file system from a mkfs(8) archive.

For the *recover* command, the named file system must be a cached WORM. *Recover* clears the associated magnetic cache and initializes the file system, effectively resetting its contents to the last dump.

Allow turns off all permission checking; use with caution.

Readonly disables all writing to all devices. This is useful for trying dangerous experiments.

Noauth disables authentication.

Noattach prevents attachs.

Copyworm will copy a file system named *main* to one named *output*, block by block, and loop. It knows how to read a fake worm file system.

Copydev will copy the device *from-dev* to the device *to-dev*. block by block, and panic.

Halt will cause the server to immediately exit and reboot.

The various configuration commands only record what to do; they write no data to disk. The command *end* exits config mode and begins running the file server proper. The server will then perform whatever I/O is required to establish the configuration.

EXAMPLE

Initialize a file server kgbsun with a single file system interleaved between SCSI targets 3 and 4.

```
service kgbsun
config w3
filsys main [w<3-4>]
ream main
```

Initialize a file server kremvax with a single disk on target 0 partitioned as a cached pseudo-WORM file system with the cache on the third quarter of the drive and the pseudo-WORM on the interleave of the first, second, and fourth quarters.

```
service kremvax
config p(w0)50.1
filsys main cp(w0)50.25f[p(w0)0.25p(w0)25.25p(w0)75.25]
filsys dump o
ream main
```

A complete and complex example: initialize a file server *fsb* with a single SCSI disk on target 0 for a scratch file system, a cached WORM file system with cache disk on target 2 and an optical-disc jukebox on targets 4 (robotics) and 5 (one optical drive), and another cached WORM file system with cache disk on target 3 and another optical-disc jukebox on a second SCSI bus at targets 3 and 4. Both jukeboxes contain 16 slots of optical discs. It has two Ethernet interfaces and can reach an SNTP server on the first one.

```
service fsb
config w0
filsys main cw2j(w4w5)(l<0-31>)
filsys dump o
filsys hp40fx cw3j(w1.<3-4>.0)(1<0-31>)
filsys hp40fxdump o
filsys other w0
ipauth 0.0.0.0
ipsntp 10.9.0.3
ip0 10.9.0.2
ipgw0 10.9.0.3
ipmask0 255.255.0.0
ip1 10.0.0.2
ipgw1 10.0.0.1
ipmask1 255.255.0.0
ream main
ream hp40fx
```

ream other end

SOURCE

/sys/src/fs/port/config.c

SEE ALSO

Ken Thompson, "The Plan 9 File Server".

fshalt, scram, reboot - halt any local file systems and optionally shut down or reboot the system

SYNOPSIS

```
fshalt[-r]
reboot[kernelpath]
scram
```

DESCRIPTION

Fshalt syncs and halts all local *cwfs*(4) and *hjfs*(4) servers. If given $-\mathbf{r}$, *fshalt* will then reboot the machine. Else it will invoke *scram* to shut down the machine. The halting and rebooting is done by copying all necessary commands into a *ramfs*(4) file system and changing directory there before attempting to halt file systems, so this will work even on standalone machines with their roots on local file systems.

Reboot restarts the machine it is invoked on. If an optional *kernelpath* is specified then the machine will load and start that kernel directly instead of returning to the system rom. (see *cons*(3)).

Scram shuts down the machine it is invoked on.

SOURCE

```
/rc/bin/fshalt
/rc/bin/reboot
/sys/src/cmd/scram.c
```

SEE ALSO

cons(3), reboot(8)

BUGS

On standalone machines, it will be impossible to do anything if scram fails after invoking bare *fshalt*.

Scram is limited to the PC and requires APM or ACPI.

HISTORY

Scram first appeared in 9front (May, 2011).

getflags, usage - command-line parsing for shell scripts

SYNOPSIS

aux/getflags \$*

aux/usage

DESCRIPTION

Getflags parses the flags in its command-line arguments according to the environment variable flagfmt. This variable should be a comma-separated list of flag specifiers. Each flag is a single letter, optionally followed by a colon and a name. It may be followed by a space-separated list of argument names.

Getflags prints an rc(1) script to be evaluated by the calling program. For every flag specified in flagfmt, the generated script sets a corresponding environment variable. If the flag specifier contains :name, the corresponding variable is named name. Otherwise, it is named flagx.

After evaluating the script, the environment variables will be set as follows: If a flag is not present in the argument list, the environment variable will default to the empty list. If the flag is present and takes no arguments, the environment variable will be initialized with the string '1'. If the flag takes arguments, the flag's variable will be initialized with a list of those argument values. The script then sets the variable \$* to the list of remaining non-flag arguments.

The *status* is variable to the empty string on success, or *'usage'* when there is an error parsing the command line.

Usage prints a usage message to standard error. The message is constructed using 0, flagfmt, and args. The program name is taken from 0, as set by rc(1) The list of flags is extracted from flagfmt. The description of positional argument list is taken from args.

EXAMPLE

SOURCE

An example of the script generated:

```
% flagfmt='e:example, x, a:arg with args'
% aux/getflags -exa arg list positional stuff
example=()
flagx=()
arg=()
example=1
flagx=1
arg=(arg list)
*=(positional stuff)
status=''
```

Parse the arguments for *leak*(1):

```
flagfmt='b:showbmp, s:acidfmt, f binary, r res, x width'
args='name | pid list'
if(! ifs=() eval '{aux/getflags $*} || ~ $#* 0){
    aux/usage
    exit usage
}
if(~ $#showbmp 0)
    echo '-b flag not set'
echo $showbmp # named
echo $acidfmt # also named
echo $flagf # default name
echo $flagr # default name
```

```
/sys/src/cmd/aux/getflags.c
```

/sys/src/cmd/aux/usage.c
SEE ALSO
 arg(2)

gpsfs, gpsevermore - GPS time and position service

SYNOPSIS

aux/gpsfs[-d device][-b baud][-s srvname][-m mntpt]

aux/gpsevermore [-d device] [-b baud] [-n baud] [-l location]

DESCRIPTION

Aux/gpsfs reads an NMEA-compatible serial GPS (Global Positioning System) device and provides time and position through a file system, by default mounted on /mnt and implementing /mnt/gps.

It implements four files in the gps directory: position, time, satellites, and raw.

The read-only position file contains one line of information in 9 tab-separated fields:

fix quality	0 means position data invalid, 1 means a 2D position is available, 2 means a 3D position is available. The value is 8, 9, or 10, respectively, when the fix data comes from a file rather than an actual GPS.
zulu time	universal coordinated time encoded as hhmmss followed by the character 'Z'.
system time	time and date converted to the format of <i>time</i> (2).
longitude	in degrees, east of Greenwich is positive, west negative.
latitude	in degrees, positive is north, negative south of the equator.
altitude	above sea level, in meters.
course	degrees, clockwise from true north.
ground speed	in km/h

magnetic deviation (not provided by all GPSs), in degrees, positive is westerly, negative easterly.

The read-only time file contains one line of information in 4 tab-separated fields:

- gps time in time(2) format.
- gps time in nsec (see time(2)) format (ms accuracy).
- system time in nsec format. This is the system time at the time of the gps time sample. The difference between this and the previous field is used in clock synchronization. See timesync(8).
- *validity* the character A meaning sample valid and usable for clock synchronization. The other values are not usable for clock sync: B means valid sample from file playback, V means invalid sample, and W means invalid playback sample.

The read-only satellites file contains information about the current satellite constellation. It consists of one line of general information, followed by zero or more lines, one for each satellite in use. The first line contains two fields:

fix quality same as in the position file.

satellites in view number of satellites above the horizon

Subsequent lines have four fields:

prn satellite ID

elevation above the horizon, degrees.

azimuth direction, degrees from true north

snr Signal to noise ratio, 0 – 99 dB

The contents of these files are refreshed once per second when reading from an actual GPS, and once per 100 ms (giving a speed up of a factor 10) when playing back from file.

The read-only raw file can be read to obtain a copy of the raw NMEA GPS output. *Gpsfs* keeps an internal buffer of 8KB, so the reader must keep up with the output (typically 500 or so bytes per

second).

The -d flag establishes the device the GPS samples are read from. If the device file is not a serial interface, *gpsfs* assumes playback from file and modifies quality parameters as such.

The -b flag specifies the baud rate of the serial line. The standard baud rate for NMEA GPS is 4800 baud, but many device allow changing to higher speeds.

The -s flag specifies the name under which the *gpsfs* service is posted in /srv.

The -m flag specifies a mount other than /mnt.

Evermore

Aux/gpsevermore is used to configure GPSs using an Evermore chipset.

The -d flag specifies the serial device to the GPS.

The -b flag specifies the baud rate of the serial line. The standard baud rate for NMEA GPS is 4800 baud, but many device allow changing to higher speeds.

The -n flag specifies the speed to set the GPS to. When the command finishes, the GPS should be read (and configured) at the new speed.

The -1 flag is sued to specify the location to initialize the GPS to. The format is dd:mm:ssX or dd:mm.mmX or dd.ddX, where dd stands for degrees (one or more digits), mm for minutes and ss for seconds of arc. X is one of W, E, N or S. Longitudes come with W or E, latitudes with N or S. The -1 flag is followed by two such fields, one for longitude, one for latitude. They may be given in a single argument (separated by white space), or in two arguments, in either order. Initialization time is taken from *time*(2).

SEE ALSO

timesync(8), time(2)

FILES

/mnt/gps/position	position, time, speed and heading
/mnt/gps/satellites	satellites in view
/mnt/gps/time	GPS time (millisecond accuracy)
/dev/eia0	default GPS device

SOURCE

/sys/src/cmd/aux/gps

hgignore - syntax for Mercurial ignore files

SYNOPSIS

The Mercurial system uses a file called .hgignore in the root directory of a repository to control its behavior when it finds files that it is not currently managing.

DESCRIPTION

Mercurial ignores every unmanaged file that matches any pattern in an ignore file. The patterns in an ignore file do not apply to files managed by Mercurial. To control Mercurial's handling of files that it manages, see the hg(1) man page. Look for the "-I" and "-X" options.

In addition, a Mercurial configuration file can point to a set of per-user or global ignore files. See the *hgrc*(8) man page for details of how to configure these files. Look for the "ignore" entry in the "ui" section.

SYNTAX

An ignore file is a plain text file consisting of a list of patterns, with one pattern per line. Empty lines are skipped. The "#" character is treated as a comment character, and the "\" character is treated as an escape character.

Mercurial supports several pattern syntaxes. The default syntax used is Python/Perl-style regular expressions.

To change the syntax used, use a line of the following form:

syntax: NAME

where NAME is one of the following:

regexp

Regular expression, Python/Perl syntax.

glob

Shell-style glob.

The chosen syntax stays in effect when parsing all patterns that follow, until another syntax is selected.

Neither glob nor regexp patterns are rooted. A glob-syntax pattern of the form "*.c" will match a file ending in ".c" in any directory, and a regexp pattern of the form "\.c\$" will do the same. To root a regexp pattern, start it with "^".

EXAMPLE

Here is an example ignore file.

```
# use glob syntax.
syntax: glob
*.elc
*.pyc
*~
# switch to regexp syntax.
syntax: regexp
^\.pc/
```

AUTHOR

Vadim Gelfer <vadim.gelfer@gmail.com>

Mercurial was written by Matt Mackall <mpm@selenic.com>.

SEE ALSO

hg(1), hgrc(8).

COPYING

This manual page is copyright 2006 Vadim Gelfer. Mercurial is copyright 2005-2007 Matt Mackall. Free use of this software is granted under the terms of the GNU General Public License (GPL).

hgrc - configuration files for Mercurial

SYNOPSIS

The Mercurial system uses a set of configuration files to control aspects of its behaviour.

FILES

Mercurial reads configuration data from several files, if they exist. The names of these files depend on the system on which Mercurial is installed. *.rc files from a single directory are read in alphabetical order, later ones overriding earlier ones. Where multiple paths are given below, settings from later paths override earlier ones.

(Unix) <install-root>/etc/mercurial/hgrc.d/*.rc, (Unix) <install-root>/etc/mercurial/hgrc Per-installation configuration files, searched for in the directory where Mercurial is installed. <install-root> is the parent directory of the hg executable (or symlink) being run. For example, if installed in /shared/tools/bin/hg, Mercurial will look in /shared/tools/etc/mercurial/hgrc. Options in these files apply to all Mercurial commands executed by any user in any directory.

(Unix) /etc/mercurial/hgrc.d/*.rc, (Unix) /etc/mercurial/hgrc

Per-system configuration files, for the system on which Mercurial is running. Options in these files apply to all Mercurial commands executed by any user in any directory. Options in these files override per-installation options.

(Windows) <install-dir>\Mercurial.ini, or else, (Windows)

HKEY_LOCAL_MACHINE\SOFTWARE\Mercurial, or else, (Windows) C:\Mercurial\Mercurial.ini Per-installation/system configuration files, for the system on which Mercurial is running. Options in these files apply to all Mercurial commands executed by any user in any directory. Registry keys contain PATH-like strings, every part of which must reference a Mercurial.ini file or be a directory where *.rc files will be read.

(Unix) \$HOME/.hgrc, (Windows) %HOME%\Mercurial.ini, (Windows) %HOME%\.hgrc, (Windows) %USERPROFILE%\Mercurial.ini, (Windows) %USERPROFILE%\.hgrc

Per-user configuration file(s), for the user running Mercurial. On Windows 9x, %HOME% is replaced by %APPDATA%. Options in these files apply to all Mercurial commands executed by this user in any directory. Options in thes files override per-installation and per-system options.

(Unix, Windows) <repo>/.hg/hgrc

Per-repository configuration options that only apply in a particular repository. This file is not version-controlled, and will not get transferred during a "clone" operation. Options in this file override options in all other configuration files. On Unix, most of this file will be ignored if it doesn't belong to a trusted user or to a trusted group. See the documentation for the trusted section below for more details.

SYNTAX

A configuration file consists of sections, led by a "[section]" header and followed by "name: value" entries; "name=value" is also accepted.

[spam] eggs=ham green= eggs

Each line contains one entry. If the lines that follow are indented, they are treated as continuations of that entry.

Leading whitespace is removed from values. Empty lines are skipped.

The optional values can contain format strings which refer to other values in the same section, or values in a special DEFAULT section.

Lines beginning with "#" or ";" are ignored and may be used to provide comments.

SECTIONS

This section describes the different sections that may appear in a Mercurial "hgrc" file, the purpose of each section, its possible keys, and their possible values.

decode/encode

Filters for transforming files on checkout/checkin. This would typically be used for newline processing or other localization/canonicalization of files.

Filters consist of a filter pattern followed by a filter command. Filter patterns are globs by default, rooted at the repository root. For example, to match any file ending in ".txt" in the root directory only, use the pattern "*.txt". To match any file ending in ".c" anywhere in the repository, use the pattern "**.c".

The filter command can start with a specifier, either "pipe:" or "tempfile:". If no specifier is given, "pipe:" is used by default.

A "pipe:" command must accept data on stdin and return the transformed data on stdout.

Pipe example:

[encode]

uncompress gzip files on checkin to improve delta compression # note: not necessarily a good idea, just an example *.gz = pipe: gunzip

[decode]

recompress gzip files when writing them to the working dir (we
can safely omit "pipe:", because it's the default)
*.gz = gzip

A "tempfile:" command is a template. The string INFILE is replaced with the name of a temporary file that contains the data to be filtered by the command. The string OUTFILE is replaced with the name of an empty temporary file, where the filtered data must be written by the command.

NOTE: the tempfile mechanism is recommended for Windows systems, where the standard shell I/O redirection operators often have strange effects and may corrupt the contents of your files.

The most common usage is for LF <-> CRLF translation on Windows. For this, use the "smart" convertors which check for binary files:

[extensions] hgext.win32text = [encode] ** = cleverencode: [decode] ** = cleverdecode:

or if you only want to translate certain files:

[extensions] hgext.win32text = [encode] **.txt = dumbencode: [decode] **.txt = dumbdecode:

defaults

Use the [defaults] section to define command defaults, i.e. the default options/arguments to pass to the specified commands.

The following example makes 'hg log' run in verbose mode, and 'hg status' show only the modified files, by default.

[defaults] log = -v status = -m

The actual commands, instead of their aliases, must be used when defining command defaults. The command defaults will also be applied to the aliases of the commands defined.

diff

Settings used when displaying diffs. They are all boolean and defaults to False.

git

Use git extended diff format.

nodates

Don't include dates in diff headers.

showfunc

Show which function each change is in.

ignorews

Ignore white space when comparing lines.

ignorewsamount

Ignore changes in the amount of white space.

ignoreblanklines

Ignore changes whose lines are all blank.

email

Settings for extensions that send email messages.

from

Optional. Email address to use in "From" header and SMTP envelope of outgoing messages.

to

Optional. Comma-separated list of recipients' email addresses.

сс

Optional. Comma-separated list of carbon copy recipients' email addresses.

bcc

Optional. Comma-separated list of blind carbon copy recipients' email addresses. Cannot be set interactively.

method

Optional. Method to use to send email messages. If value is "smtp" (default), use SMTP (see section "[smtp]" for configuration). Otherwise, use as name of program to run that acts like sendmail (takes "-f" option for sender, list of recipients on command line, message on stdin). Normally, setting this to "sendmail" or "/usr/sbin/sendmail" is enough to use sendmail to send messages.

Email example:

[email]

from = Joseph User <joe.user@example.com> method = /usr/sbin/sendmail

extensions

Mercurial has an extension mechanism for adding new features. To enable an extension, create an entry for it in this section.

If you know that the extension is already in Python's search path, you can give the name of the module, followed by "=", with nothing after the "=".

Otherwise, give a name that you choose, followed by "=", followed by the path to the ".py" file (including the file name extension) that defines the extension.

To explicitly disable an extension that is enabled in an hgrc of broader scope, prepend its path with '!', as in 'hgext.foo = !/ext/path' or 'hgext.foo = !' when no path is supplied.

Example for \sim /.hgrc:

[extensions]
(the mq extension will get loaded from mercurial's path)
hgext.mq =
(this extension will get loaded from the file specified)
myfeature = ~/.hgext/myfeature.py

format

usestore

Enable or disable the "store" repository format which improves compatibility with systems that fold case or otherwise mangle filenames. Enabled by default. Disabling this option will allow you to store longer filenames in some situations at the expense of compatibility.

merge-patterns

This section specifies merge tools to associate with particular file patterns. Tools matched here will take precedence over the default merge tool. Patterns are globs by default, rooted at the repository root.

Example:

[merge-patterns] **.c = kdiff3 **.jpg = myimgmerge

merge-tools

This section configures external merge tools to use for file-level merges.

Example ~/.hgrc:

[merge-tools]
Override stock tool location
kdiff3.executable = ~/bin/kdiff3
Specify command line
kdiff3.args = \$base \$local \$other -o \$output
Give higher priority
kdiff3.priority = 1

```
# Define new tool
myHtmlTool.args = -m $local $other $base $output
myHtmlTool.regkey = Software\FooSoftware\HtmlMerge
myHtmlTool.priority = 1
```

Supported arguments: priority;;

The priority in which to evaluate this tool. Default: 0. executable:: Either just the name of the executable or its pathname. Default: the tool name. args:: The arguments to pass to the tool executable. You can refer to the files being merged as well as the output file through these variables: \$base, \$local, \$other, \$output. Default: \$local \$base \$other premerae:: Attempt to run internal non-interactive 3-way merge tool before launching external tool. Default: True binary;; This tool can merge binary files. Defaults to False, unless tool was selected by file pattern match. symlink:: This tool can merge symlinks. Defaults to False, even if tool was selected by file pattern match. checkconflicts:: Check whether there are conflicts even though the tool reported success. Default: False checkchanged:: Check whether outputs were written even though the tool reported success. Default: False fixeol:: Attempt to fix up EOL changes caused by the merge tool. Default: False qui∷ This tool requires a graphical interface to run. Default: False regkey:: Windows registry key which describes install location of this tool. Mercurial will search for this key first under HKEY_CURRENT_USER and then under HKEY_LOCAL_MACHINE. Default: None regname;; Name of value to read from specified registry key. Defaults to the unnamed (default) value. regappend:: String to append to the value read from the registry, typically the executable name of the tool. Default: None

hooks

Commands or Python functions that get automatically executed by various actions such as starting or finishing a commit. Multiple hooks can be run for the same action by appending a suffix to the action. Overriding a site-wide hook can be done by changing its value or setting it to an empty string.

Example .hg/hgrc:

[hooks] # do not use the site-wide hook incoming = incoming.email = /my/email/hook incoming.autobuild = /my/build/hook

Most hooks are run with environment variables set that give added useful information. For each hook below, the environment variables it is passed are listed with names of the form "\$HG_foo".

changegroup

Run after a changegroup has been added via push, pull or unbundle. ID of the first new changeset is in \$HG_NODE. URL from which changes came is in \$HG_URL.

commit

Run after a changeset has been created in the local repository. ID of the newly created changeset is in \$HG_NODE. Parent changeset IDs are in \$HG_PARENT1 and \$HG_PARENT2.

incoming

Run after a changeset has been pulled, pushed, or unbundled into the local repository. The ID of the newly arrived changeset is in \$HG_NODE. URL that was source of changes came is in \$HG_URL.

outgoing

Run after sending changes from local repository to another. ID of first changeset sent is in \$HG_NODE. Source of operation is in \$HG_SOURCE; see "preoutgoing" hook for description.

post-<command>

Run after successful invocations of the associated command. The contents of the command line are passed as \$HG_ARGS and the result code in \$HG_RESULT. Hook failure is ignored.

pre-<command>

Run before executing the associated command. The contents of the command line are passed as \$HG_ARGS. If the hook returns failure, the command doesn't execute and Mercurial returns the failure code.

prechangegroup

Run before a changegroup is added via push, pull or unbundle. Exit status 0 allows the changegroup to proceed. Non-zero status will cause the push, pull or unbundle to fail. URL from which changes will come is in \$HG_URL.

precommit

Run before starting a local commit. Exit status 0 allows the commit to proceed. Non-zero status will cause the commit to fail. Parent changeset IDs are in \$HG_PARENT1 and \$HG_PARENT2.

preoutgoing

Run before collecting changes to send from the local repository to another. Non-zero status will cause failure. This lets you prevent pull over http or ssh. Also prevents against local pull, push (outbound) or bundle commands, but not effective, since you can just copy files instead then. Source of operation is in \$HG_SOURCE. If "serve", operation is happening on behalf of remote ssh or http repository. If "push", "pull" or "bundle", operation is happening on behalf of repository on same system.

pretag

Run before creating a tag. Exit status 0 allows the tag to be created. Non-zero status will cause the tag to fail. ID of changeset to tag is in \$HG_NODE. Name of tag is in \$HG_TAG. Tag is local if \$HG_LOCAL=1, in repo if \$HG_LOCAL=0.

pretxnchangegroup

Run after a changegroup has been added via push, pull or unbundle, but before the transaction has been committed. Changegroup is visible to hook program. This lets you validate incoming changes before accepting them. Passed the ID of the first new changeset in \$HG_NODE. Exit status 0 allows the transaction to commit. Non-zero status will cause the transaction to be rolled back and the push, pull or unbundle will fail. URL that was source of changes is in \$HG_URL.

pretxncommit

Run after a changeset has been created but the transaction not yet committed. Changeset is visible to hook program. This lets you validate commit message and changes. Exit status 0 allows the commit to proceed. Non-zero status will cause the transaction to be rolled back. ID of changeset is in \$HG_NODE. Parent changeset IDs are in \$HG_PARENT1 and \$HG_PARENT2.

preupdate

Run before updating the working directory. Exit status 0 allows the update to proceed. Non-zero status will prevent the update. Changeset ID of first new parent is in \$HG_PARENT1. If merge, ID of second new parent is in \$HG_PARENT2.

tag

Run after a tag is created. ID of tagged changeset is in \$HG_NODE. Name of tag is in \$HG_TAG. Tag is local if \$HG_LOCAL=1, in repo if \$HG_LOCAL=0.

update

Run after updating the working directory. Changeset ID of first new parent is in \$HG_PARENT1. If merge, ID of second new parent is in \$HG_PARENT2. If update succeeded, \$HG_ERROR=0. If update failed (e.g. because conflicts not resolved), \$HG_ERROR=1.

Note: it is generally better to use standard hooks rather than the generic pre- and post- command hooks as they are guaranteed to be called in the appropriate contexts for influencing transactions. Also, hooks like "commit" will be called in all contexts that generate a commit (eg. tag) and not just the commit command.

Note2: Environment variables with empty values may not be passed to hooks on platforms like Windows. For instance, \$HG_PARENT2 will not be available under Windows for non-merge changesets while being set to an empty value under Unix-like systems.

The syntax for Python hooks is as follows:

hookname = python:modulename.submodule.callable

Python hooks are run within the Mercurial process. Each hook is called with at least three keyword arguments: a ui object (keyword "ui"), a repository object (keyword "repo"), and a "hooktype" keyword that tells what kind of hook is used. Arguments listed as environment variables above are passed as keyword arguments, with no "HG_" prefix, and names in lower case.

If a Python hook returns a "true" value or raises an exception, this is treated as failure of the hook.

http_proxy

Used to access web-based Mercurial repositories through a HTTP proxy.

host

Host name and (optional) port of the proxy server, for example "myproxy:8000".

no

Optional. Comma-separated list of host names that should bypass the proxy.

passwd

Optional. Password to authenticate with at the proxy server.

user

Optional. User name to authenticate with at the proxy server.

smtp

Configuration for extensions that need to send email messages.

host

Host name of mail server, e.g. "mail.example.com".

port

Optional. Port to connect to on mail server. Default: 25.

tls

Optional. Whether to connect to mail server using TLS. True or False. Default: False.

username

Optional. User name to authenticate to SMTP server with. If username is specified, password must also be specified. Default: none.

password

Optional. Password to authenticate to SMTP server with. If username is specified, password must also be specified. Default: none.

local_hostname

Optional. It's the hostname that the sender can use to identify itself to the MTA.

paths

Assigns symbolic names to repositories. The left side is the symbolic name, and the right gives the directory or URL that is the location of the repository. Default paths can be declared by setting the following entries.

default

Directory or URL to use when pulling if no source is specified. Default is set to repository from which the current repository was cloned.

default-push

Optional. Directory or URL to use when pushing if no destination is specified.

server

Controls generic server settings.

uncompressed

Whether to allow clients to clone a repo using the uncompressed streaming protocol. This transfers about 40% more data than a regular clone, but uses less memory and CPU on both server and client. Over a LAN (100Mbps or better) or a very fast WAN, an uncompressed streaming clone is a lot faster (~10x) than a regular clone. Over most WAN connections (anything slower than about 6Mbps), uncompressed streaming is slower, because of the extra data transfer overhead. Default is False.

trusted

For security reasons, Mercurial will not use the settings in the .hg/hgrc file from a repository if it doesn't belong to a trusted user or to a trusted group. The main exception is the web interface, which automatically uses some safe settings, since it's common to serve repositories from different users.

This section specifies what users and groups are trusted. The current user is always trusted. To trust everybody, list a user or a group with name "*".

users

Comma-separated list of trusted users.

groups

Comma-separated list of trusted groups.

ui

User interface controls.

archivemeta

Whether to include the .hg_archival.txt file containing metadata (hashes for the repository base and for tip) in archives created by the hg archive command or downloaded via hgweb. Default is true.

debug

Print debugging information. True or False. Default is False.

editor

The editor to use during a commit. Default is \$EDITOR or "vi".

fallbackencoding

Encoding to try if it's not possible to decode the changelog using UTF-8. Default is ISO-8859-1.

ignore

A file to read per-user ignore patterns from. This file should be in the same format as a repository-wide .hgignore file. This option supports hook syntax, so if you want to specify multiple ignore files, you can do so by setting something like "ignore.other = \sim /.hgignore2". For details of the ignore file format, see the *hgignore*(8) man page.

interactive

Allow to prompt the user. True or False. Default is True.

logtemplate

Template string for commands that print changesets.

merge

The conflict resolution program to use during a manual merge. There are some internal tools available:

internal:local

keep the local version

internal:other

use the other version

internal:merge

use the internal non-interactive merge tool

internal:fail

fail to merge

See the merge-tools section for more information on configuring tools. patch;;

command to use to apply patches. Look for 'gpatch' or 'patch' in PATH if unset.

quiet;;

Reduce the amount of output printed. True or False. Default is False. remotecmd;;

remote command to use for clone/push/pull operations. Default is 'hg'. report_untrusted;;

Warn if a .hg/hgrc file is ignored due to not being owned by a trusted user or group. True or False. Default is True.

slash;;

Display paths using a slash ("/") as the path separator. This only makes a difference on systems where the default path separator is not the slash character (e.g. Windows uses the backslash character ("\")). Default is False.

ssh;;

command to use for SSH connections. Default is 'ssh'. strict;;

Require exact command names, instead of allowing unambiguous abbreviations. True or False. Default is False.

style;;

Name of style to use for command output.

timeout;;

The timeout used when a lock is held (in seconds), a negative value means no timeout. Default is 600.

username;;

The committer of a changeset created when running "commit". Typically a person's name and email address, e.g. "Fred Widget <fred@example.com>". Default is \$EMAIL or username@hostname. If the username in hgrc is empty, it has to be specified manually or in a different hgrc file (e.g. \$HOME/.hgrc, if the admin set "username =" in the system hgrc).

verbose;;

Increase the amount of output printed. True or False. Default is False.

web

Web interface configuration.

accesslog

Where to output the access log. Default is stdout.

address

Interface address to bind to. Default is all.

allow_archive

List of archive format (bz2, gz, zip) allowed for downloading. Default is empty.

allowbz2

(DEPRECATED) Whether to allow .tar.bz2 downloading of repo revisions. Default is false.

allowgz

(DEPRECATED) Whether to allow .tar.gz downloading of repo revisions. Default is false.

allowpull

Whether to allow pulling from the repository. Default is true.

allow_push

Whether to allow pushing to the repository. If empty or not set, push is not allowed. If the special value "*", any remote user can push, including unauthenticated users. Otherwise, the remote user must have been authenticated, and the authenticated user name must be present in this list (separated by whitespace or ","). The contents of the allow_push list are examined after the deny_push list.

allowzip

(DEPRECATED) Whether to allow .zip downloading of repo revisions. Default is false. This feature creates temporary files.

baseurl

Base URL to use when publishing URLs in other locations, so third-party tools like email notification hooks can construct URLs. Example: "http://hgserver/repos/"

contact

Name or email address of the person in charge of the repository. Defaults to ui.username or \$EMAIL or "unknown" if unset or empty.

deny_push

Whether to deny pushing to the repository. If empty or not set, push is not denied. If the special value "*", all remote users are denied push. Otherwise, unauthenticated users are all denied, and any authenticated user name present in this list (separated by whitespace or ",") is also denied. The contents of the deny_push list are examined before the allow_push list.

description

Textual description of the repository's purpose or contents. Default is "unknown".

encoding

Character encoding name. Example: "UTF-8"

errorlog

Where to output the error log. Default is stderr.

hidden

Whether to hide the repository in the hgwebdir index. Default is false.

ipv6

Whether to use IPv6. Default is false.

name

Repository name to use in the web interface. Default is current working directory.

maxchanges

Maximum number of changes to list on the changelog. Default is 10.

maxfiles

Maximum number of files to list per changeset. Default is 10.

port

Port to listen on. Default is 8000.

prefix

Prefix path to serve from. Default is " (server root).

push_ssl

Whether to require that inbound pushes be transported over SSL to prevent password sniffing. Default is true.

staticurl

Base URL to use for static files. If unset, static files (e.g. the hgicon.png favicon) will be served by the CGI script itself. Use this setting to serve them directly with the HTTP server. Example: "http://hgserver/static/"

stripes

How many lines a "zebra stripe" should span in multiline output. Default is 1; set to 0 to disable.

style

Which template map style to use.

templates

Where to find the HTML templates. Default is install path.

AUTHOR

Bryan O'Sullivan <bos@serpentine.com>.

Mercurial was written by Matt Mackall <mpm@selenic.com>.

SEE ALSO

hg(1), hgignore(8).

COPYING

This manual page is copyright 2005 Bryan O'Sullivan. Mercurial is copyright 2005-2007 Matt Mackall. Free use of this software is granted under the terms of the GNU General Public License (GPL).

histogram - draw a histogram

SYNOPSIS

```
histogram[-h][-c index][-r minx,miny,maxx,maxy][-s scale][-t title][-v maxv]
```

DESCRIPTION

Histogram reads numbers, one per line, from its standard input and draws them as bars in a histogram.

Use -c to set the color *index* for the graph. A modulus operation on the value keeps the color index within the available range.

Unless -h (*hold*) is given, *histogram* will exit when it reaches the end-of-file. It will exit immediately if it is interrupted or if the *exit* menu option is chosen.

 $-\mathbf{r}$ sets the initial window *rectangle* coordinates.

-s sets the scaling factor.

-t sets the *title* displayed on a line above the histogram. The last value read is displayed to the right of the title.

-v sets the maximum *value* that can be expected.

EXAMPLE

Plot a sine wave:

```
hoc -e 'for(i=0.0;i<20*PI;i=i+0.1) print (10+10*sin(i)), "\n"'|
histogram -t 'sin(t), 0 ≤ t ≤ 20π' -v 20 -h
```

Show the Dow Jones adjusted daily closing price back to January 1, 2000:

SOURCE

/sys/src/cmd/histogram.c

SEE ALSO

statusbar(8)

hjfs - file server maintenance

SYNOPSIS

```
allow
chatty
create path uid gid perm [lad]
df
disallow
dump
echo [on | off]
halt
newuser name [options]
users
sync
debug-chdeind file [offset value]
debug-deind file
debug-getblk file [blk | start end]
```

DESCRIPTION

The following commands should be written to the console of an hjfs(4) file server.

Allow disables permission checking and allows changing file ownership (see chgrp(1)). This may help in initializing a file system. Use this with caution.

Chatty enables chatty 9p.

Create creates a file on the current file system. *Uid* and *gid* are names or numbers from /adm/users. *Perm* is the low 9 bits of the permission mode of the file, in octal. An optional final 1, a, or d creates a locked file, append-only file, or directory.

Df prints the number of free, used and total blocks/megabytes. It scans the block table and can be slow on large hard disks.

Disallow restores permission checking back to normal after a file system has been initialized.

Dump immediately starts a dump.

Echo expects the argument *on* or *off. On* causes all executed commands to be printed on the system console. *Off* reverses the effects of *on.*

Halt exits the program.

Newuser requires a *name* argument. With no options it adds user *name*, with group leader *name*, to /adm/users and makes the directory /usr/name owned by user and group *name*. The options are

:	Add a group: add the name to /adm/users but don't create the directory. By convention, groups are numbered starting from 10000, users from 0.
newname	Rename existing user name to newname.
=leader	Change the leader of <i>name</i> to <i>leader</i> . If <i>leader</i> is missing, remove the existing leader.
+member	Add <i>member</i> to the member list of <i>name</i> .
– member	Remove existing <i>member</i> from the member list of <i>name</i> .

After a successful *newuser* command the file server overwrites /adm/users to reflect the internal state of the user table.

Users reads the contents of file /adm/users to initialize the file server's internal representation of the users structure.

Sync writes dirty blocks in memory to the magnetic disk cache.

Note: Debug commands operate on internal data structures; they are inherently dangerous and can cause file system damage.

Debug-chdeind changes the value of the byte at the specified *offset* in the in-memory directory entry and prints the old *value*. Dangerous if used carelessly.

Debug-deind requires a file argument. It prints the directory entry of file.

Debug-getblk prints the physical blocks of *file* corresponding to the logical block *blk* or the logical blocks between *start* and *end*.

EXAMPLES

Check disk usage (output appears on the system console).

% echo df >>/srv/hjfs.cmd

SEE ALSO

hjfs(4)

SOURCE

/sys/src/cmd/hjfs

BUGS

Debug-chdeind should perhaps be less crazy and have a portable interface.

httpd, save, imagemap, man2html, webls - HTTP server

SYNOPSIS

ip/httpd/httpd [-a srvaddr] [-c cert [-C certchain]] [-d domain] [-n namespace] [-w webroot]

ip/httpd/save [-b inbuf] [-d domain] [-r remoteip] [-w webroot] [-N netdir] method version uri [search]

ip/httpd/imagemap ...
ip/httpd/man2html ...

ip/httpd/webls ...

DESCRIPTION

Httpd serves the *webroot* directory of the file system described by *namespace* (default /lib/namespace.httpd), using version 1.1 of the HTTP protocol. It announces the service *srvaddr* (default tcp!*!http), and listens for incoming calls. If an X.509 certificate is supplied with the -c option, then the service is instead tcp!*!https. There should already be a facto-tum holding the corresponding private key. If the specified certificate has been signed by a certificate authority, the -C option may be used to specify a file containing a chain of signed certificates.

Httpd supports only the GET and HEAD methods of the HTTP protocol; some magic programs support POST as well. Persistent connections are supported for HTTP/1.1 or later clients; all connections close after a magic command is executed. The Content-type (default

application/octet-stream) and Content-encoding (default binary) of a file are determined by looking for suffixes of the file name in /sys/lib/mimetype.

Redirection

Each requested URI is looked up in a redirection table, read from /sys/lib/httpd.rewrite. Fields are separated by spaces and tabs. Anything following a # is ignored. The first field of each line is a URI; the second a replacement path. If a prefix of the URI matches a redirection path, the URI is rewritten using the corresponding replacement path instead of the prefix, and a temporary redirect is sent to the HTTP client. If the replacement path does not specify a server name, and the request has no explicit host, then *domain* is the host name used in the redirection. The prefix can either be a domain root like http://system/ (which matches that URL only) or a path like /who/rob (which matches that path no matter what the requested server), but not both: http://system/who/rob will never match a request. If the first field ends in a slash, this is an exact match; otherwise it is a prefix match. The first field is a literal string, matched against each file prefix of each URL. The most specific, i.e., longest, pattern wins, and is applied once (there is no rescanning), except for the following exceptions. *Httpd* omits the unmatched part of the original URI from the rewritten URI if the replacement is prefixed with *. This permits many-toone mappings; for example, to send all references to an old subtree to a single error page.

Httpd handles replacements prefixed with @ internally, treating the request as if it were for the replacement (without the @) but not informing the client of the rewritten name. Replacement URLs prefixed with = generate a permanent redirection instead of a temporary one. *Httpd* checks to see if this file has changed once every 50 new TCP connections. HTTP 1.1 persistent connection implies many pages may come in one browser connection, so to kick-start *httpd*, try

for(i in '{seq 50}) hget http://www.your-domain.com/ >/dev/null

Access Control

Before opening any file, *httpd* looks for a file in the same directory called .httplogin. If the file exists, the directory is considered locked and the client must specify a user name and password matching a pair in the file. .httplogin contains a list of space or newline separated tokens, each possibly delimited by single quotes. The first is a domain name presented to the HTTP client. The rest are pairs of user name and password. Thus, there can be many user name/password pairs valid for a directory.

Auxiliaries (magic)

If the requested URI begins with /magic/server/, httpd executes the file /bin/ip/httpd/server to finish servicing the request. All the auxiliaries take the same

arguments. *Method* and *version* are those received on the first line of the request. *Uri* is the remaining portion of the requested URI. *Inbuf* contains the rest of the bytes read by the server, and *netdir* is the network directory for the connection. There are routines for processing command arguments, parsing headers, etc. in the httpd library,

/sys/src/cmd/ip/httpd/libhttpd.a.\$0. See httpd.h in that directory and existing
magic commands for more details.

Save writes a line to /usr/web/save/uri.data and returns the contents of /usr/web/save/uri.html. Both files must be accessible for the request to succeed. The saved line includes the current time and either the search string from a HEAD or GET or the first line of the body from a POST. It is used to record form submissions.

Imagemap processes an HTML imagemap query. It looks up the point *search* in the image map file given by *uri*, and returns a redirection to the appropriate page. The map file defaults to NCSA format. Any entries after a line starting with the word #cern are interpreted in CERN format.

Man2html converts *man*(6) format manual pages into html. It includes some abilities to search the manuals.

Webls produces directory listings on the fly, with output in the style of *ls*(1). /sys/lib/webls.allowed and /sys/lib/webls.denied contain regular expressions describing what parts of *httpd*'s namespace may and may not be listed, respectively. Webls.denied is first searched to see if access is by default denied. If so webls.allowed is then searched to see if access is explicitly allowed. Thus one can have very general expressions in the denied list (like .*), yet still allow exceptions. If webls.denied does not exist or is unreadable, all accesses are assumed to be denied unless explicitly allowed in webls.allowed.

Other sites will note that if neither webls.denied nor webls.allowed exist, any portion of *httpd's* namespace can be listed (however, *webls* will always endeavor to prevent listing of '.' and '..'). If webls.allowed exists but webls.denied does not, any directory to be listed must be described by a regular expression in webls.allowed. Similarly, if webls.denied exists but webls.allowed does not, any directory to be listed must *not* be described by a regular expression in webls.denied and set is denied by a regular expression in webls.denied. If both exist, a directory is listable if either it doesn't appear in webls.denied, or it appears in both webls.denied and webls.allowed. In other words, webls.allowed overrides webls.denied. If a listing for a directory is requested and access is denied, or another error occurs, a simple error page is returned.

EXAMPLES

These are all examples of how to use httpd.rewrite.

A local redirection:

	<pre>/netlib/c++/idioms/index.html.Z /netlib/c++/idioms/index.html</pre>				
	Redirection to another site: /netlib/lapack/lawn http://inferno.bel		=http://netlib.org/lapack/lawns =http://www.vitanuova.com		
	Root directory for virtual host: http://www.ampl.com	m /cm/	cs/what/ampl		
;					
	/sys/lib/mimetype /lib/namespace.httpd /sys/lib/httpd.rewrite /sys/lib/webls.allowed	redirection file	bace file for httpd sions describing explicitly listable pathnames;		
	/sys/lib/webls.denied	regular expres	sions describing explicitly unlistable pathnames		
RCE					

SOURCE

FILES

/sys/src/cmd/ip/httpd

SEE ALSO

newns in auth(2), listen(8), rsa(8)

icanhasmsi – print MSI configuration

SYNOPSIS

aux/icanhasmsi

DESCRIPTION

Prints information about Message Signaled Interrupt (MSI) devices found on the system, one line per device.

SOURCE

/sys/src/cmd/aux/icanhasmsi.c

SEE ALSO

pci(8), *pnp*(3)

BUGS

Should probably be renamed to *msi* or merged with *pci*(8).

HISTORY

Icanhasmsi first appeared in 9front (May, 2011).

init – initialize machine upon booting

SYNOPSIS

/\$cputype/init[-ctm][command...]

DESCRIPTION

Init initializes the machine: it establishes the name space (see namespace(4) and newns in auth(2)), and environment (see env(3)) and starts a shell (rc(1)) on the console. If a command is supplied, that is run instead of the shell. On a CPU server the invoked shell runs cpurc(8) before accepting commands on the console; on a terminal, it runs termrc and then the user's profile. Options -t (terminal) and -c (CPU) force the behavior to correspond to the specified service class. Otherwise *init* uses the value of the environment variable service to decide the service class.

Init sets environment variables service (either to the incoming value or according to -t or -c), objtype (to the value of cputype), user (to the contents of #c/user), and timezone (to the contents of /adm/timezone/local).

With option -m *init* starts only an interactive shell regardless of the *command* or service class.

On a CPU server, *init* requires the machine's password to be supplied before starting *rc* on the console.

Init is invoked by *boot*(8), which sets the arguments as appropriate.

SOURCE

/sys/src/cmd/init.c

SEE ALSO

rc(1), auth(2), boot(8)

ipconfig, rip, linklocal - Internet configuration and routing

SYNOPSIS

ip/ipconfig [-6DGNOPdnpruX] [-b baud] [-c ctl] [-g gateway] [-h host] [-m mtu] [-o dhcp-opt] [-f dbfile] [-x netmtpt] [type [device]] [verb] [local [mask [remote [file-server [auth]]]]]

ip/rip [-bdr] [-x netmtpt]

ip/linklocal[-t gwipv4] mac...

DESCRIPTION

Ipconfig binds a device interface to a mounted IP stack (default /net) and configures the interface with a local address and optionally a mask, a remote address, a file server and an authentication server address. If no device is specified, the first ether device on the mounted IP stack is used. The addresses can be specified in the command line or obtained via DHCP. If DHCP is requested, it will also obtain the addresses of DNS servers, NTP servers, gateways, a Plan 9 file server, and a Plan 9 authentication server. Information from DHCP and IPv6 router advertisements is written to /net/ndb in the form of an ndb(8) entry unless the P flag has been specified.

Type may be ether, gbe, ppp, pkt, or loopback. The gbe type is equivalent to ether except that it allows jumbo packets (up to ~9KB). The pkt interface passes all IP packets to and from a user program. For ppp the device can be any byte stream device.

The verb (default *add*) determines the action performed. The usual verbs are:

- add if the device is not bound to the IP stack, bind it. Add the given local address, mask, and remote address to the interface. An interface may have multiple addresses. remove the address from the device interface.
- unbind unbind the device interface and all its addresses from the IP stack.

The IPv6-specific verbs, which take different arguments, are:

- add6 *prefix pfx-len onlink auto validlt prefit* sets the named IPv6 parameters; see *ip*(3) for more detail.
- ra6 [keyword value]...

sets IPv6 router advertisement parameter *keyword*'s *value*. See ip(3) for more detail. Setting *recvra* non-zero also forks a process to receive and process router advertisements. Setting *sendra* non-zero also enables IP routing on the interface, forks a process to send router advertisements, and if no *recvra* process is running, forks one.

The options are:

- 6 if adding an address (the default action), add the IPv6 link-local address.
- b the baud rate to use on a serial line when configuring PPP.
- c write the control string *ctl* to the ethernet device control file before starting to configure it. May be repeated to specify multiple control writes.
- d use DHCP to determine any unspecified configuration parameters.
- D turn on debugging.
- g the default gateway.
- G use only generic DHCP and RA options. Without this option, *ipconfig* adds to requests a Vendor Class option with value plan9_\$ *cputype* and also requests vendor specific options 128 and 129 which we interpret as the Plan 9 file server and auth server. Replies to these options contain a list of IP addresses for possible file servers and auth servers.
- h the hostname to add to DHCP requests. Some DHCP servers, such as the one used by Comcast, will not respond unless a correct hostname is in the request.
- m the maximum IP packet size to use on this interface.
- n determine parameters but don't configure the interface.

- N look in *dbfile* (default /lib/ndb/local) for the IP parameters for the specified *local* IP address or if *local* is omited and the device is an ethernet then all IP parameters associated with the MAC address. IPv6 addresses are added only if a IPv6 link-local address exists on the interface or the 6 flag has been given to automatically configure one.
- 0 addresses specified on the command line override those obtained via DHCP. A command line address of 0 implies no override.
- p write configuration information to /net/ndb.
- P do not write configuration information to /net/ndb.
- r by default, *ipconfig* exits after trying DHCP for 15 seconds with no answer. This option directs *ipconfig* instead to fork a background process that keeps trying forever.
- u disable IPv6 duplicate discovery detection, which removes any existing ARP table entry for one of our IPv6 addresses before adding new ones.
- f use the ndb database file *dbfile*.
- x use the IP stack mounted at *netmtpt* instead of at /net.
- X don't fork a process to keep the DHCP lease alive.
- o adds *dhcpoption* to the list of paramters requested of the DHCP server. The result will appear in /net/ndb should this be the first interface. The known options are:

arptimeout, baddr, bflen, bootfile, clientid, cookie, discovermask, discoverrouter, dns, dom, dumpfile, etherencap, extpath, finger, homeagent, impress, ipaddr, ipforward, ipgw, ipmask, irc, lease, log, lpr, maxdatagram, maxmsg, message, mtu, name, netbiosdds, netbiosns, netbiosscope, netbiostype, ni, nisdomain, nisplus, nisplusdomain, nntp, nonlocal, ntp, overload, params, pathplateau, pathtimeout, policyfilter, pop3, rebindingtime, renewaltime, rl, rootpath, rs, serverid, smtp, st, staticroutes, stdar, subnetslocal, supplymask, swap, sys, tcpka, tcpkag, tcpttl, tftp, time, timeoff, trailerencap, ttl, type, vendorclass, www, xdispmanager, xfont

The options ipmask, ipgw, dns, sys, and ntp are always requested.

If DHCP is requested, a process is forked off to renew the lease before it runs out. If the lease does run out, this process will remove any configured addresses from the interface.

Rip runs the routing protocol RIP. It listens for RIP packets on connected networks and updates the kernel routing tables. The options are:

- b broadcasts routing information onto the networks.
- n gathers routing information but doesn't write to the route table. This is useful with -d to debug a network.
- x use the IP stack mounted at *netmtpt* instead of at /net.
- d turn on (voluminous) debugging.

Linklocal prints the IPv6 link-local address corresponding to the given mac address. Given -t, linklocal instead prints the 6to4 EUI-64-based IPv6 address corresponding to mac and 6to4 gateway gwipv4.

EXAMPLES

Configure Ethernet 0 as the primary IP interface. Get all addresses via DHCP. Start up a connection server and DNS resolver for this IP stack.

% bind -b '#10' /net % bind -a '#10' /net % ip/ipconfig % ndb/cs % ndb/dns -r Add a second address to the stack.

% ip/ipconfig ether /net/ether0 add 12.1.1.2 255.255.255.0

At Bell Labs, our primary IP stack is always to the company's internal firewall-protected network. The following creates an external IP stack to directly access the outside Internet. Note that the connection server uses a different set of *ndb* files. This prevents us from confusing inside and outside name/address bindings.

% bind -b '#l1' /net.alt % bind -b '#I1' /net.alt % ip/ipconfig -x /net.alt -g 204.178.31.1 ether /net.alt/ether1\ 204.178.31.6 255.255.255.0 % ndb/cs -x /net.alt -f /lib/ndb/external % ndb/dns -sx /net.alt -f /lib/ndb/external % aux/listen -d /rc/bin/service.alt /net.alt/tcp Configure the IPv6 link-local address automatically and listen for router announcements.

ip/ipconfig -6 ip/ipconfig ra6 recvra 1

FILES

/sys/log/ipconfig

SOURCE

/sys/src/cmd/ip/ipconfig
/sys/src/cmd/ip/rip.c
/sys/src/cmd/ip/linklocal.c

SEE ALSO

ether(3), ip(3), loopback(3), ndb(6), 6in4(8), dhcpd(8), ppp(8)
/lib/rfc/rfc2373 for IPv6's modified EUI-64

telnetd, rlogind, rexexec, ftpd, socksd, hproxy - Internet remote access daemons

SYNOPSIS

ip/telnetd[-adnptN][-u user]

ip/rlogind

ip/rexexec

ip/ftpd [-aAde] [-n namepace-file]

ip/socksd[-x inside][-o outside]

ip/hproxy

DESCRIPTION

These programs support remote access across the Internet. All expect the network connection to be standard input, output, and error. They are normally started from scripts in /rc/bin/service (see *listen*(8)).

Telnetd allows login from a remote client. There are three types of login:

normal Normal users log in by encrypting and returning a challenge printed by telnetd. The user can use either the netkey program (see passwd(1)) or a SecureNet handheld authenticator to encrypt the challenge. /lib/namespace defines the namespace. Users in group noworld in /adm/users authenticate with a password in the clear. /lib/namespace.noworld defines the namespace.

anonymous User none requires no authentication. /lib/namespace defines the namespace.

Telnetd's options are:

- a allow anonymous login by none
- d print debugging to standard error
- p don't originate any telnet control codes
- n turn on local character echoing and imply the p option
- t trusted, that is, don't authenticate
- u use *user* as the local account name
- N permit connections by 'noworld' users only.

Rlogind logs in using the BSD remote login protocol. *Rlogind* execs *telnetd* – nu after completing its initial handshake.

Rexexec executes a command locally for a remote client. It uses the standard Plan 9 authentication (see *authsrv*(6)).

Ftpd runs the Internet file transfer protocol. Users may transfer files in either direction between the local and remote machines. As for *telnetd*, there are three types of login:

normal	nal Normal users authenticate via the same challenge/response as for <i>telnetd</i> .		
	/usr/username/lib/namespace.ftp or, if that file does not exist,		
	/lib/namespace defines the namespace.		
noworld	Users in group noworld in /adm/users login using a password in the clear.		
	/lib/namespace.noworld defines the namespace.		
anonymous	Users anonymous and none require no authentication. The argument to the -n		
	option (default <i>/lib/namespace.ftp</i>) defines the namespace. Anonymous users may		

only store files in the subtree below /incoming.

Ftpd's options are:

- a allow anonymous access
- A allow *only* anonymous access
- d write debugging output to standard error
- e treat any user as anonymous

n the namespace for anonymous users (default /lib/namespace.ftp)

To preserve intended protections in shared file trees, any directory containing a file *.httplogin* is locked by *ftpd*; see *httpd*(8).

Socksd is a SOCKS4 and SOCKS5 proxy server allowing non Plan9 machines to access the outside network. The net to use for outgoing calls can be specified with the -o outside and the internal network is specified with -x inside (for UDP relay). If not specified, inside and outside will default to /net.

Hproxy is a simple HTTP proxy server.

FILES

/lib/namepace
/usr/username/lib/namespace.ftp
/lib/namespace.world
/lib/namespace.ftp

SOURCE

```
/sys/src/cmd/ip/telnetd.c
/sys/src/cmd/ip/rlogind.c
/sys/src/cmd/ip/rexexec.c
/sys/src/cmd/ip/ftpd.c
/sys/src/cmd/ip/socksd.c
/sys/src/cmd/ip/hproxy.c
```

SEE ALSO

ftpfs(4), pop3(8)

HISTORY

Hproxy first appeared in 9front (July, 2012). Socksd first appeared in 9front (March, 2012).

kbdfs, console - keyboard and console filesystem

SYNOPSIS

aux/kbdfs[-Dd][-s srv][-m mntpnt][consfile]

```
mount -b /srv/cons /dev
/dev/cons
/dev/consctl
/dev/kbd
/dev/kbdin
/dev/kbin
/dev/kbin
```

console [cmd args...]

DESCRIPTION

Started on *boot*(8), *kbdfs* translates raw keyboard scancodes from /dev/scancode (see *kbd*(3)) and its kbin and kbdin file and optionally reads console input from *consfile* to provide initial keyboard and console input.

It serves a one-level directory containing the files cons, consctl, kbd, kbdin, kbin and kbmap.

The -D flag enables a debug trace of 9p messages and -d prevents *kbdfs* from making its memory private.

The -s option causes *kbdfs* to post its channel on /srv/srv. On system startup, *boot*(8) sets this to cons. With the -m option, *kbdfs* mounts itself on *mntpnt* (see *bind*(2)), otherwise on /dev (the default).

The console command executes *cmd* (defaults to the system shell) under its own *kbdfs* instance providing a serial console if \$console environment variable is set.

Console

Reading the cons file returns characters typed on the console. Normally, characters are buffered to enable erase and kill processing. A control–U, \wedge U, typed at the keyboard *erases* the current input line (removes all characters from the buffer of characters not yet read via cons), and a back-space *erases* the previous non–kill, non–erase character from the input buffer. The combination control–W, \wedge W, deletes the input last word. Killing and erasing only delete characters back to, but not including, the last newline. Characters typed at the keyboard actually produce 16–bit runes (see *utf*(6)), but the runes are translated into the variable–length UTF encoding (see *utf*(6)) before putting them into the buffer. A *read*(2) of a length greater than zero causes the process to wait until a newline or a \wedge D ends the buffer, and then returns as much of the buffer as the argument to read allows, but only up to one complete line. A terminating \wedge D is not put into the buffer. If part of the line remains, the next read will return bytes from that remainder and not part of any new line that has been typed since.

If the string rawon has been written to the consctl file and the file is still open, cons is in *raw mode*: characters are not echoed as they are typed, backspace, \land U, \land W and \land D are not treated specially, and characters are available to read as soon as they are typed. Ordinary mode is reentered when rawoff is written to consctl or this file is closed.

A write (see *read*(2)) to cons causes the characters to be printed on the console screen.

When a *consfile* is passed to *kbdfs*(8) as its last argument, it reads and processes the characters from that file and forwards them to the cons file with the same text processing applied as on keyboard input. This is used to provide a serial console when \$console environment variable is set. (see *plan9.ini*(8)).

Keyboard

A read on the kbd file returns the character k, K or c followed by a null terminated, variablelength, UTF encoded string. The k message is sent when a key is pressed down and K when a key is released. The following string contains all the keycodes of the keys that are currently pressed down in unshifted form. This includes all keys that have a keyboard mapping and modifier keys. The string following the c message contains the single character that would have been returned on the cons file instead. The c message will be resent at the keyboard repeat rate. A single *read*(2) can return multiple concatenated messages at once (delimited by the null byte) or block when there are no messages queued. Opening the kbd file disables input processing on the cons file until it is closed again.

K, k and c messages can be written to kbdin and will forwarded to the reader of cons or kbd. Writing a r or R message followed by a UTF encoded rune will simulate the press or release of that particular rune.

Raw scancodes can be written to the kbin file for external keyboard input (used for USB keyboards).

Keyboard map

Scancodes are mapped to Unicode characters with a number of translation tables. These tables can be accessed with the kbmap file.

Reads return the current contents of the map. Each entry is one line containing three 11 character numeric fields, each followed by a space: a table number, an index into the table (scan code), and the decimal value of the corresponding Unicode character (0 if none). The table numbers are platform dependent; they typically distinguish between unshifted and shifted keys. The scan code values are hardware dependent and can vary from keyboard to keyboard.

Writes to the file change the map. Lines written to the file must contain three space-separated fields, representing the table number, scan code index, and Unicode character. Values are taken to be decimal unless they start with 0x (hexadecimal) or 0 (octal). The Unicode character can also be represented as 'x where x gives the UTF-8 representation of the character (see utf(6)), or as $\wedge X$ to represent a control character.

SEE ALSO

cons(3), keyboard(6), utf(6), kbd(3), plan9.ini(8)

FILES

/sys/lib/kbmap/*

SOURCE

/sys/src/cmd/aux/kbdfs
/rc/bin/console

HISTORY

Kbdfs first appeared in 9front (May, 2011).

listen, listen1, tcp7, tcp9, tcp19, tcp21, tcp23, tcp25, tcp53, tcp110, tcp113, tcp143, tcp445, tcp513, tcp515, tcp564, tcp565, tcp566, tcp567, tcp993, tcp995, tcp1723, tcp17007, tcp17008, tcp17009, tcp17010, tcp17013, tcp17019, tcp17020 – listen for calls on a network device

SYNOPSIS

aux/listen [-iq] [-d srvdir] [-t trustsrvdir] [-n namespace] [-p maxprocs] [-a addr]
[proto]

aux/listen1[-1tv][-p maxprocs][-n namespace] addr cmd[args...]

DESCRIPTION

Listen listens on a network for inbound calls to local services. Proto is the network protocol on which to listen, by default tcp. Incoming calls to any address * are accepted unless *addr* is specified with the –a option. The services available are executable, non-empty files in *srvdir* or *trustsrvdir*. If neither *srvdir* nor *trustsrvdir* is given, *listen* looks for executable files in /bin/service. Services found in *srvdir* are executed as user none; services found in *trustsrvdir* are executed as the user who started *listen*. When changing user to none, a new namespace is created, usually by executing /lib/namespace, but –n selects an alternate *namespace*. The –p option limits the number of processes that *listen* spawns to service the connections. If the *maxprocs* limit is reached, *listen* will log the event and delay servicing until the number of connection processes drops below the limit again. A *maxprocs* smaller or equal zero means no limit (default). Option –q suppresses affirmative log information. Option –i suppresses the periodic scan of the service directories for changes.

Service names are made by concatenating the name of the network with the name of the service or port. For example, an inbound call on the TCP network for port 565 executes service tcp565.

At least the following services are available in /bin/service.

tcp564	serve a piece of the name space using the Plan 9 file system protocol, with authenti-
	cation via <i>Tauth</i> (in <i>attach</i> (5)), no encryption, and multiplex multiple users on a sin-
	gle connection (used by <i>srv</i> (4), and also by Unix systems to see Plan 9 files).
tcp17007	serve a piece of the name space using the Plan 9 file system protocol, with authenti-

- cation at the start, optional SSL encryption, and no multiplexing of users (typically used by *cpu*(1) and *import*(4)). Not usable by user *none*.
- tcp17008 like tcp17007, but serves the root of the tree, forgoing the negotiation for which subtree to serve.
- tcp17009 *rx* remote execution.
- tcp17010 server for *cpu*(1) command.
- tcp17013 server for old *cpu*(1) command for compatibility with old clients.
- tcp17019 server for *rcpu*(1), replaces *rx*, *import*(4) and *cpu*(1) using TLS for encryption.
- tcp17020 TLS encrypted 9P fileserver (t9fs) for *srvtls* (see *srv*(4)).
- tcp7 echo any bytes received (bit mirror)
- tcp9 consume any bytes received (bit bucket)
- tcp19 chargen service.
- tcp21 FTP daemon
- tcp23 telnet terminal connection.
- tcp25 mail delivery.
- tcp53 TCP port for DNS.
- tcp110 POP3 port.
- tcp113 Ident port (always reports none).
- tcp143 IMAP4rev1 port.
- tcp445 CIFS/SMB file sharing.
- tcp513 rlogin terminal connection.
- tcp515 LP daemon; see lp(8).
- tcp565 report the address of the incoming call.
- tcp993 Secure IMAP4rev1 port.
- tcp995 Secure POP3 port.
- tcp1723 PPTP (point-to-point tunnelling protocol) service.

At least the following services are available in /bin/service.auth, the usual *trustsrvdir*.

tcp566 validate a SecureNet box.

tcp567 Plan 9 authentication-ticket service.

Listen1 is a lightweight listener intended for personal use, modeled from Inferno's *listen*(1). It announces on *address*, running *cmd args...* for each incoming connection; the network directory is passed in the environment as \$net. Option -t causes *listen1* to run as the invoking user; the default is to become none before listening. Option -1 arms a one-shot listener; it terminates listen1 upon receiving a single call. Option -v causes verbose logging on standard output. See /rc/bin/tlssrvtunnel for an example.

FILES

/net/tcp by convention, TCP device bind point

SOURCE

/sys/src/cmd/aux/listen*.c
/rc/bin/service*

SEE ALSO

authsrv(6), dial(2)

BUGS

Srvdir, trustsrvdir and namespace must all be absolute path names.

lp – PostScript preprocessors

DESCRIPTION

These programs are part of the lp(1) suite. Each corresponds to a *process* in the -p *process* option of lp and exists as an rc(1) script in /sys/lib/lp/process that provides an interface to a PostScript conversion program in /\$cputype/bin/aux. The list of processors follows; after each description is a bracketed list of lp options to which the processor responds:

dpost	converts <i>troff</i> (1) output for device post to PostScript. This is used for files troff'ed on our UNIX systems that do not handle UTF characters. [DLcimnorxy]
dvipost g3post	converts tex output to PostScript. [Lcinor] converts CCITT Group 3 FAX data to PostScript. [DLm]
gifpost generic	converts GIF image data to PostScript. [DLm] is the default processor. It uses <i>file</i> (1) to determine the type of input and executes the correct processor for a given (input, printer) pair.
hpost	adds a header page to the beginning of a PostScript printer job so that it may be sepa- rated from other jobs in the output bin. The header has the image of the job's owner from the directory of faces (see <i>face</i> (6)). Page reversal is also done in this processor.
jpgpost	converts JPEG image data to PostScript. [DLm]
noproc	passes files through untouched.
p9bitpost	converts a Plan 9 image to PostScript, such as /dev/screen for the whole screen, /dev/window for that window's data, and /dev/wsys//window for some other window's data. [DLm]
pdfpost	converts PDF data to PostScript.
post .	passes PostScript through, adding option patches for paper tray information. This does not always work with PostScript generated on other systems.
ppost tr2post	<pre>converts UTF text to PostScript. [DLcfilmnorxy] converts troff(1) output for device utf (the default) to PostScript. See</pre>
tr2post	/sys/lib/troff/font/devutf directory for troff font width table descriptions. See also the /sys/lib/postscript/troff directory for mappings of troff UTF character space to PostScript font space. [DLcimnorxy]

SOURCE

/sys/src/cmd/postscript

SEE ALSO

lp(1)

BUGS

The *file* command is not always smart enough to deal with certain file types. There are PostScript conversion programs that do not have processors to drive them.

memory - print memory statistics in human-readable format

SYNOPSIS

memory

DESCRIPTION

Memory prints statistics about the total system memory, followed by the memory that is currently use, by concatenating the file /dev/swap and filtering the output for human consumption.

SOURCE

/rc/bin/memory

dump9660, mk9660 - create an ISO-9660 CD image

SYNOPSIS

disk/mk9660[-:D][-9cjr][-b bootfile][-B bootfile][-E bootfile][-p proto][-s src][-v volume] image

disk/dump9660[-:D][-9cjr][-p proto][-s src][-v volume][-m maxsize][-n now] image

DESCRIPTION

Mk9660 writes to the random access file *image* an ISO-9660 CD image containing the files named in *proto* (by default, /sys/lib/sysconfig/proto/portproto) from the file tree *src* (by default, the current directory). The *proto* file format is described in *proto*(2).

The created CD image will be in ISO-9660 format, but by default the file names will be stored in UTF-8 with no imposed length or character restrictions. The -c flag causes *mk9660* to use only file names in "8.3" form that use digits, letters, and underscore. File names that do not conform are changed to D*nnnnn* (for directories) or F*nnnnn* (for files); a key file _CONFORM.MAP is created in the root directory to ease the reverse process.

If the -9 flag is given, the system use fields at the end of each directory entry will be populated with Plan directory information (owner, group, mode, full name); this is interpreted by 9660srv.

If the -j flag is given, the usual directory tree is written, but an additional tree in Microsoft Joliet format is also added. This second tree can contain long Unicode file names, and can be read by *9660srv* as well as most versions of Windows and many Unix clones. The characters *, :, ;, ?, and \ are allowed in Plan 9 file names but not in Joliet file names; non-conforming file names are translated and a _CONFORM.MAP file written as in the case of the -c option.

If the -r flag is given, Rock Ridge extensions are written in the format of the system use sharing protocol; this format provides Posix-style file metadata and is common on Unix platforms.

The options -c, -9, -j, and -r may be mixed freely with the exception that -9 and -r are mutually exclusive.

The -v flag sets the volume title; if unspecified, the base name of *proto* is used.

The -: flag causes mk9660 to replace colons in scanned file names with spaces; this is the inverse of the map applied by *dossrv*(4) and is useful for writing Joliet CDs containing data from FAT file systems.

The -b option creates a bootable CD. Bootable CDs contain pointers to floppy images which are loaded and booted by the BIOS. *Bootfile* should be the name of the floppy image to use; it is a path relative to the root of the created CD. That is, the boot floppy image must be listed in the *proto* file already: the -b option just creates a pointer to it.

The -B option is similar to -b but the created CD image is marked as having a non-floppyemulation boot block. This gives the program in the boot block full (ATA) LBA access to the CD filesystem, not just the initial blocks that would fit on a floppy.

In addition to -b and -B a boot entry for UEFI systems can be created with the -E option and with *bootfile* pointing to a FAT image containing the contents of the efi system partition.

The -D flag creates immense amounts of debugging output on standard error.

Dump9660 is similar in specification to mk9660 but creates and updates backup CD images in the style of the dump file system (see fs(4)). The dump is file-based rather than block-based: if a file's contents have not changed since the last backup, only its directory entry will be rewritten.

The -n option specifies a time (in seconds since January 1, 1970) to be used for naming the dump directory.

The *m* option specifies a maximum size for the image; if a backup would cause the image to grow larger than *maxsize*, it will not be written, and *dump9660* will exit with a non-empty status.

EXAMPLE

Create an image of the Plan 9 source tree, including a conformant ISO-9660 directory tree, Plan 9 extensions in the system use fields, and a Joliet directory tree.

```
disk/mk9660 -9cj -s /sys/src \
    -p /sys/lib/sysconfig/proto/allproto cdimage
```

SOURCE

/sys/src/cmd/disk/9660

SEE ALSO

9660srv (in dossrv(4)), cdfs(4), mkfs(8)

mkflashfs - make a journalling file system for flash memory

SYNOPSIS

aux/mkflashfs[-n nsect][-z sectsize] file

DESCRIPTION

Mkflashfs creates an empty journalling file system in *file*, typically /dev/flash/flash.

The files and directory structure are divided into *sectsize* (default 4096) byte blocks. Larger blocks make large files more compact but take longer to access. Supplying the -n option forces *file* to contain exactly *nsect* sectors.

SOURCE

/sys/src/cmd/aux/flashfs/mkfs.c

SEE ALSO

flashfs(4), paqfs(4), sacfs(4)

mkfs, mkext - archive or update a file system

SYNOPSIS

disk/mkfs [-aprvoxU] [-d root] [-s source] [-z n] proto ...

disk/mkext [-d name] [-u] [-h] [-v] [-x] [-T] file ...

DESCRIPTION

Mkfs copies files from the file tree *source* (default /) to a new file system *root* (default /n/newfs). The *proto* files are read (see *proto*(2) for their format) and any files specified in them that are out of date are copied.

Mkfs copies only those files that are out of date. Such a file is first copied into a temporary file in the appropriate destination directory and then moved to the destination file. Files that are not specified in the *proto* file are not updated and not removed.

The options to *mkfs* are:

- a Instead of writing to new file system, write an archive file to standard output, suitable for *mkext*. All files in *proto*, not just those out of date, are archived.
- x For use with -a, this option writes a list of file names, dates, and sizes to standard output rather than producing an archive file.
- o Similar to -x above, but produces a list of source file names to standard output rather than producing an archive file.
- d root
 Copy files into the tree rooted at root (default /n/newfs). This option suppresses setting the uid and gid fields when copying files. Use -U to reenable it.
 p
 Update the permissions of a file even if it is up to date.
- pUpdate the permissions of a file even if it isUUpdate of uid and gid of the target files.
- r Copy all files.
- s *source* Copy from files rooted at the tree *source*.
- v Print the names of all of the files as they are copied.
- z *n* Copy files assuming block size *n* (default 1024) bytes long. If a block contains only 0-valued bytes, it is not copied.

Mkext unpacks archive files made by the -a option of *mkfs*. Each file on the command line is unpacked in one pass through the archive. If the file is a directory, all files and subdirectories of that directory are also unpacked. When a file is unpacked, the entire path is created if it does not exist. If no files are specified, the entire archive is unpacked; in this case, missing intermediate directories are not created. The options are:

- d specifies a directory (default /) to serve as the root of the unpacked file system.
- u sets the owners of the files created to correspond to those in the archive and restores the modification times of the files.
- T restores only the modification times of the files.
- v prints the names and sizes of files as they are extracted.
- h prints headers for the files on standard output instead of unpacking the files.

EXAMPLES

Make an archive to establish a new file system:

disk/mkfs -a -s dist proto > arch

Unpack that archive onto a new file system:

```
srv newfs
mount -c /srv/newfs /n/newfs
disk/mkext -u -d /n/newfs < arch</pre>
```

SOURCE

```
/sys/src/cmd/disk/mkfs.c
/sys/src/cmd/disk/mkext.c
```

SEE ALSO

prep(8), *sd*(3), *tar*(1)

mkpaqfs - make a compressed read-only file system

SYNOPSIS

mkpaqfs [-u] [-b blocksize] [-1 label] [-o file] [source]

DESCRIPTION

Mkpaqfs copies files from the file tree *source* (default .) to the *paqfs*(4) file system archive *file*.

The files and directory structure are divided into *blocksize* (default 4096) byte blocks. Larger blocks make large files more compact but take longer to access. *Blocksize* must be in the range of 512 bytes to 512K bytes. If the -u option is set, the blocks are not compressed. Otherwise each block is compressed using the *flate*(2) compression algorithm. The -1 option embeds a label of up to 32 bytes within the file header and may be useful for identifying the file system.

SOURCE

/sys/src/cmd/paqfs/mkpaqfs.c

SEE ALSO

paqfs(4)

mksacfs - make a compressed file system

SYNOPSIS

disk/mksacfs [-u] [-b blocksize] [-o file] source

DESCRIPTION

Mksacfs copies files from the file tree source (default .) to a the sacfs(4) file system archive file.

The files and directory structure are divided into *blocksize* (default 4096) byte blocks. Larger blocks make large files more compact but take longer to access. *Blocksize* must be at least 116. If -u is given, the blocks are not compressed. Otherwise each block is compressed using an efficient compression algorithm.

SOURCE

/sys/src/cmd/disk/sacfs/mksacfs.c

SEE ALSO

sacfs(4)

aux/mouse, aux/accupoint - configure a mouse to a port

SYNOPSIS

aux/mouse [-b baud] [-d type] [-n] port

aux/accupoint

DESCRIPTION

Mouse queries a mouse on a serial or PS2 port for its type and then configures the port and the mouse to be used to control the cursor.

Port can be either a port number (e.g. 0 or 1) or the string ps2 or ps2intellimouse. The initialization can be automated by setting mouseport in *plan9.ini*(8), which will enable a call to *mouse* in termrc (see *cpurc*(8)).

The option -d provides a default mouse type should mouse fail to determine it. The types are:

- C Logitech type C mouse
- W Logitech type W mouse
- M Microsoft compatible mouse

The -n flag queries the mouse and reports its type but does not set the device type.

The -b flag sets the baud rate for communication; it is effectual only for serial mice.

Accupoint is a process, to be used with *pipefile*(1), that processes events from an AccuPoint II pointing device with four buttons, such as on Toshiba Portégé 3440CT and 3480CT laptops, converting events on the two extra buttons (which appear as buttons 4 and 5 in the mouse(3) interface) into a simulation of button 2. These extra buttons on laptops are in turn simulations of Intellimouse scrolling buttons and have peculiar properties: they generate only 'down' events that repeat automatically, like a keypad, in an approximation of the Intellimouse scroll wheel. Accupoint overcomes this behavior to produce a reasonable approximation of a normal mouse button 2: it makes left button act like a regular button 2, but is slow to release (the program must wait for a repeat time before it knows the button has been released), while the right button generates a fast button 2 'click'. To use accupoint, add a line like this to /usr/\$user/lib/profile or to a system-dependent configuration script in termrc (see cpurc(8)):

pipefile -dr /bin/aux/accupoint /dev/mouse

Before running *accupoint*, the mouse should be configured as an intellimouse or ps2intellimouse.

SOURCE

/sys/src/cmd/aux/mouse.c
/sys/src/cmd/aux/accupoint.c

SEE ALSO

cons(3), cpurc(8), pipefile(1).

BUGS

Due to the limitations of *pipefile*(1), when running *accupoint* it is difficult restart *rio*(1) if it has exited.

na - assembler for the Symbios Logic PCI-SCSI I/O Processors

SYNOPSIS

aux/na file

DESCRIPTION

The SYM53C8XX series of PCI-SCSI I/O Processors contain loadable microcode to control their operation. The microcode is written in a language called SCRIPTS. *Aux/na* is an assembler for the SCRIPTS programming language. It assembles SCRIPTS code in *file* into an array of assembled SCRIPTS instructions, patches, defines and enums that can be included in a C device driver.

SOURCE

/sys/src/cmd/aux/na

SEE ALSO

Symbios Logic, "PCI-SCSI I/O Processors Programming Guide Version 2.1"

/sys/src/9/*/sd53c8xx.n SCRIPTS source code

/sys/src/9/*/sd53c8xx.c driver for the SYM53C8XX series of PCI-SCSI controllers

AUTHOR

Nigel Roles (ngr@9fs.org)

query, ipquery, mkhash, mkdb, mkhosts, cs, csquery, dns, dnstcp, dnsquery, dnsdebug, dnsgetip, inform - network database

SYNOPSIS

ndb/query [-am] [-f dbfile] attr value [rattr]
ndb/ipquery attr value rattr...
ndb/mkhash file attr
ndb/mkhosts [domain [dbfile]]
ndb/mkhosts [domain [dbfile]]
ndb/cs [-46n] [-f dbfile] [-x netmtpt]
ndb/csquery [-s] [/net/cs [addr...]]
ndb/dns [-norRs] [-a maxage] [-f dbfile] [-N target] [-x netmtpt] [-z program]
ndb/dnstcp [-arR] [-f dbfile] [-x netmtpt] [conn-dir]
ndb/dnsquery [-x] [/net/dns]
ndb/dnsdebug [-rxc] [-f dbfile] [@ server] domain-name [type]]
ndb/dnsgetip [-ax] domain-name
ndb/inform [-x netmtpt]

DESCRIPTION

The network database holds administrative information used by network programs such as *dhcpd*(8), *ipconfig*(8), *con*(1), etc.

Ndb/query searches the database *dbfile* (/lib/ndb/local by default) for an attribute of type *attr* and value *value*. If *rattr* is not specified, all entries matched by the search are printed. If *rattr* is specified, the value of the first pair with attribute *rattr* of all the matched entries normally is printed. Under -m and *rattr*, the values of all pairs with a *rattr* attribute within the first matching entry are printed. Under -a and *rattr*, all values of pairs with a *rattr* attribute within all entries are printed.

Ndb/ipquery uses *ndbipinfo* (see *ndb*(2)) to search for the values of the attributes *rattr* corresponding to the system with entries of attribute type *attr* and value *value*.

Ndb/inform sends an RFC2136 DNS *inform* packet to a nameserver to associate the host's IP address with its DNS name. This is required if the domain's nameserver is a Microsoft Windows Active Directory controller. The host's domain name will be sent to the AD controller unless a tuple of the form inform=xxx is found in the host's *ndb* entry.

Database maintenance

Ndb/mkhash creates a hash file for all entries with attribute *attr* in database file *file*. The hash files are used by *ndb/query* and by the ndb library routines.

Ndb/mkdb is used in concert with awk(1) scripts to convert uucp systems files and IP host files into database files. It is very specific to the situation at Murray Hill.

When the database files change underfoot, *ndb/cs* and *ndb/dns* track them properly. Nonetheless, to keep the database searches efficient it is necessary to run *ndb/mkhash* whenever the files are modified. It may be profitable to control this by a frequent *cron*(8) job.

Ndb/mkhosts generates a BSD style hosts, hosts.txt, and hosts.equiv files from an ndb data base file specified on the command line (default /lib/ndb/local). For local reasons the files are called hosts.1127, astro.txt, and hosts.equiv.

Connection service

Ndb/cs is a server used by *dial*(2) to translate network names. It is started at boot time. It finds out what networks are configured by looking for /net/*/clone when it starts. It can also be told about networks by writing to /net/cs a message of the form:

add net1 net2 ...

Ndb/cs also sets the system name in /dev/sysname if it can figure it out. The options are:

- -4 Only look up IPv4 addresses (A records) when consulting DNS. The default is to also look up v6 addresses (AAAA records). Writing ipv4 to /net/cs will toggle IP v4 look-ups.
- -6 Only look up IPv6 addresses in DNS. Writing ipv6 to /net/cs toggles v6 lookups.

- -f supplies the name of the data base file to use, default /lib/ndb/local.
- -n causes cs to do nothing but set the system name.
- -x specifies the mount point of the network.

Ndb/csquery queries *ndb/cs* to see how it resolves addresses. *Ndb/csquery* prompts for addresses and prints what *ndb/cs* returns. *Server* defaults to /net/cs. If any *addrs* are specified, *ndb/csquery* prints their translations and immediately exits. The exit status will be nil only if all addresses were successfully translated. The -s flag sets exit status without printing any results.

Domain name service

Ndb/dns serves *ndb/cs* and remote systems by translating Internet domain names. *Ndb/dns* is started at boot time. By default *dns* serves only requests written to /net/dns. Programs must *seek* to offset 0 before reading or writing /net/dns or /net/cs. The options are:

- -a sets the maximum time in seconds that an unreferenced domain name will remain cached. The default is one hour (3600).
- -f supplies the name of the data base file to use, default /lib/ndb/local.
- -n whenever a DNS zone that we serve changes, send UDP NOTIFY messages to any dns slaves for that zone (see the dnsslave attribute below).
- -N sets the goal for the number of domain names cached to *target* rather than the default of 8,000.
- -o used with -s, -o causes *dns* to assume that it straddles inside and outside networks and that the outside network is mounted on /net.alt. Queries for inside addresses will be sent via /net/udp (or /net/tcp in response to truncated replies) and those for outside addresses via /net.alt/udp (or /net.alt/tcp). This makes *dns* suitable for serving non-Plan-9 systems in an organization with firewalls, DNS proxies, etc., particularly if they don't work very well. See 'Straddling Server' below for details.
- -r act as a resolver only: send 'recursive' queries, asking the other servers to complete lookups. If present, /env/DNSSERVER must be a space-separated list of such DNS servers' IP addresses, otherwise optional *ndb*(6) dns attributes name DNS servers to forward queries to.
- -R ignore the 'recursive' bit on incoming requests. Do not complete lookups on behalf of remote systems.
- -s also answer domain requests sent to UDP port 53.
- -x specifies the mount point of the network.
- -z whenever we receive a UDP NOTIFY message, run *program* with the domain name of the area as its argument.

When the $-\mathbf{r}$ option is specified, the servers used come from the *dns* attribute in the database. For example, to specify a set of dns servers that will resolve requests for systems on the network *mh*-*net*:

ipnet=mh-net ip=135.104.0.0 ipmask=255.255.0.0
 dns=ns1.cs.bell-labs.com
 dns=ns2.cs.bell-labs.com
dom=ns1.cs.bell-labs.com ip=135.104.1.11
dom=ns2.cs.bell-labs.com ip=135.104.1.12

The server for a domain is indicated by a database entry containing both a *dom* and a *ns* attribute.

dom=

ns=A.ROOT-SERVERS.NET
ns=B.ROOT-SERVERS.NET
ns=C.ROOT-SERVERS.NET
dom=A.ROOT-SERVERS.NET ip=198.41.0.4
dom=B.ROOT-SERVERS.NET ip=128.9.0.107
dom=C.ROOT-SERVERS.NET ip=192.33.4.12

The last three lines provide a mapping for the server names to their ip addresses. This is only a hint and will be superseded from whatever is learned from servers owning the domain.

Authoritative Name Servers

You can also serve a subtree of the domain name space from the local database. You indicate subtrees that you would like to serve by adding an soa = attribute to the root entry. For example, the Bell Labs CS research domain is:

```
dom=cs.bell-labs.com soa=
   refresh=3600 ttl=3600
   ns=plan9.bell-labs.com
   ns=ns1.cs.bell-labs.com
   mb=presotto@plan9.bell-labs.com
   mx=mail.research.bell-labs.com pref=20
   mx=plan9.bell-labs.com pref=10
   dnsslave=nslocum.cs.bell-labs.com
   dnsslave=vex.cs.bell-labs.com
```

Here, the mb entry is the mail address of the person responsible for the domain (default postmaster). The mx entries list mail exchangers for the domain name and refresh and ttl define the area refresh interval and the minimum TTL for records in this domain. The dnsslave entries specify slave DNS servers that should be notified when the domain changes. The notification also requires the -n flag.

Reverse Domains

You can also serve reverse lookups (returning the name that goes with an IP address) by adding an soa= attribute to the entry defining the root of the reverse space.

For example, to provide reverse lookup for all addresses in starting with 135.104 or fd00::, *ndb* must contain a record like:

Notice the form of the reverse address. For IPv4, it's the bytes of the address range you are serving reversed and expressed in decimal, and with .in-addr.arpa appended. For IPv6, it's the nibbles (4-bit fields) of the address range you are serving reversed and expressed in hexadecimal, and with .ip6.arpa appended. These are the standard forms for a domain name in a PTR record.

If such an soa entry exists in the database, reverse addresses will automatically be generated from any IP addresses in the database that are under this root. For example

dom=ns1.cs.bell-labs.com ip=135.104.1.11

will automatically create both forward and reverse entries for ns1.cs.bell-labs.com. Unlike other DNS servers, there's no way to generate inconsistent forward and reverse entries.

Classless reverse delegation

Following RFC 2317, it is possible to serve reverse DNS data for IPv4 subnets smaller than /24. Declare the non-/24 subnet, the reverse domain and the individual systems.

For example, this is how to serve RFC-2317 ptr records for the subnet 65.14.39.128/123.

```
ipnet=our-t1 ip=65.14.39.128 ipmask=/123
dom=128.39.14.65.in-addr.arpa soa=
    refresh=3600 ttl=3600
    ns=ns1.our-domain.com
    ns=ns2.our-domain.com
    ip=65.14.39.129 dom=router.our-domain.com
```

Delegating Name Service Authority

Delegation of a further subtree to another set of name servers is indicated by an soa=delegated attribute.

dom=bignose.cs.research.bell-labs.com
 soa=delegated
 ns=anna.cs.research.bell-labs.com
 ns=dj.cs.research.bell-labs.com

Nameservers within the delegated domain (as in this example) must have their IP addresses listed elsewhere in *ndb* files.

Wildcards, MX and CNAME records

Wild-carded domain names can also be used. For example, to specify a mail forwarder for all Bell Labs research systems:

dom=*.research.bell-labs.com
 mx=research.bell-labs.com

'Cname' aliases may be established by adding a cname attribute giving the real domain name; the name attached to the dom attribute is the alias. 'Cname' aliases are severely restricted; the aliases may have no other attributes than dom and are daily further restricted in their use by new RFCs.

cname=anna.cs.bell-labs.com dom=www.cs.bell-labs.com

makes www.... a synonym for the canonical name anna.....

Straddling Server

Many companies have an inside network protected from outside access with firewalls. They usually provide internal 'root' DNS servers (of varying reliability and correctness) that serve internal domains and pass on DNS queries for outside domains to the outside, relaying the results back and caching them for future use. Some companies don't even let DNS queries nor replies through their firewalls at all, in either direction.

In such a situation, running dns -so on a machine that imports access to the outside network via /net.alt from a machine that straddles the firewalls, or that straddles the firewalls itself, will let internal machines query such a machine and receive answers from outside nameservers for outside addresses and inside nameservers for inside addresses, giving the appearance of a unified domain name space, while bypassing the corporate DNS proxies or firewalls. This is different from running dns -s and dns -sRx /net.alt -f /lib/ndb/external on the same machine, which keeps the inside and outside namespaces entirely separate.

Under -o, several sys names are significant: inside-dom, inside-ns, and outside-ns. *Inside-dom* should contain a series of dom pairs naming domains internal to the organization. *Inside-ns* should contain a series of ip pairs naming the internal DNS 'root' servers. *Outside-ns* should contain a series of ip pairs naming the external DNS servers to consult.

Zone Transfers and TCP

Dnstcp is invoked, usually from /rc/bin/service/tcp53, to answer DNS queries with long answers via TCP, notably to transfer a zone within the database *dbfile* (default /lib/ndb/local) to its invoker on the network at *netmtpt* (default /net). Standard input will be read for DNS requests and the DNS answers will appear on standard output. Recursion is disabled by -R; acting as a pure resolver is enabled by -r. Unless the -a flag is provided, clients requesting DNS zone transfer must be listed with a dnsslave attribute for the relevant domain. If *conn-dir* is provided, it is assumed to be a directory within *netmtpt*/tcp and is used to find the caller's address.

DNS Queries and Debugging

Ndb/dnsquery can be used to query *ndb/dns* to see how it resolves requests. *Ndb/dnsquery* prompts for commands of the form

domain-name request-type

where *request-type* can be ip, ipv6, mx, ns, cname, ptr.... In the case of the inverse query type, ptr, *dnsquery* will reverse the ip address and tack on the .in-addr.arpa if necessary. The -x option switches *ndb/dnsquery* to query the dns server on /net.alt instead of /net

Ndb/dnsdebug is like *ndb/dnsquery* but bypasses the local server. It communicates via UDP (and sometimes TCP) with the domain name servers in the same way that the local resolver would and displays all packets received. The query can be specified on the command line or can be prompted for. The queries look like those of *ndb/dnsquery* with one addition. *Ndb/dnsdebug* can be directed to query a particular name server by the command @*name-server*. From that point on, all queries go to that name server rather than being resolved by *dnsdebug*. The @ command returns query resolution to *dnsdebug*. Finally, any command preceded by a @*name-server* sets the name server only for that command.

Normally *dnsdebug* uses the /net interface and the database file /lib/ndb/local. The -f option supplies the name of the data base file to use. The -r option is the same as for *ndb/dns*. The -x option directs *dnsdebug* to use the /net.alt interface and /lib/ndb/external database file. The -c option enables caching which is handy for debugging the dns code.

Ndb/dnsgetip resolves and prints A and AAAA records without consulting *ndb/dns*. By default, *ndb/dnsgetip* queries A records first and then AAAA records. As with *ndb/dns*, /env/DNSSERVER or *ndb*(6) dns attributes are used as the DNS server. The -*a* flag will return all records. The -x option switches *ndb/dnsgetip* to query the dns server through /net.alt instead of /net.

EXAMPLES

Look up helix in *ndb*.

```
% ndb/query sys helix
sys=helix dom=helix.research.bell-labs.com bootf=/mips/9powerboot
ip=135.104.117.31 ether=080069020427
```

Look up plan9.bell-labs.com and its IP address in the DNS.

```
% ndb/dnsquery
> plan9.bell-labs.com ip
plan9.bell-labs.com ip 204.178.31.2
> 204.178.31.2 ptr
2.31.178.204.in-addr.arpa ptr plan9.bell-labs.com
2.31.178.204.in-addr.arpa ptr ampl.com
>
```

Print the names of all systems that boot via PXE.

```
% ndb/query -a bootf /386/9bootpxe sys
```

FILES

```
/env/DNSSERVER resolver's DNS servers' IP addresses.
/lib/ndb/local first database file searched
/lib/ndb/local.* hash files for /lib/ndb/local
/srv/cs service file for ndb/cs
/net/cs where /srv/cs gets mounted
/srv/dns service file for ndb/dns
/net/dns where /srv/dns gets mounted
```

SOURCE

/sys/src/cmd/ndb

SEE ALSO

ndb(2), ndb(6)

BUGS

Ndb databases are case-sensitive; ethernet addresses must be in lower-case hexadecimal.

netaudit – network configuration checker

SYNOPSIS

netaudit

DESCRIPTION

Netaudit checks the effective network configuration on the local system and reports any inconsistencies found.

It starts its search by querying common ndb entries for sysname, checking and validating the ip=, ether= and dom= entries.

The presence of an ipnet= entry and the reachability of dns and auth servers is checked.

If the machine is an auth server, *netaudit* checks if keyfs(4) is running and the local tcp port 567 is open and listening.

The root filesystem /srv/boot is tested if it requires authentication on mount.

SOURCE

/rc/bin/netaudit

SEE ALSO

keyfs(4), auth(8), ndb(8), ndb(6).

HISTORY

Netaudit first appeared in 9front (August, 2012).

newuser - adding a new user

SYNOPSIS

/sys/lib/newuser

DESCRIPTION

To establish a new user on Plan 9, add the user to /adm/users by running the *newuser* command on the console of the file server (see fs(8)). Next, give the user a password using *auth/changeuser* on the console of the authentication server (see *auth*(8)). At this point, the user can bootstrap a terminal using the new name and password. The terminal will only get as far as running rc, however, as no profile exists for the user.

The rc(1) script /sys/lib/newuser sets up a sensible environment for a new user of Plan 9. Once the terminal is running rc, type

/sys/lib/newuser

to build the necessary directories in /usr/\$user, create /mail/box/\$user/mbox, /cron/\$user/cron, a reasonable initial profile in /usr/\$user/lib/profile and plumbing rules in /usr/\$user/lib/plumbing (see *plumber*(4)). The script then runs the profile which, as its last step, brings up *rio*(1). At this point the user's environment is established and running. (There is no need to reboot.) It may be prudent at this point to run *passwd*(1) to change the password, depending on how the initial password was chosen.

The profile built by /sys/lib/newuser looks like this:

```
bind -a $home/bin/rc /bin
bind -a $home/bin/$cputype /bin
bind -c tmp /tmp
font = /lib/font/bit/pelm/euro.9.font
switch($service){
case terminal
     plumber
     upas/fs
     echo -n accelerated > '#m/mousectl'
     echo -n 'res 3' > '#m/mousectl'
prompt=('term% ' ' ')
     fn term%{ $* }
     exec rio
case cpu
     if (test -e /mnt/term/mnt/wsys) {
          # rio already running
          wsys = /mnt/term^'{cat /mnt/term/env/wsys}
          bind -a /mnt/term/mnt/wsys /dev
          echo -n $sysname > /dev/label
     }
     bind /mnt/term/dev/cons /dev/cons
     bind /mnt/term/dev/consctl /dev/consctl
     bind -a /mnt/term/dev /dev
     prompt=('cpu% ' '
                          ')
     fn cpu%{ $* }
     upas/fs
     news
     if (! test -e /mnt/term/mnt/wsys) {
          # cpu call from drawterm
          font=/lib/font/bit/pelm/latin1.8.font
          auth/factotum
          plumber
          exec rio
     }
case con
```

```
prompt=('cpu% ' ' ')
news
```

}

Sites may make changes to /sys/lib/newuser that reflect the properties of the local environment.

SEE ALSO

passwd(1), rio(1), namespace(4), fs(8), auth(8).

nfsserver, portmapper, pcnfsd - NFS service

SYNOPSIS

aux/nfsserver[rpc-options...][nfs-options...]
aux/pcnfsd[rpc-options...]
aux/portmapper[rpc-options...]

DESCRIPTION

These programs collectively provide NFS access to Plan 9 file servers. *Nfsserver*, *pcnfsd*, and *portmapper* run on a Plan 9 CPU server, and should be started in that order. All users on client machines have the access privileges of the Plan 9 user none. Currently only NFS version 2 is served.

The *rpc-options* are all intended for debugging:

- -r Reject: answer all RPC requests by returning the AUTH_TOOWEAK error.
- -v Verbose: show all RPC calls and internal program state, including 9P messages. (In any case, the program creates a file /srv/name.chat where *name* is that of the program; echoing 1 or 0 into this file sets or clears the -v flag dynamically.)
- -D Debug: show all RPC messages (at a lower level than -v). This flag may be repeated to get more detail.
- -C Turn off caching: do not answer RPC requests using the RPC reply cache.

The *nfs-options* are:

- -a *addr* Set up NFS service for the 9P server at network address *addr*.
- -f *file* Set up NFS service for the 9P server at *file* (typically an entry in /srv).
- -n Do not allow per-user authentication (default and mandatory).
- -c file File contains the uid/gid map configuration. It is read at startup and subsequently every hour (or if c is echoed into /srv/nfsserver.chat). Blank lines or lines beginning with # are ignored; lines beginning with ! are executed as commands; otherwise lines contain four fields separated by white space: a regular expression (in the notation of regexp(6)) for a class of servers, a regular expression for a class of clients, a file of user id's (in the format of a Unix password file), and a file of group id's (same format).
- -s Expect a network connection on file descriptor 1 instead of listening for incoming calls.
- -t Listen for incoming TCP calls, rather than UDP calls.

NFS clients must be in the Plan 9 /lib/ndb database. The machine name is deduced from the IP address via ndb/query. The machine name specified in the NFS Unix credentials is completely ignored.

Pcnfsd is a toy program that authorizes PC-NFS clients. All clients are mapped to uid=1, gid=1 (daemon on most systems) regardless of name or password.

EXAMPLES

A simple /lib/ndb/nfs might contain:

```
!9fs tcp!ivy
.+ [^.]+\.cvrd\.hall\.edu /n/ivy/etc/passwd /n/ivy/etc/group
A typical entry in /rc/bin/cpurc might be:
aux/nfsserver -a tcp!pie -a tcp!yoshimi -c /lib/ndb/nfs
aux/pcnfsd
aux/portmapper
```

Assuming the CPU server's name is eduardo, the mount commands on the client would be:

```
/etc/mount -o soft,intr eduardo:pie /n/pie
/etc/mount -o soft,intr eduardo:yoshimi /n/yoshimi
```

Note that a single instance of *nfsserver* may provide access to several 9P servers.

FILES

/lib/ndb/nfs List of uid/gid maps.
/sys/log/nfs Log file.

SOURCE

/sys/src/cmd/9nfs

BUGS

It would be nice to provide authentication for users, but Unix systems provide too low a level of security to be trusted in a Plan 9 world.

SEE ALSO

nfs(4)

RFC1057, RPC: Remote Procedure Call Protocol Specification, Version 2, describes Sun's RPC protocol.

RFC1094, NFS: Network File System Protocol Specification, describes NFS version 2.

RFC1813, NFS Version 3 Protocol Specification.

RFC3530, Network File System (NFS) version 4 Protocol.

nusbrc – Universal Serial Bus startup script

SYNOPSIS

nusbrc

DESCRIPTION

Started by *bootrc* (see *boot*(8)), *termrc* or *cpurc* (see *cpurc*(8)), *nusbrc* handles the startup and shutdown of usb drivers on physical device attach and detach events by reading /dev/usbevent file.

SOURCE

/rc/bin/nusbrc/sys/src/9/boot/nusbrc

SEE ALSO

nusb(4)

BUGS

Usb devices appear as files under /dev and /shr identified by the devices unique name assigned by usbd. When the environment variable *nousbhname* is defined, devies are named by ther dynamically assigned usb device address instead. This emulates the old behaviour.

partfs - serve file, with partitions

SYNOPSIS

disk/partfs[-Dr][-d diskname][-m mtpt][-s srvname] diskimage

DESCRIPTION

Partfs presents the file *diskimage* in the manner of sd(3) on mtpt/diskname (default /dev/sdXX). Changes made to the disk are written through to *diskimage* unless the -r option is given.

When setting disk geometry with the geometry control message, the arguments are sectors and sector size.

The -s option causes *partfs* to post its 9P service at /srv/service.

EXAMPLES

Partition a USB flash device:

usb/disk disk/partfs /n/disk/0/data disk/mbr -m /386/mbr /dev/sdXX/data disk/fdisk -baw /dev/sdXX/data disk/prep /dev/sdXX/plan9

SOURCE

/sys/src/cmd/disk/partfs.c

SEE ALSO

sd(3), disksim(8), prep(8)

pci - print PCI bus configuration

SYNOPSIS

pci[-bv][vid/did ...]

DESCRIPTION

Pci normally prints one line per device found on the local PCI bus described by #/pci. The fields are *bus*. *device*. *function*, class, class code, *vendor/device* ids, IRQ (interrupt), followed by the configuration registers in pairs of *index*: *address* and *size*. The –b option suppresses output for PCI bridges. The –v option adds a second line per device, containing an English description obtained from /lib/pci.

If any number of vid/did pairs is specified, *pci* instead looks up each pair in the database and prints the vid/did, followed by the English description of the vendor and device on a new line if it exists in the database.

FILES

/lib/pci

SOURCE

/rc/bin/pci

SEE ALSO pnp(3)

pcmcia - identify a PCMCIA card

SYNOPSIS

aux/pcmcia[file]

DESCRIPTION

Aux/pcmcia translates the PCMCIA information structure from *file* (default #y/pcm0attr) into a readable description and writes it to standard output.

FILES

#y/pcm0attr The attribute memory of the card in the PCMCIA slot.

SOURCE

/sys/src/cmd/aux/pcmcia.c

pemdecode, pemencode - encode files in Privacy Enhanced Mail (PEM) format

SYNOPSIS

auth/pemdecode section [file]

auth/pemencode section [file]

DESCRIPTION

PEM is a textual encoding for binary data originally used by the Privacy Enhanced Mail program but now commonly used for other applications, notably TLS. PEM encodes data in base 64 (see *encode*(2)) between lines of the form:

-----BEGIN SECTION-----

where SECTION may be any string describing the encoded data. The most common use of PEM format on Plan 9 is for encoding X.509 certificates; see *rsa*(8).

Pemdecode extracts the named section and writes the decoded data to standard output.

Pemencode encodes its standard input, labels it as a section, and writes it to standard output.

EXAMPLES

Encode and decode a simple greeting:

SOURCE

/sys/src/cmd/auth

SEE ALSO

rsa(8)

ping, gping, traceroute, hogports - probe the Internet

SYNOPSIS

ip/ping [-6aflqr][-i interval][-n count][-s size][-w waittime] destination

ip/gping [-r] [-l] [-i interval] destination [destination ...]

ip/traceroute [-dn][-a n][-h nbuck][-t sttl] dest

ip/hogports [mtpt/]proto!address!startport[-endport]

DESCRIPTION

Ping sends ICMP echo request messages to a system. It can be used to determine the network delay and whether or not the destination is up. By default, a line is written to standard output for each request. If a reply is received the line contains the request id (starting at 0 and incrementing), the round trip time for this request, the average round trip time, and the time to live in the reply packet. If no reply is received the line contains the word "lost", the request id, and the average round trip time.

If a reply is received for each request, *ping* returns successfully. Otherwise it returns an error status of "lost messages".

The options are:

- 6 force the use of IPv6's ICMP, icmpv6, instead of IPv4's ICMP. *Ping* tries to determine which version of IP to use automatically.
- a adds the IP source and destination addresses to each report.
- f send messages as fast as possible (flood).
- i sets the time between messages to be *interval* milliseconds, default 1000 ms.
- 1 causes only lost messages to be reported.
- n requests that a total of *count* messages be sent, default 32.
- q suppresses any output (i.e. be quiet).
- r randomizes the delay with a minimum extra delay of 0 ms and a maximum extra delay of the selected interval.
- s sets the length of the message to be *size* bytes, ICMP header included. The size cannot be smaller than 32 or larger than 8192. The default is 64.
- w sets the additional time in milliseconds to wait after all packets are sent.

Gping is a *ping* with a graphical display. It presents separate graphs for each destination specified. The options are:

- r display round trip time in seconds. This is the default.
- 1 display percentage of lost messages. A message is considered lost if not replied to in 10 seconds. The percentage is an exponentially weighted average.
- i sets the time between messages to be *interval* milliseconds, default 5000 ms.

Graphs can be dropped and added using the button 3 menu. Clicking button 1 on a datapoint displays the value of the datapoint and the time it was recorded.

Traceroute displays the IP addresses and average round trip times to all routers between the machine it is run on and *dest*. It does this by sending packets to *dest* with increasing times to live (TTL) in their headers. Each router that a packet expires at replies with an ICMP warning message. The options are:

- d print debugging to standard error
- n just print out IP numbers, don't try to look up the names of the routers.
- a make *n* attempts at each TTL value (default 3).
- t set the starting TTL value to *sttl* (default 1).

h print out a histogram of times from request to response at each TTL value. The histogram contains *nbuck* buckets.

Hogports announces on a range of ports to keep them from other processes. For example, to keep anyone from making a vncserver visible on the network mounted at /net.alt:

ip/hogports /net.alt/tcp!*!5900-5950

SOURCE

/sys/src/cmd/ip/ping.c
/sys/src/cmd/ip/gping.c
/sys/src/cmd/ip/traceroute.c
/sys/src/cmd/ip/hogports.c

SEE ALSO

ip(3)

plan9.ini - configuration file for PCs

SYNOPSIS

none

DESCRIPTION

When booting Plan 9 on a PC, the bootloader program *9boot*(8) first reads configuration information from a file on the boot media. This file, plan9.ini, looks like a shell script containing lines of the form

name=value

each of which defines a kernel or device parameter.

Blank lines and Carriage Returns ($\r)$ are ignored. # comments are ignored, but are only recognised if # appears at the start of a line.

For devices, the generic format of *value* is

type=TYPE [port=N] [irq=N] [mem=N] [size=N] [dma=N] [ea=N]

specifying the controller type, the base I/O port of the interface, its interrupt level, the physical starting address of any mapped memory, the length in bytes of that memory, the DMA channel, and for Ethernets an override of the physical network address. Not all elements are relevant to all devices; the relevant values and their defaults are defined below in the description of each device.

The file is used by the kernel to configure the hardware available. The information it contains is also passed to the boot process, and subsequently other programs, as environment variables (see *boot*(8)). However, values whose names begin with an asterisk * are used by the kernel and are not converted into environment variables.

The following sections describe how variables are used.

ETHERNET

ether*X=value*

This defines an Ethernet interface. X, a unique monotonically increasing number beginning at 0, identifies an Ethernet card to be probed at system boot. Probing stops when a card is found or there is no line for etherX+1. After probing as directed by the etherX lines, any remaining Ethernet cards that can be automatically detected are added. Almost all cards can be automatically detected. For debugging purposes, automatic probing can be disabled by specifying the line *noetherprobe=.

Some cards are software configurable and do not require all options. Unspecified options default to the factory defaults.

Known TYPEs are

igbe The Intel 8254X Gigabit Ethernet controllers, as found on the Intel PRO/1000 adapters for copper (not fiber). Completely configurable.

igbepcie

The Intel 8256[36], 8257[12], and 82573[ev] Gigabit Ethernet PCI-Express controllers. Completely configurable.

- rt18169 The Realtek 8169 Gigabit Ethernet controller. Completely configurable.
- ga620 Netgear GA620 and GA620T Gigabit Ethernet cards, and other cards using the Alteon Acenic chip such as the Alteon Acenic fiber and copper cards, the DEC DEGPA-SA and the SGI Acenic. Completely configurable.
- dp83820 National Semiconductor DP83820-based Gigabit Ethernet adapters, notably the D-Link DGE-500T. Completely configurable.
- vgbe The VIA Velocity Gigabit Ethernet controller. Known to drive the VIA8237 (ABIT AV8), but at 100Mb/s full-duplex only.
- m10g The Myricom 10-Gigabit Ethernet 10G-PCIE-8A controller. Completely configurable. Can't boot through these due to enormous firmware loads.

- i82598 The Intel 8259[89] 10-Gigabit Ethernet PCI-Express controllers. Completely configurable.
- 182557 Cards using the Intel 8255[789] Fast Ethernet PCI Bus LAN Controller such as the Intel EtherExpress PRO/100B. Completely configurable, no options need be given. If you need to force the media, specify one of the options (no value) 10BASE-T, 10BASE-2, 10BASE-5, 100BASE-TX, 10BASE-TFD, 100BASE-TXFD, 100BASE-T4, 100BASE-FX, or 100BASE-FXFD. Completely configurable.
- 2114x Cards using the Digital Equipment (now Intel) 2114x PCI Fast Ethernet Adapter Controller, for example the Netgear FA310. Completely configurable, no options need be given. Media can be specified the same was as for the 182557. Some cards using the PNIC and PNIC2 near-clone chips may also work.
- 83815 National Semiconductor DP83815-based adapters, notably the Netgear FA311, Netgear FA312, and various SiS built-in controllers such as the SiS900. On the SiS controllers, the Ethernet address is not detected properly; specify it with an ea= attribute. Completely configurable.
- rtl8139 The Realtek 8139 Fast Ethernet controller. Completely configurable.
- vt6102 The VIA VT6102 Fast Ethernet Controller (Rhine II).

smc91cxx

SMC 91cXX chip-based PCMCIA adapters, notably the SMC EtherEZ card.

- elnk3 The 3COM Etherlink III series of cards including the 5x9, 59x, and 905 and 905B. Completely configurable, no options need be given. The media may be specified by setting media= to the value 10BaseT, 10Base2, 100BaseTX, 100BaseFX, aui, and mii. If you need to force full duplex, because for example the Ethernet switch does not negotiate correctly, just name the word (no value) fullduplex or 100BASE-TXFD. Similarly, to force 100Mbit operation, specify force100. Port 0x110 is used for the little ISA configuration dance.
- 3c589 The 3COM 3C589 series PCMCIA cards, including the 3C562 and the 589E. There is no support for the modem on the 3C562. Completely configurable, no options need be given. Defaults are

port=0x240 irq=10

The media may be specified as media=10BaseT or media=10Base2.

ec2t The Linksys Combo PCMCIA EthernetCard (EC2T), EtherFast 10/100 PCMCIA cards (PCMPC100) and integrated controllers (PCM100), the Netgear FA410TX 10/100 PCM-CIA card and the Accton EtherPair-PCMCIA (EN2216). Completely configurable, no options need be given. Defaults are

port=0x300 irq=9

These cards are NE2000 clones. Other NE2000 compatible PCMCIA cards may be tried with the option

id=string

where string is a unique identifier string contained in the attribute memory of the card (see *pcmcia*(8)); unlike most options in plan9.ini, this string is case-sensitive. The option dummyrr=[01] can be used to turn off (0) or on (1) a dummy remote read in the driver in such cases, depending on how NE2000 compatible they are.

ne2000 Not software configurable iff ISA; PCI clones or supersets are software configurable; includes the Realtek 8029 clone used by Parallels. 16-bit card. Defaults are port=0x300 irg=2 mem=0x04000 size=0x4000

The option (no value) nodummyrr is needed on some (near) clones to turn off a dummy remote read in the driver.

amd79c970

The AMD PCnet PCI Ethernet Adapter (AM79C970). (This is the Ethernet adapter used by VMware.) Completely configurable, no options need be given.

BUG: On many machines only the 16 bit card works.

- bcm Broadcom BCM57xx Gigabit Ethernet controllers. Completely configurable, no options need be given.
- yuk Marvell 88e8057 Yukon2 Gigabit Ethernet controller. Completely configurable, no options need be given.
- virtio Virtual Ethernet interface provided by QEMU/KVM and VirtualBox. No options need be given. The MAC address can be changed with the ea= option.
- sink A /dev/null for Ethernet packets the interface discards sent packets and never receives any. This is used to provide a test bed for some experimental Ethernet bridging software.
- wavelan Lucent Wavelan (Orinoco) IEEE 802.11b and compatible PCMCIA cards. Compatible cards include the Dell TrueMobile 1150 and the Linksys Instant Wireless Network PC Card. Port and IRQ defaults are 0x180 and 3 respectively.

These cards take a number of unique options to aid in identifying the card correctly on the 802.11b network. The network may be *ad hoc* or *managed* (i.e. use an access point):

mode=[adhoc, managed]

and defaults to *managed*. The 802.11b network to attach to (*managed* mode) or identify as (*ad hoc* mode), is specified by

essid=string

and defaults to a null string. The card station name is given by station=string

and defaults to Plan 9 STA. The channel to use is given by

channel=number

where *number* lies in the range 1 to 16 inclusive; the channel is normally negotiated automatically.

If the card is capable of encryption, the following options may be used:

crypt=[off, on]

and defaults to *on*.

keyN=string

sets the encryption key N (where N is in the range 1 to 4 inclusive) to *string*; this will also set the transmit key to N (see below). There are two formats for *string* which depend on the length of the string. If it is exactly 5 or 13 characters long it is assumed to be an alphanumeric key; if it is exactly 10 or 26 characters long the key is assumed to be in hex format (without a leading 0x). The lengths are checked, as is the format of a hex key.

txkey=number

sets the transmit key to use to be *number* in the range 1 to 4 inclusive. If it is desired to exclude or include unencrypted packets

```
clear=[off, on]
```

configures reception and defaults to inclusion.

The defaults are intended to match the common case of a managed network with encryption and a typical entry would only require, for example

essid=left-armpit key1=afish key2=calledraawaru
if the port and IRQ defaults are used. These options may be set after boot by writing
to the device's ctl file using a space as the separator between option and value, e.g.
 echo 'key2 1d8f65c9a52d83c8e4b43f94af' >/net/ether0/0/ctl

Card-specific power management may be enabled/disabled by
 pm=[on, off]

wavelanpci

PCI Ethernet adapters that use the same Wavelan programming interface. Currently the only tested cards are those based on the Intersil Prism 2.5 chipset.

iwl Intel Wireless WiFi Link mini PCI-Express adapters require firmware from http://firmware.openbsd.org/firmware/*/iwn-firmware*.tgz to be present on attach in /lib/firmware or /boot. To limit the selected APs the options essid= and bssid= may be set at boot or in the ether interface clone file using a space as the separator between option and value, e.g.

echo essid left-armpit >/net/ether1/clone

Ad-hoc mode or WEP encryption is currently not supported.

- rt2860 Ralink Technology PCI/PCI-Express wireless adapters require firmware from http://firmware.openbsd.org/firmware/*/ral-firmware*.tgz to be present on attach in /lib/firmware or /boot. See iwl section above for configuration details.
- wpi Intel PRO Wireless 3945abg PCI/PCI-Express wireless adapters require firmware from http://firmware.openbsd.org/firmware/*/wpi-firmware*.tgz to be present on attach in /lib/firmware or /boot. See iwl section above for configuration details.

wpapsk=password

WPA/WPA2 encryption is detected automatically and a prompt for the *password* will appear when using the WIFI interface for netbooting. To avoid the prompt, the *password* can be specified with the boot parameter above.

nora6=

Disable automatic IPv6 configuration from incoming router advertisements.

DISKS, TAPES

(S)ATA controllers are autodetected.

*nodma=

disables dma on ata devices.

*sdXXdma=on

explicitly enables dma on a specific ata device.

scsi*X*=value

This defines a SCSI interface which cannot be automatically detected by the kernel.

Known TYPEs are

aha1542

Adaptec 154x series of controllers (and clones). Almost completely configurable, only the port=0x300

option need be given.

NCR/Symbios/LSI-Logic 53c8xx-based adapters and Mylex MultiMaster (Buslogic BT-*) adapters are automatically detected and need no entries.

By default, the NCR 53c8xx driver searches for up to 32 controllers. This can be changed by setting the variable *maxsd53c8xx.

By default the Mylex driver resets SCSI cards by using both the hard reset and SCSI bus reset flags in the driver interface. If a variable *noscsireset is defined, the SCSI bus reset flag is omitted.

aoeif=list

This specifies a space-separated *list* of Ethernet interfaces to be bound at boot to the ATA-over-Ethernet driver, *aoe*(3). For example, aoeif=ether0 ether1. Only interfaces on this list will initially be accessible via AoE.

aoedev=e!#æ/aoe/shelf.slot

This specifies an ATA-over-Ethernet device accessible via the interfaces named in *aoeif* on AoE *shelf* and *slot* to use as a root device for bootstrapping.

ramdisk*X=size*

ramdiskX=size sectorsize

ramdiskX=address size sectorsize

This reserves physical memory as a ramdisk that will appear as sd(3) device sdZX. When the *address* argument is omited or zero, then the ramdisk will be allocated from the top of physical memory.

AUDIO

audioX=value

This defines a sound interface. PCI based audio devices such as Intel HD audio or AC97 are autodetected and do not require any settings.

Known types are

hda Intel HD audio.

ac97 AC97 based card.

sb16 Sound Blaster 16.

ess1688 A Sound Blaster clone.

The DMA channel may be any of 5, 6, or 7. The defaults are

port=0x220 irq=7 dma=5

UARTS

Plan 9 automatically configures COM1 and COM2, if found, as eia0 (port 0x3F8, IRQ4) and eia1 (port 0x2F8, IRQ3) respectively. These devices can be disabled by adding a line:

eiaX=disabled

This is typically done in order to reuse the IRQ for another device.

Additional i8250 (ISA) uarts (uart2 to uart5) can be configured using:

uartX=type=isa port=port irq=irq

Perle PCI-Fast4, PCI-Fast8, and PCI-Fast16 controllers are automatically detected and need no configuration lines.

The line serial=type=com can be used to specify settings for a PCMCIA modem.

kbmap=value

This specifies the keyboard map to use. *Value* can be a map file found in /sys/lib/kbmap on the ramdisk.

For example:

kbmap=colemak

mouseport=value

This specifies where the mouse is attached. *Value* can be a map file found in /sys/lib/kbmap on the ramdisk.

ps2 the PS2 mouse/keyboard port. The BIOS setup procedure should be used to configure the machine appropriately.

ps2intellimouse

an Intellimouse on the PS2 port.

- 0 for COM1
- 1 for COM2

modemport=value

Picks the UART line to call out on. This is used when connecting to a file server over an async line. *Value* is the number of the port.

console=value params

This is used to specify the console device. The default *value* is cga; a number 0 or 1 specifies *COM1* or *COM2* respectively. A serial console is initially configured with the *uart*(3) configuration string b9600 18 pn s1, specifying 9600 baud, 8 bit bytes, no parity, and one stop bit. If *params* is given, it will be used to further configure the uart. Notice that there is no = sign in the *params* syntax. For example,

console=0 b19200 po

would use COM1 at 19,200 baud with odd parity.

The value net specifies "netconsole" which sends console messages as UDP packets over the network. It bypasses the IP stack and writes Ethernet packets directly to the NIC. In this case *params* is mandatory and takes the form

srcip [!srcport] [/devno] , dstip [!dstport] [/dstmac]

Srcip, srcport (default 6665), dstip and dstport (default 6666) specify the source IP address, source port, destination IP address and destination port, respectively. Devno (default 0) specifies which NIC to use, a value of *n* corresponds to NIC at #ln (see *ether*(3)). Dstmac specifies the destination MAC address; broadcast packets are sent if it is unspecified. Note that it is possible, but not recommended, to send packets to a host outside the local network by specifying the MAC address of the gateway as *dstmac*. Example lines are

console=net 192.168.0.4,192.168.0.8

console=net 192.168.2.10!1337/1,192.168.2.3!1337/0ea7deadbeef

PC CARD

pccard0=disabled

Disable probing for and automatic configuration of PC card controllers.

pcmciaX=type=XXX irq=value

If the default IRQ for the PCMCIA is correct, this entry can be omitted. The value of type is ignored.

pcmcia0=disabled

Disable probing for and automatic configuration of PCMCIA controllers.

BOOTING

bootfile=value

This is used to direct the actions of *9boot*(8) by naming the file from which to load the kernel in the current BIOS boot device.

bootargs=*value*

The *value* of this variable is passed to *boot*(8) by the kernel as the name of the root file system to automatically mount and boot into. It is typically used to specify additional arguments to pass to cwfs(4) or *ipconfig*(8). For example, if the system is to run from a local cwfs(4) partition, the definition might read bootargs=local!/dev/sdC0/fscache. See *boot*(8) for more.

nobootprompt=value

Suppress the bootargs prompt and use *value* as the answer instead.

rootdir=/root/dir

rootspec=*spec*

Changes the mount arguments for the root file server that was specified by *bootargs* above. By changing *dir* in *\$rootdir*, a different sub-directory on the root file server can be used as the system root. see *boot*(8) for details.

user=value

Suppress the user prompt and use *value* as the answer instead.

service=value

Changes the systems default role. Possible settings for *value* are cpu and terminal.

debugfactotum=

Causes *boot*(8) to start *factotum* with the -p option, so that it can be debugged.

cfs=value

This gives the name of the file holding the disk partition for the cache file system, cfs(4). Extending the bootargs example, one would write cfs=#S/sdC0/cache.

bootdisk=*value*

This deprecated variable was used to specify the disk used by the cache file system and other disk-resident services. It is superseded by bootargs and cfs.

fs=address

auth=*address*

secstore=*address*

These specify the network address (IP or domain name) of the file, authentication and secstore server to use when mounting a network-provided root file system. When not specified, then these settings are determined via DHCP. When secstore is not specified, then the authentication server is used.

PROCESSOR

*e820=type **Ox**start **Ox**end ...

This variable is automatically generated by the boot loader (see *9boot*(8)) by doing a BIOS E820 memory scan while still in realmode and passed to the kernel. The format is a unordered list of decimal region *type* and hexadecimal 64-bit *start* and *end* addresses of the area.

*maxmem=value

This defines the maximum physical address that the system will scan when sizing memory. By default the PC operating system will scan up to 3.75 gigabytes (0xF0000000, the base of kernel virtual address space), but setting *maxmem will limit the scan. *maxmem must be less than 3.75 gigabytes. This variable is not consulted if using the E820 memory map.

*kernelpercent=value

This defines what percentage of available memory is reserved for the kernel allocation pool. The remainder is left for user processes. The default *value* is 30 on CPU servers, 60 on terminals with less than 16MB of memory, and 40 on terminals with memories of 16MB or more. Terminals use more kernel memory because *draw*(3) maintains its graphic images in kernel memory. This deprecated option is rarely necessary in newer kernels.

*imagemaxmb=value

This limits the maximum amount of memory (in megabytes) the graphics image memory pool can grow. The default is unlimited for terminals and cpu servers.

*noavx=

Disables AVX and AVX2 on AMD64 CPUs.

*nomce=

If machine check exceptions are supported by the processor, then they are enabled by default. Setting *nomce causes them to be disabled even when available.

*nomp=

A multiprocessor machine will enable all processors by default. Setting *nomp restricts the kernel to starting only one processor and using the traditional interrupt controller.

*ncpu=value

Setting *ncpu restricts the kernel to starting at most *value* processors.

*apicdebug=

Prints a summary of the multiprocessor APIC interrupt configuration.

*nomsi=

Disables message signaled interrupts for PCI devices. This option has no effect when *nomp is set.

*nomtrr=

Disables memory type range register (MTRR) support when set. (debug)

*notsc=

Disables the use of the per processor timestamp counter registers as high resolution clock.

*nohpet=

Disables the HPET timer to be used as the high resolution clock.

*pcimaxbno=value

This puts a limit on the maximum bus number probed on a PCI bus (default 7). For example, a *value* of 1 should suffice on a 'standard' motherboard with an AGP slot. This, and *pcimaxdno below are rarely used and only on troublesome or suspect hardware.

*pcimaxdno=value

This puts a limit on the maximum device number probed on a PCI bus (default 31).

*nopcirouting=

Disable pci routing during boot. May solve interrupt routing problems on certain machines.

*pcihinv=

Prints a summary of the detected PCI busses and devices.

*nodumpstack=

Disable printing a stack dump on panic. Useful if there is only a limited cga screen available, otherwise the textual information about the panic may scroll off.

ioexclude=value

Specifies a list of ranges of I/O ports to exclude from use by drivers. Ranges are inclusive on both ends and separated by commas. For example:

ioexclude=0x330-0x337,0x430-0x43F

umbexclude=value

Specifies a list of ranges of UMB to exclude from use by drivers. Ranges are inclusive on both ends and separated by commas. For example:

umbexclude=0xD1800-0xD3FFF

*acpi=value

The presence of this option enables ACPI and the export of the #P/acpitbls file in *arch*(3) device. In multiprocessor mode, the kernel will use the ACPI tables to configure APIC interrupts unless a *value* of 0 is specified.

apm0=

This enables the "advanced power management" interface as described in apm(3) and apm(8). The main feature of the interface is the ability to watch battery life (see *stats*(8)). It is not on by default because it causes problems on some laptops.

USB

*nousbprobe=

Disable USB host controller detection.

*nousbohci=

*nousbuhci=

- *nousbehci=
- *nousbxhci=

Disable specific USB host controller types.

nousbrc=

Disable *nusbrc*(8) startup at boot time.

nousbhname=

When defined, *nusbrc*(8) will use the dynamically assigned usb device address to name usb devices instead of the device unique name.

VIDEO

- monitor=value
- vgasize=*value*

These are used not by the kernel but by *termrc* (see *cpurc*(8)) when starting vga(8). If *value* is set to ask then the user is prompted for a choice on boot.

*bootscreen=value

This is used by the kernel to attach a pre-initialized linear framebuffer that was setup by the bootloader or firmware. The *value* has four space separated fields: the resolution and bitdepth of the screen, the color channel descriptor, the physical address of the framebuffer and a optional aperture size.

*bootscreen=800x600x32 x8r8g8b8 0x80000000 0x001d4c00

*dpms=value

This is used to specify the screen blanking behavior of the MGA4xx video driver. Values are standby, suspend, and off. The first two specify differing levels of power saving; the third turns the monitor off completely.

NVRAM

nvram=file

nvrlen=length

nvroff=offset

This is used to specify an nvram device and optionally the length of the ram and read/write offset to use. These values are consulted by *readnvram* (see *authsrv*(2)). The most common use of the nvram is to hold a *secstore*(1) password for use by *factotum*(4).

nvr=value

This is used by the WORM file server kernel to locate a file holding information to configure the file system. The file cannot live on a SCSI disk. The default is fd!0!plan9.nvr (sic), unless bootfile is set, in which case it is plan9.nvr on the same disk as bootfile. The syntax is

either fd! unit! name or hd! unit! name where unit is the numeric unit id. This variant syntax is a vestige of the file server kernel's origins.

EXAMPLES

A representative plan9.ini:

```
% cat /n/9fat:/plan9.ini
ether0=type=3C509
mouseport=ps2
modemport=1
serial0=type=generic port=0x3E8 irq=5
monitor=445x
vgasize=1600x1200x8
bootfile=/386/9pc
%
```

SEE ALSO

9boot(8), booting(8), boot(8)

pop3, imap4d - Internet mail servers

SYNOPSIS

upas/pop3 [-d debugfile][-a mailbox][-r peeraddr][-t tlscertfile][-p]

upas/imap4d [-acpv] [-d smtpdomain] [-s servername]

DESCRIPTION

These programs support remote access to mail across the Internet. All expect the network connection to be standard input, output, and error. They are normally started from scripts in /rc/bin/service (see *listen*(8)).

Pop3 provides access to a user's mailboxes via the POP3 protocol. The options are:

- -d create *debugfile* and write debugging output to it
- -a causes pop3 to assume that it already authenticated and to read *mailbox* immediately
- -r causes *pop3* to create the file /mail/ratify/trusted/*peeraddr*#32 to allow subsequent SMTP sessions from that address. See *ratfs*(4) for details.
- -t get the local TLS certificate from the file *tlscertfile*.

-p allow passwords in the clear for authenticating the connection

Imap4d provides access to a user's mailboxes via the IMAP4rev1 protocol. Only files rooted in /mail/box/username/ are accessible. The list of subscribed mailboxes is contained in /mail/box/username/imap.subscribed, and initially contains only INBOX, IMAP's name for the user's mailbox. A shadow file, mailbox.imp, is created for each mailbox examined.

Imap4d's options are:

- -a Assume the user is already authenticated. By default, the user must authenticate using CRAM-MD5 or *securenet*(8) challenge/response authentication.
- -c Allow plan 9 challenge response authentication.
- -p Allow login authentication. This option should only be enabled for servers using an encrypted connection, such as SSL, and when enabled, all non-encrypted connections should be disallowed. *Imap4d* does not enforce this policy.
- -v Turn on verbose output to the debug file.
- -s The server's name. If none is provided, cs (see ndb(8)) is queried or /env/sysname is used.
- -d The local mail domain. Defaults to the server /env/site in the mail server's domain.

For both *imap4d* and *pop3*, the password used to authenticate the connection is the APOP secret held by *keyfs*(4) running on the authentication server.

FILES

debugging output

/sys/log/imap4d comparison compared compare

SOURCE

/sys/src/cmd/upas/pop3
/sys/src/cmd/upas/imap4d

SEE ALSO

aliasmail(8), faces(1), filter(1), mail(1), marshal(1), mlmgr(1), nedmail(1), qer(8), rewrite(6), send(8), upasfs(4)

BUGS

Usually messages flagged for deletion with DELE are not actually deleted until the client sends a QUIT command to end the conversation. *Pop3* implements a non-standard command SYNC that deletes messages flagged for deletion without ending the conversation.

ppp, pppoe, pptp, pptpd – point-to-point protocol

SYNOPSIS

ip/ppp [-CPSacdfu] [-b baud] [-k keyspec] [-m mtu] [-M chatfile] [-p dev] [-x netmntpt] [-t modemcmd] [local [remote]]

ip/pppoe [-PdcC][-A acname][-S srvname][-k keyspec][-m mtu][-b baud][-x pppnetmntpt][ether]

ip/pptp[-dP][-k keyspec][-w window][-x pppnetmntpt] server

ip/pptpd [-d] [-p pppnetmtpt] [-w window] [-D fraction] tcp-dir

DESCRIPTION

The Point-to-Point Protocol is used to encapsulate Internet Protocol packets in IPv4 packets for transfer over serial lines or other protocol connections. *Ppp* can run either as a client or, with the -S option, as a server. The only differences between a client and a server is that the server will not believe any local address the client tries to supply it and that the server always initiates the authentication of the client.

With no option, *ppp* communicates with the remote system via standard input and output. This is useful if a program wants to use *ppp* in a communications stream. However, the normal mode is to specify a communications device, usually a serial line with a modem.

Ppp supports the following options:

- a as server, don't request authentication from the client
- b set the baud rate on the communications device
- c disallow packet compression
- C disallow IP header compression
- ${\bf f}\,$ make PPP add HDLC framing. This is necessary when using PPP over a serial line or a TCP connection
- k add keyspec to the factotum(4) key pattern when looking for a user name and password for authentication.
- m set the maximum transfer unit (default 1450)
- M chat with the modem as specified in the chat file. Each line in the chat file contains a string that is transmitted to the modem and the response expected (e.g. 'AT' 'OK')
- P use this as the primary IP interface; set the default route through this interface and write its configuration to /net/ndb
- p communicate over *dev* instead of standard I/O
- S run as a server
- t before starting the PPP protocol, write *modemcmd* to the device
- u before starting the PPP protocol with the remote end, shuttle bytes between the device and standard I/O until an EOF on standard input. This allows a user to start *ppp* and then type commands at a modem before *ppp* takes over
- x use the IP stack mounted at *netmntpt*

If both the *local* and *remote* addresses are specified, don't ask the other end for either or believe it if it supplies one. If either is missing, get it from the remote end.

Pppoe is a PPP over ethernet (PPPoE) client. It invokes *ppp* to start a PPP conversation which is tunneled in PPPoE packets on the ethernet device mounted at *etherdir* (default /net/ether0). The *pppoe*-specific options are:

- A insist on an access concentrator named *acname* during PPPoE discovery
- d write debugging output to standard error, and pass -d to ppp
- S insist on a service named *srvname* during PPPoE discovery

The other options are relayed to *ppp*.

Pptp is a client for a PPTP encrypted tunnel. *Server* is the name of the server to dial. *Pptp* takes the same options as *pppoe*, except for the lack of a -m option and the addition of a -w option. The -w option specifies the local send window size (default 16) in packets.

Pptpd is the server side of a PPTP encrypted tunnel. *Tcpdir* is the directory of a TCP connection to the client. The TCP connection is used to control the tunnel while packets are sent back and forth using PPP inside of GRE packets. The options are:

- d write debugging output to standard error.
- D drop *fraction* of the received packets. This is used for testing.
- p use the IP stack mounted at *pppnetmtpt* to terminate the PPP connection.
- w set the receive window to window.

SOURCE

/sys/src/cmd/ip/ppp /sys/src/cmd/ip/pptpd.c /sys/src/cmd/ip/pppoe.c

SEE ALSO

gre in *ip*(3)

prep, edisk, fdisk, format, mbr - prepare disks, floppies and flashes

SYNOPSIS

disk/prep[-bcfnprw][-a name]... [-s sectorsize] plan9partition disk/edisk[-abfprw][-s sectorsize] disk disk/fdisk[-abfprw][-s sectorsize] disk

disk/format[-dfvx][-b bootblock][-c csize][-l label][-r nresrv][-t type] disk[
file...]

disk/mbr[-9][-m mbrfile] disk

DESCRIPTION

A partition table is stored on a hard disk to specify the division of the physical disk into a set of logical units. On PCs using traditional DOS partition table, the partition entries are stored at the end of the master boot record of the disk. Partitions of type 0x39 are Plan 9 partitions. EFI systems use GUID partition table (GPT) format where partition types are identied by a 128-bit long identifiers. The randomly generated GUID C91818F9-8025-47AF-89D2-F030D7000C2C is used to identify the Plan 9 partition type in this scheme. The names of DOS and GPT partitions are chosen by convention from the type: dos, plan9, etc. Second and subsequent partitions of the same type on a given disk are given unique names by appending a number (or a period and a number if the name already ends in a number).

Plan 9 partitions (and Plan 9 disks on non-PCs) are themselves divided, using a textual partition table, called the Plan 9 partition table, in the second sector of the partition (the first is left for architecture-specific boot data, such as PC boot blocks). The table is a sequence of lines of the format part *name start end*, where *start* and *end* name the starting and ending sector. Sector 0 is the first sector of the Plan 9 partition or disk, regardless of its position in a larger disk. Partition extents do not contain the ending sector, so a partition from 0 to 5 and a partition from 5 to 10 do not overlap.

The Plan 9 partition often contains a number of conventionally named subpartitions. They include:

- 9fat A small FAT file system used to hold configuration information (such as plan9.ini and plan9.nvr) and kernels. This typically begins in the first sector of the partition, and contains the partition table as a "reserved" sector. See the discussion of the -r option to *format*.
- arenas A venti(8) arenas partition.
- bloom A *venti*(8) bloom-filter partition.
- cache A *cfs*(4) file system cache.
- fscache A cwfs(4) worm cache partition.
- fsworm A *cwfs*(4) worm filesystem.
- fs A kfs file system.
- fscfg A one-sector partition used to store an *fs*(3) configuration.
- isect A *venti*(8) index section.
- nvram A one-sector partition used to simulate non-volatile RAM on PCs.
- other A non-archived *cwfs*(4) file system.
- swap A *swap*(8) swap partition.

Fdisk edits the DOS partition table and is usually invoked with a disk like /dev/sdC0/data as its argument, while *prep* edits the Plan 9 partition table and is usually invoked with a disk partition like /dev/sdC0/plan9 as its argument. *Edisk* is similar to *fdisk* but edits the GPT partition table on EFI systems. *Fdisk* works in units of disk "cylinders": the cylinder size in bytes is printed when *fdisk* starts. *Prep* and *edisk* works in units of disk sectors, which are almost always 512 bytes. *Fdisk*, *edisk* and *prep* share most of their options:

-a Automatically partition the disk. *Fdisk* and *edisk* will create a Plan 9 partition in the largest unused area on the disk, doing nothing if a Plan 9 partition already exists. *Edisk* also adds a EFI system partition (esp) when not already exists. If no other partition on the disk is marked active (i.e. marked as the boot partition), *fdisk* will mark the new partition active. *Prep*'s – a flag takes the name of a partition to create. (See the list above for partition names.) It can

be repeated to specify a list of partitions to create. If the disk is currently unpartitioned, *prep* will create the named partitions on the disk, attempting to use the entire disk in a sensible manner. The partition names must be from the list given above.

- -b Start with a blank disk, ignoring any extant partition table.
- -p Print a sequence of commands that when sent to the disk device's ctl file will bring the partition table information kept by the sd(3) driver up to date. Then exit. *Prep* will check to see if it is being called with a disk partition (rather than an entire disk) as its argument; if so, it will translate the printed sectors by the partition's offset within the disk. Since *fdisk* and *edisk* operate on a table of unnamed partitions, they assign names based on the partition type (e.g., plan9, dos, ntfs, linux, linuxswap) and resolve collisions by appending a numbered suffix. (e.g., dos, dos.1, dos.2).
- -r In the absence of the -p and -w flags, *prep*, *edisk* and *fdisk* enter an interactive partition editor; the -r flag runs the editor in read-only mode.
- –s sectorsize

Specify the disk's sector size. In the absence of this flag, *prep*, *edisk* and *fdisk* look for a disk ctl file and read it to find the disk's sector size. If the ctl file cannot be found, a message is printed and a sector size of 512 bytes is assumed.

-w Write the partition table to the disk and exit. This is useful when used in conjunction with -a or -b.

If neither the -p flag nor the -w flag is given, *prep*, *edisk* and *fdisk* enter an interactive partition editor that operates on named partitions. The DOS partition table distinguishes between primary partitions, which can be listed in the boot sector at the beginning of the disk, and secondary (or extended) partitions, arbitrarily many of which may be chained together in place of a primary partition. Primary partitions are named pn, secondary partitions sn. The number of primary partitions plus number of contiguous chains of secondary partitions cannot exceed four. The GPT partition table is a fixed array of partition entries (usually 128). Partitions are named pn, where n indexes the entry in array starting from 1 for the first entry.

The commands are as follows. In the descriptions, read "sector" as "cylinder" when using *fdisk*.

a name [start [end]]

Create a partition named *name* starting at sector offset *start* and ending at offset *end*. The new partition will not be created if it overlaps an extant partition. If *start* or *end* are omitted, the editor will prompt for them. In *fdisk* and *edisk* the newly created partition is of the Plan 9 type; to set a different type, use the t command (q.v.). *Start* and *end* may be expressions using the operators +, -, *, and /, numeric constants, and the pseudovariables . and \$. At the start of the program, . is set to zero; each time a partition is created, it is set to the end sector of the new partition. It can also be explicitly set using the . command. When evaluating *start*, \$ is set to one past the last disk sector. When evaluating *end*, \$ is set to the maximum value that *end* can take on without running off the disk or into another partition. Numeric constants followed by k, m, g, or t (or upper-case equivalents) are scaled to the respective size in kilo-, mega-, giga-, or tera-bytes. Finally, the expression *n*% evaluates to ($n \times disksize$)/100. As examples, a . .+20% creates a new partition starting at . that takes up a fifth of the disk, a . .+21G creates a new partition starting at sector 1000 and extending as far as possible.

- . *newdot* Set the value of the variable . to *newdot*, which is an arithmetic expression as described in the discussion of the a command.
- d name Delete the named partition.
- h Print a help message listing command synopses.
- p Print the disk partition table. Unpartitioned regions are also listed. The table consists of a number of lines containing partition name, beginning and ending sectors, and total size. A ' is prefixed to the names of partitions whose entries have been modified but not written to disk. *Fdisk* adds to the end of each line a textual partition type, and places a * next to the name of the active partition (see the A command below).

- P Print the partition table in the format accepted by the disk's ctl file, which is also the format of the output of the -p option.
- W Write the partition table to disk. *Prep* will also inform the kernel of the changed partition table. The write will fail if any programs have any of the disk's partitions open. If the write fails (for this or any other reason), the program will attempt to restore the partition table to its former state.
- q Quit the program. If the partition table has been modified but not written, a warning is printed. Typing q again will quit the program.

Fdisk also has the following commands.

- A *name* Set the named partition active. The active partition is the one whose boot block is used when booting a PC from disk.
- t name [type]

Set the partition type. If it is not given, *fdisk* will display a list of choices and then prompt for it.

Edisk also has the following commands.

t name [type]

Set the partition type; like *fdisk* above.

f name [+-attr]

Set or clear partition attributes.

1 name [label]

Set the partition label.

Format prepares for use the floppy diskette or hard disk partition in the file named *disk*, for example /dev/fd0disk or /dev/sdC0/9fat. The options are:

- -f Do not physically format the disc. Used to install a FAT file system on a previously formatted disc. If *disk* is not a floppy device, this flag is a no-op.
- -t specify a density and type of disk to be prepared. The possible *types* are:
 - 3½DD 3½" double density, 737280 bytes
 - 3½HD 3½" high density, 1474560 bytes
 - 5¹/₄DD 5¹/₄" double density, 368640 bytes
 - 5¼HD 5¼" high density, 1146880 bytes
 - hard fixed disk

The default when *disk* is a floppy drive is the highest possible on the device. When *disk* is a regular file, the default is $3\frac{3}{4}$ HD. When *disk* is an *sd*(3) device, the default is hard.

- -d initialize a FAT file system on the *disk*.
- -b use the contents of *bootblock* as a bootstrap block to be installed in sector 0.

The remaining options have effect only when -d is specified:

- -c use a FAT cluster size of *csize* sectors when creating the FAT.
- -1 add a *label* when creating the FAT file system.
- -r mark the first *nresrv* sectors of the partition as "reserved". Since the first sector always contains the FAT parameter block, this really marks the *nresrv*-1 sectors starting at sector 1 as "reserved". When formatting the 9fat partition, -r 2 should be used to jump over the partition table sector.

Again under -d, any *files* listed are added, in order, to the root directory of the FAT file system. The files are contiguously allocated.

Format checks for a number of common mistakes; in particular, it will refuse to format a 9fat partition unless -r is specified with *nresrv* larger than two. It also refuses to format a raw sd(3) partition that begins at offset zero in the disk. (The beginning of the disk should contain an *fdisk* partition table with master boot record, not a FAT file system or boot block.) Both checks are

disabled by the -x option. The -v option prints debugging information.

The file /386/pbs is an example of a suitable *bfile* to make the disk a boot disk. It gets loaded by the BIOS at 0x7C00, reads the first sector of the root directory into address 0x7E00, and looks for a directory entry named 9BOOTFAT. If it finds such an entry, it uses single sector reads to load the file into address 0x7C00 and then jumps to the loaded file image.

Mbr installs a new boot block in sector 0 (the master boot record) of a disk such as /dev/sdC0/data. If *mbrfile* contains more than one sector of 'boot block', the rest will be copied into the first track of the disk, if it fits. This boot block should not be confused with the boot block used by *format*, which goes in sector 0 of a partition. Typically, the boot block in the master boot record scans the PC partition table to find an active partition and then executes the boot block for that partition. The partition boot block then loads a bootstrap program such as *9boot*(8), which then loads the operating system. If MS-DOS or Windows 9[58] is already installed on your hard disk, the master boot record already has a suitable boot block. Otherwise, /386/mbr is an appropriate *mbrfile*. It detects and uses LBA addressing when available from the BIOS (the same could not be done in the case of pbs due to space considerations). If the *mbrfile* is not specified, a boot block is installed that prints a message explaining that the disk is not bootable. The -9 option initialises the partition table to consist of one plan9 partition which spans the entire disc starting at the end of the first track.

EXAMPLES

Initialize the kernel disk driver with the partition information from the FAT boot sectors. If Plan 9 partitions exist, pass that partition information as well.

```
for(disk in /dev/sd??) {
    if(test -f $disk/data && test -f $disk/ctl)
        disk/fdisk -p $disk/data >$disk/ctl
    for(part in $disk/plan9*)
        if(test -f $part)
            disk/prep -p $part >$disk/ctl
}
```

Initialize the blank hard disk /dev/sdC0/data.

FILES

```
/386/mbr
```

/386/pbs

SOURCE

/sys/src/cmd/disk/prep
/sys/src/boot/pc

SEE ALSO

floppy(3), sd(3), nusb(4), 9boot(8), partfs(8), diskparts(8)

BUGS

If prep -p doesn't find a Plan 9 partition table, it will emit commands to delete *all* extant partitions. Similarly, fdisk -p will delete all partitions, including data, if there are no partitions defined in the MBR.

qer, runq - queue management for spooled files

SYNOPSIS

```
qer [ -q subdir ] [ -f file ] root tag reply args
```

```
rung [-adER] [-f file] [-q subdir] [-t time] [-r nfiles] [-n njobs] root cmd
```

DESCRIPTION

Qer creates a control and a data file in a queue directory. The control file contents consist of the *tag*, *reply*, and *args* separated by spaces. The data file contains the standard input to *qer*. The files are created in the directory *root/subdi* The names of the control and data files differ only in the first character which is 'C' and 'D' respectively. *Mktemp*(2) is used to create the actual names of the control and data file.

Some commands, such as fax (see telco(4)), must queue more files than just the data file. Each *file* following a -f flag is copied into the queue directory. The names of the copies differ from the name of the data file only in the first character. The first one starts with 'F', the second 'G', etc.

Qer takes the following arguments:

-q subdir

Specifies the queue subdirectory to use. If unspecified, the contents of /dev/user are used.

-f file

Specifies the files to copy into the queue directory, in the manner described above.

Runq processes the files queued by *qer*. *Runq* processes all requests in the directory *root/subdir*, where *subdir* is the argument to -q if present, else the contents of /dev/user. Each request is processed by executing the command *cmd* with the contents of the control file as its arguments, the contents of the data file as its standard input, and standard error appended to the error file E.XXXXXX.

The action taken by *runq* depends on the return status of *cmd*. If *cmd* returns a null status, the processing is assumed successful and the control, data, and error files are removed. If *cmd* returns an error status containing the word Retry, the files are left to be reprocessed at a later time. For any other status, an error message is mailed to the requester and the files are removed. *Runq* uses the *reply* field in the control file as a mail address to which to send an error notification. The notification contains the contents of the control file to identify the failed request.

To avoid reprocessing files too often, the following algorithm is used: a data file younger than one hour will not be processed if its error file exists and was last modified within the preceding 10 minutes. A data file older than one hour will not be processed if its error file exists and was last modified within the preceding hour.

The following flags are accepted by runq:

- -a Causes rung to process all user directories in sequence, instead of only the directory of the current user.
- -E Causes all files to be reprocessed regardless of the file times.
- -R Instructs *runq* never to give up on a failed queue job, instead leaving it in the queue to be retried.
- -d Causes debugging output on standard error describing the progress through the queues.
- -t Specifies the number of hours that retries will continue after a send failure. The default is 48 hours.
- -r Limits the number of files that are processed in a single pass of a queue. *Runq* accumulates the entire directory containing a queue before processing any files. When a queue contains many files and the system does not have enough memory, *runq* exits without making progress. This flag forces *runq* to process the directory in chunks, allowing the queue to be drained incrementally. It is most useful in combination with the -q flag.
- -n Specifies the number of queued jobs that are processed in parallel from the queue; the default is 1. This is useful for a large queue to be processed with a bounded amount of

parallelism.

Runq is often called from cron(8) by an entry such as

0,10,20,30,40,50 * * * * kremvax /bin/upas/rung -a /mail/queue /mail/lib/remotemail

The entry must be a single line; it is folded here only so it fits on the page.

FILES

e directory for user
file
ol file
file
ndary data files

SOURCE

/sys/src/cmd/upas/q

SEE ALSO

mail(1)

rc-httpd - HTTP server

SYNOPSIS

rc-httpd/rc-httpd

DESCRIPTION

Rc-httpd serves the requested file or an index of files found under a website's root directory, or, in the case of CGI, executes a specified CGI program.

CONFIGURATION

As all pieces of rc-httpd are shell scripts, configuration is achieved by setting variables and adding, removing or modifying commands in various files.

rc-httpd

rc_httpd_dir must be set to the root of the rc-httpd installation, the directory containing the rc-httpd script.

path must include rc_httpd_dir/handlers ahead of the base system's path elements.

cgi_path is substituted for *path* when cgi scripts are run. (Be sure to set *path* back in rc-based cgi scripts.)

extra_headers is an optional list of strings to emit when sending http headers.

SERVER_PORT is the port HTTP is to be served on.

select-handler

PATH_INFO is the location relative to the website's root directory of the file to be displayed. Typically, the *location* from the incoming request is honored.

FS_ROOT sets the root directory of the website.

NOINDEXFILE instructs the dir-index module not to look for index.html files, otherwise if an index.html file is found dir-index will exec serve-static to serve the file. At present there is no module to serve an index file but not a directory.

If you do not want directory indexing at all, replace static-or-index with serve-static, which will report 503 forbidden for directories.

Multiple virtual hosts may be configured by creating conditional statements that act upon the *SERVER_NAME* variable. Fine-grained control of specific request strings may be configured via a similar method acting upon the *location* and/or other variables.

EXAMPLES

The following examples demonstrate possible ways to configure select-handler.

```
Serve static files:
```

```
if(~ $SERVER_NAME 9front.org){
          PATH_INFO=$location
          FS_ROOT=/usr/sl/www/$SERVER_NAME
          exec static-or-index
     }
CGI:
     if(~ $SERVER_NAME *cat-v.org){
          PATH_INFO=$location
          FS_ROOT=/usr/sl/www/werc/sites/$SERVER_NAME
          exec static-or-cgi /usr/sl/www/werc/bin/werc.rc
     }
Custom error message for a denied URL:
     fn do_error{
          do_log $1
          echo 'HTTP/1.1 '^$1^$cr
          emit_extra_headers
          echo 'Content-type: text/html'^$cr
```

```
echo $cr
     echo '<html>
<head>
<title>'^$1^'</title>
</head>
<body>
<h1>'^$1^'</h1>'
     echo $2
     echo '<i>rc-httpd at' $SERVER_NAME '</i>'</i>
     echo '
     </body>
     </html>
if(~ $location /v8.tar.bz2){
     do_error '27b/6'
     exit
}
```

STARTUP

Rc-httpd is run from a file in the directory scanned by *listen*(8), or called as an argument to aux/listen1. The program's standard error may be captured to a log file: exec /rc/bin/rc-httpd/rc-httpd >>[2]/sys/log/www

FILES

```
/rc/bin/rc-httpd/rc-httpd
/rc/bin/rc-httpd/select-handler
/rc/bin/rc-httpd/handlers/cgi
/rc/bin/rc-httpd/handlers/dir-index
/rc/bin/rc-httpd/handlers/error
/rc/bin/rc-httpd/handlers/redirect
/rc/bin/rc-httpd/handlers/static-or-cgi
/rc/bin/rc-httpd/handlers/static-or-index
/rc/bin/service/tcp80
/sys/log/www
```

SOURCE

/rc/bin/rc-httpd

SEE ALSO

rc(1), listen(8)

HISTORY

Rc-httpd first appeared in 9front (February, 2013).

realemu - software emulation of /dev/realmode

SYNOPSIS

aux/realemu[-Dpt][-s srvname][-m mountpoint]

DESCRIPTION

Originally, kernel provided /dev/realmode files with the *arch*(3) device to access and call the BIOS.

Interrupts had to be disabled and the processor was switched in the legacy 16-bit realmode with memory protection disabled to execute BIOS code.

This is problematic in case the BIOS reprograms hardware currently used by the operating system or when it reenables interrupts or just crashes. This will freeze or reboot the machine with no way to recover or diagnose the problem.

To avoid this, *realemu* is used to emulate the execution of the BIOS routines by interpreting the machine instructions and intercepting dangerous actions that would compromise the systems stability.

Running *realemu* with no arguments, it mounts itself before /dev and replaces the original /dev/realmode file in the current namespace.

Then programs like vga(8) can use it to make their BIOS calls.

The D flag will enable debug messages for 9P. The p and t flags control tracing of i/o port access and cpu instructions to stderr (fd 2).

When a *srvname* is given with the s argument, the default *mountpoint* is ignored and a 9P channel is created in /srv that can be used to mount the filesystem from another namespace. If a *mountpoint* is given before the *srvname* argument then it is ignored, otherwise it will be used.

EXAMPLES

The *realemu* process is only needed when accessing /dev/realmode. To invoke a subshell so that *realemu* exits normally after aux/vga completes:

% @{rfork n; aux/realemu; aux/vga -m vesa -l \$vgasize}

SOURCE

/sys/src/cmd/aux/realemu

SEE ALSO

vga(8), *arch*(3)

HISTORY

Realemu first appeared in 9front (April, 2011).

reboot - reboot the system upon loss of remote file server connection

SYNOPSIS

aux/reboot [file]

DESCRIPTION

Reboot stats *file*, default /\$*cputype*/lib, once every five minutes. If the stat fails, rather than timing out, *reboot* reboots the system. This is used to restart diskless cpu servers whenever their file server connection is broken.

SOURCE

/sys/src/cmd/aux/reboot.c

applychanges, applylog, compactdb, updatedb - simple client-server replica management

SYNOPSIS

```
replica/compactdb db
```

replica/updatedb[-cl][-p proto][-r root][-t now n][-u uid][-x path]... db
replica/applylog[-nuv][-c name]... [-s name]... clientdb clientroot serverroot[
path ...]

replica/applychanges [-nuv] [-p proto] [-x path] ... clientdb clientroot serverroot [
path ...]

DESCRIPTION

These four tools collectively provide simple log-based client-server replica management. The shell scripts described in *replica*(1) provide a more polished interface.

Both client and server maintain textual databases of file system metadata. Each line is of the form

path mode uid gid mtime length

Later entries for a *path* supersede previous ones. A line with the string REMOVED in the *mode* field annuls all previous entries for that *path*. The entries in a file are typically kept sorted by *path* but need not be. These properties facilitate updating the database atomically by appending to it. *Compactdb* reads in a database and writes out an equivalent one, sorted by path and without outdated or annulled records.

A replica is further described on the server by a textual log listing creation and deletion of files and changes to file contents and metadata. Each line is of the form:

time gen verb path serverpath mode uid gid mtime length

The *time* and *gen* fields are both decimal numbers, providing an ordering for log entries so that incremental tools need not process the whole log each time they are run. The *verb*, a single character, describes the event: addition of a file (a), deletion of a file (d), a change to a file's contents (c), or a change to a file's metadata (m). *Path* is the file path on the client; *serverpath* the path on the server (these are different when the optional fifth field in a proto file line is given; see *proto*(2)). *Mode*, *uid*, *gid*, and *mtime* are the files metadata as in the Dir structure (see *stat*(5)). For deletion events, the metadata is that of the deleted file. For other events, the metadata is that after the event.

Updatedb scans the file system rooted at *root* for changes not present in *db*, noting them by appending new entries to the database and by writing log events to standard output. The -c option causes *updatedb* to consider only file and metadata changes, ignoring file additions and deletions. By default, the log events have *time* set to the current system time and use incrementing *gen* numbers starting at 0. The -t option can be used to specify a different time and starting number. If the -u option is given, all database entries and log events will use *uid* rather than the actual uids. The -x option (which may be specified multiple times) excludes the named path and all its children from the scan. If the -1 option is given, the database is not changed and the *time* and *gen* fields are omitted from the log events; the resulting output is intended to be a human-readable summary of file system activity since the last scan.

Applylog is used to propagate changes from server to client. It applies the changes listed in a log (read from standard input) to the file system rooted at *clientroot*, copying files when necessary from the file system rooted at *serverroot*. By default, *applylog* does not attempt to set the uid on files; the -u flag enables this. *Applylog* will not overwrite local changes made to replicated files. When it detects such conflicts, by default it prints an error describing the conflict and takes no action. If the -c flag is given, *applylog* still takes no action for files beginning with the given names, but does so silently and will not report the conflicts in the future. (The conflict is resolved in favor of the client.) The -s is similar but causes *applylog* to overwrite the local changes. (The conflict is resolved in favor of the server.)

Applychanges is, in some sense, the opposite of *applylog*; it scans the client file system for changes, and applies those changes to the server file system. *Applychanges* will not overwrite remote changes made to replicated files. For example, if a file is copied from server to client and subsequently changed on both server and client, *applychanges* will not copy the client's new

version to the server, because the server also has a new version. Applychanges and applylog detect the same conflicts; to resolve conflicts reported by applychanges, invoke applylog with the -c or -s flags.

EXAMPLE

One might keep a client kfs file system up-to-date against a server file system using these tools. First, connect to a CPU server with a high-speed network connection to the file server and scan the server file system, updating the server database and log:

```
repl=$home/lib/replica
proto=/sys/lib/sysconfig/proto/portproto
db=$repl/srv.portproto.db
log=$repl/srv.portproto.log
```

```
9fs $fs
replica/updatedb -p $proto -r /n/$fs -x $repl $db >>$log
replica/compactdb $db >/tmp/a && mv /tmp/a $db
```

Then, update the client file system:

repl=\$home/lib/replica
db=\$repl/cli.portproto.db
log=\$repl/srv.portproto.log

```
9fs $fs
9fs kfs
replica/applylog $db /n/kfs /n/$fs <$log
replica/compactdb $db >/tmp/a && mv /tmp/a $db
```

The *\$repl* directory is excluded from the sync so that multiple clients can each have their own local database. The shell scripts in */rc/bin/replica* are essentially a further development of this example.

The Plan 9 distribution update program operates similarly, but omits the first scan; it is assumed that the Plan 9 developers run scans manually when the distribution file system changes. The manual page replica(1) describes this in full.

SEE ALSO

replica(1)

BUGS

These tools assume that *mtime* combined with *length* is a good indicator of changes to a file's contents.

rsagen, rsafill, asn12rsa, rsa2asn1, rsa2pub, rsa2ssh, rsa2x509, rsa2csr - generate and format rsa keys

SYNOPSIS

```
rsagen [ -b nbits ] [ -t tag ]
rsafill [ file ]
asn12rsa [ -t tag ] [ file ]
rsa2asn1 [ -a ] [ file ]
rsa2pub [ file ]
rsa2ssh [ -c comment ] [ file ]
rsa2x509 [ -e expiretime ] certinfo [ file ]
rsa2csr subject [ file ]
```

DESCRIPTION

Plan 9 represents an RSA key as an attribute-value pair list prefixed with the string key; this is the generic key format used by factotum(4). A full RSA private key has the following attributes:

proto must be r sa	proto	must be rsa
--------------------	-------	-------------

- size the number of significant bits in n
- ek the encryption exponent
- n the product of !p and !q
- !dk the decryption exponent
- !p a large prime
- ! q another large prime

!kp, !kq, !c2

parameters derived from the other attributes, cached to speed decryption

All the numbers are in hexadecimal except *size*, which is decimal. An RSA public key omits the attributes beginning with ! . A key may have other attributes as well (for example, a service attribute identifying how this key is typically used), but to these utilities such attributes are merely comments.

For example, a very small (and thus insecure) private key and corresponding public key might be:

key proto=rsa size=8 ek=7 n=8F !dk=67 !p=B !q=D !kp=3 !kq=7 !c2=6 key proto=rsa size=8 ek=7 n=8F

Note that the order of the attributes does not matter.

Rsagen prints a randomly generated RSA private key whose n has exactly *nbits* (default 2048) significant bits. If *tag* is specified, it is printed between key and proto=rsa; typically, *tag* is a sequence of attribute-value comments describing the key.

Rsafill reads a private key, recomputes the !kp, !kq, and !c2 attributes if they are missing, and prints a full key.

Asn12rsa reads an RSA private or public key stored as ASN.1 encoded in the binary Distinguished Encoding Rules (DER) and prints a Plan 9 RSA key, inserting *tag* exactly as *rsagen* does. ASN.1/DER is a popular key format on Unix and Windows; it is often encoded in text form using the Privacy Enhanced Mail (PEM) format in a section labeled as an "RSA PRIVATE KEY." The command:

auth/pemdecode 'RSA PRIVATE KEY' | auth/asn12rsa

extracts the key section from a textual ASN.1/DER/PEM key into binary ASN.1/DER format and then converts it to a Plan 9 RSA key.

Rsa2pub reads a Plan 9 RSA public or private key, removes the private attributes, and prints the resulting public key. Comment attributes are preserved.

Rsa2asn1 is like *rsa2pub* but outputs the public key in ASN.1/DER format. With the -a flag a private key is read and encoded in ANS.1/DER format.

Rsa2ssh reads a Plan 9 RSA public or private key and prints the public portion in the format used by SSH2. The -c option will set the comment.

Rsa2x509 reads a Plan 9 RSA private key and writes a self-signed X.509 certificate encoded in ASN.1/DER format to standard output. (Note that ASN.1/DER X.509 certificates are different from ASN.1/DER private keys). The certificate uses the current time as its start time and expires *expiretime* seconds (default 3 years) later. It contains the public half of the key and includes *certinfo* as the issuer/subject string (also known as a "Distinguished Name"). This info is typically in the form:

C=US ST=NJ L=07974 O=Lucent OU='Bell Labs' CN=G.R.Emlin

One can append further Distinguished Names, DNS Names and E-Mail addresses as a "Subject Alternative Name" separated with a comma after the main subject.

The X.509 ASN.1/DER format is often encoded in text using a PEM section labeled as a "CERTIFICATE." The command:

auth/rsa2x509 'C=US OU=''Bell Labs''' file |
auth/pemencode CERTIFICATE

generates such a textual certificate. Applications that serve TLS-encrypted sessions (for example, *httpd*(8), *pop3*(8), and *tlssrv*(8)) expect certificates in ASN.1/DER/PEM format.

The Plan 9 RSA private key needs to be loaded into factorum for TLS server applications. It is recommended to put the key into *secstore*(1), avoiding it being stored unencrypted on the filesystem.

Rsa2csr takes the subject and a RSA private key and outputs a signing request in ASN.1 format.

EXAMPLES

Generate a fresh key and use it to start a TLS-enabled web server:

```
auth/rsagen -t 'service=tls owner=*' >key
auth/rsa2x509 'C=US CN=*.cs.bell-labs.com' key |
            auth/pemencode CERTIFICATE >cert
cat key >/mnt/factotum/ctl
ip/httpd/httpd -c cert
```

Generate a fresh key and configure a remote Unix system to allow use of that key for logins:

```
auth/rsagen -t 'service=ssh' >key
auth/rsa2ssh key | ssh unix 'cat >>.ssh/authorized_keys'
cat key >/mnt/factotum/ctl
ssh unix
```

Convert a private key in PEM format (as generated by OpenSSL) and load it into factotum:

auth/pemdecode 'PRIVATE KEY' key.pem |
 auth/asn12rsa -t 'service=tls' >/mnt/factotum/ctl

Generate a certificate signing request (CSR) in PEM format:

Generate a tinc host key:

```
auth/rsagen -t 'service=tinc role=client host=myhost' > myhost.key
auth/rsa2pub < myhost.key |</pre>
```

```
auth/rsa2asn1 | auth/pemencode 'RSA PUBLIC KEY' > hosts/myhost
```

SOURCE

/sys/src/cmd/auth

SEE ALSO

factotum(4), pem(8),

BUGS

There are too many key formats.

scanmail, testscan - spam filters

SYNOPSIS

upas/scanmail [options] [ger-args] root mail sender system rcpt-list

upas/testscan[-avd][-p patfile][filename]

DESCRIPTION

Scanmail accepts a mail message supplied on standard input, applies a file of patterns to a portion of it, and dispatches the message based on the results. It exactly replaces the generic queuing command qer(8) that is executed from the rc(1) script /mail/lib/qmail in the mail processing pipeline. Associated with each pattern is an *action* in order of decreasing priority:

- dump the message is deleted and a log entry is written to /sys/log/smtpd
- hold the message is placed in a queue for human inspection
- log a line containing the matching portion of the message is written to a log

If no pattern matches or only patterns with an action of \log match, the message is accepted and *scanmail* queues the message for delivery. *Scanmail* meshes with the blocking facilities of *smtpd*(6) to provide several layers of filtering on gateway systems. In all cases the sender is notified that the message has been successfully delivered, leaving the sender unaware that the message has been potentially delayed or deleted.

Scanmail accepts the arguments of qer(8) as well as the following:

- -c Save a copy of each message in a randomly-named file in directory /mail/copy.
- -d Write debugging information to standard error.
- -h Queue held messages by sending domain name. The -q option must specify a root directory; messages are queued in subdirectories of this directory. If the -h option is not specified, messages are accumulated in a subdirectory of /mail/queue.hold named for the contents of /dev/user, usually none.
- -n Messages are never held for inspection, but are delivered. Also known as *vacation mode*.
- -p *filename* Read the patterns from *filename* rather than /mail/lib/patterns.
- -q holdroot Queue deliverable messages in subdirectories of holdroot. This option is the same as the -q option of *qer*(8) and must be present if the -h option is given.
- -s Save deleted messages. Messages are stored, one per randomly-named file, in subdirectories of /mail/queue.dump named with the date.
- -t Test mode. The pattern matcher is applied but the message is discarded and the result is not logged.
- -v Print the highest priority match. This is useful with the -t option for testing the pattern matcher without actually sending a message.

Testscan is the command line version of *scanmail*. If *filename* is missing, it applies the pattern set to the message on standard input. Unlike *scanmail*, which finds the highest priority match, *testscan* prints all matches in the portion of the message under test. It is useful for testing a pattern set or implementing a personal filter using the pipeto file in a user's mail directory. *Testscan* accepts the following options:

- -a Print matches in the complete input message
- -d Enable debug mode
- -v Print the message after conversion to canonical form (q.v.).
- -p filename

Read the patterns from *filename* rather than /mail/lib/patterns.

Canonicalization

Before pattern matching, both programs convert a portion of the message header and the beginning of the message to a canonical form. The amount of the header and message body processed are set by compile-time parameters in the source files. The canonicalization process converts letters to lower-case and replaces consecutive spaces, tabs and newline characters with a single space. HTML commands are deleted except for the parameters following A HREF, IMG SRC, and IMG BORDER directives. Additionally, the following MIME escape sequences are replaced by their ASCII equivalents:

Escape Seq ASCII ----- ----=2e . =2f / =20 <space> =3d =

and the sequence =<newline> is elided. Scanmail assembles the sender, destination domain and recipient fields of the command line into a string that is subjected to the same canonical processing. Following canonicalization, the command line and the two long strings containing the header and the message body are passed to the matching engine for analysis.

Pattern Syntax

The matching engine compiles the pattern set and matches it to each canonicalized input string. Patterns are specified one per line as follows:

{*}action: pattern-spec {~~override...~override}

On all lines, a # introduces a comment; there is no way to escape this character.

Lines beginning with * contain a *pattern-spec* that is a string; otherwise, the *pattern-spec* is a regular expression in the style of *regexp*(6). Regular expression matching is many times less efficient than string matching, so it is wiser to enumerate several similar strings than to combine them into a regular expression. The *action* is a keyword terminated by a : and separated from the pattern by optional white-space. It must be one of the following:

- dump if the pattern matches, the message is deleted. If the -s command line option is set, the message is saved.
- hold if the pattern matches, the message is queued in a subdirectory of /mail/queue.hold for manual inspection. After inspection, the queue can be swept manually using rung (see *qer*(8)) to deliver messages that were inadvertently matched.
- header this is the same as the hold action, except the pattern is only applied to the message header. This optimization is useful for patterns that match header fields that are unlikely to be present in the body of the message.
- line the sender and a section of the message around the match are written to the file /sys/log/lines. The message is always delivered.
- loff patterns of this type are applied only to the canonicalized command line. When a match occurs, all patterns with line actions are disabled. This is useful for limiting the size of the log file by excluding repetitive messages, such as those from mailing lists.

Patterns are accumulated into pattern sets sharing the same action. The matching engine applies the dump pattern set first, then the header and hold pattern sets, and finally the line pattern set. Each pattern set is applied three times: to the canonicalized command line, to the message header, and finally to the message body. The ordering of patterns in the pattern file is insignificant.

The *pattern-spec* is a string of characters terminated by a newline, # or override indicator, ~~. Trailing white-space is deleted but patterns containing leading or trailing white-space can be enclosed in double-quote characters. A pattern containing a double-quote must be enclosed in double-quote characters and preceded by a backslash. For example, the pattern

"this is not "spam'"

matches the string this is not "spam". The *pattern-spec* is followed by zero or more *override* strings. When the specific pattern matches, each override is applied and if one matches, it cancels the effect of the pattern. Overrides must be strings; regular expressions are not supported. Each override is introduced by the string ~~ and continues until a subsequent ~~, # or newline, white-space included. A ~~ immediately followed by a newline indicates a line continuation and further overrides continue on the following line. Leading white-space on the continuation line is ignored. For example,

*hold: sex.com~~essex.com~~sussex.com~~sysex.com~~ lasex.com~~cse.psu.edu!owner-9fans

matches all input containing the string sex.com except for messages that also contain the strings in the override list. Often it is desirable to override a pattern based on the name of the sender or recipient. For this reason, each override pattern is applied to the header and the command line as well as the section of the canonicalized input containing the matching data. Thus a pattern matching the command line or the header searches both the command line and the header for overrides while a match in the body searches the body, header and command line for overrides.

The structure of the pattern file and the matching algorithm define the strategy for detecting and filtering unwanted messages. Ideally, a hold pattern selects a message for inspection and if it is determined to be undesirable, a specific dump pattern is added to delete further instances of the message. Additionally, it is often useful to block the sender by updating the smtpd control file.

In this regime, patterns with a *dump* action, generally match phrases that are likely to be unique. Patterns that hold a message for inspection match phrases commonly found in undesirable material and occasionally in legitimate messages. Patterns that log matches are less specific yet. In all cases the ability to override a pattern by matching another string, allows repetitive messages that trigger the pattern, such as mailing lists, to pass the filter after the first one is processed manually. The -s option allows deleted messages to be salvaged by either manual or semi-automatic review, supporting the specification of more aggressive patterns. Finally, the utility of the pattern matcher is not confined to filtering spam; it is a generally useful administrative tool for deleting inadvertently harmful messages, for example, mail loops, stuck senders or viruses. It is also useful for collecting or counting messages matching certain criteria.

FILES

/mail/lib/patterns	default pattern file
/sys/log/smtpd	log of deleted messages
/mail/log/lines	file where <i>log</i> matches are logged
/mail/queue/*	directories where legitimate messages are queued for delivery
/mail/queue.hold	directory where held messages are queued for inspection
/mail/queue.dump/*	directory where <i>dumped</i> messages are stored when the -s command
	line option is specified.
/mail/copy/*	directory where copies of all incoming messages are stored.

SOURCE

/sys/src/cmd/upas/scanmail

SEE ALSO

mail(1), *qer*(8), *smtpd*(6)

BUGS

Testscan does not report a match when the body of a message contains exactly one line.

screenlock - disable access to a terminal

SYNOPSIS

screenlock

DESCRIPTION

Screenlock grabs the screen, keyboard, and mouse devices to disable access to the Plan 9 terminal on which it is run. The screen can be unlocked by typing the invoking user's Plan 9 password and a newline.

FILES

/lib/bunny.bit the image displayed while the terminal is locked

SOURCE

/sys/src/cmd/screenlock.c

BUGS

Use of this program on communal terminals is anti-social.

scuzz – SCSI target control

SYNOPSIS

scuzz[-6eq][-m max-xfer][[-r] sddev]

DESCRIPTION

Scuzz is an interactive program for exercising raw SCSI devices. Its intended purpose is to investigate and manipulate odd devices without the effort of writing a special driver, such as shuffling the media around on an optical jukebox. It reads commands from standard input and applies them to a SCSI target (other devices accessed through the sd(3) interface, such as ATA(PI) devices, may also work). If *sddev* is given on the command line, an open (see below) is immediately applied to the target. On successful completion of a command, ok *n* is printed, where *n* is the number of bytes transferred to/from the target; the -q command line option suppresses the ok message.

The -6 forces the use of 6-byte SCSI commands rather than 10-byte ones. Some older devices require this, though *scuzz* attempts to adapt automatically. The -e makes *scuzz* more willing to retry I/O errors but less tolerant of other errors and implies -6. This option is often needed to read Exabyte 8mm tapes. The -m option sets the maximum I/O transfer size to *max-xfer*. Exabyte drives often require this to be 1024 or the exact tape block size and some 4mm drives require this to be the exact tape block size or larger.

Commands

help command

Help is rudimentary and prints a one line synopsis for the named *command*, or for all commands if no argument is given.

probe Probe attempts an inquiry command on all SCSI units, and prints the result preceded by the name of those targets which respond.

The help and probe commands may be given at any time.

open [-r] sddev

Open must be given before any of the remaining commands will be accepted. Internally, unless the -r option is given, open issues ready then inquiry, followed by a device class-specific command to determine the logical block size of the target. *Sddev* is an *sd*(3) device directory like */dev/sdC0*.

close Close need only be given if another target is to be opened in the current session.

The remaining commands are in rough groups, intended for specific classes of device. With the exception of the read, write, and space commands, all arguments are in the style of ANSI-C integer constants.

- ready Test Unit Ready checks if the unit is powered up and ready to do read and write commands.
- rezero Rezero Unit requests that a disk be brought to a known state, usually by seeking to track zero.
- rewind Rewind positions a tape at the beginning of current partition (there is usually only one partition, the beginning of tape).
- reqsense Request Sense retrieves Sense Data concerning an error or other condition and is usually issued following the completion of a command that had check-condition status. *Scuzz* automatically issues a reqsense in response to a check-condition status and prints the result.
- format Format Unit performs a "low level" format of a disk.
- rblimits Read Block Limits reports the possible block lengths for the logical unit. Tapes only.
- read file nbytes

Read transfers data from the target to the host. A missing *nbytes* causes the entire device to be read.

write file nbytes

Write transfers data from the host to the target. A missing *nbytes* causes the entire input file to be transferred.

The first argument to the read and write commands specifies a source (write) or destination (read) for the I/O. The argument is either a plain file name or | followed by a command to be executed by rc(1). The argument may be quoted in the style of rc(1).

seek offset whence

Seek requests the target to seek to a position on a disk, arguments being in the style of *seek*(2); *whence* is 0 by default.

Scuzz maintains an internal notion of where the current target is positioned. The seek, read, write, rewind, rezero, and wtrack commands all manipulate the internal offset.

filemark *howmany*

Write Filemarks writes one (default) or more filemarks on a tape.

space [-b] [-f] [[--]howmany]

Space positions a tape forwards or backwards. The arguments specify logical block (-b) or filemark (-f) spacing; default is -b. If *howmany* is negative it specifies spacing backwards, and should be preceded by -- to turn off any further option processing. Default is 1.

inquiry Inquiry is issued to determine the device type of a particular target, and to determine some basic information about the implemented options and the product name.

modeselect bytes...

modeselect6bytes...

Mode Select is issued to set variable parameters in the target. *Bytes* given as arguments comprise all the data for the target; see an appropriate manual for the format. The default is the 10-byte form of the command; modeselect6 is the 6-byte version.

modesense [page [nbytes]]

modesense6 [page[nbytes]]

Mode Sense reports variable and fixed parameters from the target. If no *page* is given, all pages are returned. *Nbytes* specifies how many bytes should be returned. The default is the 10-byte form of the command; modesense6 is the 6-byte version.

start [code]

stop [code]

eject [code]

ingest [code]

Start, stop, eject, and ingest are synonyms for Start/Stop Unit with different default values of *code*. Start/Stop Unit is typically used to spin up and spin down a rotating disk drive. *Code* is 0 to stop, 1 to start and 3 to eject (if the device supports ejection of the medium).

capacity Read Capacity reports the number of blocks and the block size of a disk.

The following commands are specific to CD and CD-R/RW devices. A brief description of each is given; see the SCSI-3 Multimedia Commands (MMC) Specification for details of arguments and interpretation of the results.

blank [track/LBA[type]]

Erase a CD-RW disk. Type identifies the method and coverage of the blanking.

rtoc [track/session-number[ses]]

The Read TOC/PMA command transfers data from one of the tables of contents (TOC or PMA) on the CD medium.

rdiscinfo

(Note the spelling.) Provides information about disks, including incomplete CD-

R/RW.

rtrackinfo [track]

Provides information about a track, regardless of its status.

cdpause

cdresume Pause/resume playback.

cdstop Stop playback.

cdplay [track-number] or [-r[LBA[length]]]

Play audio. With no arguments, starts at the beginning of the medium. If a track number is given, the table of contents is read to find the playback start point. If the -r option is given, block addressing is used to find the playback start point.

cdload [slot]

cdunload [slot]

Load/unload a disk from a changer.

cdstatus Read the mechanism status.

The following commands are specific to Media Changer devices. A brief description of each is given; see the SCSI-3 Medium Changer Commands (SMC) Specification for details of arguments.

einit Initialize element status.

estatus type [length]

Report the status of the internal elements. Type 0 reports all element types.

mmove transport source destination[invert]

Move medium.

FILES

/dev/sdXX/raw raw SCSI interface for command, I/O, and status.

SOURCE

/sys/src/cmd/scuzz

SEE ALSO

sd(3) Small Computer System Interface – 2 (X3T9.2/86–109), .}f Global Engineering Documents SCSI Bench Reference, ENDL Publications SCSI–3 Multimedia Commands (MMC) Specification, www.t10.org SCSI–3 Medium Changer Commands (SMC) Specification, .}f www.t10.org

BUGS

Only a limited subset of SCSI commands has been implemented (as needed).

Only one target can be open at a time.

LUNs other than 0 are not supported.

No way to force 10-byte commands, though they are the default.

Should be recoded to use *scsi*(2) in order to get more complete sense code descriptions.

Scuzz betrays its origins by spelling rdiscinfo with a c even though the devices it manipulates are spelled with a k.

The max-xfer value is currently limited to 245760 to limit kernel memory consumption.

It may be necessary to set *max-xfer* to exactly the block size used to write a tape in order to read it on some drives.

secstored, secuser - secstore commands

SYNOPSIS

```
auth/secstored [-R] [-S servername] [-s address] [-x network] [-v]
```

auth/secuser[-v] username

DESCRIPTION

Secstored serves requests from secstore(1). By default it listens on port tcp!*!5356; the -s option specifies an alternative address. In the connection protocol, secstored describes itself as service secstore, but the -S option can specify a different servername. The -R option supplements the password check with a call to a RADIUS server, for checking hardware tokens or other validation. The -x option specifies an alternative network to the default /net. By default, secstored puts itself into the background; the -v option enables a verbose debugging mode that suppresses that.

Secuser is an administrative command that runs on the secstore machine, normally the authserver, to create new accounts and to change status on existing accounts. It prompts for account information such as password and expiration date, writing to /adm/secstore/who/user for a given secstore *user*. The directory /adm/secstore should be created mode 770 with owner or group allowing access to the user that runs *secstored*. The -v option makes the command chattier.

By default, *secstored* warns the client if no account exists. If you prefer to obscure this information, use *secuser* to create an account FICTITIOUS.

FILES

/adm/secstore/who/user /adm/secstore/store/user/ /lib/ndb/auth /sys/log/secstore secstore account name, expiration date, verifier user 's file storage for mapping local userid to RADIUS userid log file (if it does not exist, secstored logs to /dev/cons)

SOURCE

/sys/src/cmd/auth/secstore

SEE ALSO

secstore(1)

securenet - Digital Pathways SecureNet Key remote authentication box

DESCRIPTION

The *SecureNet* box is used to authenticate connections to Plan 9 from a foreign system such as a Unix machine or plain terminal. The box, which looks like a calculator, performs DES encryption with a key held in its memory. Another copy of the key is kept on the authentication server. Each box is protected from unauthorized use by a four digit PIN.

When the system requires SecureNet authentication, it prompts with a numerical challenge. The response is compared to one generated with the key stored on the authentication server. Respond as follows:

Turn on the box and enter your PIN at the EP prompt, followed by the ENT button. Enter the challenge at Ed prompt, again followed ENT. Then type to Plan 9 the response generated by the box. If you make a mistake at any time, reset the box by pressing ON. The authentication server compares the response generated by the box to one computed internally. If they match, the user is accepted.

The box will lose its memory if given the wrong PIN five times in succession or if its batteries are removed.

To reprogram it, type a 4 at the E0 prompt.

At the E1 prompt, enter your key, which consists of eight three-digit octal numbers. While you are entering these digits, the box displays a number ranging from 1 to 8 on the left side of the display. This number corresponds to the octal number you are entering, and changes when you enter the first digit of the next number.

When you are done entering your key, press ENT twice.

At the E2 prompt, enter a PIN for the box.

After you confirm by retyping the PIN at the E3 prompt, you can use the box as normal.

You can change the PIN using the following procedure. First, turn on the box and enter your current PIN at the EP prompt. Press ENT three times; this will return you to the EP prompt. Enter your PIN again, followed by ENT; you should see a Ed prompt with a – on the right side of the display. Enter a 0 and press ENT. You should see the E2 prompt; follow the instructions above for entering a PIN.

The *SecureNet* box performs the same encryption as the netcrypt routine (see *encrypt*(2)). The entered challenge, a decimal number between 0 and 100000, is treated as a text string with trailing binary zero fill to 8 bytes. These 8 bytes are encrypted with the DES algorithm. The first four bytes are printed on the display as hexadecimal numbers. However, when set up as described, the box does not print hexadecimal digits greater than 9. Instead, it prints a 2 for an A, B, or C, and a 3 for a D, E, or F. If a 5 rather than a 4 is entered at the EO print, the hexadecimal digits are printed. This is not recommended, as letters are too easily confused with digits on the *SecureNet* display.

SEE ALSO

encrypt(2), *auth*(2) Digital Pathways, Mountain View, California

BUGS

The box is clumsy to use and too delicate. If carried in a pocket, it can turn itself on and wear out the batteries.

send - mail routing and delivery

SYNOPSIS

upas/send[-b][-i][-r][-x][-#][*mailaddr*...]

DESCRIPTION

Send is not normally run directly by the user. Instead, mail protocol agents like *smtpd* (see *smtp*(8)) and mail preparers like *marshal*(1) fork and execute *send*.

Send reads a message from standard input and disposes of it in one of four ways:

- If mailaddr refers to a local mailbox, it appends it to the recipient's mailbox.
- If *mailaddr* is remote, it queues the mail for remote delivery.
- If the -r option is given and the mail is undeliverable, the message mail rejected: is printed on standard error, setting exit status.
- if the -r option is not given and the mail is undeliverable, it appends the mail to /mail/box/username/dead.letter and prints a message to standard error.

The file /mail/lib/rewrite determines exactly how to deliver or queue the mail. The decision is based purely on the recipient address.

The options are:

- -b suppresses the addition of the To: line.
- -i let the message input be terminated by a line containing only a period, for compatibility with old mailers.
- -x do not send mail, but instead report the full mail address of the recipient.
- -# do not send mail, but instead report what command would be used to send the mail.
- -r input is via a pipe from another program. Expect a From line at the start of the message to provide the name of the sender and timestamp. This implies the -b option.

Send uses the login name as the reply address.

FILES

/sys/log/mail	mail log file
/mail/box/*/dead.letter	unmailable text
/mail/lib/rewrite	rules for handling addresses
/mail/box/*/names	personal alias files
/mail/lib/namefiles	lists names of files containing system aliases

SOURCE

/sys/src/cmd/upas/send

SEE ALSO

aliasmail(8), faces(1), filter(1), mail(1), marshal(1), mlmgr(1), nedmail(1), qer(8), rewrite(6), smtp(8), upasfs(4)

disk/smart - SMART error monitoring

SYNOPSIS

disk/smart[-aptv] drive...

DESCRIPTION

The disk/smart command uses the sd(3) raw interface for continuous disk health logging to /sys/log/smart and, with the -v flag, the console for ATA and SCSI disks supporting SMART-style reporting. The -t flag causes disk/smart to exit after a single probe and implies -v. With the -p flag or no arguments, disk/smart probes for all SMART-capable drives. With -a SMART-capable drives are announced. Logging behaves as if level triggered. If a smart condition is set it will be logged every 6 hours. Condition reset also resets the log timer.

FILES

/lib/scsicodes,/dev/sdXX/raw

SEE ALSO

atazz(8), scuzz(8), sd(3).

SOURCE

/sys/src/cmd/disk/smart

BUGS

Past failures are no indication of future performance.

smtp, smtpd - mail transport

SYNOPSIS

- upas/smtp [-aAdfipst] [-b busted-mx] ... [-g gateway] [-h host] [-u user] [. domain] destaddr sender rcpt-list
- upas/smtpd[-adDfrg][-c certfile][-h mydom][-k evilipaddr][-m mailer][-n netdir]

DESCRIPTION

Smtp sends the mail message from standard input to the users *rcpt-list* on the host at network address *address* using the Simple Mail Transfer Protocol. The options are:

- -a if the server supports PLAIN or LOGIN authentication, authenticate to the server using a password from *factotum*(4). See RFCs 3207 and 2554. This option implies -s.
- -A autistic server: don't wait for an SMTP greeting banner but immediately send a NOOP command to provoke the server into responding.
- -b ignore *busted-mx* when trying MX hosts. May be repeated.
- -d turn on debugging to standard error.
- -f just filter the converted message to standard output rather than sending it.
- -g makes *gateway* the system to pass the message to if *smtp* can't find an address nor MX entry for the destination system.
- -h use *host* as the local system name; it may be fully-qualified or not. If not specified, it will default to the contents of /dev/sysname.
- -i under -a, authenticate even if we can't start TLS.
- -p ping: just verify that the users named in the *rcpt-list* are valid users at *destaddr*; don't send any mail.
- -s if the server supports the ESMTP extension to use TLS encryption, turn it on for this session. See RFC3207 for details.
- -t preemtively establish TLS connection before SMTP handshake (SMTPS).
- -u specify a user name to be used in authentication. The default name is the current login id.

Finally if *.domain* is given, it is appended to the end of any unqualified system names in the envelope or header.

Smtpd receives a message using the Simple Mail Transfer Protocol. Standard input and output are the protocol connection. SMTP authentication by *login* and *cram-md5* protocols is supported; authenticated connections are permitted to relay.

The options are:

- -a requires that all clients authenticate to be able to send mail.
- -c specifies a certificate to use for TLS. Without this option, the capability to start TLS will not be advertised.
- -d turns on debugging output, with each connection's output going to a uniquely-named file in /sys/log/smtpdb.
- -D sleeps for 15 seconds usually at the start of the SMTP dialogue; this deters some spammers. Connections from Class A networks frequented by spammers will incur a longer delay.
- -f prevents relaying from non-trusted networks. It also tags messages from non-trusted sites when they deliver mail from an address in a domain we believe we represent.
- -g turns on grey/white list processing. All mail is rejected (with a retry code) unless the sender's IP address is on the whitelist, /mail/grey/whitelist, an append only file. Addresses can be added to the whitelist by the administrator. However, the usual way for addresses to be added is by *smtpd* itself. Whenever a message is received and the sender's address isn't on the whitelist, *smtpd* first looks for the file /mail/grey/tmp/local/remote/recipient,

where *local* and *remote* are IP addresses of the local and remote systems, respectively. If it exists and was created more than a few minutes go, the remote address is added to the whitelist. If not, the file is created and the mail is rejected with a 'try again' code. The expectation is that spammers will not retry for more than a few minutes and that others will.

- -h specifies the receiving domain. If this flag is not specified, the receiving domain is inferred from the host name.
- -k causes connections from the host at the IP address, *evilipaddr*, to be dropped at program startup. Multiple addresses can be specified with several -k options. This option should be used carefully; it is intended to lessen the effects of denial of service attacks or broken mailers which continually connect. The connections are not logged and the remote system is not notified via the protocol.
- -m set the *mailer* to which *smtpd* passes a received message. The default is /bin/upas/send.
- -n specifies the name of the network directory assigned to the incoming connection. This is used to determine the peer IP address. If this flag is not specified, the peer address is determined using standard input.
- -p permits clients to authenticate using protocols which transfer the password in the clear, e.g. login protocol. This should only be used if the connection has previously encrypted using e.g. tlssrv(8).
- -r turns on forward DNS validation of non-trusted sender address.
- -s causes copies of blocked messages to be saved in a sub-directory of /mail/queue.dump.

Smtpd is normally run by a network listener such as *listen*(8). Most of the command line options are more conveniently specified in the smtpd configuration file stored in /mail/lib/smtpd.conf.

SOURCE

/sys/src/cmd/upas/smtp

SEE ALSO

aliasmail(8), faces(1), filter(1), mail(1), marshal(1), mlmgr(1), nedmail(1), qer(8), rewrite(6), send(8), tlssrv(8), upasfs(4)

snoopy - spy on network packets

SYNOPSIS

snoopy[-CDdpst][-M m][-N n][-f filter-expression][-h first-header][packet-source]

snoopy -? [proto...]

DESCRIPTION

Snoopy reads packets from a *packet-source* (default /net/ether0), matches them to a filter (by default anything matches), and writes matching packets to standard output either in human readable form (default) or in a binary trace format that can be later read by *snoopy*. *Packet-source* can be the name of an Ethernet (e.g., /net/ether0), an interface (e.g., /net/ipifc/0), or a file of captured packets.

The human readable format consists of multiple lines per packet. The first line contains the milliseconds since the trace was started. Subsequent ones are indented with a tab and each contains the dump of a single protocol header. The last line contains the dump of any contained data. For example, a BOOTP packet would look like:

324389 ms

```
ether(s=0000929b1b54 d=ffffffffff pr=0800 ln=342)
ip(s=135.104.9.62 d=255.255.255.255 id=5099 frag=0000...
udp(s=68 d=67 ck=d151 ln= 308)
bootp(t=Req ht=1 hl=16 hp=0 xid=217e5f27 sec=0 fl=800...
dhcp(t=Request clientid=0152415320704e7266238ebf01030...
```

The binary format consists of:

2 bytes of packet length, msb first

8 bytes of nanosecond time, msb first

the packet

Filters are expressions specifying protocols to be traced and specific values for fields in the protocol headers. The grammar is:

```
expr: protocol

| field '=' value

| field '!=' value

| protocol '(' expr ')'

| '(' expr ')'

| expr '||' expr

| expr '&&' expr

| '!' expr
```

The values for *protocol* and *field* can be obtained using the -? option. With no arguments, it lists the known protocols. Otherwise it prints, for each protocol specified, which subprotocols it can multiplex to, and which fields can be used for filtering. For example, the listing for ethernet is currently:

```
ether's filter attributes:
    s - source address
    d - destination address
    a - source|destination address
    sd - source|destination address
    t - type
ether's subprotos:
    0x0800 ip 0x8863 pppoe_disc
    0x0806 arp 0x8864 pppoe_sess
    0x0806 rarp 0x888e eapol
    0x86dd ip6
```

The format of *value* depends on context. In general, ethernet addresses are entered as a string of hex digits; IP numbers in the canonical '.' format for v4 and ':' format for v6; and ports in decimal.

Snoopy's options are:

- -C compute the correct checksum for each packet; on mismatch, add a field ! ck=xxxx where xxxx is the correct checksum.
- -D output will be a binary trace file in Unix pcap format.
- -d output will be a binary trace file.
- -t input is a binary trace file as generated with the -d option.
- -p do not enter promiscuous mode. Only packets to this interface will be seen.
- -s force one output line per packet. The default is multiline.
- -M discard all but the first *m* bytes of each packet. The default is to keep the entire packet. This option is most useful when writing packets to a file with the -d option.
- -N dump *n* data bytes per packet. The default is 32.
- -f use *filter-expression* to filter the packet stream. The default is to match all packets.
- -h assume the first header per packet to be of the *first-header* protocol. The default is ether.

EXAMPLES

To display only BOOTP and ARP packets:

```
% snoopy -f 'arp || bootp'
after optimize: ether(arp || ip(udp(bootp)))
```

The first line of output shows the completed filter expression. *Snoopy* will fill in other protocols as necessary to complete the filter and then optimize to remove redundant comparisons.

To save all packets between 135.104.9.2 to 135.104.9.6 and later display those to/from TCP port 80:

FILES

/net/ether0

Ethernet device

SOURCE

/sys/src/cmd/ip/snoopy

BUGS

Snoopy only dumps ethernet packets, because there's no device to get IP packets without a media header.

splitmbox - split a mailbox into mdir format

SYNOPSIS

splitmbox[-l][mbox]

DESCRIPTION

Splitmbox converts a mailbox in mbox format into *mdir*(6) format. *Mbox* is the mailbox to convert. The default is /mail/box/*user*/mbox and the temporary destination is /mail/box/*user*/mboxdir.

After conversion, commands are printed to remove the old mailbox and replace it with the new. These must be executed by hand to complete the conversion. The -1 flag executes these commands rather than printing them.

SEE ALSO

mdir(6), pop3(8)

BUGS

Curious manumatic process.

It's imperative that one close all imap clients using the old upas system on imap.coraid.com.

stats - display graphs of system activity

SYNOPSIS

stats [- option] [machine ...]

DESCRIPTION

Stats displays a rolling graph of various statistics collected by the operating system and updated once per second. The statistics may be from a remote *machine* or multiple *machines*, whose graphs will appear in adjacent columns. The columns are labeled by the machine names and the number of processors on the machine if it is a multiprocessor.

The right mouse button presents a menu to enable and disable the display of various statistics; by default, *stats* begins by showing the load average on the executing machine.

The lower-case *options* choose the initial set to display:

- b battery percentage battery life remaining.
- c context number of process context switches per second.
- d draw draw memory allocation size in bytes.
- e ether total number of packets sent and received per second.
- E etherin,out
- number of packets sent and received per second, displayed as separate graphs.
- f fault number of page faults per second.
- i intr number of interrupts per second.
- I idle system load, % time in idle, and % time in interrupts. The last two are averaged over all processors on a multiprocessor.
- k kern kernel memory allocation size in bytes.
- 1 load (default) system load average. The load is computed as a running average of the number of processes ready to run, multiplied by 1000.
- m mem total pages of active memory. The graph displays the fraction of the machine's total memory in use.
- n etherin,out,err
 - number of packets sent and received per second, and total number of errors, displayed as separate graphs.
- p tlbpurge number of translation lookaside buffer flushes per second.
- r reclaim total pages of reclaimable memory. The graph displays the fraction of the machine's total memory in use.
- s syscall number of system calls per second.
- t tlbmiss number of translation lookaside buffer misses per second.
- w swap number of valid pages on the swap device. The swap is displayed as a fraction of the number of swap pages configured by the machine.
- 8 802.11b display the signal strength detected by the 802.11b wireless ether card; the value is usually below 50% unless the receiver is in the same room as the transmitter, so a midrange value represents a strong signal.
- z temp current temperature reported by the cpu.

The graphs are plotted with time on the horizontal axis. The vertical axes range from 0 to 1000*sleepsecs, multiplied by the number of processors on the machine when appropriate. The only exceptions are memory, and swap space, which display fractions of the total available, system load, which displays a number between 0 and 1000, idle and intr, which display percentages and the Ethernet error count, which goes from 0 to 10.. If the value of the parameter is too large for the visible range, its value is shown in decimal in the upper left corner of the graph.

Upper-case options control details of the display. All graphs are affected; there is no mechanism to affect only one graph.

-T sleepsecs

Set the number of seconds between samples to *sleepsecs* (default one second). *Sleepsecs* may be a floating-point number.

–S scale

Sets a scale factor for the displays. A value of 2, for example, means that the highest value

plotted will be twice as large as the default.

- -L Plot all graphs with logarithmic y axes. The graph is plotted so the maximum value that would be displayed on a linear graph is 2/3 of the way up the y axis and the total range of the graph is a factor of 1000; thus the y origin is 1/100 of the default maximum value and the top of the graph is 10 times the default maximum.
- -Y If the display is large enough to show them, place value markers along the y axes of the graphs. Since one set of markers serves for all machines across the display, the values in the markers disregard scaling factors due to multiple processors on the machines. On a graph for a multiprocessor, the displayed values will be larger than the markers indicate. The markers appear along the right, and the markers show values appropriate to the rightmost machine; this only matters for graphs such as memory that have machine-specific maxima.

```
FILES
```

/net/ether0/0/stats
#c/swap
#c/sysstat

SOURCE

/sys/src/cmd/stats.c

BUGS

Some machines do not have TLB hardware.

statusbar, statusmsg - display a bar graph or status message window

SYNOPSIS

```
aux/statusbar[-kt][-w minx,miny,maxx,maxy][title]
aux/statusmsg[-kt][-w minx,miny,maxx,maxy][title]
```

DESCRIPTION

Statusbar and *statusmsg* read textual status lines from standard input into a continuously updated bar graph or text message displayed in a new window on the screen. The *title* is displayed on a line above the bar graph or message. For *statusbar*, each input line is two space-separated decimal numbers: the numerator and denominator of a fraction.

The programs exit when it reaches end-of-file on standard input. Typing DEL or control-C will also cause it to exit.

The options are:

- -k do not allow typing to cause exit
- -t print an ASCII version of the bar or message to standard output, using backspace to redraw it.
- -w set the coordinates of the window created

SOURCE

/sys/src/cmd/aux/statusbar.c
/sys/src/cmd/aux/statusmsg.c

stub – provide mount point stubs

SYNOPSIS

aux/stub[-Dd]path/name

DESCRIPTION

Aux/stub union mounts itself before *path* in the name space. It serves a file system containing a single entry, *name*, with file mode 0. The intent is to provide a place to bind or mount other resources. The options are:

- -D print all 9P messages
- -d make *name* a directory; by default it is a file

SOURCE

/sys/src/cmd/aux/stub.c

SEE ALSO

mntgen(4)

swap – establish a swap file

SYNOPSIS

swap file

DESCRIPTION

Swap establishes a file for the system to swap on. If *file* is an existing file, it is used for system swap. If it does not exist, a new file is created. If *file* is a directory, a unique file is created in that directory on which to swap. The environment variable swap is set to the full name of the resulting file. The number of blocks available in the file or device must be at least the number of swap blocks configured at system boot time.

If a swap channel has already been set and no blocks are currently valid in the file the old file will be closed and then replaced. If any blocks are valid on the device an error is returned instead.

SOURCE

/sys/src/cmd/swap.c

BUGS

Swapping to a file served by a local user-level process will lead to deadlock if the process isn't made non-swappable (see the noswap ctl-message in *proc*(3)).

SEE ALSO

swap(3), proc(3)

timesync - synchronize the system clock to a time source

SYNOPSIS

aux/timesync[-a accuracy][-S stratum][-s netroot][-frnDdLilG][timeserver]

DESCRIPTION

Aux/timesync synchronizes the system clock to a time source, by default a file server. The options are:

- -f synchronize to a file server. If *timeserver* is missing, use /srv/boot.
- -r synchronize to the local real time clock, #r/rtc.
- -L used with -r to indicate the real time clock is in local time rather than GMT. This is useful on PCs that also run the Windows OS.
- -n synchronize to an NTP server. If *timeserver* is missing, dial the server udp!\$ntp!ntp.
- -D print debugging to standard error
- -d put file containing last determined clock frequency in directory *dir*, default /tmp.
- -i stands for impotent. *Timesync* announces what it would do but doesn't do it. This is useful for tracking alternate time sources.
- -a specifies the *accuracy* in nanoseconds to which the clock should be synchronized. This determines how often the reference clock is accessed.
- -G causes *timesync* to use a gps server (see *gpsfs*(8)) as a time source.
- -s causes *timesync* to listen for UDP NTP requests on the network rooted at *netroot*. Up to 4 -s options are allowed.
- -S sets the stratum number to *stratum*.
- -1 turns on logging to /sys/log/timesync.

FILES

/tmp/ts.<sysname>.<type>.timeserver where the last frequency guess is kept
/sys/log/timesync log file

SOURCE

/sys/src/cmd/aux/timesync.c

tinc - mesh peer to peer VPN

SYNOPSIS

ip/tinc [-d][-p maxprocs][-x inside][-o outside][-c confdir][-n myname] localip localmask [hosts...]

DESCRIPTION

Tinc implements the mesh peer to peer VPN protocol from *https://www.tinc-vpn.org/* as of version 1.0.32. Within a tinc VPN one can reach all the subnets of all hosts within the network even when not directly connected to the owning host of the subnet.

Each host that is directly connected to us has its own hostfile under *confdir*/hosts/*hostname* containing its public address, owned subnets, options and RSA public key. The hostfile format is the same as the original tinc implementation. The *confdir* is specified with the -c option or defaults to the current working directory. Other hosts might exist behind these directly connected nodes but this information is distributed automatically within the protocol.

On startup, *tinc* creates an ip interface with the address *localip* and network mask *localmask* on the *inside* ip stack (specified with -x option) and starts listening for incoming connections on the *outside* ip stack (specified with the -o option). When optional *hosts* are specified on the command line, then it will also do outgoing connections using the *outside* ip stack. The *localmask* usually is a supernet of all the subnets within the VPN. Our own hostname *myhost* can be specified with -n option or is assumed to be the *sysname* when not specified. This host's RSA private key needs to be present in factorum and tagged with service=tinc and host=myhost.

The options:

- -d Enable debug output and do not fork to the background.
- -p Limit the number of client processes (incoming and outgoing connections per protocol) to *maxprocs*.
- -x Specifies the *inside* and *outside* network stack directory where the tinc ip interface is bound. Defaults to /net.
- -o Specifies the *outside* network stack directory where incoming and outgoing tinc connections are made. Defaults to inside.
- -c Specifies the configuration directory *confdir* for the VPN.
- -n Sets our hostname to *myhost*.

SEE ALSO

rsa(8), ip(3)

https://www.tinc-vpn.org/documentation/

SOURCE

/sys/src/cmd/ip/tinc.c

HISTORY

Tinc first appeared in 9front (October, 2017).

tlssrv, tlsclient, tlssrvtunnel, tlsclienttunnel - TLS server and client

SYNOPSIS

tlssrv[-D][-[aA][-k keyspec]][-c cert.pem][-l logfile][-r remotesys] cmd[args ...]

tlsclient[-D][-a[-k keyspec]][-c clientcert.pem][-d servercert][-t trustedkeys][-x excludedkeys][-n servername][-0] address[cmd[args ...]]

tlssrvtunnel plain-addr crypt-addr cert.pem

tlsclienttunnel crypt-addr plain-addr trustedkeys

DESCRIPTION

Tlssrv is a helper program, typically exec'd in a /bin/service file to establish an SSL or TLS connection before launching *cmd args*; a typical command might start the IMAP or HTTP server. *Cert.pem* is the server certificate; *factotum*(4) should hold the corresponding private key. The specified *logfile* is by convention the same as for the target server. *Remotesys* is mainly used for logging. If the -a or -A flag is specified, p9any authentication is run before the TLS handshake and the resulting plan9 session secret is used as a pre-shared key for TLS encryption. This enables the use of TLS without certificates and also runs the server command as the authorized user when the -a flag was specified.

Tlsclient is the reverse of *tlssrv*: it connects to *address*, starts TLS, and then relays between the network connection and standard input and output or executes *cmd args* with standard input and output redirected to the connection. The –D flag enables some debug output. Specifying a certificate in pem(8) format with the –c flag, causes the client to submit this certificate upon server's request. A corresponding key has to be present in *factotum*(4). The –d flag writes the server's certificate to the file *servercert* in binary ASN.1 encoding. If the server doesnt provide a certificate, an empty file is created. If the –t flag (and, optionally, the –x flag) is given, the remote server must present a public key whose SHA1 or SHA256 hash is listed in the file *trustedkeys* but not in the file *excludedkeys*. See *thumbprint*(6) for more information. The –n option passes the string *servername* in the TLS hello message (Server Name Idenfitication) which is usefull when talking to webservers. When the –o option was specified, *address* is interpreted as a filename to be opend read-write instead of a dial string.

Tlssrvtunnel and *tlsclienttunnel* use these tools and *listen1* (see *listen*(8)) to provide TLS network tunnels, allowing legacy application to take advantage of TLS encryption.

EXAMPLES

Listen for TLS-encrypted IMAP by creating a server certificate /sys/lib/tls/imap.pem and a listener script /bin/service.auth/tcp993 containing:

```
#!/bin/rc
exec tlssrv -c/sys/lib/tls/imap.pem -limap4d -r'{cat $3/remote} \
    /bin/ip/imap4d -p -dyourdomain -r'{cat $3/remote} \
    >[2]/sys/log/imap4d
```

Interact with the server, putting the appropriate hash into /sys/lib/tls/mail and running:

tlsclient -t /sys/lib/tls/mail tcp!server!imaps

Create a TLS-encrypted VNC connection from a client on kremvax to a server on moscvax:

(The port numbers passed to the VNC tools are offset by 5900 from the actual TCP port numbers.)

FILES

/sys/lib/tls

SOURCE

```
/sys/src/cmd/tlssrv.c
/sys/src/cmd/tlsclient.c
/rc/bin/tlssrvtunnel
/rc/bin/tlsclienttunnel
```

SEE ALSO

factotum(4), listen(8), rsa(8) Unix's stunnel

trampoline - forward incoming calls to another address

SYNOPSIS

```
aux/trampoline[-9][-a altaddr][-m netdir][-t timeout] addr
```

DESCRIPTION

Trampoline can be used in a service file (see *listen*(8)) to link an incoming call to another address that provides the service, typically on another machine.

Trampoline dials *addr* and copies data between that connection and its own standard input and output.

The options are:

-9 The connection carries only 9P messages. In this case *trampoline* will relay whole messages at a time.

-a altaddr

Dial *altaddr* and relay between the two network connections, ignoring standard input and output.

-m netdir

Restrict forwarding to particular machines. *Netdir* must be the incoming call directory. *Trampoline* finds the caller's MAC address *m* and checks that ndb(6) contains an entry with ether=*m* and the attribute trampok. If no such entry is found, the call is rejected.

-t timeout

Terminates the connection after *timeout* milliseconds of inactivity.

FILES

/sys/log/trampoline logs rejected calls

SOURCE

/sys/src/cmd/aux/trampoline.c

SEE ALSO

dial(2), listen(8)

udpecho - echo UDP packets

SYNOPSIS

ip/udpecho[-x ext]

DESCRIPTION

Listen on UDP port 7 and echo back any packets received. This should only be run for testing since it can be used to disguise the identity of someone doing a denial of service attack.

vblade - virtual AoE target

SYNOPSIS

disk/vblade[-ir][-s size][-a shelf.slot][-c config] file[-e ether]

DESCRIPTION

For each *file* specified, *vblade* serves it as an AoE (ATA-over-Ethernet) target via the specified interfaces. The default interface is /net/ether0. Since AoE uses raw Ethernet frames, the target is only visible on the local ethernet segment.

All target-related options are reset for each *file*.

Options

- -i Initialize the configuration header in *file*. All previous configuration information is lost. Without this option, configuration is read from *file* and command like options override previous settings.
- -r Raw. Do not use a configuration header. This is useful when exporting a device or file not generally exported by *vblade*.
- -s n The exported target will have size *n*, rather than the available space in the target. A size may end in p, t, g, m, or k to specify a customary *binary* multiplier.
- -a *m.n* Specify the shelf and slot (or major and minor) address of the target. Valid shelf numbers are between 0 and 65534. Valid slots are 0-255.
- $-c \ s$ Set the AoE config string to s.
- -e *ether* Listen to the network port *ether*. Multiple ports may be specified.

SEE ALSO

aoe(3), sdaoe(3), http://www.coraid.com/documents/AoEr11.txt.

SOURCE

/sys/src/cmd/disk/vblade

BUGS

Security depends on control of the local Ethernet segment. It may be unwise to serve AoE on a segment bridged to a wireless network.

venti - archival storage server

SYNOPSIS

```
venti/venti [ -Ldrs ] [ -a address ] [ -B blockcachesize ] [ -c config ] [ -C lumpcachesize ]
      [ -h httpaddress ] [ -I indexcachesize ] [ -m free-memory% ] [ -W webroot ]
```

DESCRIPTION

Venti is a SHA1-addressed archival storage server. See *venti*(6) for a full introduction to the system. This page documents the structure and operation of the server.

A venti server requires multiple disks or disk partitions, each of which must be properly formatted before the server can be run.

Disk

The venti server maintains three disk structures, typically stored on raw disk partitions: the append-only *data log*, which holds, in sequential order, the contents of every block written to the server; the *index*, which helps locate a block in the data log given its score; and optionally the *bloom filter*, a concise summary of which scores are present in the index. The data log is the primary storage. To improve the robustness, it should be stored on a device that provides RAID functionality. The index and the bloom filter are optimizations employed to access the data log efficiently and can be rebuilt if lost or damaged.

The data log is logically split into sections called *arenas*, typically sized for easy offline backup (e.g., 500MB). A data log may comprise many disks, each storing one or more arenas. Such disks are called *arena partitions*. Arena partitions are filled in the order given in the configuration.

The index is logically split into block-sized pieces called *buckets*, each of which is responsible for a particular range of scores. An index may be split across many disks, each storing many buckets. Such disks are called *index sections*.

The index must be sized so that no bucket is full. When a bucket fills, the server must be shut down and the index made larger. Since scores appear random, each bucket will contain approximately the same number of entries. Index entries are 40 bytes long. Assuming that a typical block being written to the server is 8192 bytes and compresses to 4096 bytes, the active index is expected to be about 1% of the active data log. Storing smaller blocks increases the relative index footprint; storing larger blocks decreases it. To allow variation in both block size and the random distribution of scores to buckets, the suggested index size is 5% of the active data log.

The (optional) bloom filter is a large bitmap that is stored on disk but also kept completely in memory while the venti server runs. It helps the venti server efficiently detect scores that are *not* already stored in the index. The bloom filter starts out zeroed. Each score recorded in the bloom filter is hashed to choose *nhash* bits to set in the bloom filter. A score is definitely not stored in the index of any of its *nhash* bits are not set. The bloom filter thus has two parameters: *nhash* (maximum 32) and the total bitmap size (maximum 512MB, 2^{32} bits).

The bloom filter should be sized so that $nhash \times nblock \leq 0.7 \times b$, where nblock is the expected number of blocks stored on the server and b is the bitmap size in bits. The false positive rate of the bloom filter when sized this way is approximately $2^{-nblock}$. Nhash less than 10 are not very useful; *nhash* greater than 24 are probably a waste of memory. *Fmtbloom* (see *venti-fmt*(8)) can be given either *nhash* or *nblock*; if given *nblock*, it will derive an appropriate *nhash*.

Memory

Venti can make effective use of large amounts of memory for various caches.

The *lump cache* holds recently-accessed venti data blocks, which the server refers to as *lumps*. The lump cache should be at least 1MB but can profitably be much larger. The lump cache can be thought of as the level-1 cache: read requests handled by the lump cache can be served instantly.

The *block cache* holds recently-accessed *disk* blocks from the arena partitions. The block cache needs to be able to simultaneously hold two blocks from each arena plus four blocks for the currently-filling arena. The block cache can be thought of as the level-2 cache: read requests handled by the block cache are slower than those handled by the lump cache, since the lump data must be extracted from the raw disk blocks and possibly decompressed, but no disk accesses are necessary.

The *index cache* holds recently-accessed or prefetched index entries. The index cache needs to be able to hold index entries for three or four arenas, at least, in order for prefetching to work properly. Each index entry is 50 bytes. Assuming 500MB arenas of 128,000 blocks that are 4096 bytes each after compression, the minimum index cache size is about 6MB. The index cache can be thought of as the level-3 cache: read requests handled by the index cache must still go to disk to fetch the arena blocks, but the costly random access to the index is avoided.

The size of the index cache determines how long venti can sustain its 'burst' write throughput, during which time the only disk accesses on the critical path are sequential writes to the arena partitions. For example, if you want to be able to sustain 10MB/s for an hour, you need enough index cache to hold entries for 36GB of blocks. Assuming 8192-byte blocks, you need room for almost five million index entries. Since index entries are 50 bytes each, you need 250MB of index cache. If the background index update process can make a single pass through the index in an hour, which is possible, then you can sustain the 10MB/s indefinitely (at least until the arenas are all filled).

The *bloom filter* requires memory equal to its size on disk, as discussed above.

A reasonable starting allocation is to divide memory equally (in thirds) between the bloom filter, the index cache, and the lump and block caches; the third of memory allocated to the lump and block caches should be split unevenly, with more (say, two thirds) going to the block cache.

Network

The venti server announces two network services, one (conventionally TCP port venti, 17034) serving the venti protocol as described in *venti*(6), and one serving HTTP (conventionally TCP port http, 80).

The venti web server provides the following URLs for accessing status information:

/index A summary of the usage of the arenas and index sections.

/xindex An XML version of /index.

/storage Brief storage totals.

/set/variable

The current integer value of *variable*. Variables are: compress, whether or not to compress blocks (for debugging); logging, whether to write entries to the debugging logs; stats, whether to collect run-time statistics; icachesleeptime, the time in milliseconds between successive updates of megabytes of the index cache; arenasumsleeptime, the time in milliseconds between reads while checksumming an arena in the background. The two sleep times should be (but are not) managed by venti; they exist to provide more experience with their effects. The other variables exist only for debugging and performance measurement.

/set/variable/value

Set variable to value.

/graph/name/param/param

A PNG image graphing the named run-time statistic over time. The details of names and parameters are undocumented; see httpd.c in the venti sources.

/log A list of all debugging logs present in the server's memory.

 $/\log/name$ The contents of the debugging log with the given *name*.

/flushicache

Force venti to begin flushing the index cache to disk. The request response will not be sent until the flush has completed.

/flushdcache

Force venti to begin flushing the arena block cache to disk. The request response will not be sent until the flush has completed.

Requests for other files are served by consulting a directory named in the configuration file (see webroot below).

Configuration File

A venti configuration file enumerates the various index sections and arenas that constitute a venti

system. The components are indicated by the name of the file, typically a disk partition, in which they reside. The configuration file is the only location that file names are used. Internally, venti uses the names assigned when the components were formatted with *fmtarenas* or *fmtisect* (see *venti-fmt*(8)). In particular, only the configuration needs to be changed if a component is moved to a different file.

The configuration file consists of lines in the form described below. Lines starting with # are comments.

index *name* Names the index for the system.

arenas file File is an arena partition, formatted using fmtarenas.

isect file File is an index section, formatted using fmtisect.

bloom *file* File is a bloom filter, formatted using *fmtbloom*.

After formatting a venti system using *fmtindex*, the order of arenas and index sections should not be changed. Additional arenas can be appended to the configuration; run *fmtindex* with the -a flag to update the index.

The configuration file also holds configuration parameters for the venti server itself. These are:

mem size	lump cache size
bcmem size	block cache size
icmem <i>size</i>	index cache size
addr <i>netaddr</i>	network address to announce venti service (default tcp!*!venti)
httpaddr <i>netaddr</i>	network address to announce HTTP service (default tcp!*!http)
queuewrites	queue writes in memory (default is not to queue)
webroot <i>dir</i>	directory tree containing files for <i>venti</i> 's internal HTTP server to consult for
	unrecognized URLs

The units for the various cache sizes above can be specified by appending a k, m, or g (case-insensitive) to indicate kilobytes, megabytes, or gigabytes respectively.

The *file* name in the configuration lines above can be of the form *file*: lo-hi to specify a range of the file. Lo and hi are specified in bytes but can have the usual k, m, or g suffixes. Either *lo* or hi may be omitted. This notation eliminates the need to partition raw disks on non-Plan 9 systems.

Command Line

Many of the options to Venti duplicate parameters that can be specified in the configuration file. The command line options override those found in a configuration file. Additional options are:

-c config The server configuration file (default venti.conf)

- -d Produce various debugging information on standard error. Implies -s.
- -L Enable logging. By default all logging is disabled. Logging slows server operation considerably.
- -m Allocate *free-memory%* percent of the available free RAM, and partition it per the guidelines in the Memory subsection. This percentage should be large enough to include the entire bloom filter. This overrides all other memory sizing parameters, including those on the command line and in the configuration file.
- -r Allow only read access to the venti data.
- -s Do not run in the background. Normally, the foreground process will exit once the Venti server is initialized and ready for connections.

EXAMPLE

A simple configuration:

% cat venti.conf index main isect /tmp/disks/isect0 isect /tmp/disks/isect1 arenas /tmp/disks/arenas bloom /tmp/disks/bloom % Format the index sections, the arena partition, the bloom filter, and finally the main index:

```
% venti/fmtisect isect0. /tmp/disks/isect0
% venti/fmtisect isect1. /tmp/disks/isect1
% venti/fmtarenas arenas0. /tmp/disks/arenas &
% venti/fmtbloom /tmp/disks/bloom &
% wait
% venti/fmtindex venti.conf
%
```

Start the server and check the storage statistics:

% venti/venti % hget http://\$sysname/storage

SOURCE

/sys/src/cmd/venti/srv

SEE ALSO

venti(1), venti(2), venti(6), venti-backup(8), venti-fmt(8)

Sean Quinlan and Sean Dorward, "Venti: a new approach to archival storage", Usenix Conference on File and Storage Technologies, 2002.

BUGS

Setting up a venti server is too complicated.

rdarena, wrarena - copy arenas between venti servers

SYNOPSIS

venti/rdarena[-qv] arenapart arenaname

venti/wrarena[-o fileoffset][-h host] arenafile[clumpoffset]

DESCRIPTION

Rdarena extracts the named *arena* from the arena partition *arenapart* and writes this arena to standard output. This command is typically used to back up an arena to external media. The -v option generates more verbose output on standard error; -q generates only errors on standard error.

Wrarena writes the blocks contained in the arena *arenafile* (typically, the output of *rdarena*) to a Venti server. It is typically used to reinitialize a Venti server from backups of the arenas. For example,

venti/rdarena /dev/sdC0/arenas arena.0 >external.media
venti/wrarena -h venti2 external.media

writes the blocks contained in arena.0 to the Venti server venti2 (typically not the one using /dev/sdC0/arenas).

The -o option specifies that the arena starts at byte *fileoffset* (default 0) in *arenafile*. This is useful for reading directly from the Venti arena partition:

venti/wrarena -h venti2 -o 335872 /dev/sdC0/arenas

(In this example, 335872 is the offset shown in the Venti server's index list (344064) minus one block (8192). You will need to substitute your own arena offsets and block size.)

Finally, the optional *offset* argument specifies that the writing should begin with the clump starting at *offset* within the arena. *Wrarena* prints the offset it stopped at (because there were no more data blocks). This could be used to incrementally back up a Venti server to another Venti server:

last='{cat last}
venti/wrarena -h venti2 -o 335872 /dev/sdC0/arenas \$last >output
awk '/^end offset/ { print \$3 }' offset >last

Of course, one would need to add wrapper code to keep track of which arenas have been processed. See /sys/src/cmd/venti/words/backup.example for a version that does this.

SOURCE

/sys/src/cmd/venti/srv

SEE ALSO

venti(6), venti(8)

BUGS

Wrarena can't read a pipe or network connection containing an arena; it needs a file already containing the entire arena.

buildindex, checkarenas, checkindex, conf, fmtarenas, fmtbloom, fmtindex, fmtisect, syncindex - prepare and maintain a venti server

SYNOPSIS

venti/fmtarenas [-Z] [-a *arenasize*] [-b *blocksize*] *name file*

venti/fmtisect[-1Z][-b blocksize] name file

venti/fmtbloom [-n nblocks | -N nhash] [-s size] file

venti/fmtindex[-a]venti.conf

venti/conf[-w] partition[configfile]

venti/buildindex[-bd][-i isect]...[-M imemsize] venti.conf

venti/checkindex[-f][-B blockcachesize] venti.conf tmp

venti/checkarenas[-afv] file

DESCRIPTION

These commands aid in the setup, maintenance, and debugging of venti servers. See *venti*(6) for an overview of the venti system and *venti*(8) for an overview of the data structures used by the venti server.

Note that the units for the various sizes in the following commands can be specified by appending k, m, or g to indicate kilobytes, megabytes, or gigabytes respectively.

Formatting

To prepare a server for its initial use, the arena partitions and the index sections must be formatted individually, with *fmtarenas* and *fmtisect*. Then the collection of index sections must be combined into a venti index with *fmtindex*.

Fmtarenas formats the given *file*, typically a disk partition, into an arena partition. The arenas in the partition are given names of the form name%d, where %d is replaced with a sequential number starting at 0.

Options to *fmtarenas* are:

–a arenasize

The arenas are of *arenasize* bytes. The default is 512M, which was selected to provide a balance between the number of arenas and the ability to copy an arena to external media such as recordable CDs and tapes.

-b blocksize

The size, in bytes, for read and write operations to the file. The size is recorded in the file, and is used by applications that access the arenas. The default is 8k.

- -4 Create a 'version 4' arena partition for backwards compatibility with old servers. The default is version 5, used by the current venti server.
- -Z Do not zero the data sections of the arenas. Using this option reduces the formatting time but should only be used when it is known that the file was already zeroed. (Version 4 only; version 5 sections are not and do not need to be zeroed.)

Fmtisect formats the given *file*, typically a disk partition, as a venti index section with the specified *name*. Each of the index sections in a venti configuration must have a unique name.

Options to *fmtisect* are:

–b bucketsize

The size of an index bucket, in bytes. All the index sections within a index must have the same bucket size. The default is 8k.

- -1 Create a 'version 1' index section for backwards compatibility with old servers. The default is version 2, used by the current venti server.
- -Z Do not zero the index. Using this option reduces the formatting time but should only be used when it is known that the file was already zeroed. (Version 1 only; version 2 sections are not and do not need to be zeroed.)

Fmtbloom formats the given *file* as a Bloom filter (see *venti*(6)). The options are:

-n nblock | -N nhash

The number of blocks expected to be indexed by the filter or the number of hash functions to use. If the -n option is given, it is used, along with the total size of the filter, to compute an appropriate *nhash*.

-s size The size of the Bloom filter. The default is the total size of the file. In either case, size is rounded down to a power of two.

The *file* argument in the commands above can be of the form *file*: lo-hi to specify a range of the file. *Lo* and *hi* are specified in bytes but can have the usual k, m, or g suffixes. Either *lo* or *hi* may be omitted. This notation eliminates the need to partition raw disks on non-Plan 9 systems.

Fmtindex reads the configuration file *venti.conf* and initializes the index sections to form a usable index structure. The arena files and index sections must have previously been formatted using *fmtarenas* and *fmtisect* respectively.

The function of a venti index is to map a SHA1 fingerprint to a location in the data section of one of the arenas. The index is composed of blocks, each of which contains the mapping for a fixed range of possible fingerprint values. *Fmtindex* determines the mapping between SHA1 values and the blocks of the collection of index sections. Once this mapping has been determined, it cannot be changed without rebuilding the index. The basic assumption in the current implementation is that the index structure is sufficiently empty that individual blocks of the index will rarely overflow. The total size of the index should be about 2% to 10% of the total size of the arenas, but the exact percentage depends both on the index block size and the compressed size of blocks stored. See the discussion in *venti*(8) for more.

Fmtindex also computes a mapping between a linear address space and the data section of the collection of arenas. The -a option can be used to add additional arenas to an index. To use this feature, add the new arenas to *venti.conf* after the existing arenas and then run *fmtindex* -a.

A copy of the above mappings is stored in the header for each of the index sections. These copies enable *buildindex* to restore a single index section without rebuilding the entire index.

To make it easier to bootstrap servers, the configuration file can be stored in otherwise empty space at the beginning of any venti partitions using *conf*. A partition so branded with a configuration file can be used in place of a configuration file when invoking any of the venti commands. By default, *conf* prints the configuration stored in *partition*. When invoked with the -w flag, *conf* reads a configuration file from *configfile* (or else standard input) and stores it in *partition*.

Checking and Rebuilding

Buildindex populates the index for the Venti system described in *venti.conf*. The index must have previously been formatted using *fmtindex*. This command is typically used to build a new index for a Venti system when the old index becomes too small, or to rebuild an index after media failure. Small errors in an index can usually be fixed with *checkindex*, but *checkindex* requires a large temporary workspace and *buildindex* does not.

Options to *buildindex* are:

- -b Reinitialise the Bloom filter, if any.
- -d 'Dumb' mode; run all three passes.
- -i *isect* Only rebuild index section *isect*; may be repeated to rebuild multiple sections. The name none is special and just reads the arenas.
- -M *imemsize* The amount of memory, in bytes, to use for caching raw disk accesses while running *buildindex*. (This is not a property of the created index.) The usual suffices apply. The default is 256M.

Checkindex examines the Venti index described in *venti.conf*. The program detects various error conditions including: blocks that are not indexed, index entries for blocks that do not exist, and duplicate index entries. If requested, an attempt can be made to fix errors that are found.

The *tmp* file, usually a disk partition, must be large enough to store a copy of the index. This temporary space is used to perform a merge sort of index entries generated by reading the arenas.

Options to *checkindex* are:

–B blockcachesize

The amount of memory, in bytes, to use for caching raw disk accesses while running *checkindex*. The default is 8k.

-f Attempt to fix any errors that are found.

Checkarenas examines the Venti arenas contained in the given *file*. The program detects various error conditions, and optionally attempts to fix any errors that are found.

Options to *checkarenas* are:

- -a For each arena, scan the entire data section. If this option is omitted, only the end section of the arena is examined.
- -f Attempt to fix any errors that are found.
- -v Increase the verbosity of output.

SOURCE

/sys/src/cmd/venti/srv

SEE ALSO

venti(6), venti(8)

BUGS

Buildindex should allow an individual index section to be rebuilt.

vga – configure a VGA card

SYNOPSIS

aux/vga[-BcdilpvV][-b bios-string][-m monitor][-t tilt][-x file][mode[size]]

DESCRIPTION

Vga configures a VGA controller for various display sizes and depths. Using the monitor type specified in /env/monitor (default vga) and the *mode* given as argument (default 640x480x1), *vga* uses the database of known VGA controllers and monitors in /lib/vgadb (see *vgadb*(6)) to configure the display via the devices provided by *vga*(3). The options are:

–b bios–string

use the VGA database entry corresponding to *bios-string* (e.g. 0xC0045="Stealth 64 DRAM Vers. 2.02") rather than looking for identifying strings in the BIOS memory.

- -B dump the BIOS memory (in hex) to standard output and exit.
- -c disable the use of the hardware graphics cursor.
- -d include the color palette in whatever actions are performed, usually printing the contents.
- -i when used with -p display the register values that will be loaded.
- -1 load the desired mode.

-m *monitor*

override the /env/monitor value. /env/monitor is usually set by including it in the plan9.ini file read by the PC boot program.

- -p print the current or expected register values at appropriate points depending on other options.
- -v print a trace of the functions called.
- -V print a verbose trace of the functions called.
- -t can be used to change the tilt of the screen. The value is one of none, left, inverted and right. See vga(3).

-x file

use *file* as the VGA database rather than /lib/vgadb.

Mode is of the form $X \ge Y \ge Z[,S][,\#N]$, where X, Y, and Z are numbers specifying the display height, width, and depth respectively. S is scaling mode, either *scalefull* or *scaleaspect*; not specifying it disables scaling altogether. #N is used to switch to a specific display using its index N.

The mode must appear in /lib/vgadb as a value for one of the monitor entries. The usual modes are 640x480x[18], 800x600x[18], 1024x768x[18][i], 1280x1024x[18][i], 1376x1024x8, and 1600x1200x8. A trailing i indicates interlaced operation. The default mode is 640x480x8. *Size* is of the form *X x Y* and configures the display to have a virtual screen of the given size.

Using the monitor name vesa instructs *vga* to use VESA BIOS calls to configure the display. Also, if our VGA controller can't be found in *vgadb*, *vga* will try the VESA calls. There are no entries for the vesa monitor in *vgadb*. For a list of available VESA modes and connected displays, use

aux/vga -m vesa -p

Loading the special mode text:

aux/vga -l text

switches out of graphics mode back into text mode. It uses the VESA BIOS.

EXAMPLES

Change the display resolution:

aux/vga -l 1600x1200x8

Show connected and active displays:

aux/vga -m vesa -p | grep dsp

Switch to display 4 and load a specific mode:

aux/vga -m vesa -l '1920x1080x16,#4'

Print the current VGA controller registers. It is usually best to redirect the output of a -p command to a file to prevent confusion caused by using the VGA controller while trying to dump its state:

aux/vga -p >/tmp/x

Force the VGA controller to a known state:

aux/vga -m vga -l

Print the current VGA controller state and what would be loaded into it for a new resolution, but don't do the load:

aux/vga -ip 1376x1024x8 >/tmp/x

FILES

/env/monitor display type (default vga).
/lib/vgadb VGA configuration file.

SOURCE

/sys/src/cmd/aux/vga

SEE ALSO

vga(3), *vgadb*(6),

BUGS

Aux/vga makes every effort possible to verify that the mode it is about to load is valid and will bail out with an error message before setting any registers if it encounters a problem. However, things can go wrong, especially when playing with a new VGA controller or monitor setting. It is useful in such cases to have the above command for setting the controller to a known state at your fingertips.

Scaling modes currently work with Intel and NVIDIA video adapters only, using VESA. Intel doesn't support *scaleaspect* mode.

Display switching currently works with Intel video adapters only, using VESA.

wol - send wake-on-lan Ethernet packet

SYNOPSIS

ip/wol[-v][-a dialstr][-c password] macaddr

DESCRIPTION

Wol sends a magic wake-on-lan Ethernet packet to *dialstr* (default udp!255.255.255.255.255!0, the IPv4 broadcast address), intended to wake up the machine with an Ethernet interface with the MAC address *macaddr*. *Macaddr* is not used to route the packet, but is inserted into the magic packet as required by the wake-on-lan protocol.

An optional *password* of at most six bytes can be sent. The option -v prints verbose information about the packet sent.

SEE ALSO

dial(2), parseether in ip(2)
http://en.wikipedia.org/wiki/Wake-on-LAN

wpa – Wi–Fi Protected Access setup

SYNOPSIS

aux/wpa [-dp12] [-s essid] dev

DESCRIPTION

Wpa handles the authentication and key exchange with WPA protected wireless networks.

The *dev* parameter specifies the network interface that needs to be setup with WPA. The *essid* can be set with the *-s* option. Otherwise, the previously configured essid on the interface will be used. The *-p* option will prompt and install the preshared key or pap/chap credentials into factotum, otherwise the key has to be already present in factotum or an interactive key prompter like auth/fgui (see *factotum*(4)) needs to provide it.

The authentication protocol is initiated by the wireless access point so *wpa* will background itself after the keyprompt and establish the encryption automatically as needed. The optional -1 or -2 arguments can be used to select between WPA1/TKIP (default) or WPA2/CCMP encryption with WPA PSK.

The -d option enables debugging and causes *wpa* to stay in foreground writing protocol messages to standard error.

EXAMPLES

Setup wireless encryption: % bind -a '#l1' /net % aux/wpa -s 9HAL -p /net/ether1 !Adding key: proto=wpapsk essid=9HAL password: ***** !

% ip/ipconfig ether /net/ether1

SOURCE

/sys/src/cmd/aux/wpa.c

SEE ALSO

factotum(4), ipconfig(8)

HISTORY

Wpa first appeared in 9front (March, 2013).

zerotrunc - truncate input on zero byte

SYNOPSIS

aux/zerotrunc

DESCRIPTION

Zerotrunc copies input to output until reading a first zero byte or end-of-file.

EXAMPLES

Zerotrunc can be used to read metadata of Plan 9 image files, e. g.:

% aux/zerotrunc < /dev/window</pre>

SOURCE

/sys/src/cmd/aux/zerotrunc.c

SEE ALSO

cat(1)

intro - introduction to kernel functions

DESCRIPTION

This section of the manual describes the functions publicly available to the authors of kernel code, particularly device drivers (real and virtual). This section will eventually be much expanded, but this makes a start.

The SYNOPSIS subsections do not show the header files needed for the standard kernel declarations. The primary combinations summarised below:

```
#include "u.h"
#include "../port/lib.h"
#include "mem.h"
#include "dat.h"
#include "fns.h"
#include "../port/error.h"
furthermore, added in IP code:
#include "../ip/ip.h"
furthermore, in hardware device drivers:
#include "io.h"
#include "ureg.h"
furthermore, in network interfaces or ether drivers:
#include "../port/netif.h"
```

There might also be specific include files needed by drivers on particular platforms or to use specialised kernel interfaces. The easiest method is to check the source of likely-looking drivers nearby.

allocb, iallocb, freeb, freeblist, BLEN, BALLOC, blocklen, blockalloclen, readblist, concatblock, copyblock, trimblock, packblock, padblock, pullblock, pullupblock, adjustblock, checkb - data block management

SYNOPSIS

{

Block*

Block*

uchar*

uchar*

uchar*

uchar*

ushort

ushort

next:

list;

rp;

wp;

lim:

base: void (*free)(Block*);

flag;

```
Block* allocb(int size)
     Block* iallocb(int size)
     void
            freeb(Block *b)
     void
            freeblist(Block *b)
            blocklen(Block *b)
     int
            blockalloclen(Block *b)
     int
     long
            readblist(Block *b, uchar *p, long n, ulong offset)
     Block* concatblock(Block *b)
     Block* copyblock(Block *b, int n)
     Block* trimblock(Block *b, int offset, int n)
     Block* packblock(Block *b)
     Block* padblock(Block *b, int n)
     int
            pullblock(Block **bph, int n)
     Block* pullupblock(Block *b, int n)
     Block* adjustblock(Block *b, int n)
            checkb(Block *b, char *msg)
     void
     #define BLEN(s)((s)->wp - (s)->rp)
     #define BALLOC(s) ((s)->lim - (s)->base)
DESCRIPTION
     A Block provides a receptacle for data:
          typedef
          struct Block
```

} Block; Each Block has an associated buffer, located at base, and accessed via wp when filling the buffer, or rp when fetching data from it. Each pointer should be incremented to reflect the amount of data written or read. A Block is empty when rp reaches wp. The pointer lim bounds the allocated space. Some operations described below accept lists of Blocks, which are chained via their next pointers, with a null pointer ending the list. Blocks are usually intended for a Queue (see *qio*(9)), but can be used independently.

/* first unconsumed byte */

/* 1 past the end of the buffer */

/* first empty byte */

/* start of the buffer */

checksum; /* IP checksum of complete packet */

A Block and its buffer are normally allocated by one call to *malloc*(9) and aligned on an 8 byte (BY2V) boundary. Some devices with particular allocation constraints (eg, requiring certain addresses for DMA) might allocate their own Block and buffer; free must then point to a function that can deallocate the specially allocated Block.

Many Block operations cannot be used in interrupt handlers because they either *sleep*(9) or raise an *error*(9). Of operations that allocate blocks, only *iallocb* is usable.

Allocb allocates a Block of at least *size* bytes. The block is initially empty: rp and wp point to the start of the data. If it cannot allocate memory, *allocb* raises an *error*(9); it cannot be used by an interrupt handler.

lallocb is similar to *allocb* but is intended for use by interrupt handlers, and returns a null pointer if no memory is available. It also limits its allocation to a quota allocated at system initialisation to interrupt-time buffering.

Freeb frees a single Block (and its buffer).

Freeblist frees the whole list of blocks headed by *b*.

BLEN returns the number of unread bytes in a single block.

BALLOC returns the number of allocated bytes in a single block.

Blocklen returns the number of bytes of unread data in the whole list of blocks headed by b.

Blockalloclen returns the number of total bytes allocated in the whole list of blocks headed by b.

Readblist copies n bytes of data at offset *offset* from the list of blocks headed by b into p, then returns the amount of bytes copied. It leaves the block list intact.

Concatblock returns b if it is not a list, and otherwise returns a single Block containing all the data in the list of blocks b, which it frees.

Copyblock by contrast returns a single Block containing a copy of the first n bytes of data in the block list b, padding with zeroes if the list contained less than n bytes. The list b is unchanged.

Padblock can pad a single Block at either end, to reserve space for protocol headers or trailers. If $n \ge 0$, it inserts *n* bytes at the start of the block, setting the read pointer rp to point to the new space. If n < 0, it adds *n* bytes at the end of the block, leaving the write pointer wp pointing at the new space. In both cases, it allocates a new Block if necessary, freeing the old, and it always returns a pointer to the resulting Block.

Trimblock trims the list b to contain no more than n bytes starting at *offset* bytes into the data of the original list. It returns a new list, freeing unneeded parts of the old. If no data remains, it returns a null pointer.

Packblock examines each Block in the list b, reallocating any block in the list that has four times more available space than actual data. It returns a pointer to the revised list.

Pullblock discards up to n bytes from the start of the list headed by * *bph*. Unneeded blocks are freed. *Pullblock* sets * *bph* to point to the new list head and returns the number of bytes discarded (which might be less than n). It is used by transport protocols to discard ack'd data at the head of a retransmission queue.

Pullupblock rearranges the data in the list of blocks b to ensure that there are at least n bytes of contiguous data in the first block, and returns a pointer to the new list head. It frees any blocks that it empties. It returns a null pointer if there is not enough data in the list.

Adjustblock ensures that the block b has at least n bytes of data, reallocating or padding with zero if necessary. It returns a pointer to the new Block. (If n is negative, it frees the block and returns a null pointer.)

Checkb does some consistency checking of the state of b; a *panic*(9) results if things look grim. It is intended for internal use by the queue I/O routines (see *qio*(9)) but could be used elsewhere.

The only functions that can be called at interrupt level are *iallocb*, *freeb*, *freeblist*, *BLEN*, *BALLOC*, *blocklen*, *blockalloclen*, *readblist* and *trimblock*. The others allocate memory and can potentially block.

SOURCE

/sys/src/9/port/allocb.c
/sys/src/9/port/qio.c

DIAGNOSTICS

Many functions directly or indirectly can raise an *error*(9), and callers must therefore provide for proper error recovery as described therein to prevent memory leaks and other bugs. Except for

iallocb, any functions that allocate new blocks or lists are unsuitable for use by interrupt handlers. *Iallocb* returns a null pointer when it runs out of memory.

SEE ALSO

qio(9)

delay, microdelay, addclock0link - small delays, clock interrupts

SYNOPSIS

```
void delay(int ms)
```

```
void microdelay(int µs)
```

Timer* addclock0link(void(*clockf)(void), int ms)

DESCRIPTION

Delay busy waits for ms milliseconds. The minimum value of ms is one on most architectures.

Microdelay works exactly the same as *delay* but using microseconds instead.

These routines are intended for use in interrupt contexts, device reset and shutdown functions, and other places where the scheduler is unavailable. When you have a process context, and can sleep, consider *tsleep*(9). *Tsleep* does not busy wait.

AddclockOlink adds a new periodic timer to the current processor's timer list, with clockf executing every ms milliseconds. If ms is zero a default clock is used, it will panic otherwise (i.e. ms < 0).

SOURCE

```
/sys/src/9/port/portclock.c
/sys/src/9/*/clock.c
```

SEE ALSO

sleep(9)

error, nexterror, poperror, waserror - error handling functions

SYNOPSIS

```
void error(char*)
void nexterror(void)
#define poperror() (up->nerrlab--)
#define waserror() (setlabel(&up->errlab[up->nerrlab++]))
```

DESCRIPTION

The kernel handles error conditions using non-local gotos, similar to setjmp(2), but using a stack of error labels to implement nested exception handling. This simplifies many of the internal interfaces by eliminating the need for returning and checking error codes at every level of the call stack, at the cost of requiring kernel routines to adhere to a strict discipline.

Each process has in its defining kernel Proc structure a stack of labels, NERR (currently 64) elements deep. A kernel function that must perform a clean up or recovery action on an error makes a stylised call to *waserror*, *nexterror* and *poperror*:

```
if(waserror()){
    /* recovery action */
    nexterror();
}
/* normal action */
poperror();
```

When called in the normal course of events, *waserror* registers an error handling block by pushing its label onto the stack, and returns zero. The return value of *waserror* should be tested as shown above. If non-zero (true), the calling function should perform the needed error recovery, ended by a call to *nexterror* to transfer control to the next location on the error stack. Typical recovery actions include deallocating memory, unlocking resources, and resetting state variables.

Within the recovery block, after handling an error condition, there must normally be a call to *nexterror* to transfer control to any error recovery lower down in the stack. The main exception is in the outermost function in a process, which must not call *nexterror* (there being nothing further on the stack), but calls *pexit* (see *kproc*(9)) instead, to terminate the process.

When the need to recover a particular resource has passed, a function that has called *waserror* must remove the corresponding label from the stack by calling *poperror*. This must be done before returning from the function; otherwise, a subsequent call to *error* will return to an obsolete activation record, with unpredictable but unpleasant consequences.

Error copies the given error message, which is limited to ERRMAX bytes, into the Proc.errstr of the current process, enables interrupts by calling *spllo* (*native* only), and finally calls *nexterror* to start invoking the recovery procedures currently stacked by *waserror*. The file /sys/src/9/port/error.h offers a wide selection of predefined error messages, suitable for almost any occasion. The message set by the most recent call to *error* can be obtained within the kernel by examining up->error and in an application, by using the %r directive of *print*(2).

A complex function can have nested error handlers. A *waserror* block will follow the acquisition of a resource, releasing it on error before calling *nexterror*, and a *poperror* will precede its release in the normal case. For example:

```
error(Enomem); /* returns to A */
if(waserror()){ /* B */
        free(m);
        nexterror(); /* invokes A */
    }
    inner(t);
    poperror(); /* pops B */
    free(m);
    poperror();
                      /* pops A */
    qunlock(t);
}
void
inner(Thing *t)
{
    if(t->bad)
        error(Egreg); /* returns to B */
    t->valid++;
}
```

SOURCE

/sys/src/9/port/proc.c

CAVEATS

The description above has many instances of *should*, *will*, *must* and *must not*.

SEE ALSO

panic(9), kproc(9), splhi(9)

eve, iseve – privileged user

SYNOPSIS

char *eve;

int iseve(void)

DESCRIPTION

Eve is a null-terminated string containing the name of the owner of the Plan 9 system (sometimes called the 'host owner', see *cons*(3)). The identity is set on a terminal to the name of the user who logs in. It is set on a CPU server to the *authid* obtained either from NVRAM or by a console prompt. The initial process created by system initialisation is given the *eve* identity.

Iseve returns true if the current user is *eve*. Several drivers use *iseve* to check the caller's identity before granting permission to perform certain actions. For example, the console driver allows only the user *eve* to write a new identity into the /dev/user file. The privileges are strictly local and do not extend into the network (in particular, to file servers—even ones running on the local machine).

SOURCE

/sys/src/9/port/auth.c

SEE ALSO

auth(2), *cap*(3), *cons*(3), *authsrv*(6), *auth*(8)

inb, ins, inl, outb, outs, outl, insb, inss, insl, outsb, outss, outsl - programmed I/O

```
SYNOPSIS
     int
            inb(int port)
     ushort ins(int port)
     ulong
            inl(int port)
     void
            outb(int port, int value)
     void
            outs(int port, ushort value)
     void
            outl(int port, ulong value)
     void
            insb(int port, void *address, int count)
            inss(int port, void *address, int count)
     void
     void
            insl(int port, void *address, int count)
     void
            outsb(int port, void *address, int count)
     void
            outss(int port, void *address, int count)
     void
            outsl(int port, void *address, int count)
```

DESCRIPTION

The *x86* implementation provides functions to allow kernel code written in C to access the I/O address space. On several other architectures such as the PowerPC and Strongarm, the platform-dependent code provides similar functions to access devices with an I/O space interface, even when that is memory mapped, to encourage portability of device drivers.

Inb, ins and *inl* apply the corresponding hardware instruction to fetch the next byte, short or long from the I/O *port. Outb, outs* and *outl* output a *value* to the I/O *port.*

The remaining functions transfer *count* bytes, shorts, or longs using programmed I/O between a memory *address* and *port*. Functions insX copy values into memory; functions outsX copy values from memory. The *count* is in elements, not bytes.

SOURCE

/sys/src/9/pc/l.s

SEE ALSO

dma(9)

intrenable, intrdisable - enable (disable) an interrupt handler

SYNOPSIS

```
void intrenable(int v, void (*f)(Ureg*, void*), void* a, int tbdf,
char *name)
void intrdisable(int v, void (*f)(Ureg*, void*), void* a, int tbdf,
char *name)
```

DESCRIPTION

Intrenable registers f to be called by the kernel's interrupt controller driver each time an interrupt denoted by v occurs, and unmasks the corresponding interrupt in the interrupt controller. The encoding of v is platform-dependent; it is often an interrupt vector number, but can be more complex. Tbdf is a platform-dependent value that might further qualify v. It might for instance denote the type of bus, bus instance, device number and function (following the PCI device indexing scheme), hence its name, but can have platform-dependent meaning. Name is a string that should uniquely identify the corresponding device (eg, "uart0"); again it is usually platform-dependent. Intrenable supports sharing of interrupt levels when the hardware does.

Almost invariably f is a function defined in a device driver to carry out the device-specific work associated with a given interrupt. The pointer a is passed to f; typically it points to the driver's data for a given device or controller. It also passes f a Ureg* value that contains the registers saved by the interrupt handler (the contents are platform specific; see the platform's include file ureg.h).

F is invoked by underlying code in the kernel that is invoked directly from the hardware vectors. It is therefore not running in any process (see kproc(9); indeed, on many platforms the current process pointer (up) will be nil. There are many restrictions on kernel functions running outside a process, but a fundamental one is that they must not *sleep*(9), although they often call wakeup to signal the occurrence of an event associated with the interrupt. *Qio*(9) and other manual pages note which functions are safe for *f* to call.

The interrupt controller driver does whatever is required to acknowledge or dismiss the interrupt signal in the interrupt controller, before calling f, for edge-triggered interrupts, and after calling f for level-triggered ones. F is responsible for dealing with the cause of the interrupt in the device, including any acknowledgement required in the device, before it returns.

Intrdisable removes any registration previously made by *intrenable* with matching parameters, and if no other interrupt is active on v, it masks the interrupt in the controller. Device drivers that are not dynamically configured tend to call *intrenable* during reset or initialisation (see dev(9)), but can call it at any appropriate time, and instead of calling *intrdisable* they can simply enable or disable interrupts in the device as required.

SOURCE

/sys/src/9/*/trap.c

SEE ALSO

malloc(9), qio(9), sleep(9), splhi(9)

kproc, pexit, postnote - kernel process creation, termination and interruption

SYNOPSIS

```
void kproc(char *name, void (*func)(void*), void *arg)
```

void pexit(char *note, int freemem)

int postnote(Proc *p, int dolock, char *n, int flag)

DESCRIPTION

Kproc creates a new kernel process to run the function *func*, which is invoked as (*func)(arg). The string *name* is copied into the text field of the Proc structure of the new process; this value is the name of the kproc in the output of ps(1). The process is made runnable; it will run when selected by the scheduler *sched*(9). The process is created with base and current priorities set to PriKproc. It shares the kernel process group and thus name space.

A kernel process terminates only when it calls *pexit*, thereby terminating itself. There is no mechanism for one process to force the termination of another, although it can send a software interrupt using *postnote*. *Note* is a null string on normal termination, or the cause of If *freemem* is nonzero, any memory allocated by the process is discarded; it should normally be non-zero for any process created by *kproc*. Use the following to terminate a kernel process normally:

pexit("", 1);

Postnote sends a software interrupt to process p, causing it, if necessary, to wake from sleep(9) or break out of a *rendezvous*(2) or an *eqlock*(9), with an *error*(9) 'interrupted'. Up to NNOTE notes can be pending at once (currently 5); if more than that arrive, the process is forced out of *sleep*, *rendezvous* and *eqlock*, but the message itself is discarded. *Postnote* returns non-zero iff the note has been delivered successfully. If *dolock* is non-zero, *postnote* synchronises delivery of the note with the debugger and other operations of *proc*(3). *Flag* is zero, or one of the following

NDebug

Print the note message on the user's standard error. Furthermore, suspend the process in a Broken state, preserving its memory, for later debugging.

NExit

Deliver the note quietly.

NUser

The note comes from another process, not the system.

The kernel uses *postnote* to signal processes that commit grave faults, and to implement the note and kill functions of proc(3). A device driver should use *postnote* only to tell a service process, previously started by the driver using *kproc*, that it should stop; the note will cause that process to raise an *error*(9). For example, a process started to read packets from a network device could be stopped as follows when the interface is unbound:

postnote(readp, 1, "unbind", 0);

where *readp* points to the appropriate Proc. The text of the message is typically irrelevant.

SOURCE

/sys/src/9/port/proc.c

malloc, mallocz, smalloc, realloc, free, msize, secalloc, secfree, setmalloctag, setrealloctag, getmalloctag, getrealloctag - kernel memory allocator

SYNOPSIS

```
void* malloc(ulong size)
```

```
void* mallocalign(ulong size, ulong align, long offset, ulong span)
```

```
void* mallocz(ulong size, int clr)
```

void* smalloc(ulong size)

void* realloc(void *p, ulong size)

```
void free(void *ptr)
```

```
ulong msize(void *ptr)
```

```
void* secalloc(ulong size)
```

```
void secfree(void *ptr)
```

void setmalloctag(void *ptr, ulong tag)

ulong getmalloctag(void *ptr)

void setrealloctag(void *ptr, ulong tag)

```
ulong getrealloctag(void *ptr)
```

DESCRIPTION

These are kernel versions of the functions in malloc(2). They allocate memory from the mainmem memory pool, which is managed by the allocator pool(2), which in turn replenishes the pool as required by calling xalloc(9). All but *smalloc* (which calls *sleep*(9)) may safely be called by interrupt handlers.

Malloc returns a pointer to a block of at least *size* bytes, initialised to zero. The block is suitably aligned for storage of any type of object. The call malloc(0) returns a valid pointer rather than null. *Mallocz* is similar, but only clears the memory if *clr* is non-zero.

Smalloc returns a pointer to a block of *size* bytes, initialised to zero. If the memory is not immediately available, *smalloc* retries every 100 milliseconds until the memory is acquired.

Mallocalign allocates a block of at least *n* bytes of memory respecting alignment contraints. If *align* is non-zero, the returned pointer is aligned to be equal to *offset* modulo *align*. If *span* is non-zero, the *n* byte block allocated will not span a *span*-byte boundary.

Realloc changes the size of the block pointed to by p to *size* bytes, if possible without moving the data, and returns a pointer to the block. The contents are unchanged up to the lesser of old and new sizes, and any new space allocated is initialised to zero. *Realloc* takes on special meanings when one or both arguments are zero:

```
realloc(0, size)
```

means malloc(size); returns a pointer to the newly-allocated memory

```
realloc(ptr, 0)
```

means free(ptr); returns null

```
realloc(0, 0)
```

no-op; returns null

The argument to *free* is a pointer to a block of memory allocated by one of the routines above, which is returned to the allocation pool, or a null pointer, which is ignored.

When a block is allocated, sometimes there is some extra unused space at the end. *Msize* grows the block to encompass this unused space and returns the new number of bytes that may be used.

Secalloc and *secfree* are security-aware functions that use a pool flagged by POOL_ANTAGONISM (see *pool*(2)), which fills every allocated block with garbage before and after its use, to prevent leakage.

The memory allocator maintains two word-sized fields associated with each block, the "malloc tag" and the "realloc tag". By convention, the malloc tag is the PC that allocated the block, and the realloc tag the PC that last reallocated the block. These may be set or examined with *setmalloctag*, *getmalloctag*, *setrealloctag*, and *getrealloctag*. When allocating blocks directly with *malloc* and *realloc*, these tags will be set properly. If a custom allocator wrapper is used, the allocator wrapper can set the tags itself (usually by passing the result of *getcallerpc*(2) to *setmalloctag*) to provide more useful information about the source of allocation.

SOURCE

/sys/src/9/port/alloc.c

DIAGNOSTICS

All functions except *smalloc* return a null pointer if space is unavailable. If the allocated blocks have no malloc or realloc tags, *getmalloctag* and *getrealloctag* return ~ 0 .

SEE ALSO

pool(2), xalloc(9)

panic - abandon hope, all ye who enter here

SYNOPSIS

void panic(char *fmt, ...)

DESCRIPTION

Panic writes a message to the console and causes the system to give up the host. It enables interrupts, dumps the kernel stack, and halts the current processor; if more than one, others will gradually come to a halt. Depending on configuration settings, the platform-dependent *exit* might reboot the system. The format *fmt* and associated arguments are the same as those for *print*(9). *Panic* adds a prefix panic: and a trailing newline.

parsecmd, cmderror, lookupcmd - parse device commands

SYNOPSIS

Cmdbuf* parsecmd(char *a, int n)
void cmderror(Cmdbuf *cb, char *s)
Cmdtab* lookupcmd(Cmdbuf *cb, Cmdtab *ctab, int nctab)

DESCRIPTION

Parsecmd is an interface to *tokenize* (see *getfields*(2)), that safely parses a command, with blank-separated fields, as might be written to a device's ctl file. The buffer *a* and count *n* can be those passed to the driver's *write* function. *Parsecmd* converts the byte array (which might not be null-terminated) to a null-terminated string, trimming any trailing new line, before invoking *tokenize* to break the string into arguments, interpreting blank and tab as field separators when they are not quoted (in the style of *rc*(1)). It returns a pointer to a dynamically-allocated Cmdbuf structure, which holds a copy of the string and the resulting fields; it is defined as follows:

```
typedef
struct Cmdbuf
{
    char *buf;
    char **f;
    int nf;
} Cmdbuf;
```

The array f holds the field pointers; nf gives the number of fields. Cmdbuf is allocated by *smalloc* (see *malloc*(9)), and the caller is responsible for freeing it using *free*. *Cmderror* prepends the given format with the original command, then calls *error*(9).

Command strings may be turned into a (typically enumerated) integer with *lookupcmd*. The catchall * matches any text. Unrecognized commands, or commands given an unacceptable number of arguments generate a call to *error*. The definition is as follows

```
typedef
struct Cmdtab
{
    int index; /* used by client to switch on result */
    char *cmd; /* command name */
    int narg; /* expected #args; 0 ==> variadic */
} Cmdtab;
```

The integer index is the number returned on command match. The string cmd is the command name, and narg is 0 (indicating a variadic function) or the number of arguments.

SOURCE

```
/sys/src/9/port/parse.c
```

qlock, qunlock, canqlock, rlock, runlock, wlock, wunlock - serial synchronisation

```
SYNOPSIS
     typedef struct
     {
                             /* to access Qlock structure */
          Lock use;
                             /* next process waiting for object */
          Proc *head;
                              /* last process waiting for object */
          Proc *tail;
                              /* flag */
          int
              locked;
     } OLock:
     typedef struct
     {
          Lock
                    use;
                              /* list of waiting processes */
                    *head;
          Proc
                    *tail;
          Proc
                               /* pc of writer */
          uintptr
                    wpc;
                              /* writing proc */
          Proc
                    *wproc;
          int
                    readers;
                             /* number of readers */
          int
                    writer;
                              /* number of writers */
     } RWlock;
     void eqlock(QLock *1)
     void qlock(QLock *1)
     void qunlock(QLock *1)
     int canqlock(QLock *1)
     void rlock(RWlock *1)
     void runlock(RWlock *1)
     int canrlock(RWlock *1)
     void wlock(RWlock *1)
     void wunlock(RWlock *1)
```

DESCRIPTION

The primitive locking functions described in lock(9) guarantee mutual exclusion, but they implement spin locks, and should not be used if the process might sleep(9) within a critical section. The following functions serialise access to a resource by forming an orderly queue of processes.

Each resource to be controlled is given an associated QLock structure; it is usually most straightforward to put the QLock in the structure that represents the resource. It must be initialised to zero before use (as guaranteed for global variables and for structures allocated by *malloc*).

On return from *qlock*, the process has acquired the lock *I*, and can assume exclusive access to the associated resource. If the lock is not immediately available, the requesting process is placed on a FIFO queue of processes that have requested the lock. Processes on this list are blocked in the Queueing state.

Eqlock is an interruptible form of qlock.

Qunlock unlocks I and schedules the first process queued for it (if any).

Canqlock is a non-blocking form of *qlock*. It tries to obtain the lock *l* and returns true if successful, and 0 otherwise; it always returns immediately.

RWlock is a form of lock for resources that have distinct readers and writers. It allows concurrent readers but gives each writer exclusive access. A caller announces its read or write intentions by choice of lock (and unlock) function; the system assumes the caller will not modify a structure accessed under read lock.

Rlock acquires *I* for reading. The holder can read but agrees not to modify the resource. There may be several concurrent readers. *Canrlock* is non-blocking: it returns non-zero if it successfully

acquired the lock immediately, and 0 if the resource was unavailable.

Runlock returns a read lock; the last reader out enables the first writer waiting (if any).

Wlock acquires a write lock. The holder of such a lock may assume exclusive access to the resource, and is allowed to modify it.

Wunlock returns a write lock. The next pending process, whether reader or writer, is scheduled.

SOURCE

/sys/src/9/port/qlock.c

SEE ALSO

lock(9), malloc(9), splhi(9)

readnum, readstr - device read routines

SYNOPSIS

```
int readstr(ulong off, char *buf, ulong n, char *str)
```

```
int readnum(ulong off, char *buf, ulong n, ulong val, int size)
```

DESCRIPTION

Readstr and *readnum* simplify the return of strings and numbers from device *read* routines, because they deal with any buffering and boundary cases. Several parameters to the read call are often handed on directly to these functions: the file offset, as *off*; the address of the user's buffer, as *buf*; and the number of bytes requested, as *n*. Both functions return the number of bytes they have stored in *buf*, and which can often be returned directly from the device read routine.

Readstr satisfies a read by copying data into *buf* from the NUL-terminated string in *str*. The data transferred is selected and limited by *off*, *n* and the length of *str*.

Readnum converts the unsigned integer *val* to a decimal representation in *buf*. The value is right-justified in a field of *size*-1 places and is followed by a blank. *Size* can be the global constant NUMSIZE for 32-bit integers; the largest *size* allowed is 64 bytes.

SOURCE

/sys/src/9/port/devcons.c

anyhigher, anyready, hzsched, procpriority, procrestore, procsave, scheddump, schedinit, sched, yield - scheduler interactions

SYNOPSIS

```
anyhigher(void)
int
int
      anyready(void)
void hzsched(void)
void procpriority(Proc *p, int priority, int fixed)
void procrestore(Proc *p)
void procsave(Proc *p)
void procwired(Proc *p, int machno)
void scheddump(void)
void
      schedinit(void)
void
      sched(void)
void
     vield(void)
enum {
                  = 20, /* scheduler priority levels */
      Npriq
                  = 10, /* base for normal processes */
      PriNormal
                  = 13, /* base for kernel processes */
      PriKproc
                  = 13, /* base for root processes */
      PriRoot
}:
```

DESCRIPTION

These functions define the priority process scheduler's interface. Processes are scheduled strictly by priority, and processor affinity. When possible, processes with no affinity will be rescheduled on the same processor. Within a priority, scheduling is round-robin. Long-running processes of the same priority are preempted and rescheduled. But cpu use (or lack thereof) may adjust the priority up or down, unless it has been explicitly fixed. Kernel processes are started with PriKproc while user processes start with PriNormal.

Anyhigher returns true if any higher priority processes are runnable, while anyready returns true if any processes are runnable at all. Yield gives up the processor and pretends to consume ½ clock tick, while sched invokes the scheduler, potentially recursively. Sched may be called outside process context. Either may return immediately. Schedinit initializes scheduling on the running processor.

Procpriority sets a process' priority directly. Fixed-priority processes are not reprioritized based on cpu use. *Procwired* makes a process runnable only on a single processor.

Hzsched is called by the clock routine on every tick to collect statistics. Periodically (typically once a second) *hzsched* reprioritizes based on cpu use.

Procsave and *procrestore* are architecture-dependent routines used by the scheduler to save and restore processes. *Scheddump* prints scheduler statistics.

SOURCE

```
/sys/src/9/port/proc.c
```

```
Procsave and procrestore can be found at
/sys/src/9/*/main.c
/sys/src/9/*/arch.c
/sys/src/9/*/trap.c
```

SEE ALSO

edf(9), sleep(9)

seconds, ticks, fastticks, HZ, MS2HZ, MS2TK, TK2MS, TK2SEC - kernel times and time conversions

```
SYNOPSIS
```

```
long seconds(void)
vlong fastticks(uvlong *hz)
#define HZ ...
#define MS2HZ (1000/HZ)
#define TK2SEC(t) ((t)/HZ)
#define TK2MS(t) ((t)*(1000/HZ))
```

DESCRIPTION

Seconds returns the system's idea of the current time as the number of seconds since the start of the epoch (00:00:00 GMT, January 1, 1970).

The ticks field of the Mach structure returns the number of system-dependent clock ticks on the given processor since system boot. On a multiprocessor, MACHP(0) is sometimes used to provide a reference time, since the tick value might vary slightly across processors.

Fastticks returns the number of ticks since boot as measured by the fastest clock provided by the platform. The frequency of the clock, in ticks per second, is returned through *hz*, unless it is nil.

The system clock frequencies are platform-dependent. Several symbolic constants and macro functions are defined by the file mem.h to convert between different time units:

HZ	The number of clock ticks per second.
MS2HZ	Milliseconds per clock tick.
TK2SEC(t)	Convert <i>t</i> clock ticks to seconds (truncating not rounding).
TK2MS(t)	Convert t clock ticks to milliseconds.

SOURCE

/sys/src/9/*/mem.h
/sys/src/9/*/clock.c
/sys/src/9/*/devarch.c
/sys/src/9/*/timer.c
/sys/src/9/port/tod.c

sleep, wakeup, tsleep, return0 - process synchronisation

SYNOPSIS

```
void sleep(Rendez *r, int (*f)(void*), void *arg)
```

void wakeup(Rendez *r)

```
void tsleep(Rendez *r, int (*f)(void*), void *arg, ulong ms)
```

int return0(void *arg)

DESCRIPTION

A process running in the kernel can use these functions to synchronise with an interrupt handler or another kernel process. In particular, they are used by device drivers to wait for an event to be signalled on receipt of an interrupt. (In practice, they are most often used indirectly, through *qio*(9) for instance.)

The caller of *sleep* and a caller of *wakeup* share a Rendez structure, to provide a rendezvous point between them to synchronise on an event. *Sleep* uses a condition function f that returns true if the event has occurred.

Sleep evaluates f(arg). If true, the event has happened and sleep returns immediately. Otherwise, sleep blocks on the event variable r, awaiting wakeup.

Wakeup is called by either a process or an interrupt handler to wake any process sleeping at r, signifying that the corresponding condition is true (the event has occurred). It has no effect if there is no sleeping process.

Tsleep is similar to *sleep*, except that if the condition f(arg) is false and the caller does sleep, and nothing else wakes it within *ms* millliseconds, the system will wake it. *Tsleep*'s caller must check its environment to decide whether timeout or the event occurred. The timing provided by *tsleep* is imprecise, but adequate in practice for the normal use of protecting against lost interrupts and otherwise unresponsive devices or software.

ReturnO ignores its arguments and returns zero. It is commonly used as the predicate f in a call to *tsleep* to obtain a time delay, using the Rendez variable sleep in the Proc structure, for example:

tsleep(&up->sleep, return0, nil, 10);

Both *sleep* and *tsleep* can be interrupted by *postnote* (see *kproc*(9)).

SOURCE

/sys/src/9/port/proc.c
/sys/src/9/port/sysproc.c

DIAGNOSTICS

There can be at most one process waiting on a Rendez, and if two processes collide, the system will *panic*(9) ("double sleep"). Access to a Rendez must therefore be serialised by some other mechanism, usually *qlock*(9).

SEE ALSO

lock(9), qlock(9), delay(9)

"Process Sleep and Wakeup on a Shared-memory Multiprocessor", in *Plan 9 Programmer's Manual: Volume 2*.

splhi, spllo, splx, islo - enable and disable interrupts

SYNOPSIS

```
int spllo(void)
```

```
int splhi(void)
```

```
void splx(int x)
```

```
int islo(void)
```

DESCRIPTION

These primitives enable and disable maskable interrupts on the current processor. Generally, device drivers should use *ilock* (see *lock*(9)), *sleep*(9), or the functions in *qio*(9) to control interaction between processes and interrupt handlers. Those routines (but not these) provide correct synchronisation on multiprocessors.

Spllo enables interrupts and returns a flag representing the previous interrupt enable state. It must not normally be called from interrupt level.

Splhi disables all maskable interrupts and returns the previous interrupt enable state. The period during which interrupts are disabled had best be short, or real-time applications will suffer.

Splx restores the interrupt enable state to x, which must be a value returned by a previous call to splhi or spllo.

Islo returns true (non-zero) if interrupts are currently enabled, and 0 otherwise.

SOURCE

/sys/src/9/*/l.s

SEE ALSO

lock(9), qio(9), sleep(9), intrenable(9)

xalloc, xallocz, xspanalloc, xfree, xsummary - basic memory management

SYNOPSIS

```
void* xalloc(ulong size)
```

void* xallocz(ulong size, int clr)

void* xspanalloc(ulong size, int align, ulong span)

void xfree(void *p)

void xsummary(void)

DESCRIPTION

These are primitives used by higher-level memory allocators in the kernel, such as *malloc*(9). They are not intended for use directly by most kernel routines. The main exceptions are routines that permanently allocate large structures, or need the special alignment properties guaranteed by *xspanalloc*.

Xalloc returns a pointer to a range of size bytes of memory. The memory will be zero filled and aligned on a 8 byte (BY2V) address. If the memory is not available, xalloc returns a null pointer.

Xmallocz will clear the memory after allocation if *clr* is set to a value other than zero. Since it is used by *xmalloc*, the same diagnostics apply.

Xspanalloc allocates memory given alignment and spanning constraints. The block returned will contain *size* bytes, aligned on a boundary that is 0 mod *align*, in such a way that the memory in the block does not span an address that is 0 mod *span. Xspanalloc* is intended for use allocating hardware data structures (eg, page tables) or I/O buffers that must satisfy specific alignment restrictions. If *xspanalloc* cannot allocate memory to satisfy the given constraints, it will *panic*(9). The technique it uses can sometimes cause memory to be wasted. Consequently, *xspanalloc* should be used sparingly.

Xfree frees the block of memory at *p*, which must be an address previously returned by *xalloc* (not *xspanalloc*).

Xsummary dumps memory allocation statistics to the console. The output includes the total free space, the number of free holes, and a summary of active holes. Each line shows 'address top size'.

SOURCE

/sys/src/9/port/xalloc.c

SEE ALSO

malloc(9)

PERMUTED INDEX

Manual pages for all sections are accessible on line through *man*(1).

To save space, neighboring references to the same page have been collapsed into a single reference. This should cause no difficulty in cases like 'atan' and 'atan2', but is somewhat obscure in the case of 'strcat' and 'strchr'.

exec, exit, flag, rfork, shift, wait, whatis, .,	~ - command language rc, cd, eval,	rc(1)	239
procsave, scheddump, schedinit, sched, yield	- scheduler interactions /procrestore,	sched(9)	
compilors	0a, 1a, 2a, 5a, 6a, 8a, ka, qa, va - assemblers .	2a(1)	4 5
compilers	0c, 1c, 2c, 5c, 6c, 7c, 8c, kc, qc, vc - C 0l, 1l, 2l, 5l, 6l, 8l, kl, ql, vl - loaders	2c(1) 2l(1)	5 8
vt – emulate a	100 or VT-220 terminal	vt(1)	333
	1.2 BIOS interface	apm(3)	674
1 5	1.2 BIOS interface	apm(8)	927
1 5	1a, 2a, 5a, 6a, 8a, ka, qa, va – assemblers	2a(1)	4
	1c, 2c, 5c, 6c, 7c, 8c, kc, qc, vc – C compilers	2c(1)	5
01,		21(1)	8
	2 encryption to a communication channel	pushssl(2)	582
vt – emulate a VT–100 or	220 terminal	vt(1)	333
	2600 – emulator	atari(1)	25
0a, 1a,	2a, 5a, 6a, 8a, ka, qa, va - assemblers	2a(1)	4
0c, 1c,	2c, 5c, 6c, 7c, 8c, kc, qc, vc - C compilers	2c(1)	5
	21, 51, 61, 81, k1, q1, v1 - loaders	2l(1)	8
zipfs - mount archival file systems		tapefs(4)	814
	3-d points and planes /pn2f3, ppp2f3,	arith3(2)	375
qball –		qball(2)	586
	4) filter	ptrap(4)	802
geigerstats, glendy, juggle, life, mandel,/	4s, 5s, blabs, catclock, doom, festoon,	games(1)	109
0a, 1a, 2a,	5a, 6a, 8a, ka, qa, va - assemblers	2a(1)	4
0c, 1c, 2c,		2c(1)	5
	5e – user-mode ARM emulation	5e(1)	10
	5i, ki, vi, qi – instruction simulators	vi(1)	327 8
0l, 1l, 2l, geigerstats, glendy, juggle, life, mandel,/ . 4s,		2I(1) games(1)	109
0a, 1a, 2a, 5a,		2a(1)	4
0a, 1a, 2a, 3a, 0c, 1c, 2c, 5c,		2c(1)	5
manual tunnel of IPv6 through IPv4	6 6 6 6 6 6 6 6 6 6 6 6 6 6 6 6 6 6 6	6in4(8)	919
0l, 1l, 2l, 5l,		21(1)	8
	8a, ka, qa, va – assemblers	2a(1)	4
	8c, kc, gc, vc - C compilers	2c(1)	5
	81, kl, gl, vl - loaders	21(1)	8
	9660 CD image	mk9660(8)	992
file systems dossrv,		dossrv(4)	765
bootx64.efi, efiboot.fat -/ 9bootfat, 9bootiso,	9boothyb, 9bootpxe, bootia32.efi,	9boot(8)	921
srv, srvtls,		srv(4)	811
intro - introduction to the Plan 9 File Protocol,		intro(5)	830
	9P connection and negotiate version	fversion(2)	484
	9P fid, request tracking /freereqpool,	9pfid(2)	355
	9P file service /srvrelease, threadlistensrv,	9p(2)	349
	9P requests . /reqqueuecreate, reqqueuepush,	9pqueue(2)	359
mnt – attach to	9P servers	mnt(3)	711
225	9pcon – 9P to text translator	9pcon(8)	923 924
aan,	aanuke – always available network	aan(8)	924 11
nanic	abardon hope, all ye who enter here	abaco(1) panic(9)	
panc -	abort – generate a fault	abort(2)	360
flush –	5	flush(5)	837
Tiu Sii	abs, labs – integer absolute values	abs(2)	361
functions fabs, fmod, floor, ceil -		floor(2)	465
	access	consolefs(4)	760

	accord datarming accordibility of file	$\alpha = \alpha =$	262
500	access – determine accessibility of file	access(2) seg(1)	362 270
	access daemons telnetd, rlogind, rexexec,	ipserv(8)	984
RGB, readcolmap, writecolmap –	access display color map		595
getenv, putenv –	access environment variables	getenv(2)	486
	access functions . /textsym, file2pc, fileelem,	symbol(2)	635
io - Wi Ei Protoctad	access PC I/O registers	io(1) wpa(8)	152
	access to a terminal	screenlock(8)	
	access to executable files /beswal, beswav,	mach(2)	529
	accessibility of file	access(2)	362
	according to condition	test(1)	301
aux/mouse,	accupoint - configure a mouse to a port	mouse(8)	998
	acid, truss, trump – debuggeracme – control files for text windows	acid(1) acme(4)	12 750
	acme, win – interactive text windows	acme(1)	16
sin, cos, tan, asin,	acos, atan, atan2 – trigonometric functions	sin(2)	623
Interface	acpi - Advanced Configuration and Power	acpi(8)	925
amleval, amlenum, amltake, amldrop -	ACPI machine language interpreter /amlwalk,	aml(2)	370
controlcalled,/ Control, Controlset,	activate, closecontrol, closecontrolset,	control(2)	403
<pre>closept3, dot3, cross3, len3, dist3, unit3,/ /vdiv3, vrem3, pn2f3, ppp2f3, fff2p3, pdiv4,</pre>	add3, sub3, neg3, div3, mul3, eqpt3,add4, sub4 – operations on 3-d points and/	arith3(2) arith3(2)	375 375
delay, microdelay,	addclock0link - small delays, clock interrupts	delay(9)	
newuser –	adding a new user	newuser(8)	
auth_proxy, fauth_proxy,/ amount, newns,	addns, login, noworld, procsetuser,	auth(2)	379
rectsubpt, insetrect, canonrect, eqpt, eqrect,/	addpt, subpt, mulpt, divpt, rectaddpt,	addpt(2)	363
trampoline – forward incoming calls to another ratfs – mail	address	trampoline(8) ratfs(4)	1068 804
hnputs, ptclbsum, readipifc – Internet Protocol	addressing . /nhgetl, nhgets, hnputv, hnputl,	ip(2)	519
ident, matmul, matmulr, determinant,	adjoint, invertmat, xformpoint, xformpointd,/	matrix(2)	534
/packblock, padblock, pullblock, pullupblock,	adjustblock, checkb - data block management	allocb(9)	1085
inflatezlibblock, flateerr, mkcrctab, blockcrc,	adler32 - deflate compression . /inflateblock,	flate(2)	463
intro – introduction to system	administration	intro(8)	918
acpi –	Advanced Configuration and Power Interface advanced encryption standard (rijndael)	acpi(8) aes(2)	925 365
(Serial AT) storage device/ sdahci - AHCI	Advanced Host Controller Interface) SATA	sdahci(3)	725
interface apm -	Advanced Power Management 1.2 BIOS	apm(3)	674
interface apm -	Advanced Power Management 1.2 BIOS	apm(8)	927
cotup AESctato _ accCBC an en unt	aescbc, ipso, secstore - secstore commands	secstore(1)	265
setupAESstate, aesCBCencrypt, setupAESstate,			
aesCBCdecrypt, aesCFBencrypt,			
/setupAESGCMstate, aesgcm_setiv, aesgcm_encrypt,	aesgcm_decrypt - advanced encryption/	aes(2)	365
aes_xts_decrypt, / / aesCFBdecrypt,	anafant laadabay Subfant Fantabay Fant	a = a + a = b = a = a = (2)	205
font utilities cachechars, factotum, fgui, userpasswd - authentication	agefont, loadchar, Subfont, Fontchar, Font agent	cachechars(2) factotum(4)	395 770
SATA (Serial AT) storage device/ sdahci -	AHCI (Advanced Host Controller Interface)	sdahci(3)	725
language interpreter)	Aladdin Ghostscript (PostScript and PDF	gs(1)	116
	alarm - ask for delayed note	alarm(1)	21
sleep,	alarm - delay, ask for delayed note	sleep(2)	625
dsasigfree, dsaprivtopub – digital signature X509rsaverifydigest – RSA encryption	algorithm /dsaprivfree, dsasigalloc, algorithm /X509rsareq, X509rsaverify,	dsa(2) rsa(2)	438 601
X30913aventyulgest - K5A encryption	aliasmail – expand system wide mail aliases	aliasmail(8)	926
col – column	1 /	col(1)	50
setupRC4state, rc4, rc4skip, rc4back -			
/writeimage, bytesperline, wordsperline -	alleged rc4 encryption	rc4(2)	593
	alleged rc4 encryptionallocating, freeing, reading, writing images	rc4(2) allocimage(2)	367
binalloc, bingrow, binfree - grouped memory	alleged rc4 encryptionallocating, freeing, reading, writing images allocation	rc4(2) allocimage(2) bin(2)	367 387
brk, sbrk – change memory	alleged rc4 encryptionallocating, freeing, reading, writing images allocationallocation	rc4(2) allocimage(2) bin(2) brk(2)	367 387 394
	alleged rc4 encryptionallocating, freeing, reading, writing images allocation	rc4(2) allocimage(2) bin(2)	367 387
brk, sbrk – change memory segbrk – change memory getrealloctag, malloctopoolblock – memory getmalloctag, getrealloctag – kernel memory	alleged rc4 encryptionallocating, freeing, reading, writing images allocationallocationallocationallocationallocator/setrealloctag, getmalloctag, allocator/setmalloctag, setrealloctag, setrealloctag,	rc4(2) allocimage(2) bin(2) brk(2) segbrk(2) malloc(2) malloc(9)	367 387 394 619 532 1095
brk, sbrk – change memory segbrk – change memory getrealloctag, malloctopoolblock – memory getmalloctag, getrealloctag – kernel memory vtstrdup, vtfree – error-checking memory	alleged rc4 encryptionallocating, freeing, reading, writing images allocationallocationallocationallocationallocator/setrealloctag, getmalloctag, allocator/setmalloctag, setrealloctag, allocator/setmalloctag, setrealloctag, allocators/vtmalloc, vtmallocz, vtrealloc,	rc4(2) allocimage(2) bin(2) brk(2) segbrk(2) malloc(2) malloc(9) venti-mem(2)	367 387 394 619 532 1095 662
brk, sbrk – change memory segbrk – change memory getrealloctag, malloctopoolblock – memory getmalloctag, getrealloctag – kernel memory vtstrdup, vtfree – error-checking memory blocklen, blockalloclen, readblist,/	alleged rc4 encryption allocating, freeing, reading, writing images allocation allocation allocator/setrealloctag, getmalloctag, allocator/setmalloctag, setrealloctag, allocators/vtmalloc, vtmallocz, vtrealloc, allocb, iallocb, freeb, freeblist, BLEN, BALLOC, .	rc4(2) allocimage(2) bin(2) brk(2) segbrk(2) malloc(2) malloc(9) venti-mem(2) allocb(9)	367 387 394 619 532 1095 662 1085
brk, sbrk – change memory segbrk – change memory getrealloctag, malloctopoolblock – memory getmalloctag, getrealloctag – kernel memory vtstrdup, vtfree – error-checking memory blocklen, blockalloclen, readblist,/ lookupfid, removefid, Req,/ Fid, Fidpool,	alleged rc4 encryptionallocating, freeing, reading, writing images allocationallocationallocationallocationallocationallocator/setrealloctag, getmalloctag, allocator/setmalloctag, setrealloctag, allocators/vtmalloc, vtmallocz, vtrealloc, allocb, iallocb, freeb, freeblist, BLEN, BALLOC, allocfidpool, freefidpool, allocfid, closefid,	rc4(2) allocimage(2) bin(2) brk(2) segbrk(2) malloc(2) malloc(9) venti-mem(2) allocb(9) 9pfid(2)	367 387 394 619 532 1095 662
brk, sbrk – change memory segbrk – change memory getrealloctag, malloctopoolblock – memory getmalloctag, getrealloctag – kernel memory vtstrdup, vtfree – error-checking memory blocklen, blockalloclen, readblist,/ lookupfid, removefid, Req,/ Fid, Fidpool, namedimage, setalpha,/ allocimage, lookupkey, deletekey – integer to/ Intmap,	alleged rc4 encryption	rc4(2) allocimage(2) bin(2) brk(2) segbrk(2) malloc(2) malloc(9) venti-mem(2) allocb(9) 9pfid(2) allocimage(2) intmap(2)	367 387 394 619 532 1095 662 1085 355
brk, sbrk – change memory segbrk – change memory getrealloctag, malloctopoolblock – memory getmalloctag, getrealloctag – kernel memory vtstrdup, vtfree – error-checking memory blocklen, blockalloclen, readblist,/ lookupfid, removefid, Req,/ Fid, Fidpool, namedimage, setalpha,/ allocimage, lookupkey, deletekey – integer to/ Intmap, /wordaddr, byteaddr, memimagemove,	alleged rc4 encryption	rc4(2) allocimage(2) bin(2) brk(2) segbrk(2) malloc(2) malloc(9) venti-mem(2) allocimage(2) allocimage(2) intmap(2) memdraw(2)	367 387 394 619 532 1095 662 1085 355 367 515 536
brk, sbrk – change memory segbrk – change memory getrealloctag, malloctopoolblock – memory getmalloctag, getrealloctag – kernel memory vtstrdup, vtfree – error-checking memory blocklen, blockalloclen, readblist,/ lookupfid, removefid, Req,/ Fid, Fidpool, namedimage, setalpha,/ allocimage, lookupkey, deletekey – integer to/ Intmap, /wordaddr, byteaddr, memimagemove, /byteaddr, memimagemove, alloccmemimage,	alleged rc4 encryption	rc4(2) allocimage(2) bin(2) brk(2) segbrk(2) malloc(2) malloc(9) venti-mem(2) allocb(9) 9pfid(2) allocimage(2) intmap(2) memdraw(2)	367 387 394 619 532 1095 662 1085 367 515 536 536
brk, sbrk – change memory segbrk – change memory getrealloctag, malloctopoolblock – memory getmalloctag, getrealloctag – kernel memory vtstrdup, vtfree – error-checking memory blocklen, blockalloclen, readblist,/ lookupfid, removefid, Req,/ Fid, Fidpool, namedimage, setalpha,/ allocimage, lookupkey, deletekey – integer to/ Intmap, /wordaddr, byteaddr, memimagemove, /byteaddr, memimagemove, alloccmemimage, /memlinebbox, memlineendsize,	alleged rc4 encryption	rc4(2) allocimage(2) bin(2) brk(2) segbrk(2) malloc(2) malloc(9) venti-mem(2) allocb(9) 9pfid(2) allocimage(2) intmap(2) memdraw(2) memdraw(2)	367 387 394 619 532 1095 662 1085 367 515 536 536 536
brk, sbrk – change memory segbrk – change memory getrealloctag, malloctopoolblock – memory getmalloctag, getrealloctag – kernel memory vtstrdup, vtfree – error-checking memory blocklen, blockalloclen, readblist,/ lookupfid, removefid, Req,/ Fid, Fidpool, namedimage, setalpha,/ allocimage, lookupkey, deletekey – integer to/ Intmap, /wordaddr, byteaddr, memimagemove, /byteaddr, memimagemove, alloccmemimage,	alleged rc4 encryption	rc4(2) allocimage(2) bin(2) brk(2) segbrk(2) malloc(2) malloc(9) venti-mem(2) allocb(9) 9pfid(2) allocimage(2) intmap(2) memdraw(2)	367 387 394 619 532 1095 662 1085 367 515 536 536
brk, sbrk – change memory segbrk – change memory getrealloctag, malloctopoolblock – memory getmalloctag, getrealloctag – kernel memory vtstrdup, vtfree – error-checking memory blocklen, blockalloclen, readblist,/ lookupfid, removefid, Req,/ Fid, Fidpool, namedimage, setalpha,/ allocimage, lookupkey, deletekey – integer to/ Intmap, /wordaddr, byteaddr, memimagemove, /byteaddr, memimagemove, allocmemimage, /memlinebbox, memlineendsize, /closefid, lookupfid, removefid, Req, Reqpool, allocwindow, bottomwindow,/ Screen, lookupsubfont, uninstallsubfont,/	alleged rc4 encryption	rc4(2) allocimage(2) bin(2) brk(2) segbrk(2) malloc(2) malloc(9) venti-mem(2) allocb(9) 9pfid(2) allocimage(2) intmap(2) memdraw(2) memdraw(2) memdraw(2) gpfid(2) window(2) subfont(2)	367 387 394 619 532 1095 662 1085 355 367 515 536 536 536 536 536 536 668 633
brk, sbrk – change memory segbrk – change memory getrealloctag, malloctopoolblock – memory getmalloctag, getrealloctag – kernel memory vtstrdup, vtfree – error-checking memory blocklen, blockalloclen, readblist,/ lookupfid, removefid, Req,/ Fid, Fidpool, namedimage, setalpha,/ allocimage, lookupkey, deletekey – integer to/ Intmap, /wordaddr, byteaddr, memimagemove, /byteaddr, memimagemove, allocmemimage, /memlinebbox, memlineendsize, /closefid, lookupfid, removefid, Req, Reqpool, allocwindow, bottomwindow,/ Screen, lookupsubfont, uninstallsubfont,/	alleged rc4 encryption	rc4(2) allocimage(2) bin(2) brk(2) segbrk(2) malloc(2) malloc(9) venti-mem(2) allocb(9) 9pfid(2) allocimage(2) intmap(2) memdraw(2) memdraw(2) gpfid(2) window(2) subfont(2) 9pfile(2)	367 387 394 619 532 1095 662 1085 355 367 515 536 536 536 536 536 536 668 633 357
brk, sbrk – change memory segbrk – change memory getrealloctag, malloctopoolblock – memory getmalloctag, getrealloctag – kernel memory vtstrdup, vtfree – error-checking memory blocklen, blockalloclen, readblist,/ lookupfid, removefid, Req,/ Fid, Fidpool, namedimage, setalpha,/ allocimage, lookupkey, deletekey – integer to/ Intmap, /wordaddr, byteaddr, memimagemove, /byteaddr, memimagemove, allocmemimage, /memlinebbox, memlineendsize, /closefid, lookupfid, removefid, Req, Reqpool, allocwindow, bottomwindow,/ Screen, lookupsubfont, uninstallsubfont,/	alleged rc4 encryption	rc4(2) allocimage(2) bin(2) brk(2) segbrk(2) malloc(2) malloc(9) venti-mem(2) allocb(9) 9pfid(2) allocimage(2) intmap(2) memdraw(2) memdraw(2) memdraw(2) gpfid(2) window(2) subfont(2)	367 387 394 619 532 1095 662 1085 355 367 515 536 536 536 536 536 536 668 633

chanclosing, chanprint, mainstacksize,/	alt, chanclose, chancreate, chanfree,	thread(2)	638
aan, aanuke -	always available network	aan(8)	924
/amlload, amlwalk, amleval, amlenum, amltake,	amldrop – ACPI machine language interpreter .	aml(2)	370
/amlinit, amlexit, amlload, amlwalk, amleval,	amlenum, amltake, amldrop – ACPI machine/ .	aml(2)	370
amlload, amlwalk, amleval, / amltag, amlval,	amlint, amllen, amlnew, amlinit, amlexit,	aml(2)	370
/amlexit, amlload, amlwalk, amleval, amlenum,	amltake, amldrop – ACPI machine language/	aml(2)	370
amlexit, amlload, amlwalk, amleval, / . amltag,	amlval, amlint, amllen, amlnew, amlinit,	aml(2)	370
/auth_freerpc, auth_rpc, auth_getkey,	amount_getkey, auth_freeAI, auth_chuid,/	auth(2)	379
lex – generator of lexical	analysis programs	lex(1)	165
setnetmtpt, getnetconninfo,/ dial, hangup,	announce, listen, accept, reject, netmkaddr,	dial(2)	427
procsave, scheddump, schedinit,/ . anyhigher,	anyready, hzsched, procpriority, procrestore,	sched(9)	1102
sdaoe - ATA-over-Ethernet	Ao) storage device interface	sdaoe(3)	727
	aoe – ATA-over-Ethernet (Ao) interface	aoe(3)	671
vblade – virtual	AoE target	vblade(8)	1070
	a.out - object file format	a.out(6)	847
	ap – fetch Associated Press news articles	ap(1)	22
pcc –	APE C compiler driver	pcc(1)	216
interface	apm – Advanced Power Management 1.2 BIOS .	apm(3)	674
interface	apm – Advanced Power Management 1.2 BIOS .	apm(8)	927
client-server replica/ applychanges,	applylog, compactdb, updatedb - simple	replica(8)	1039
	ar - archive and library maintainer	ar(1)	23
	ar – archive (library) file format	ar(6)	850
/fillbezier, fillbezspline, ellipse, fillellipse,	arc, fillarc, icossin, icossin2, border, string,/	draw(2)	432
	archfs - mount mkfs-style archive	archfs(4)	753
arch –		arch(3)	675
	archival file systems 32vfs, cpiofs,	tapefs(4)	814
venti –		venti(2)	650
venti –	······································	venti(6)	897
venti –		venti(8)	
	archive	archfs(4)	753
ar –		ar(1)	23
ar –		ar(6)	850
	archive on Venti	vac(1)	324
mkfs, mkext -	· · · ·	mkfs(8)	995
tar, dircp –	archiver	tar(1)	293
rdarena, wrarena – copy	arenas between venti servers		
/tobackup, dumparenas, restore - backup venti	arenas to blu-ray discs or restore from them	backup(8)	932
from argv ARGBEGIN, ARGEND,	ARGC, ARGF, EARGF – process option letters	arg(2)	373
	argument list and execute	xargs(1)	340
	arguments	echo(1)	83
procsetname – set process	arguments ARGBEGIN, ARGEND, ARGC,		580 373
ARGF, EARGF – process option letters from crtprefree, crtresfree – extended precision	arithmetic . /mpmagsub, crtpre, crtin, crtout,	arg(2) mp(2)	547
ginv, glen, slerp, gmid, gsgrt – Quaternion	arithmetic /qsub, qneg, qmul, qdiv, qunit,	quaternion(2)	588
mpc – extended precision	arithmetic code generator	mpc(1)	188
bc – arbitrary-precision	arithmetic language	bc(1)	34
combinerect, badrect, Dx, Dy, Pt, Rect, Rpt -	arithmetic on points and rectangles . /rectclip,	addpt(2)	363
	ARM emulation	5e(1)	10
	arrays as strings /enc32chr, dec16chr,	encode(2)	445
PB L /runestringbg, runestringnbg, _string,	ARROW. drawsetdebug – graphics functions	draw(2)	432
ap – fetch Associated Press news	articles	ap(1)	22
toascii, _toupper, _tolower, toupper, tolower -	ASCII character classification . /iscntrl, isascii,	ctype(2)	421
			741
xd – hex, octal, decimal. or	ASCII dump	xd(1)	341
	ASCII dump	xd(1)	
UTF, Unicode,		· · · · · · · · · · · · · · · · · · ·	341
UTF, Unicode, ascii, unicode - interpret	ASCII dump ASCII, rune - character set and format ASCII, Unicode characters	xd(1) utf(6)	341 896
UTF, Unicode,	ASCII dump ASCII, rune - character set and format ASCII, Unicode characters asctime, tm2sec, timezone - convert date and .	xd(1) utf(6) ascii(1)	341 896 24
UTF, Unicode, ascii, unicode - interpret timectime, localtime, gmtime,	ASCII dump ASCII, rune - character set and format ASCII, Unicode characters	xd(1) utf(6) ascii(1) ctime(2)	341 896 24 419
UTF, Unicode, ascii, unicode - interpret timectime, localtime, gmtime, /convM2PR, _asgetticket, _asrequest, functionssin, cos, tan, rsa2x509, rsa2csr - generate/ . rsagen, rsafill,	ASCII dump ASCII, rune - character set and format ASCII, Unicode characters asctime, tm2sec, timezone - convert date and . _asgetresp, _asrdresp, _asgetpakkey,/ asin, acos, atan, atan2 - trigonometric asn12rsa, rsa2asn1, rsa2pub, rsa2ssh,	xd(1) utf(6) ascii(1) ctime(2) authsrv(2)	341 896 24 419 382 623
UTF, Unicode, ascii, unicode - interpret timectime, localtime, gmtime, /convM2PR, _asgetticket, _asrequest, functionssin, cos, tan,	ASCII dump ASCII, rune - character set and format ASCII, Unicode characters asctime, tm2sec, timezone - convert date and . _asgetresp, _asrdresp, _asgetpakkey,/ asin, acos, atan, atan2 - trigonometric	xd(1) utf(6) ascii(1) ctime(2) authsrv(2) sin(2)	341 896 24 419 382 623
UTF, Unicode, ascii, unicode - interpret time ctime, localtime, gmtime, /convM2PR, _asgetticket, _asrequest, functions sin, cos, tan, rsa2x509, rsa2csr - generate/ . rsagen, rsafill, decodePEM,/ asn1dump, asn1toRSApriv, /convM2A, convPR2M, convM2PR, _asgetticket,	ASCII dump ASCII, rune - character set and format ASCII, Unicode characters asctime, tm2sec, timezone - convert date and _asgetresp, _asrdresp, _asgetpakkey,/ asin, acos, atan, atan2 - trigonometric asn12rsa, rsa2asn1, rsa2pub, rsa2ssh, asn1encodeRSApriv, asn1encodeRSApub, _asrequest, _asgetresp, _asrdresp,/	xd(1) utf(6) ascii(1) ctime(2) authsrv(2) sin(2) rsa(8) rsa(2) authsrv(2)	341 896 24 419 382 623 1041 601 382
UTF, Unicode, ascii, unicode - interpret time	ASCII dump ASCII, rune - character set and format ASCII, Unicode characters asctime, tm2sec, timezone - convert date and . _asgetresp, _asrdresp, _asgetpakkey,/ asin, acos, atan, atan2 - trigonometric asn12rsa, rsa2asn1, rsa2pub, rsa2ssh, asn1encodeRSApriv, asn1encodeRSApub, _asrequest, _asgetresp, _asrdresp,/ assemble a stream of bullshit from words in a	xd(1) utf(6) ascii(1) ctime(2) authsrv(2) rsa(8) rsa(2) authsrv(2) bullshit(1)	341 896 24 419 382 623 1041 601 382 40
UTF, Unicode, ascii, unicode - interpret time ctime, localtime, gmtime, /convM2PR, _asgetticket, _asrequest, functions sin, cos, tan, rsa2x509, rsa2csr - generate/ . rsagen, rsafill, decodePEM,/ asn1dump, asn1toRSApriv, /convM2A, convPR2M, convM2PR, _asgetticket, file bullshit - mix - MIX	ASCII dump ASCII, rune - character set and format ASCII, Unicode characters asctime, tm2sec, timezone - convert date and . _asgetresp, _asrdresp, _asgetpakkey,/ asin, acos, atan, atan2 - trigonometric asn12rsa, rsa2asn1, rsa2pub, rsa2ssh, asn1encodeRSApriv, asn1encodeRSApub, _asrequest, _asgetresp, _asrdresp,/ assemble a stream of bullshit from words in a assembler and emulator	xd(1) utf(6) ascii(1) ctime(2) authsrv(2) sin(2) rsa(8) rsa(2) authsrv(2)	341 896 24 419 382 623 1041 601 382 40 178
UTF, Unicode, ascii, unicode - interpret time	ASCII dump ASCII, rune - character set and format ASCII, Unicode characters asctime, tm2sec, timezone - convert date and . _asgetresp, _asrdresp, _asgetpakkey,/ asin, acos, atan, atan2 - trigonometric asn12rsa, rsa2asn1, rsa2pub, rsa2ssh, asn1encodeRSApriv, asn1encodeRSApub, _asrequest, _asgetresp, _asrdresp,/ assemble a stream of bullshit from words in a . assembler and emulator assembler for the Symbios Logic PCI-SCSI I/O	xd(1) utf(6) ascii(1) ctime(2) authsrv(2) rsa(8) rsa(2) authsrv(2) bullshit(1) mix(1) na(8)	341 896 24 419 382 623 1041 601 382 40 178 999
UTF, Unicode, ascii, unicode - interpret time ctime, localtime, gmtime, /convM2PR, _asgetticket, _asrequest, functions sin, cos, tan, rsa2x509, rsa2csr - generate/ . rsagen, rsafill, decodePEM,/ asn1dump, asn1toRSApriv, /convM2A, convPR2M, convM2PR, _asgetticket, file bullshit - mix - MIX	ASCII dump ASCII, rune - character set and format ASCII, Unicode characters asctime, tm2sec, timezone - convert date and . _asgetresp, _asrdresp, _asgetpakkey,/ asin, acos, atan, atan2 - trigonometric asn12rsa, rsa2asn1, rsa2pub, rsa2ssh, asn1encodeRSApriv, asn1encodeRSApub, _asrequest, _asgetresp, _asrdresp,/ assemble a stream of bullshit from words in a assembler and emulator assembler for the Symbios Logic PCI-SCSI I/O . assemblers	xd(1) utf(6) ascii(1) ctime(2) authsrv(2) sin(2) rsa(8) rsa(2) authsrv(2) bullshit(1) mix(1) na(8) 2a(1)	341 896 24 419 382 623 1041 601 382 40 178 999 4
UTF, Unicode, ascii, unicode - interpret time	ASCII dump ASCII, rune - character set and format ASCII, Unicode characters asctime, tm2sec, timezone - convert date and . _asgetresp, _asrdresp, _asgetpakkey,/ asin, acos, atan, atan2 - trigonometric asn12rsa, rsa2asn1, rsa2pub, rsa2ssh, asn1encodeRSApriv, asn1encodeRSApub, _asrequest, _asgetresp, _asrdresp,/ assemble a stream of bullshit from words in a assembler and emulator assembler for the Symbios Logic PCI-SCSI I/O assemblers	xd(1) utf(6) ascii(1) ctime(2) authsrv(2) sin(2) rsa(2) rsa(2) authsrv(2) bullshit(1) mix(1) na(8) 2a(1) assert(2)	341 896 24 419 382 623 1041 601 382 40 178 999 4 377
UTF, Unicode, ascii, unicode - interpret time	ASCII dump ASCII, rune - character set and format ASCII, Unicode characters asctime, tm2sec, timezone - convert date and . _asgetresp, _asrdresp, _asgetpakkey,/ asin, acos, atan, atan2 - trigonometric asn12rsa, rsa2asn1, rsa2pub, rsa2ssh, asn1encodeRSApriv, asn1encodeRSApub, _asrequest, _asgetresp, _asrdresp,/ assemble a stream of bullshit from words in a assembler and emulator assembler for the Symbios Logic PCI-SCSI I/O assemblers assert - check program invariants Associated Press news articles	xd(1) utf(6) ascii(1) ctime(2) authsrv(2) sin(2) rsa(8) rsa(2) authsrv(2) bullshit(1) mix(1) na(8) 2a(1) assert(2) ap(1)	341 896 24 419 382 623 1041 601 382 40 178 999 4 377 22
UTF, Unicode, ascii, unicode - interpret time	ASCII dump ASCII, rune - character set and format ASCII, rune - character set and format ASCII, Unicode characters asctime, tm2sec, timezone - convert date and _asgetresp, _asrdresp, _asgetpakkey,/ asin, acos, atan, atan2 - trigonometric asn12rsa, rsa2asn1, rsa2pub, rsa2ssh, asn1encodeRSApriv, asn1encodeRSApub, _asrequest, _asgetresp, _asrdresp,/ assemble a stream of bullshit from words in a assembler and emulator assembler for the Symbios Logic PCI-SCSI I/O assemblers assert - check program invariants Associated Press news articles associated with file descriptor	xd(1) utf(6) ascii(1) ctime(2) authsrv(2) sin(2) rsa(8) rsa(2) authsrv(2) bullshit(1) mix(1) na(8) 2a(1) assert(2) ap(1) fd2path(2)	341 896 24 419 382 623 1041 601 382 40 178 999 4 377 22 460
UTF, Unicode, ascii, unicode - interpret time	ASCII dump ASCII, rune - character set and format ASCII, Unicode characters asctime, tm2sec, timezone - convert date and _asgetresp, _asrdresp, _asgetpakkey,/ asin, acos, atan, atan2 - trigonometric asn12rsa, rsa2asn1, rsa2pub, rsa2ssh, asn1encodeRSApriv, asn1encodeRSApub, _asrequest, _asgetresp, _asrdresp,/ assemble a stream of bullshit from words in a assembler and emulator assembler for the Symbios Logic PCI-SCSI I/O assemblers assert - check program invariants Associated Press news articles associated with file descriptor Association (PCMCI) device i82365	xd(1) utf(6) ascii(1) ctime(2) authsrv(2) sin(2) rsa(8) rsa(2) authsrv(2) bullshit(1) mix(1) na(8) 2a(1) assert(2) ap(1) fd2path(2) i82365(3)	341 896 24 419 382 623 1041 601 382 40 178 999 4 377 22 460 697
UTF, Unicode, ascii, unicode - interpret time	ASCII dump	xd(1) utf(6) ascii(1) ctime(2) authsrv(2) sin(2) rsa(8) rsa(2) authsrv(2) bullshit(1) mix(1) na(8) 2a(1) assert(2) ap(1) fd2path(2) i82365(3) astro(7)	341 896 24 419 382 623 1041 601 382 40 178 999 4377 22 460 697 905
UTF, Unicode, ascii, unicode - interpret time	ASCII dump	xd(1) utf(6) ascii(1) ctime(2) authsrv(2) sin(2) rsa(8) rsa(2) authsrv(2) bullshit(1) mix(1) na(8) 2a(1) assert(2) i82365(3) astro(7) notify(2)	341 896 24 419 382 623 1041 601 382 40 178 999 47 22 460 697 905 558
UTF, Unicode, ascii, unicode - interpret time	ASCII dump	xd(1) utf(6) ascii(1) ctime(2) authsrv(2) sin(2) rsa(8) rsa(2) authsrv(2) bullshit(1) mix(1) na(8) 2a(1) assert(2) ap(1) fd2path(2) i82365(3) astro(7) notify(2) pump(1)	341 896 24 419 382 623 1041 601 382 40 178 999 4 377 22 460 697 905 558 231
UTF, Unicode, ascii, unicode - interpret time	ASCII dump	xd(1) utf(6) ascii(1) ctime(2) authsrv(2) sin(2) rsa(8) rsa(2) authsrv(2) bullshit(1) mix(1) na(8) 2a(1) assert(2) i82365(3) astro(7) notify(2)	341 896 24 419 382 623 1041 601 382 40 178 999 47 22 460 697 905 558

	ATA target control	atazz(8)	928 623
sin, cos, tan, asin, acos, atan,	atan2 - trigonometric functions	sin(2) aoe(3)	625
	ATA-over-Ethernet (Ao) storage device	sdaoe(3)	727
	atazz – ATA target control	atazz(8)	928
process cleanup exits, _exits, atexit,	atexitdont, terminate – terminate process,	exits(2)	454
notification notify, noted,	atnotify - handle asynchronous process	notify(2)	558
strtoll, strtoul, strtoull - convert text to/ atof,	atoi, atol, atoll, charstod, strtod, strtol,	atof(2)	378
iounit – return size of	atomic I/O unit for file descriptor	iounit(2)	518
connection	attach, auth - messages to establish a	attach(5)	834
pipefile - communication channel pushssl -	attach filter to file in name space	pipefile(1) pushssl(2)	221 582
/okCertificate, readcert, readcertchain –	attach TLS1 or SSL3 encryption to a/	pushtls(2)	583
mnt -	attach to 9P servers	mnt(3)	711
put2,/ /setmap, findseg, unusemap, loadmap,	attachproc, get1, get2, get4, get8, geta, put1,	mach(2)	529
stat, wstat - inquire or change file	attributes	stat(5)	842
	audio - audio device	audio(3)	677
Universal Serial Bus drivers	audio, disk, ether, kb, serial, ptp, usbd –	nusb(4)	797
wavdec, pcmconv, mixfs - decode and encode play - simple	audio files . /oggenc, flacdec, flacenc, sundec, audio player	audio(1) play(1)	26 222
attach,	auth – messages to establish a connection	attach(5)	834
/procsetuser, auth_proxy, fauth_proxy,	auth_allocrpc, auth_freerpc, auth_rpc,/	auth(2)	379
/amount_getkey, auth_freeAl, auth_chuid,	auth_challenge, auth_response,/	auth(2)	379
convT2M, convM2T, convTR2M, convM2TR,/	authdial, passtokey, nvcsum, readnvram,	authsrv(2)	382
factotum, fgui, userpasswd -	authentication agent	factotum(4)	770
- Digital Pathways SecureNet Key remote	authentication box securenet	securenet(8)	1051
keyfs, warning -	authentication databases files	keyfs(4)	787
login, newns, none, as - maintain or query server fauth - set up	authentication databases /debug, wrkey, authentication on a file descriptor to a file	auth(8) fauth(2)	930 456
authsrv, p9any, p9sk1, dp9ik -	authentication protocols	authsrv(6)	851
- routines for communicating with	authentication servers /authpak_finish	authsrv(2)	382
/auth_rpc, auth_getkey, amount_getkey,	auth_freeAI, auth_chuid, auth_challenge,/	auth(2)	379
/auth_chuid, auth_challenge, auth_response,	auth_freechal, auth_respond, auth_respondAl,/	auth(2)	379
/auth_proxy, fauth_proxy, auth_allocrpc,	auth_freerpc, auth_rpc, auth_getkey,/	auth(2)	379
/auth_userpasswd, auth_getuserpasswd, /auth_allocrpc, auth_freerpc, auth_rpc,	auth_getinfo - routines for authenticating/	auth(2)	379 379
for/ /auth_respondAl, auth_userpasswd,	auth_getkey, amount_getkey, auth_freeAl,/ auth_getuserpasswd, auth_getinfo - routines .	auth(2) auth(2)	379
/_asgetresp, _asrdresp, _asgetpakkey,	authpak_hash, authpak_new, authpak_finish -/	authsrv(2)	382
auth_challenge, auth_response, auth_freechal,	auth_respond, auth_respondAl,/ /auth_chuid,	auth(2)	379
/fauth_proxy, auth_allocrpc, auth_freerpc,	auth_rpc, auth_getkey, amount_getkey,/	auth(2)	379
/convkeys, printnetkey, status, enable, disable,	authsrv, guard.srv, debug, wrkey, login,/	auth(8)	930
protocols	authsrv, p9any, p9sk1, dp9ik - authentication .	authsrv(6)	851
/auth_freechal, auth_respond, auth_respondAl, IPv4 6in4, ayiya - configure and run	auth_userpasswd, auth_getuserpasswd,/automatic or manual tunnel of IPv6 through	auth(2) 6in4(8)	379 919
systems mntgen -	automatically generate mount points for file	mntgen(4)	790
mouse to a port	aux/mouse, aux/accupoint – configure a	mouse(8)	998
them kbmap - show a list of	available keyboard maps and switch between	kbmap(1)	159
aan, aanuke - always	available network	aan(8)	924
Balanced binary search/ . avlcreate, avlinsert,	avldelete, avllookup, avlnext, avlprev –	avl(2)	385
exitprocessing language	await, wait, waitpid - wait for a process to awk - pattern-directed scanning and	wait(2) awk(1)	667 29
manual tunnel of IPv6 through IPv4 6in4,		6in4(8)	919
structural regular expressions	B, sam.save, samterm – screen editor with	sam(1)	258
cdfs, cddb - optical disc (CD, DVD,	B) track reader and writer file system	cdfs(4)	755
backup, tobackup, dumparenas, restore -	backup venti arenas to blu-ray discs or/	backup(8)	932
/rectinrect, rectXrect, rectclip, combinerect,	badrect, Dx, Dy, Pt, Rect, Rpt – arithmetic on/	addpt(2)	363
/avldelete, avllookup, avlnext, avlprev – allocb, iallocb, freeb, freeblist, BLEN,	Balanced binary search tree routines BALLOC, blocklen, blockalloclen, readblist,/	avl(2) allocb(9)	385
converter using GENMIDI-type instrument	banks dmid - MIDI to OPL3	dmid(1)	76
statusbar, statusmsg – display a	bar graph or status message window	statusbar(8)	
vacfs – a		vacfs(4)	822
	basename - strip file name affixes	basename(1)	33
xalloc, xallocz, xspanalloc, xfree, xsummary -	basic memory management	xalloc(9)	
/Bprint, Bvprint, Bwrite, Bflush, Bterm,	Bbuffered, Blethal, Biofn – buffered/ bc – arbitrary–precision arithmetic language	bio(2) bc(1)	390 34
cb – C program	beautifier	cb(1)	45
uptime – show how long the system has	been running	uptime(1)	323
trace - show (real-time) process	behavior	trace(1)	313
/symoff, fpformat, beieee80ftos, beieeesftos,	beieeedftos, leieee80ftos, leieeesftos,/	debugger(2)	422
/geta, put1, put2, put4, put8, puta beswab,	beswal, beswav, leswab, leswal, leswav -/	mach(2)	529
/mprand, mpnrand, strtomp, mpfmt, mptoa,	betomp, mptobe, mptober, letomp, mptole,/ bezspline, fillbezier, fillbezspline, ellipse,/	mp(2)	547 432
/drawrepl, replclipr, line, poly, fillpoly, bezier, bfECBdecrypt – blowfish/ setupBFstate,	bfCBCencrypt, bfCBCdecrypt, bfECBencrypt,	draw(2) blowfish(2)	452 393
Bgetrune, Bgetd, Bungetc, / Bopen,	Bfdopen, Binit, Binits, Brdline, Brdstr, Bgetc,	bio(2)	390
5 , 5 , 5 <u>5 - 1</u>			

/Bungetc, Bungetrune, Bread, Bseek, Boffset,		bio(2)	390
/Bputc, Bputrune, Bprint, Bvprint, Bwrite,	Bflush, Bterm, Bbuffered, Blethal, Biofn -/	bio(2)	390
src,	Bfn – find source code for executable	src(1)	282
allocation	binalloc, bingrow, binfree - grouped memory .	bin(2)	387
strip – remove symbols from	binary files	strip(1)	287
avllookup, avlnext, avlprev - Balanced	binary search tree routines /avldelete,	avl(2)	385
	bind, mount, unmount - change name space .	bind(1)	36
alla antion binalla a	bind, mount, unmount - change name space .	bind(2)	388
allocation binalloc,	bingrow, binfree – grouped memory	bin(2)	387
Bgetd, Bungetc, Bungetrune,/ Bopen, Bfdopen, Bungetc, Bungetrune,/ Bopen, Bfdopen, Binit,	Binit, Binits, Brdline, Brdstr, Bgetc, Bgetrune, Binits, Brdline, Brdstr, Bgetc, Bgetrune, Bgetd,	bio(2)	390 390
Bwrite, Bflush, Bterm, Bbuffered, Blethal,	Biofn – buffered input/output /Bvprint,	bio(2)	390
		bio(2)	868
- keys.who apm - Advanced Power Management 1.2	biographic information for key holders BIOS interface	keys.who(6) apm(3)	674
apm – Advanced Power Management 1.2	BIOS interface	apm(8)	927
light, pencal, keyboard, params, prompter –	bitsy–specific utilities bitsyload,	bitsyload(1)	38
- torrent	bittorrent client	torrent(1)	308
glendy, juggle, life, mandel,/ 4s, 5s,	blabs, catclock, doom, festoon, geigerstats,	games(1)	109
readblist,/ allocb, iallocb, freeb, freeblist,	BLEN, BALLOC, blocklen, blockalloclen,	allocb(9)	
/Byprint, Bwrite, Bflush, Bterm, Bbuffered,	Blethal, Biofn – buffered input/output	bio(2)	390
/Bungetrune, Bread, Bseek, Boffset, Bfildes,	Blinelen, Bputc, Bputrune, Bprint, Bvprint,/	bio(2)	390
/ bungetiune, breau, bseek, bonset, bindes,	blit – Blit emulator	blit(1)	39
vtglobaltolocal, vtlocaltoglobal – Venti	block cache /vtcachelocal, vtcachesetwrite,		651
vtzeroextend. vtzeroscore – Venti	block truncation	venti-zero(2)	666
/freeb, freeblist, BLEN, BALLOC, blocklen,	blockalloclen, readblist, concatblock,/	allocb(9)	
setupDESstate, des_key_setup,	block_cipher, desCBCencrypt, desCBCdecrypt,/	des(2)	425
/inflatezlibblock, flateerr, mkcrctab,	blockcrc, adler32 – deflate compression	flate(2)	463
allocb, iallocb, freeb, freeblist, BLEN, BALLOC,	blocklen, blockalloclen, readblist,/	allocb(9)	
sum, md5sum, sha1sum - sum and count	blocks in a file	sum(1)	288
bfCBCdecrypt, bfECBencrypt, bfECBdecrypt -	blowfish encryption/bfCBCencrypt,	blowfish(2)	393
/dumparenas, restore - backup venti arenas to	blu-ray discs or restore from them	backup(8)	932
togif, toppm, topng,/ . jpg, gif, png, tif, ppm,	bmp, v210, yuv, ico, tga, tojpg, togeordi,	jpg(1)	156
galaxy - representations of	body simulations	galaxy(6)	860
galaxy, mkgalaxy – galactic	body simulator	galaxy(1)	107
/Bgetd, Bungetc, Bungetrune, Bread, Bseek,	Boffset, Bfildes, Blinelen, Bputc, Bputrune,/	bio(2)	390
tel, iwhois – look in phone	book	tel(1)	300
satsolve, satmore, satval, satreset, satfree -	boolean satisfiability (SA) solver /satrangev,	sat(2)	607
	boot, bootrc - connect to the root file server	boot(8)	933
cpurc, cpurc.local, termrc, termrc.local -	boot scripts	cpurc(8)	940
9bootfat, 9bootiso, 9boothyb, 9bootpxe,	bootia32.efi, bootx64.efi, efiboot.fat - PC/	9boot(8)	921
- PC bootloader for FAT, ISO and PXE network	booting /bootx64.efi, efiboot.fat	9boot(8)	921
dhcp6d, dhcpleases, rarpd, tftpd – Internet	booting dhcpd,	dhcpd(8)	943
init – initialize machine upon	booting	init(8)	980
/bootia32.efi, bootx64.efi, efiboot.fat - PC	booting – bootstrapping procedures	booting(8) 9boot(8)	935 921
boot,	bootloader for FAT, ISO and PXE network/ bootrc - connect to the root file server	boot(8)	933
booting –	bootstrapping procedures	booting(8)	935
/9bootiso, 9boothyb, 9bootpxe, bootia32.efi,	bootx64.efi, efiboot.fat – PC bootloader for/	9boot(8)	921
Bgetc, Bgetrune, Bgetd, Bungetc, Bungetrune,/	Bopen, Bfdopen, Binit, Binits, Brdline, Brdstr,	bio(2)	390
/ellipse, fillellipse, arc, fillarc, icossin, icossin2,	border, string, stringn, runestring,/	draw(2)	432
/publicscreen, freescreen, allocwindow,	bottomwindow, bottomnwindows, topwindow,/	window(2)	668
Pathways SecureNet Key remote authentication	box securenet – Digital	securenet(8)	
Boffset, Bfildes, Blinelen, Bputc, Bputrune,	Bprint, Bvprint, Bwrite, Bflush, Bterm, / /Bseek,	bio(2)	390
/Bread, Bseek, Boffset, Bfildes, Blinelen,	Bputc, Bputrune, Bprint, Bvprint, Bwrite,/	bio(2)	390
Bungetc,/ Bopen, Bfdopen, Binit, Binits,	Brdline, Brdstr, Bgetc, Bgetrune, Bgetd,	bio(2)	390
/Bgetc, Bgetrune, Bgetd, Bungetc, Bungetrune,	Bread, Bseek, Boffset, Bfildes, Blinelen, Bputc,/	bio(2)	390
getfields, gettokens, tokenize -	break a string into fields	getfields(2)	488
getnetconninfo, freenetconninfo - make and	break network connections /setnetmtpt,	dial(2)	427
-	bridge – IP Ethernet bridge	bridge(3)	678
	brk, sbrk - change memory allocation	brk(2)	394
processes	broke, dontkill – print commands to kill	kill(1)	160
abaco –	browse the World–Wide Web	abaco(1)	11
dict - dictionary	browser	dict(7)	906
/Bgetrune, Bgetd, Bungetc, Bungetrune, Bread,	Bseek, Boffset, Bfildes, Blinelen, Bputc,/	bio(2)	390
/Bputc, Bputrune, Bprint, Bvprint, Bwrite, Bflush,	Bterm, Bbuffered, Blethal, Biofn – buffered/	bio(2)	390
- copy asynchronously via a large circular	buffer pump	pump(1)	231
Computing (VN) vncs, vncv – remote frame	buffer server and viewer for Virtual Network	vnc(1)	331
Bflush, Bterm, Bbuffered, Blethal, Biofn –	buffered input/output /Bvprint, Bwrite,	bio(2)	390
fseek, rewind, feof, ferror, clearerr - standard	buffered input/output package /fsetpos,	fopen(2)	469
packettrailer, packettrim – zero-copy network	buffers . /packetsize, packetsplit, packetstats,		663 492
/getwindow, gengetwindow, flushimage, /lockdisplay, unlockdisplay, openfont,	bufimage, lockdisplay, unlockdisplay,/ buildfont, freefont, Pfmt, Rfmt, strtochan,/	graphics(2) graphics(2)	492 492
fmtarenas, fmtbloom, fmtindex, fmtisect,/	buildindex, checkarenas, checkindex, conf,	venti–fmt(8)	
words in a file	bullshit – assemble a stream of bullshit from	bullshit(1)	40

			41
/Brdstr, Bgetc, Bgetrune, Bgetd, Bungetc,	bundle – collect files for distribution Bungetrune, Bread, Bseek, Boffset, Bfildes,/	bundle(1) bio(2)	41 390
compress and expand/	bunzip2, compress, uncompress, zip, unzip – .	gzip(1)	121
pci – print PCI		pci(8)	
ether, kb, serial, ptp, usbd – Universal Serial	Bus drivers audio, disk,	nusb(4)	797
nusbrc – Universal Serial	Bus startup script	nusbrc(8)	
/Blinelen, Bputc, Bputrune, Bprint, Bvprint,	Bwrite, Bflush, Bterm, Bbuffered, Blethal,/	bio(2)	390
zerotrunc – truncate input on zero enc16chr, encodefmt – encoding	bytebyte arrays as strings /enc32chr, dec16chr,	zerotrunc(8) encode(2)	445
/Memdrawparam, memimageinit, wordaddr,	byte arrays as strings / encszchi, decrochi, byteaddr, memimagemove, allocmemimage,/	memdraw(2)	536
/unloadimage, readimage, writeimage,		allocimage(2)	367
	bzfs - compressed read-write ram filesystem .	bzfs(4)	754
unzip - compress and expand/ . gzip, gunzip,		gzip(1)	121
style - Plan 9 coding conventions for		style(6)	893
	C, clog – file system for console access C compiler driver	consolefs(4) pcc(1)	760 216
	C compilers	2c(1)	5
	C language preprocessor	cpp(1)	56
cb –	C program beautifier	cb(1)	45
	cache /vtcachelocal, vtcachesetwrite,		651
- CTS - Fontchar, Font - font utilities	cache file system	cfs(4) cachechars(2)	757 395
	cached-worm file server, dump cwfs,	cwfs(4)	762
	caches	segflush(2)	620
5	cal - print calendar	cal(1)	42
	calculator	dc(1)	67
	calculator	pc(1)	214
cai - princ	calendar	cal(1) calendar(1)	42 43
malloc, mallocalign, mallocz, free, realloc,		malloc(2)	532
ratrace – trace process system	calls	ratrace(1)	238
	calls on a network device /tcp17010,	listen(8)	988
trampoline – forward incoming to data/ Intmap, allocmap, freemap, insertkey,	calls to another address	trampoline(8) intmap(2)	515
/mulpt, divpt, rectaddpt, rectsubpt, inserrect,	canonrect, eqpt, egrect, ptinrect, rectinrect,	addpt(2)	363
wlock,/ lock, canlock, unlock, glock,	canglock, gunlock, rlock, canrlock, runlock,	lock(2)	526
serial synchronisation qlock, qunlock,	canqlock, rlock, runlock, wlock, wunlock	qlock(9)	
/qunlock, rlock, canrlock, runlock, wlock,	canwlock, wunlock, rsleep, rwakeup,/	lock(2)	526
processespcmcia – identify a PCMCIA	cap – capabilities for setting the user id of	cap(3) pcmcia(8)	680 1013
vga – configure a VGA	card	vga(8)	
i82365 - Personal Computer Memory	Card Interface Association (PCMCI) device	i82365(3)	697
toupperrune - Unicode character classes and	cases /isdigitrune, tolowerrune, totitlerune,	•	522
cost clus	cat, read – catenate files	cat(1)	44
	catalogue and Digitized Sky Survey	scat(7) games(1)	915 109
	catenate files	cat(1)	44
	cb – C program beautifier	cb(1)	45
/chacha_encrypt, chacha_encrypt2, hchacha,	ccpoly_encrypt, ccpoly_decrypt - chacha/	chacha(2)	398
system cdfs, cddb – optical disc		cdfs(4)	755
whatis, ., ~ - command language rc,	CD image	rc(1) mk9660(8)	239 992
reader and writer file system	cdfs, cddb – optical disc (CD, DVD, B) track	cdfs(4)	755
·	cec - Coraid Ethernet Console	cec(8)	937
functions fabs, fmod, floor,		floor(2)	465
/chacha sathlack chacha sativ	cfs – cache file system chacha_encrypt2, hchacha,/ .	cfs(4)	757 398
/chacha_setblock, chacha_setiv, alt, chanclose, chancreate, chanfree,		chacha(2) thread(2)	638
	change file attributes	stat(5)	842
	change file group	chgrp(1)	46
	change file offset	seek(2)	616
	change memory allocation	brk(2) segbrk(2)	394 619
	change mode	chmod(1)	47
	change name space	bind(1)	36
	change name space	bind(2)	388
	change or verify user password	passwd(1)	211 399
replica management	change working directorychanges, pull, push, scan – client-server	chdir(2) replica(1)	246
enable, disable, authsrv, guard.srv, debug,/		auth(8)	930
pipe – create an interprocess	channel	pipe(2)	568
	channel pushssl – attach	pushssl(2)	582
	channel /readcert, readcertchain – attach chanprint, mainstacksize, proccreate,/ alt,	pushtls(2) thread(2)	583 638
chanciose, chancicate, channee, chanciosing,	championi, manistacksize, procereate,/ all,	(incau(2)	000

/buildfont, freefont, Pfmt, Rfmt, strtochan,	chantostr, chantodepth - interactive graphics .	graphics(2)	492
totitlerune, toupperrune – Unicode	character classes and cases /tolowerrune,	isalpharune(2)	522
	character classification /isascii, toascii,	ctype(2)	421
	character frequencies	freq(1)	105
scribblealloc, recognize –		scribble(2)	610
		• •	
UTF, Unicode, ASCII, rune –	character set and format	utf(6)	896
uhtml – convert foreign		uhtml(1)	320
	character sets	tcs(1)	297
doquote, needsrcquote – quoted	character strings /quotefmtinstall,	quote(2)	590
ascii, unicode - interpret ASCII, Unicode		ascii(1)	24
	characters	keyboard(6)	866
tr – translate		tr(1)	312
- convert text to/ atof, atoi, atol, atol,	charstod, strtod, strtol, strtoll, strtoul, strtoull	atof(2)	378
utfecpy, utflen, utfnlen, utfrune,/ runetochar,	chartorune, runelen, runenlen, fullrune,	rune(2)	603
ircrc – internet relay	chat client	ircrc(1)	153
estrdup9p, listensrv, postmountsrv,/ Srv,		9p(2)	349
	chdir – change working directory	chdir(2)	399
assert –	check program invariants	assert(2)	377
fmtbloom, fmtindex, fmtisect,/ buildindex,	checkarenas, checkindex, conf, fmtarenas,	venti-fmt(8)	1076
/padblock, pullblock, pullupblock, adjustblock,	checkb – data block management	allocb(9)	
		• •	
netaudit – network configuration	checker	netaudit(8)	
fmtindex, fmtisect,/ buildindex, checkarenas,	checkindex, conf, fmtarenas, fmtbloom,	venti–fmt(8)	
vtmallocz, vtrealloc, vtstrdup, vtfree –	checking memory allocators . vtbrk, vtmalloc,	venti–mem(2)	662
	chgrp – change file group	chgrp(1)	46
times, cycles - cpu time in this process and	children	cputime(2)	418
opl3 – OPL3	chip emulator	opl3(1)	205
op.o 0120	chmod – change mode	chmod(1)	47
client	cifs – Microsoft™ Windows network filesystem	cifs(4)	758
	cifsd – CIFS/SMB network daemon	cifsd(8)	938
$a_{\rm res}$ is the effects (TMC) and interview to d		• • •	
serial interface (TWS) and inter-integrated	circuit (I ² C) interface twsi – two-wire	twsi(3)	739
pump - copy asynchronously via a large	circular buffer	pump(1)	231
localaddr, symoff, fpformat, beieee80ftos,/	cisctrace, risctrace, ciscframe, riscframe,	debugger(2)	422
strlen,/ strcat, strncat, strcmp, strncmp,	cistrcmp, cistrncmp, strcpy, strncpy, strecpy,	strcat(2)	628
strcat, strncat, strcmp, strncmp, cistrcmp,	cistrncmp, strcpy, strncpy, strecpy, strlen,/	strcat(2)	628
strpbrk, strspn, strcspn, strtok, strdup, strstr,	cistrstr – string operations /strchr, strrchr,	strcat(2)	628
totitlerune, toupperrune – Unicode character	classes and cases . /isdigitrune, tolowerrune,		522
_tolower, toupper, tolower – ASCII character	classification /isascii, toascii, _toupper,	ctype(2)	421
	classification /isascii, toascii, _toupper,		
	classnama classiday configiday dayst		
getdev, loaddevstr, opendev,/ usbcmd,	classname, closedev, configdev, devctl,	nusb(2)	560
	cleanname - clean a path name	nusb(2) cleanname(1)	560 48
getdev, loaddevstr, opendev,/ usbcmd,	cleanname - clean a path name cleanname - clean a path name	nusb(2) cleanname(1) cleanname(2)	560 48 400
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process	cleanname - clean a path name cleanname - clean a path name cleanup exits, _exits, atexit, atexitdont,	nusb(2) cleanname(1) cleanname(2) exits(2)	560 48 400 454
getdev, loaddevstr, opendev,/ usbcmd,	cleanname - clean a path name cleanname - clean a path name	nusb(2) cleanname(1) cleanname(2)	560 48 400
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process	cleanname - clean a path name cleanname - clean a path name cleanup exits, _exits, atexit, atexitdont,	nusb(2) cleanname(1) cleanname(2) exits(2)	560 48 400 454
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror,	cleanname - clean a path name cleanname - clean a path name cleanup exits, _exits, atexit, atexitdont, clearerr - standard buffered input/output/ client	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2)	560 48 400 454 469
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft™ Windows network filesystem ircrc – internet relay chat	cleanname - clean a path name cleanname - clean a path name cleanup exits, _exits, atexit, atexitdont, clearerr - standard buffered input/output/ client client	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1)	560 48 400 454 469 758 153
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft™ Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT)	cleanname - clean a path name cleanname - clean a path name cleanup exits, _exits, atexit, atexitdont, clearerr - standard buffered input/output/ client client	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1)	560 48 400 454 469 758 153 198
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft™ Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system	cleanname - clean a path name cleanname - clean a path name cleanup exits, _exits, atexit, atexitdont, clearerr - standard buffered input/output/ client client client	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4)	560 48 400 454 469 758 153 198 794
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft™ Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login	cleanname - clean a path name	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) ssh(1)	560 48 400 454 469 758 153 198 794 284
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft™ Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol	cleanname - clean a path name	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) ssh(1) sshfs(4)	560 48 400 454 469 758 153 198 794 284 812
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft™ Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol sshnet – secure file transfer protocol	cleanname - clean a path name	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) ssh(1) sshfs(4) sshnet(4)	560 48 400 454 469 758 153 198 794 284 812 813
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft™ Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and	cleanname - clean a path name	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) ssh(1) sshfs(4) sshnet(4) tlssrv(8)	560 48 400 454 469 758 153 198 794 284 812 813 1066
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft™ Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and torrent – bittorrent	cleanname - clean a path name	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) sshfs(4) sshfs(4) tlssrv(8) torrent(1)	560 48 400 454 469 758 153 198 284 812 813 1066 308
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft™ Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and torrent – bittorrent vtping, vtrpc, ventidoublecheckshal – Venti	cleanname - clean a path name	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) sshfs(4) sshfs(4) tlssrv(8) torrent(1) venti-client(2)	560 48 400 454 469 758 153 198 794 284 812 813 1066 308 653
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft™ Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and torrent – bittorrent	cleanname - clean a path name	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) sshfs(4) sshfs(4) tlssrv(8) torrent(1)	560 48 400 454 469 758 153 198 284 812 813 1066 308
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft™ Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and torrent – bittorrent vtping, vtrpc, ventidoublecheckshal – Venti	cleanname - clean a path name	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) sshfs(4) sshfs(4) tlssrv(8) torrent(1) venti-client(2)	560 48 400 454 469 758 153 198 794 284 812 813 1066 308 653
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft [™] Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and torrent – bittorrent vtping, vtrpc, ventidoublechecksha1 – Venti read, write, copy – simple Venti changes, pull, push, scan –	cleanname - clean a path name	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) sshfs(4) sshfs(4) sshfs(4) tlssrv(8) torrent(1) venti-client(2) venti(1) replica(1)	560 48 400 454 469 758 153 198 794 284 812 813 1066 308 653 326 246
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft™ Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and torrent – bittorrent vtping, vtrpc, ventidoublechecksha1 – Venti read, write, copy – simple Venti changes, pull, push, scan – /applylog, compactdb, updatedb – simple	cleanname - clean a path name	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) sshfs(4) sshfs(4) sshfs(4) tlssrv(8) torrent(1) venti-client(2) venti(1) replica(1) replica(8)	560 48 400 454 469 758 153 198 794 284 813 1066 308 653 326 246 1039
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft™ Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and torrent – bittorrent vtping, vtrpc, ventidoublechecksha1 – Venti read, write, copy – simple Venti changes, pull, push, scan – /applylog, compactdb, updatedb – simple /namedimage, setalpha, loadimage,	cleanname - clean a path name	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) sshfs(4) sshfs(4) sshfs(4) tlssrv(8) torrent(1) venti-client(2) venti(1) replica(1) replica(8) allocimage(2)	560 48 400 454 469 758 153 198 794 284 812 813 1066 308 653 326 246 1039 367
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft™ Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and torrent – bittorrent vtping, vtrpc, ventidoublechecksha1 – Venti read, write, copy – simple Venti changes, pull, push, scan – /applylog, compactdb, updatedb – simple /namedimage, setalpha, loadimage, /freememimage, memsetchan, loadmemimage,	cleanname - clean a path name cleanname - clean a path name cleanup exits, _exits, atexit, atexitdont, clearerr - standard buffered input/output/ client	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) sshfs(4) sshfs(4) sshnet(4) tlssrv(8) torrent(1) venti-client(2) venti(1) replica(1) replica(8) allocimage(2) memdraw(2)	560 48 400 454 469 758 153 198 794 284 813 1066 308 653 326 246 1039 367 536
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft [™] Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and torrent – bittorrent vtping, vtrpc, ventidoublecheckshal – Venti changes, pull, push, scan – /applylog, compactdb, updatedb – simple /namedimage, setalpha, loadimage, /freememimage, memsetchan, loadmemimage, date,	cleanname - clean a path name	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) ssh(1) sshfs(4) sshnet(4) tlssrv(8) torrent(1) venti-client(2) venti(1) replica(1) replica(2) memdraw(2) date(1)	560 48 400 454 469 758 153 198 794 284 813 1066 308 653 326 246 1039 367 536 60
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft™ Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and torrent – bittorrent vtping, vtrpc, ventidoublecheckshal – Venti read, write, copy – simple Venti changes, pull, push, scan – /applylog, compactdb, updatedb – simple /namedimage, setalpha, loadimage, /freememimage, memsetchan, loadmemimage, date, rtc – real–time	cleanname - clean a path name cleanname - clean a path name cleanup exits, _exits, atexit, atexitdont, clearerr - standard buffered input/output/ client	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) sshfs(4) sshfs(4) sshfs(4) torrent(1) venti-client(2) venti(1) replica(1) replica(8) allocimage(2) memdraw(2) date(1) rtc(3)	560 48 400 454 469 758 153 198 794 284 813 1066 308 653 326 246 1039 367 536 60 722
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft™ Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and torrent – bittorrent vtping, vtrpc, ventidoublechecksha1 – Venti read, write, copy – simple Venti changes, pull, push, scan – /applylog, compactdb, updatedb – simple /namedimage, setalpha, loadimage, date, rtc – real-time cron –	cleanname - clean a path name cleanname - clean a path name cleanup exits, _exits, atexit, atexitdont, clearerr - standard buffered input/output/ client	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) sshfs(4) sshfs(4) sshfs(4) sshfs(4) sshfs(4) tlssrv(8) torrent(1) venti-client(2) venti(1) replica(1) replica(8) allocimage(2) memdraw(2) date(1) rtc(3) cron(8)	560 48 400 454 469 758 153 198 794 284 812 813 1066 308 653 326 246 1039 367 536 60 722 941
getdev, loaddevstr, opendev,/ usbcmd, terminate - terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs - Microsoft [™] Windows network filesystem ircrc - internet relay chat newt - network news transport protocol (NNT) nfs - Sun network file system ssh - secure shell remote login sshfs - secure file transfer protocol tlssrvtunnel, tlsclienttunnel - TLS server and torrent - bittorrent vtping, vtrpc, ventidoublechecksha1 - Venti read, write, copy - simple Venti changes, pull, push, scan - /applylog, compactdb, updatedb - simple /namedimage, setalpha, loadimage, /freememimage, memsetchan, loadmemimage, date, rtc - real-time cron - microdelay, addclock0link - small delays,	cleanname - clean a path name cleanname - clean a path name cleanup exits, _exits, atexit, atexitdont, clearer - standard buffered input/output/ client cloadimage, unloadim	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) sshfs(4) sshfs(4) sshfs(4) sshfs(4) sshfs(4) tlssrv(8) torrent(1) venti-client(2) venti(1) replica(1) replica(8) allocimage(2) memdraw(2) date(1) rtc(3) cron(8) delay(9)	560 48 400 454 469 758 153 198 794 284 812 813 1066 308 653 326 246 1039 367 536 60 722 941 1088
getdev, loaddevstr, opendev,/ usbcmd, terminate - terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs - Microsoft [™] Windows network filesystem ircrc - internet relay chat newt - network news transport protocol (NNT) nfs - Sun network file system ssh - secure shell remote login sshfs - secure file transfer protocol tlssrvtunnel, tlsclienttunnel - TLS server and torrent - bittorrent vtping, vtrpc, ventidoublechecksha1 - Venti read, write, copy - simple Venti changes, pull, push, scan - /applylog, compactdb, updatedb - simple /namedimage, setalpha, loadimage, /freememimage, memsetchan, loadmemimage, ttc - real-time cron - microdelay, addclock0link - small delays, timesync - synchronize the system	cleanname - clean a path name cleanname - clean a path name cleanup exits, _exits, atexit, atexitdont, clearerr - standard buffered input/output/ client cloadimage, unloadimage, readimage,/	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) sshfs(4) sshfs(4) sshfs(4) sshfs(4) torrent(1) venti-client(2) venti(1) replica(1) replica(8) allocimage(2) memdraw(2) date(1) rtc(3) cron(8) delay(9) timesync(8)	560 48 400 454 469 758 153 198 794 284 813 1068 653 326 246 1039 367 536 60 722 941 1088 1064
getdev, loaddevstr, opendev,/ usbcmd, terminate - terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs - Microsoft [™] Windows network filesystem ircrc - internet relay chat newt - network news transport protocol (NNT) nfs - Sun network file system ssh - secure shell remote login sshfs - secure file transfer protocol tlssrvtunnel, tlsclienttunnel - TLS server and torrent - bittorrent vtping, vtrpc, ventidoublechecksha1 - Venti read, write, copy - simple Venti changes, pull, push, scan - /applylog, compactdb, updatedb - simple /namedimage, setalpha, loadimage, /freememimage, memsetchan, loadmemimage, date, rtc - real-time cron - microdelay, addclock0link - small delays,	cleanname - clean a path name cleanname - clean a path name cleanup exits, _exits, atexit, atexitdont, clearerr - standard buffered input/output/ client cloadimage, unloadimage, readimage,/	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) sshfs(4) sshnet(4) tlssrv(8) torrent(1) venti-client(2) venti(1) replica(1) replica(1) replica(2) memdraw(2) date(1) rtc(3) cron(8) delay(9) timesync(8) cons(3)	560 48 400 454 469 758 153 198 794 284 812 813 1066 308 653 326 246 1039 367 536 60 722 941 1088
getdev, loaddevstr, opendev,/ usbcmd, terminate - terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs - Microsoft [™] Windows network filesystem ircrc - internet relay chat newt - network news transport protocol (NNT) nfs - Sun network file system ssh - secure shell remote login sshfs - secure file transfer protocol tlssrvtunnel, tlsclienttunnel - TLS server and torrent - bittorrent vtping, vtrpc, ventidoublechecksha1 - Venti read, write, copy - simple Venti changes, pull, push, scan - /applylog, compactdb, updatedb - simple /namedimage, setalpha, loadimage, /freememimage, memsetchan, loadmemimage, ttc - real-time cron - microdelay, addclock0link - small delays, timesync - synchronize the system	cleanname - clean a path name cleanname - clean a path name cleanup exits, _exits, atexit, atexitdont, clearerr - standard buffered input/output/ client cloadimage, unloadimage, readimage,/	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) sshfs(4) sshfs(4) sshfs(4) sshfs(4) torrent(1) venti-client(2) venti(1) replica(1) replica(8) allocimage(2) memdraw(2) date(1) rtc(3) cron(8) delay(9) timesync(8)	560 48 400 454 469 758 153 198 794 284 813 1068 653 326 246 1039 367 536 60 722 941 1088 1064
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft [™] Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and torrent – bittorrent vtping, vtrpc, ventidoublecheckshal – Venti read, write, copy – simple Venti changes, pull, push, scan – /applylog, compactdb, updatedb – simple /namedimage, setalpha, loadimage, /freememimage, memsetchan, loadmemimage, cron – microdelay, addclock0link – small delays, timesync – synchronize the system	cleanname - clean a path name cleanname - clean a path name cleanup exits, _exits, atexit, atexitdont, clearerr - standard buffered input/output/ client cloadimage, unloadimage, readimage,/	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) sshfs(4) sshnet(4) tlssrv(8) torrent(1) venti-client(2) venti(1) replica(1) replica(1) replica(2) memdraw(2) date(1) rtc(3) cron(8) delay(9) timesync(8) cons(3)	560 48 400 454 469 758 153 198 794 284 813 1066 308 653 326 246 1039 367 536 60 722 941 1088 1064 683
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft™ Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and torrent – bittorrent vtping, vtrpc, ventidoublechecksha1 – Venti changes, pull, push, scan – /applylog, compactdb, updatedb – simple /namedimage, setalpha, loadimage, /freememimage, memsetchan, loadmemimage, date, rtc – real-time cron – microdelay, addclock0link – small delays, timesync – synchronize the system reboot, etc	cleanname - clean a path name cleanname - clean a path name cleanup exits, _exits, atexit, atexitdont, clearerr - standard buffered input/output/ client cloadimage, unloadimage, readimage,/	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) sshfs(4) sshnet(4) tlssrv(8) torrent(1) venti-client(2) venti(1) replica(1) replica(1) replica(2) memdraw(2) date(1) rtc(3) cron(8) delay(9) timesync(8) cons(3) consolefs(4) open(2)	560 48 400 454 469 758 153 198 794 284 813 1066 308 653 326 246 1039 367 536 60 722 941 1088 1064 683 760
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft [™] Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and torrent – bittorrent vtping, vtrpc, ventidoublecheckshal – Venti read, write, copy – simple Venti changes, pull, push, scan – /applylog, compactdb, updatedb – simple /namedimage, setalpha, loadimage, /freememimage, memsetchan, loadmemimage, date, rtc – real-time cron – microdelay, addclock0link – small delays, timesync – synchronize the system reboot, etc	cleanname - clean a path name cleanname - clean a path name cleanup exits, _exits, atexit, atexitdont, clearerr - standard buffered input/output/ client cloadimage, unloadimage, readimage,/ cloadmemimage, unloadmemimage,/	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) sshfs(4) sshnet(4) tlssrv(8) torrent(1) venti-client(2) venti(1) replica(1) replica(1) replica(2) memdraw(2) date(1) rtc(3) cron(8) delay(9) timesync(8) consolefs(4) open(2) control(2)	$\begin{array}{c} 560\\ 48\\ 400\\ 454\\ 469\\ 758\\ 153\\ 198\\ 794\\ 284\\ 812\\ 813\\ 1066\\ 308\\ 653\\ 326\\ 246\\ 1039\\ 367\\ 536\\ 60\\ 722\\ 941\\ 1088\\ 1064\\ 683\\ 760\\ 566\\ 403\\ \end{array}$
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft [™] Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and torrent – bittorrent vtping, vtrpc, ventidoublecheckshal – Venti read, write, copy – simple Venti changes, pull, push, scan – /applylog, compactdb, updatedb – simple /namedimage, setalpha, loadimage, /freememimage, memsetchan, loadmemimage, date, rtc – real-time cron – microdelay, addclock0link – small delays, timesync – synchronize the system reboot, etc	cleanname - clean a path name cleanname - clean a path name cleanup exits, _exits, atexit, atexitdont, clearerr - standard buffered input/output/ client cloadimage, unloadimage, readimage,/ clock and non-volatile RAM	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) sshns(4) sshns(4) sshnst(4) tlssrv(8) torrent(1) venti-client(2) venti(1) replica(1) replica(1) replica(2) memdraw(2) date(1) rtc(3) cron(8) delay(9) timesync(8) cons(3) consolefs(4) open(2) control(2) nusb(2)	$\begin{array}{c} 560\\ 48\\ 400\\ 454\\ 469\\ 758\\ 198\\ 794\\ 284\\ 812\\ 813\\ 1066\\ 308\\ 653\\ 326\\ 246\\ 1039\\ 367\\ 536\\ 60\\ 722\\ 941\\ 1088\\ 1064\\ 683\\ 7666\\ 403\\ 560\\ \end{array}$
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft [™] Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and torrent – bittorrent vtping, vtrpc, ventidoublecheckshal – Venti read, write, copy – simple Venti changes, pull, push, scan – /applylog, compactdb, updatedb – simple /namedimage, setalpha, loadimage, /freememimage, memsetchan, loadememimage, date, rtc – real-time cron – microdelay, addclock0link – small delays, timesync – synchronize the system reboot, etc	cleanname - clean a path name cleanname - clean a path name cleanup exits, _exits, atexit, atexitdont, clearer - standard buffered input/output/ client cloadmage, unloadmeg	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) sshnf(4) sshnf(4) sshnf(4) sshnf(4) sshnf(4) tlssrv(8) torrent(1) venti-client(2) venti(1) replica(1) replica(1) replica(2) allocimage(2) memdraw(2) date(1) rtc(3) cron(8) delay(9) timesync(8) cons(3) consolefs(4) open(2) control(2) nusb(2) 9pfile(2)	560 48 400 454 469 758 198 794 284 812 813 1066 308 653 326 246 1039 367 536 60 722 941 1088 1064 683 760 566 403 560 357
getdev, loaddevstr, opendev,/ usbcmd, terminate - terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs - Microsoft [™] Windows network filesystem ircrc - internet relay chat newt - network news transport protocol (NNT) nfs - Sun network file system ssh - secure shell remote login sshfs - secure file transfer protocol tlssrvtunnel, tlsclienttunnel - TLS server and torrent - bittorrent vtping, vtrpc, ventidoublechecksha1 - Venti read, write, copy - simple Venti changes, pull, push, scan - /applylog, compactdb, updatedb - simple /namedimage, setalpha, loadimage, /freememimage, memsetchan, loadmemimage, date, ttc - real-time cron - microdelay, addclock0link - small delays, timesync - synchronize the system reboot, etc	cleanname - clean a path name cleanname - clean a path name cleanup exits, _exits, atexit, atexitdont, clearer - standard buffered input/output/ client	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) ssh1(4) ssh1(4) ssh1(4) ssh1(4) ssh1(4) tlssrv(8) torrent(1) venti-client(2) venti(1) replica(1) replica(1) replica(2) allocimage(2) memdraw(2) date(1) rtc(3) cron(8) delay(9) timesync(8) consolefs(4) open(2) control(2) nusb(2) 9pfile(2) graphics(2)	$\begin{array}{c} 560\\ 48\\ 400\\ 454\\ 469\\ 758\\ 153\\ 198\\ 794\\ 284\\ 812\\ 813\\ 1066\\ 308\\ 653\\ 326\\ 246\\ 1039\\ 367\\ 536\\ 603\\ 367\\ 536\\ 603\\ 566\\ 403\\ 560\\ 357\\ 492 \end{array}$
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft™ Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol sshnet – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and torrent – bittorrent vtping, vtrpc, ventidoublechecksha1 – Venti read, write, copy – simple Venti changes, pull, push, scan – /applylog, compactdb, updatedb – simple /namedimage, setalpha, loadimage, /freememimage, memsetchan, loadmemimage, uter – real-time cron – microdelay, addclock0link – small delays, timesync – synchronize the system reboot, etc	cleanname - clean a path name cleanup exits, _exits, atexit, atexitdont, clearer - standard buffered input/output/ client cloadmage, unloadimage, readimage,/ cloadmemimage, unloadmemimage,/ cloadmemimage, unloadmemimage,/	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) ssh(4) ssh(4) ssh(4) sshret(4) tlssrv(8) torrent(1) venti-client(2) venti(1) replica(1) replica(2) wenti(1) replica(2) date(1) rtc(3) cron(8) delay(9) timesync(8) consolefs(4) open(2) control(2) nusb(2) 9pfile(2)	$\begin{array}{c} 560\\ 48\\ 400\\ 454\\ 469\\ 758\\ 153\\ 198\\ 794\\ 284\\ 812\\ 813\\ 1066\\ 308\\ 653\\ 326\\ 246\\ 1039\\ 367\\ 536\\ 603\\ 722\\ 941\\ 1088\\ 1064\\ 683\\ 760\\ 566\\ 403\\ 560\\ 357\\ 492\\ 355\\ \end{array}$
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft [™] Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and torrent – bittorrent vtping, vtrpc, ventidoublecheckshal – Venti read, write, copy – simple Venti changes, pull, push, scan – /applylog, compactdb, updatedb – simple /namedimage, setalpha, loadimage, /freememimage, memsetchan, loadmemimage, date, rtc – real-time cron – microdelay, addclock0link – small delays, timesync – synchronize the system reboot, etc	cleanname - clean a path name	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) ssh1(4) ssh1(4) sshs(4) sshnet(4) tlssrv(8) torrent(1) venti(1) replica(1) replica(1) replica(2) allocimage(2) memdraw(2) date(1) rtc(3) cron(8) delay(9) timesync(8) consolefs(4) open(2) control(2) nusb(2) 9pfile(2) 9pfile(2)	$\begin{array}{c} 560\\ 48\\ 400\\ 454\\ 469\\ 758\\ 153\\ 198\\ 794\\ 284\\ 812\\ 813\\ 1066\\ 308\\ 653\\ 326\\ 246\\ 1039\\ 367\\ 536\\ 602\\ 722\\ 367\\ 536\\ 602\\ 722\\ 403\\ 566\\ 403\\ 566\\ 403\\ 566\\ 403\\ 565\\ 357\\ 492\\ 355\\ 357\\ \end{array}$
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft [™] Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and torrent – bittorrent vtping, vtrpc, ventidoublechecksha1 – Venti read, write, copy – simple Venti changes, pull, push, scan – /applylog, compactdb, updatedb – simple /namedimage, setalpha, loadimage, /freememimage, memsetchan, loadmemimage, date, rtc – real-time cron – microdelay, addclockOlink – small delays, timesync – synchronize the system reboot, etc	cleanname - clean a path name	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) sshfs(4) sshnet(4) tlssrv(8) torrent(1) venti-client(2) venti(1) replica(1) replica(1) replica(2) memdraw(2) date(1) rtc(3) cron(8) delay(9) timesync(8) conscolefs(4) open(2) control(2) nusb(2) 9pfile(2) graphics(2) 9pfile(2) ioproc(2)	$\begin{array}{c} 560\\ 48\\ 400\\ 454\\ 469\\ 758\\ 153\\ 198\\ 794\\ 284\\ 812\\ 813\\ 1066\\ 308\\ 653\\ 326\\ 246\\ 1039\\ 367\\ 536\\ 60\\ 722\\ 941\\ 1088\\ 1064\\ 683\\ 760\\ 566\\ 403\\ 566\\ 403\\ 566\\ 403\\ 557\\ 516\end{array}$
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft [™] Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and torrent – bittorrent vtping, vtrpc, ventidoublecheckshal – Venti read, write, copy – simple Venti changes, pull, push, scan – /applylog, compactdb, updatedb – simple /namedimage, setalpha, loadimage, /freememimage, memsetchan, loadmemimage, date, rtc – real-time cron – microdelay, addclock0link – small delays, timesync – synchronize the system reboot, etc	cleanname - clean a path name	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) nfs(4) ssh1(4) ssh1(4) sshs(4) sshnet(4) tlssrv(8) torrent(1) venti(1) replica(1) replica(1) replica(2) allocimage(2) memdraw(2) date(1) rtc(3) cron(8) delay(9) timesync(8) consolefs(4) open(2) control(2) nusb(2) 9pfile(2) 9pfile(2)	$\begin{array}{c} 560\\ 48\\ 400\\ 454\\ 469\\ 758\\ 153\\ 198\\ 794\\ 284\\ 812\\ 813\\ 1066\\ 308\\ 653\\ 326\\ 246\\ 1039\\ 367\\ 536\\ 60\\ 722\\ 941\\ 1088\\ 1064\\ 683\\ 760\\ 566\\ 403\\ 560\\ 357\\ 492\\ 355\\ 357\\ 516\\ 525\\ \end{array}$
getdev, loaddevstr, opendev,/ usbcmd, terminate – terminate process, process /ftell, fsetpos, fseek, rewind, feof, ferror, cifs – Microsoft [™] Windows network filesystem ircrc – internet relay chat newt – network news transport protocol (NNT) nfs – Sun network file system ssh – secure shell remote login sshfs – secure file transfer protocol tlssrvtunnel, tlsclienttunnel – TLS server and torrent – bittorrent vtping, vtrpc, ventidoublecheckshal – Venti read, write, copy – simple Venti changes, pull, push, scan – /applylog, compactdb, updatedb – simple /namedimage, setalpha, loadimage, /freememimage, memsetchan, loadmemimage, date, rtc – real-time cron – microdelay, addclockOlink – small delays, timesync – synchronize the system reboot, etc	cleanname - clean a path name	nusb(2) cleanname(1) cleanname(2) exits(2) fopen(2) cifs(4) ircrc(1) newt(1) sshfs(4) sshnet(4) tlssrv(8) torrent(1) venti-client(2) venti(1) replica(1) replica(1) replica(2) memdraw(2) date(1) rtc(3) cron(8) delay(9) timesync(8) conscolefs(4) open(2) control(2) nusb(2) 9pfile(2) graphics(2) 9pfile(2) ioproc(2)	$\begin{array}{c} 560\\ 48\\ 400\\ 454\\ 469\\ 758\\ 153\\ 198\\ 794\\ 284\\ 812\\ 813\\ 1066\\ 308\\ 653\\ 326\\ 246\\ 1039\\ 367\\ 536\\ 60\\ 722\\ 941\\ 1088\\ 1064\\ 683\\ 760\\ 566\\ 403\\ 566\\ 403\\ 566\\ 403\\ 557\\ 516\end{array}$

	closept3, dot3, cross3, len3, dist3, unit3,/	arith3(2)	375
/Reqpool, allocreqpool, freereqpool, allocreq,		9pfid(2)	355
SCSI device operations openscsi,		scsi(2)	612
	clunk – forget about a fid	clunk(5)	835
maps		color(2)	401
commands	cmd – interface to host operating system	cmd(3)	681
lookupcmd – control message parsing	Cmdbuf, parsecmd, respondcmderror,	9pcmdbuf(2)	354
commands parsecmd,		parsecmd(9)	1098
	cmp - compare two files	cmp(1)	49
	code	qr(1)	237
	code for executable	src(1)	282
	code generator	mpc(1)	188
hg – Mercurial source		hg(1)	123
style – Plan 9		style(6)	893
	col – column alignment	col(1)	50
bundle –	collect files for distribution	bundle(1)	41
	color - representation of pixels and colors	color(6)	856
	color map	colors(1)	51
RGB, readcolmap, writecolmap - access display			595
	color maps	color(2)	401
color - representation of pixels and		color(6)	856
	colors - display color map	colors(1)	51
	colors and color maps	color(2)	401
	column alignment	col(1)	50
	combinerect, badrect, Dx, Dy, Pt, Rect, Rpt -/	addpt(2)	363
sorted files	comm – select or reject lines common to two	comm(1)	52
	command	time(1)	304
	command language rc, cd, eval,	rc(1)	239
	command line for formatting a document	doctype(1)	78
	command under lock	lock(1)	166
	command-line parsing for shell scripts	getflags(8)	957
	commands	cmd(3)	681
	commands parsecmd, commands	parsecmd(9)	265
	commands	secstore(1) secstore(8)	
	commands (drawterm only)		206
	commands to kill processes	os(1) kill(1)	160
	commands to stop and start processes	stop(1)	285
	common to two sorted files	comm(1)	52
	communicating with authentication servers	authsrv(2)	382
	communication	pipe(3)	714
	communication channel	pushssl(2)	582
	communication channel /readcertchain	pushtls(2)	583
	communication control	uart(3)	740
replica management . applychanges, applylog,		replica(8)	
	comparator	diff(1)	74
	compare	derp(1)	73
cmp –	compare two files	cmp(1)	49
	compiler driver	pcc(1)	216
yacc - yet another	compiler-compiler	yacc(1)	342
0c, 1c, 2c, 5c, 6c, 7c, 8c, kc, qc, vc - C	compilers	2c(1)	5
	complete - file name completion	complete(2)	402
	compress, uncompress, zip, unzip	gzip(1)	121
	compressed file system	mksacfs(8)	997
	compressed file system	sacfs(4)	809
	compressed read-only file system	mkpaqfs(8)	996
	compressed read-only file system	paqfs(4)	800
	compressed read-write ram filesystem	bzfs(4)	754
	compression /inflateblock, inflatezlibblock,	flate(2)	463
(PCMCI) device 182365 – Personal	Computer Memory Card Interface Association .	i82365(3)	697
	Computing (VN) vncs, vncv – remote frame	vnc(1)	331
login, execution, and XMODEM file transfer		con(1) allocb(9)	53
	concatblock, copyblock, trimblock, packblock,/ concurrent systems		278
buildindex, checkarenas, checkindex,		spin(1) venti–fmt(8)	
opendev,/ usbcmd, classname, closedev,		nusb(2)	560
	configuration	icanhasmsi(8)	979
	configuration	pci(8)	
	configuration	smtpd(6)	890
	Configuration and Power Interface	acpi(8)	925
	configuration and routing	ipconfig(8)	981
	configuration checker	netaudit(8)	
	configuration file	venti.conf(6)	900
	configuration file for PCs	plan9.ini(8)	
-			

harc	configuration files for Mercurial	hgrc(8)	963
	configure a mouse to a port	mouse(8)	903
	configure a VGA card	vga(8)	
tunnel of IPv6 through IPv4 6in4, ayiya -	configure and run automatic or manual	6in4(8)	919
	configuring a file server	fsconfig(8)	952
	connect to the root file server	boot(8)	933
	connection	attach(5)	834
	connection reboot – reboot connection and negotiate version	reboot(8) fversion(2)	484
	connection to CPU server	cpu(1)	57
rcpu, rimport, rexport, rconnect -	connection to CPU server	rcpu(1)	245
freenetconninfo - make and break network	connections /setnetmtpt, getnetconninfo,	dial(2)	427
	connections	netstat(1)	196
	connections /vtfreeconn, vtsend, vtrecv,	venti-conn(2)	655
group ids, user, null, reboot, etc.	Console	cons(3) cec(8)	683 937
khdfs	console – keyboard and console filesystem	kbdfs(8)	986
	console access	consolefs(4)	760
	console, clocks, process/process group ids,	cons(3)	683
	console filesystem	kbdfs(8)	986
	consolefs, C, clog – file system for console	consolefs(4)	760
	construct argument list and execute	xargs(1)	340
	conswdir – maintain remote working directory . control	rwd(1) arch(3)	256 675
	control	atazz(8)	928
	control initkeyboard,	keyboard(2)	525
	control /moveto, getrect, drawgetrect,	mouse(2)	545
	control	scuzz(8)	
	control	swap(3)	736
closecontrolset, controlcalled, controlwire,/	control	uart(3) control(2)	740 403
	control files for text windows	acme(4)	750
	control floating point	getfcr(2)	487
	control message parsing Cmdbuf,	9pcmdbuf(2)	354
/activate, closecontrol, closecontrolset,	controlcalled, controlwire, createbox,/	control(2)	403
	controller	qball(2)	586
	controller and monitor database	vgadb(6)	901
	controller device	vga(3) usb(3)	745 741
device drivers . sdahci - AHCI (Advanced Host		sdahci(3)	725
closecontrolset, controlcalled,/ Control,		control(2)	403
	controlwire, createbox, createboxbox,/	control(2)	403
	convA2M, convM2A, convPR2M, convM2PR,/	authsrv(2)	382
dirfmt, dirmodefmt,/ Fcall, convS2M,		fcall(2)	457
	conventions for C	style(6) rune(2)	893 603
	conversion program	units(1)	322
TK2MS, TK2SEC - kernel times and time	conversions /fastticks, HZ, MS2HZ, MS2TK,	seconds(9)	
mug –	convert an image to a face icon	mug(1)	191
	convert and copy a file	dd(1)	69
ps2pdf, pdf2ps –	•	ps2pdf(1)	230
- ms2html, html2ms - gmtime, asctime, tm2sec, timezone		ms2html(1) ctime(2)	189 419
tzload, tmtime, tmparse, tmfmt, tmnorm –		tmdate(2)	643
unicode uhtml -		uhtml(1)	320
seconds since epoch seconds -	convert human-readable date (and time) to	seconds(1)	264
crop, iconv - frame, crop, and		crop(1)	59
and from unicode utf2idn, idn2utf -	convert internationalized domain names to convert pictures /ico, tga, tojpg, togeordi,	idn(2)	514
togif, toppm, topng, totif, toico - view and strtod, strtol, strtoll, strtoul, strtoul -	convert text to numbers /atoll, charstod,	jpg(1) atof(2)	156 378
troff2html -	convert troff output into HTML	troff2html(1)	316
	converter	mus(1)	192
banks dmid - MIDI to OPL3	converter using GENMIDI-type instrument	dmid(1)	76
authsrv, guard.srv, debug,/ changeuser,	convkeys, printnetkey, status, enable, disable,	auth(8)	930
<pre>/convM2TR, convA2M, convM2A, convPR2M, /readnvram, convT2M, convM2T, convTR2M,</pre>	convM2PR, _asgetticket, _asrequest,/convM2TR, convA2M, convM2A, convPR2M,/	authsrv(2)	382 382
fcallfmt, dirfmt, dirmodefmt, / Fcall,	convM21K, convA2M, convM2A, convPR2M,/ convS2M, convD2M, convM2S, convM2D,	authsrv(2) fcall(2)	382 457
webcookies – HTTP	cookie manager		825
read, write,	copy – simple Venti clients	venti(1)	326
dd - convert and		dd(1)	69
rdarena, wrarena -			
buffer pump – ecn – fast	copy asynchronously via a large circular copy, handling errors	pump(1) ecp(1)	231 84
	copy, move files	cp(1)	55

	copy network buffers /packetsplit,	venti-packet(2)	663
/blocklen, blockalloclen, readblist, concatblock,	copyblock, trimblock, packblock, padblock,/	allocb(9)	1085 937
	Coraid Ethernet Console	cec(8) hget(1)	957 145
trigonometric functions sin,		sin(2)	623
sinh,		sinh(2)	624
wc - word	count	wc(1)	336
	count blocks in a file	sum(1)	288
locks, rendezvous points, and reference	counts /rendezvous locks, reader-writer	lock(2)	526
	cp, fcp, mv – copy, move files	cp(1)	55
mount archival file systems	cpiofs, tapfs, tarfs, tpfs, v6fs, v10fs, zipfs	tapefs(4)	814
	cpp – C language preprocessor cpu – connection to CPU server	cpp(1) cpu(1)	56 57
oexportfs - legacy exportfs for	cpu and import	oexportfs(4)	799
	CPU server	rcpu(1)	245
cputime, times, cycles –	cpu time in this process and children	cputime(2)	418
information	cpuid, icanhasvmx - print processor	cpuid(8)	939
cpurc,	cpurc.local, termrc, termrc.local - boot scripts	cpurc(8)	940
process and children	cputime, times, cycles – cpu time in this	cputime(2)	418
newmap, setmap, findseg, unusemap,/		mach(2)	529
	creadmemimage, writememimage,/	memdraw(2)	536
or new file open,	create an interprocess channel	open(5)	838 568
	create an ISO-9660 CD image	pipe(2) mk9660(8)	992
	create and mount process snapshots	snap(4)	810
writing, create file open,		open(2)	566
	create, extract a vac archive on Venti	vac(1)	324
other pointing device paint -	create image files by drawing with a mouse or	paint(1)	210
/createboxbox, createbutton, createcolumn,		control(2)	403
opendirfile,/ Tree, alloctree, freetree, File,		9pfile(2)	357
/createentry, createkeyboard, createlabel,		control(2)	403
/createmenu, createradiobutton, createrow,		control(2)	403
/createscribble, createslider, createstack,		control(2)	403
	creating an http server /hurlfmt, hurlunesc,	httpd(2)	508
patch – simple patch		patch(1)	212
kproć, pexit, postnote – kernel process	creation, termination and interruption	kproc(9) cron(8)	941
	crop, iconv – frame, crop, and convert image	crop(1)	59
/sub3, neg3, div3, mul3, egpt3, closept3, dot3,		arith3(2)	375
/mpmagadd, mpmagsub, crtpre, crtin,		mp(2)	547
/hmac_sha2_384, hmac_sha2_512, poly1305 -	cryptographically secure hashes	sechash(2)	614
X509ecdsaverifydigest - elliptic curve		ec(2)	441
	cryptsetup - setup encrypted partition	cryptsetup(8)	942
/ndbfree, ipattr, ndbgetipaddr, ndbipinfo,		ndb(2)	554
query, ipquery, mkhash, mkdb, mkhosts, cs,		ndb(8)	
timezone – convert date and time	ctime, localtime, gmtime, asctime, tm2sec,	ctime(2)	419
control initkeyboard, /createtext, createtextbutton, ctlerror,		keyboard(2) control(2)	525 403
	current directory	getwd(2)	403
getwo getwo getwo getwo getwo getwo	current function	getcallerpc(2)	485
	cursor – kernel mouse interface	mouse(3)	712
	Cursor, initdraw, geninitdraw, newwindow,	graphics(2)	492
X509ecdsaverifydigest - elliptic	curve cryptography /X509ecdsaverify,	ec(2)	441
cached-worm file server, dump cwfs,			
	cycles - cpu time in this process and children .	cputime(2)	418
	daemon	cifsd(8)	938
	daemon	cron(8)	941 984
	data /bunzip2, compress, uncompress,	ipserv(8) gzip(1)	984 121
	data	prof(1)	226
	data block management /padblock,	allocb(9)	
	data caches	seqflush(2)	620
vtrootunpack, vtparsescore, vtscorefmt - venti	data formats /vtputstring, vtrootpack,	venti-fcall(2)	657
read, write - transfer	data from and to a file	read(5)	840
caninsertkey, lookupkey, deletekey – integer to	data structure maps /freemap, insertkey,	intmap(2)	515
ndbsubstitute, ndbdedup – network	database /ndbconcatenate, ndbreorder,	ndb(2)	554
ndb – Network	database	ndb(6)	879
	database /csquery, dns, dnstcp, dnsquery,	ndb(8)	
	database	vgadb(6)	901 787
	database filesdatabase operator	keyfs(4) join(1)	155
	databases /debug, wrkey, login, newns,	auth(8)	930
	databases	intro(7)	904
	datagram protocol	sdp(3)	729
		,	

	date and time ctime, localtime,	ctime(2)	419
	date and time	date(1)	60
	date and time tmnow, tzload,	tmdate(2)	643
seconds – convert numan-readable	date (and time) to seconds since epoch	seconds(1)	264
touch sat modification	date, clock – date and time	date(1) touch(1)	60 310
touch - set mounication	db – debugger	db(1)	61
	dc – desk calculator	dc(1)	67
	dd – convert and copy a file	dd(1)	69
/ctlmalloc, ctlrealloc, ctlstrdup, ctlprint,	deactivate, freectlfont, freectlimage,/	control(2)	403
/status, enable, disable, authsrv, guard.srv,	debug, wrkey, login, newns, none, as -/	auth(8)	930
acid, truss, trump –	debugger	acid(1)	12
- db	debugger	db(1)	61
ieeesftos, ieeedftos - machine-independent		debugger(2)	422
rdbfs – remote kernel	debugging file system	rdbfs(4)	805
encod/i dg c bytte h/r, enc64chr, dec32chr, enc32chr,	dec16chr, enc16chr, encodefmt –	encode(2)	445
xd – hex, octal,	decimal, or ASCII dump	xd(1)	341
flacenc, sundec, wavdec, pcmconv, mixfs -	decode and encode audio files /flacdec,	audio(1)	26
/asn1encodeRSApriv, asn1encodeRSApub,	decodePEM, rsadecrypt, rsaencrypt, rsafill,/	rsa(2)	601
dpic, todpic – Doom picture	decoder and encoder	dpic(1)	79
/wunlock, rsleep, rwakeup, rwakeupall, incref,	decref – spin locks, queueing rendezvous/	lock(2)	526
encrypt,	decrypt, netcrypt – DES encryption	encrypt(2)	447
 /reqqueuepush, reqqueueflush - /runefmtstrflush, errfmt - support for 	deferred processing of 9P requests defined print formats and output routines	9pqueue(2) fmtinstall(2)	359 466
deflatezlibblock, inflateinit, / deflateinit,	deflate, deflatezlib, deflateblock,	flate(2)	463
/myetheraddr, maskip, equivip4, equivip6,		ip(2)	519
sleep, alarm –		sleep(2)	625
delays, clock interrupts		delay(9)	
	delayed note	alarm(1)	21
sleep, alarm - delay, ask for	delayed note	sleep(2)	625
delay, microdelay, addclock0link - small	delays, clock interrupts	delay(9)	1088
delkey –		delkey(1)	71
/freemap, insertkey, caninsertkey, lookupkey,	deletekey - integer to data structure maps	intmap(2)	515
tail -	deliver the last part of a file	tail(1)	291
filter, list,	deliver, token, vf - filtering mail	filter(1)	98
send – mail routing and		send(8)	
	delkey – delete keys from factotum	delkey(1)	71 72
compare	deroff – remove formatting requests derp – directory–examining recursive	deroff(1) derp(1)	72
compareencrypt, decrypt, netcrypt -	DES encryption	encrypt(2)	447
/desECBdecrypt, des3CBCencrypt,	des3CBCdecrypt, des3ECBencrypt, /	des(2)	425
/desECBencrypt, desECBdecrypt,	des3CBCencrypt, des3CBCdecrypt,/	des(2)	425
/des3CBCdecrypt, des3ECBencrypt,	des3ECBdecrypt, key_setup, des56to64,/	des(2)	425
/des3ECBdecrypt, key_setup, des56to64,	des64to56, setupDES3state,/	des(2)	425
/des_key_setup, block_cipher, desCBCencrypt,	desCBCdecrypt, desECBencrypt,/	des(2)	425
walk -	descend a directory hierarchy	walk(5)	845
namespace – name space	description file	namespace(6)	878
errstr, rerrstr, werrstr –	description of last system call error	errstr(2)	448
dup – duplicate an open file		dup(2)	440
	descriptor	fd2path(2)	460
found - return size of atomic I/O unit for file	descriptordescriptor to a file server	iounit(2) fauth(2)	518 456
	desECBencrypt, desECBdecrypt,/	des(2)	425
dc -		dc(1)	67
desCBCdecrypt,/ setupDESstate,		des(2)	425
xformpointd,/ ident, matmul, matmulr,		matrix(2)	534
usbcmd, classname, closedev, configdev,	devctl, getdev, loaddevstr, opendev,/	nusb(2)	560
audio – audio	device	audio(3)	677
	device	ether(3)	691
	device i82365 - Personal Computer	i82365(3)	697
	device /tcp17010, tcp17013, tcp17019,	listen(8)	988
	device paint - create image files	paint(1)	210
	devicedevice commands	vga(3) parsecmd(9)	745
opendev opendevdata openen unstall - LICR	device driver library /getdev, loaddevstr,	nusb(2)	560
	device driver initially / gettev, loaddevsti, device drivers . sdahci – AHCI (Advanced Host	sdahci(3)	725
	device interface	disk(2)	431
	device interface	sd(3)	723
	device interface	sdaoe(3)	727
sdloop - loopback storage	device interface	sdloop(3)	728
	device operations openscsi, closescsi,	scsi(2)	612
	device read routines	readnum(9)	
	devices	fs(3)	695
intro – introduction to the Plan 9	devices	intro(3)	670

Internet booting	dhcpd, dhcp6d, dhcpleases, rarpd, tftpd	dhcpd(8)	943
timepic - troff preprocessor for drawing timing	diagrams	timepic(1)	305
netmkaddr, setnetmtpt, getnetconninfo,/	dial, hangup, announce, listen, accept, reject,	dial(2)	427
faxsend, fax, telcofax, telcodata - telephone	dialer network telco, faxreceive,	telco(4)	
at, drain, expect, pass –	dialer scripting tools	expect(1)	92
at, drain, expect, pass	dict – dictionary browser	dict(7)	906
idiff interactive	diff		151
ium - meracuve		idiff(1)	
	diff - differential file comparator	diff(1)	74
yesterday,		yesterday(1)	344
	digital encryption standard . /setupDES3state,	des(2)	425
authentication box securenet -		securenet(8)	1051
dsasigalloc, dsasigfree, dsaprivtopub -	digital signature algorithm /dsaprivfree,	dsa(2)	438
map -	digitized map formats	map(6)	871
scat – sky catalogue and		scat(7)	915
/validitems, freeitems, freedocinfo, dimenkind,		html(2)	496
			293
tar,		tar(1)	
awk -	J	awk(1)	29
chdir – change working	directory	chdir(2)	399
dirread, dirreadall - read	directory	dirread(2)	430
getwd – get current	directory	getwd(2)	491
ls. lc – list contents of	directory	ls(1)	170
mkdir – make a	directory	mkdir(1)	184
	directory	pwd(1)	232
pwd, pbd - working	directory		
rwu, conswuir – maintain remote working	directory	rwd(1)	256
	directory format	mdir(6)	872
	directory hierarchy	walk(5)	845
derp –	directory-examining recursive compare	derp(1)	73
/fstat, wstat, fwstat, dirstat, dirfstat, dirwstat,	dirfwstat, nulldir - get and put file status	stat(2)	626
/convD2M, convM2S, convM2D, fcallfmt, dirfmt,		fcall(2)	457
listensrv, postmountsrv,/ Srv, chatty9p,		9p(2)	349
dirread,		dirread(2)	430
stat, fstat, wstat, fwstat, dirstat, dirfstat,		stat(2)	626
		• •	
screenlock –		screenlock(8)	
	disable) an interrupt handler	intrenable(9)	
login,/ /convkeys, printnetkey, status, enable,		auth(8)	930
splhi, spllo, splx, islo - enable and	disable interrupts	splhi(9)	1105
system	disc (CD, DVD, B) track reader and writer file	cdfs(4)	755
restore – backup venti arenas to blu-rav	discs or restore from them /dumparenas,	backup(8)	932
opendisk.	Disk – generic disk device interface	disk(2)	431
	Disk – generic disk device interface	disk(2)	431 797
Serial Bus drivers audio,	disk, ether, kb, serial, ptp, usbd – Universal	nusb(4)	797
Serial Bus drivers audio, floppy - floppy	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3)	797 694
Serial Bus drivers audio, floppy – floppy disksim –	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8)	797 694 946
Serial Bus drivers audio, floppy - floppy	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1)	797 694 946 82
Serial Bus drivers audio, floppy – floppy disksim – du –	disk, ether, kb, serial, ptp, usbd – Universal disk interface disk simulator disk usage disk parts – prepare disks for use	nusb(4) floppy(3) disksim(8) du(1) diskparts(8)	797 694 946 82 945
Serial Bus drivers audio, floppy – floppy disksim – du –	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8)	797 694 946 82 945 1029
Serial Bus drivers audio, floppy – floppy disksim – du –	disk, ether, kb, serial, ptp, usbd – Universal disk interface disk simulator disk usage disk parts – prepare disks for use	nusb(4) floppy(3) disksim(8) du(1) diskparts(8)	797 694 946 82 945 1029
Serial Bus drivers audio, floppy – floppy disksim – du –	disk, ether, kb, serial, ptp, usbd – Universal disk interface disk simulator disk usage diskparts – prepare disks for use disks, floppies and flashes disksim – disk simulator	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8)	797 694 946 82 945 1029 946
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare	disk, ether, kb, serial, ptp, usbd – Universal disk interface disk simulator disk usage diskparts – prepare disks for use disks, floppies and flashes disks im – disk simulator disk/smart – SMART error monitoring	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) smart(8)	797 694 946 82 945 1029 946 1053
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg –	disk, ether, kb, serial, ptp, usbd – Universal disk interface disk simulator disk usage diskparts – prepare disks for use disks, floppies and flashes disksim – disk simulator disk/smart – SMART error monitoring display a bar graph or status message	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) smart(8) statusbar(8)	797 694 946 82 945 1029 946 1053 1061
Serial Bus drivers audio, floppy - floppy disksim - du - prep, edisk, fdisk, format, mbr - prepare window statusbar, statusmsg - getmap, colors -	disk, ether, kb, serial, ptp, usbd – Universal disk interface disk simulator disk usage diskparts – prepare disks for use disks, floppies and flashes disksim – disk simulator disk/smart – SMART error monitoring display a bar graph or status message display color map	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) smart(8) statusbar(8) colors(1)	797 694 946 82 945 1029 946 1053 1061 51
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access	disk, ether, kb, serial, ptp, usbd – Universal disk interface disk simulator disk usage diskparts – prepare disks for use disks, floppies and flashes disks, floppies and flashes disk/smart – SMART error monitoring display a bar graph or status message display color map display color map	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) statusbar(8) statusbar(8) colors(1) readcolmap(2)	797 694 946 82 945 1029 946 1053 1061 51 595
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats –	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) statusbar(8) statusbar(8) colors(1) readcolmap(2) stats(8)	797 694 946 82 945 1029 946 1053 1061 51 595 1059
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – ns –	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) statusbar(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1)	797 694 946 82 945 1029 946 1053 1061 51 595 1059 204
Serial Bus drivers audio, floppy - floppy disksim - du - prep, edisk, fdisk, format, mbr - prepare window statusbar, statusmsg - getmap, colors - RGB, readcolmap, writecolmap - access stats - ns - geninitdraw, newwindow, drawerror,/	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) statusbar(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2)	797 694 946 82 945 1029 946 1053 1061 51 595 1059 204 492
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – ns – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof –	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) smart(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1)	797 694 946 82 945 1029 946 1053 1061 51 595 1059 204 492 226
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof – mothra – retrieve and	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) statusbar(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2)	797 694 946 82 945 1029 946 1053 1061 51 595 1059 204 492
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – ns – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof –	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) smart(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1)	797 694 946 82 945 1029 946 1053 1061 51 595 1059 204 492 226
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof – mothra – retrieve and	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1) mothra(1)	797 694 946 82 945 1029 946 1053 1061 51 595 1059 204 492 226 186
Serial Bus drivers audio, floppy - floppy disksim - du - prep, edisk, fdisk, format, mbr - prepare window statusbar, statusmsg - getmap, colors - RGB, readcolmap, writecolmap - access stats - ns - geninitdraw, newwindow, drawerror,/ prof, tprof, kprof - mothra - retrieve and mul3, eqpt3, closept3, dot3, cross3, len3, hypot - Euclidean	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) smart(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1) mothra(1) arith3(2) hypot(2)	797 694 946 82 945 1029 946 1053 1061 51 595 1059 204 492 226 186 375 513
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – ns – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof – mothra – retrieve and mul3, eqpt3, closept3, dot3, cross3, len3, hypot – Euclidean bundle – collect files for	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) smart(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1) mothra(1) arith3(2) hypot(2) bundle(1)	797 694 946 82 945 1029 946 1053 1061 51 595 1059 204 492 226 186 375 513 41
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – ns – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof – mothra – retrieve and mul3, eqpt3, closept3, dot3, cross3, len3, hypot – Euclidean bundle – collect files for len3, dist3, unit3, midpt3,/ add3, sub3, neg3,	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1) mothra(1) arith3(2) bundle(1) arith3(2)	797 694 946 82 945 1029 946 1053 1051 51 595 1059 204 492 226 186 375 513 41 375
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – ns – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof – mothra – retrieve and mul3, eqpt3, closept3, dot3, cross3, len3, hypot – Euclidean bundle – collect files for len3, dist3, unit3, midpt3,/ add3, sub3, neg3, umuldiv – high–precision multiplication and	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) statusbar(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1) mothra(1) arith3(2) bundle(1) arith3(2) muldiv(2)	797 694 946 82 945 1029 946 1053 1061 51 595 1059 204 492 226 186 375 513 41 375 552
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – ns – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof – mothra – retrieve and mul3, eqpt3, closept3, dot3, cross3, len3, hypot – Euclidean bundle – collect files for len3, dist3, unit3, midpt3,/ add3, sub3, neg3, umuldiv – high–precision multiplication and canonrect, eqpt, eqrect,/ addpt, subpt, mulpt,	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) statusbar(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1) mothra(1) arith3(2) hypot(2) bundle(1) arith3(2) muldiv(2) addpt(2)	797 694 946 82 945 1029 946 1053 1061 51 595 1059 204 492 226 186 375 513 41 375 552 363
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – ns – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof – mothra – retrieve and mul3, eqpt3, closept3, dot3, cross3, len3, hypot – Euclidean bundle – collect files for len3, dist3, unit3, midpt3,/ add3, sub3, neg3, umuldiv – high–precision multiplication and canorrect, eqpt, eqrect,/ addpt, subpt, mulpt, GENMIDI–type instrument banks	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1) mothra(1) arith3(2) hypot(2) bundle(1) arith3(2) muldiv(2) addpt(2) dmid(1)	797 694 946 82 945 1029 946 1053 1061 51 595 1059 204 492 226 186 375 513 41 375 552 363 76
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – ns – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof – mothra – retrieve and mul3, eqpt3, closept3, dot3, cross3, len3, hypot – Euclidean bundle – collect files for len3, dist3, unit3, midpt3,/ add3, sub3, neg3, umuldiv – high–precision multiplication and canorrect, eqpt, eqrect,/ addpt, subpt, mulpt, GENMIDI–type instrument banks	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1) mothra(1) arith3(2) hypot(2) bundle(1) arith3(2) muldiv(2) addpt(2) dmid(1) ndb(8)	797 694 946 82 945 1029 946 1053 1061 51 595 1059 204 492 226 186 375 513 41 375 552 363 76 1000
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – ns – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof – mothra – retrieve and mul3, eqpt3, closept3, dot3, cross3, len3, hypot – Euclidean bundle – collect files for len3, dist3, unit3, midpt3,/ add3, sub3, neg3, umuldiv – high–precision multiplication and canonrect, eqpt, eqrect,/ addpt, subpt, mulpt, GENMIDI–type instrument banks	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) smart(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1) mothra(1) arith3(2) hypot(2) bundle(1) arith3(2) muldiv(2) addpt(2) dmid(1) ndb(8) ndb(2)	797 694 946 82 945 1029 946 1053 1061 51 595 1059 204 492 226 186 375 513 41 375 552 363 76 1000 554
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – ns – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof – mothra – retrieve and mul3, eqpt3, closept3, dot3, cross3, len3, hypot – Euclidean bundle – collect files for len3, dist3, unit3, midpt3,/ add3, sub3, neg3, umuldiv – high–precision multiplication and canorrect, eqpt, eqrect,/ addpt, subpt, mulpt, GENMIDI–type instrument banks/mkhosts, cs, csquery, dns, dnstcp, dnsquery, /ndbhash, ndbparse, csgetvalue, ndbfindattr, mswordstrings, msexceltables – extract/	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) smart(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1) arith3(2) hypot(2) bundle(1) arith3(2) muldiv(2) addpt(2) dmid(1) ndb(8) ndb(2) doc2txt(1)	797 694 946 82 945 1053 1061 51 595 1059 204 492 226 186 375 513 41 375 552 363 76 1000 554 77
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – ns – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof – mothra – retrieve and mul3, eqpt3, closept3, dot3, cross3, len3, hypot – Euclidean bundle – collect files for len3, dist3, unit3, midpt3,/ add3, sub3, neg3, umuldiv – high–precision multiplication and canonrect, eqpt, eqrect,/ addpt, subpt, mulpt, GENMIDI–type instrument banks	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) smart(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1) mothra(1) arith3(2) hypot(2) bundle(1) arith3(2) muldiv(2) addpt(2) dmid(1) ndb(8) ndb(2)	797 694 946 82 945 1029 946 1053 1061 51 595 1059 204 492 226 186 375 513 41 375 552 363 76 1000 554
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – ns – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof – mothra – retrieve and mul3, eqpt3, closept3, dot3, cross3, len3, hypot – Euclidean bundle – collect files for len3, dist3, unit3, midpt3,/ add3, sub3, neg3, umuldiv – high–precision multiplication and canorrect, eqpt, eqrect,/ addpt, subpt, mulpt, GENMIDI–type instrument banks/mkhosts, cs, csquery, dns, dnstcp, dnsquery, /ndbhash, ndbparse, csgetvalue, ndbfindattr, mswordstrings, msexceltables – extract/	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) smart(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1) arith3(2) hypot(2) bundle(1) arith3(2) muldiv(2) addpt(2) dmid(1) ndb(8) ndb(2) doc2txt(1)	797 694 946 82 945 1053 1061 51 595 1059 204 492 226 186 375 513 41 375 552 363 76 1000 554 77
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – ns – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof – mothra – retrieve and mul3, eqpt3, closept3, dot3, cross3, len3, hypot – Euclidean bundle – collect files for len3, dist3, unit3, midpt3,/ add3, sub3, neg3, umuldiv – high–precision multiplication and canorrect, eqpt, eqrect,/ addpt, subpt, mulpt, GENMIDI-type instrument banks /mkhosts, cs, csquery, dns, dnstcp, dnsquery, /ndbhash, ndbparse, csgetvalue, ndbfindattr, mswordstrings, msexceltables – extract/ a document	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1) mothra(1) arith3(2) hypot(2) bundle(1) arith3(2) muldiv(2) addpt(2) dmid(1) ndb(8) ndb(2) doc2txt(1) doctype(1) fmtinstall(2)	797 694 946 82 945 1029 946 1053 1061 51 595 1059 204 492 226 186 375 513 41 375 552 363 76 1000 554 77 78 466
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – ns – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof – mothra – retrieve and mul3, eqpt3, closept3, dot3, cross3, len3, hypot – Euclidean bundle – collect files for len3, dist3, unit3, midpt3,/ add3, sub3, neg3, umuldiv – high–precision multiplication and canorrect, eqpt, eqrect,/ addpt, subpt, mulpt, GENMIDI-type instrument banks /mkhosts, cs, csquery, dns, dnstcp, dnsquery, /ndbhash, ndbparse, csgetvalue, ndbfindattr, mswordstrings, msexceltables – extract/ a document fmtstrcpy, fmtrunestrcpy,/ fmtinstall, utf2idn, idn2utf – convert internationalized	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1) mothra(1) arith3(2) hypot(2) bundle(1) arith3(2) muldiv(2) addpt(2) dmid(1) ndb(8) ndb(2) doc2txt(1) doctype(1) fmtinstall(2) idn(2)	797 694 946 82 945 1029 946 1053 1059 204 492 226 186 375 513 41 375 552 363 76 1000 554 77 78 466 514
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof – mothra – retrieve and mul3, eqpt3, closept3, dot3, cross3, len3, hypot – Euclidean bundle – collect files for len3, dist3, unit3, midpt3,/ add3, sub3, neg3, umuldiv – high–precision multiplication and canorrect, eqpt, eqrect,/ addpt, subpt, mulpt, GENMIDI–type instrument banks /mkhosts, cs, csquery, dns, dnstcp, dnsquery, /ndbhash, ndbparse, csgetvalue, ndbfindattr, mswordstrings, msexceltables – extract/ a document fmtstrcpy, fmtrunestrcpy,/ fmtinstall, utf2idn, idn2utf – convert internationalized kill, slay, broke,	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1) mothra(1) arith3(2) hypot(2) bundle(1) arith3(2) muldiv(2) dundl(1) ndb(8) ndb(2) doc2txt(1) doctype(1) fmtinstall(2) idn(2) kill(1)	797 694 946 82 945 1029 946 1053 1061 51 595 1059 204 492 226 186 375 513 41 375 552 363 76 1000 554 77 78 466 514 160
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof – mothra – retrieve and mul3, eqpt3, closept3, dot3, cross3, len3, hypot – Euclidean bundle – collect files for len3, dist3, unit3, midpt3,/ add3, sub3, neg3, umuldiv – high–precision multiplication and canorrect, eqpt, eqrect,/ addpt, subpt, mulpt, GENMIDI–type instrument banks /mkhosts, cs, csquery, dns, dnstcp, dnsquery, /ndbhash, ndbparse, csgetvalue, ndbfindattr, mswordstrings, msexceltables – extract/ a document fmtstrcpy, fmtrunestrcpy,/ fmtinstall, utf2idn, idn2utf – convert internationalized kill, slay, broke, life, mandel,/ 4s, 5s, blabs, catclock,	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) smart(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1) mothra(1) arith3(2) hypot(2) bundle(1) arith3(2) muldiv(2) addpt(2) dmid(1) ndb(8) ndb(2) doc2txt(1) doctype(1) fmtinstall(2) idn(2) kill(1) games(1)	$\begin{array}{c} 797\\ 694\\ 946\\ 82\\ 945\\ 1029\\ 946\\ 1053\\ 1061\\ 51\\ 595\\ 1059\\ 204\\ 492\\ 226\\ 186\\ 375\\ 513\\ 41\\ 375\\ 552\\ 363\\ 76\\ 1000\\ 554\\ 77\\ 78\\ 466\\ 514\\ 160\\ 109\\ \end{array}$
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – ns – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof – mothra – retrieve and mul3, eqpt3, closept3, dot3, cross3, len3, hypot – Euclidean bundle – collect files for len3, dist3, unit3, midpt3,/ add3, sub3, neg3, umuldiv – high–precision multiplication and canonrect, eqpt, eqrect,/ addpt, subpt, mulpt, GENMIDI–type instrument banks /mkhosts, cs, csquery, dns, dnstcp, dnsquery, /ndbhash, ndbparse, csgetvalue, ndbfindattr, mswordstrings, msexceltables – extract/ a document	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) smart(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1) mothra(1) arith3(2) hypot(2) bundle(1) arith3(2) muldiv(2) addpt(2) dmid(1) ndb(8) ndb(2) doc2txt(1) doctype(1) fmtinstall(2) kill(1) games(1) dpic(1)	797 694 946 82 945 1029 946 1053 1061 51 595 1059 204 492 226 186 375 513 41 375 552 363 76 1000 554 77 78 466 514 160 109 79
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – ns – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof – mothra – retrieve and mul3, eqpt3, closept3, dot3, cross3, len3, hypot – Euclidean bundle – collect files for len3, dist3, unit3, midpt3,/ add3, sub3, neg3, umuldiv – high–precision multiplication and canonrect, eqpt, eqrect,/ addpt, subpt, mulpt, GENMIDI–type instrument banks /mkhosts, cs, csquery, dns, dnstcp, dnsquery, /ndbhash, ndbparse, csgetvalue, ndbfindattr, mswordstrings, msexceltables – extract/ a document fmtstrcpy, fmtrunestrcpy,/ fmtinstall, utf2idn, idn2utf – convert internationalized kill, slay, broke, life, mandel,/ 4s, 5s, blabs, catclock, dpic, todpic – /quotestrfmt, quoterunestrfmt, quotefmtinstall,	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) smart(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1) mothra(1) arith3(2) hypot(2) bundle(1) arith3(2) muldiv(2) addpt(2) dmid(1) ndb(8) ndb(2) doc2txt(1) doctype(1) fmtinstall(2) idn(2) kill(1) games(1) dpic(1) quote(2)	797 694 946 82 945 1053 1061 51 595 1059 204 492 226 186 375 513 41 375 552 363 76 1000 554 77 78 466 514 160 109 79 590
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – ns – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof – mothra – retrieve and mul3, eqpt3, closept3, dot3, cross3, len3, hypot – Euclidean bundle – collect files for len3, dist3, unit3, midpt3,/ add3, sub3, neg3, umuldiv – high–precision multiplication and canorrect, eqpt, eqrect,/ addpt, subpt, mulpt, GENMIDI-type instrument banks	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) smart(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1) mothra(1) arith3(2) hypot(2) bundle(1) arith3(2) muldiv(2) addpt(2) dmid(1) ndb(8) ndb(2) doc2txt(1) doctype(1) fmtinstall(2) kill(1) games(1) dpic(1) quote(2) fmtinstall(2)	$\begin{array}{c} 797\\ 694\\ 946\\ 82\\ 945\\ 1029\\ 946\\ 1053\\ 1061\\ 51\\ 595\\ 1059\\ 204\\ 492\\ 226\\ 186\\ 375\\ 513\\ 41\\ 375\\ 552\\ 363\\ 76\\ 1000\\ 554\\ 77\\ 78\\ 466\\ 514\\ 160\\ 109\\ 79\\ 590\\ 466\\ \end{array}$
Serial Bus drivers audio, floppy – floppy disksim – du – prep, edisk, fdisk, format, mbr – prepare window statusbar, statusmsg – getmap, colors – RGB, readcolmap, writecolmap – access stats – ns – geninitdraw, newwindow, drawerror,/ prof, tprof, kprof – mothra – retrieve and mul3, eqpt3, closept3, dot3, cross3, len3, hypot – Euclidean bundle – collect files for len3, dist3, unit3, midpt3,/ add3, sub3, neg3, umuldiv – high–precision multiplication and canonrect, eqpt, eqrect,/ addpt, subpt, mulpt, GENMIDI–type instrument banks /mkhosts, cs, csquery, dns, dnstcp, dnsquery, /ndbhash, ndbparse, csgetvalue, ndbfindattr, mswordstrings, msexceltables – extract/ a document fmtstrcpy, fmtrunestrcpy,/ fmtinstall, utf2idn, idn2utf – convert internationalized kill, slay, broke, life, mandel,/ 4s, 5s, blabs, catclock, dpic, todpic – /quotestrfmt, quoterunestrfmt, quotefmtinstall,	disk, ether, kb, serial, ptp, usbd – Universal disk interface	nusb(4) floppy(3) disksim(8) du(1) diskparts(8) prep(8) disksim(8) smart(8) statusbar(8) colors(1) readcolmap(2) stats(8) ns(1) graphics(2) prof(1) mothra(1) arith3(2) hypot(2) bundle(1) arith3(2) muldiv(2) addpt(2) dmid(1) ndb(8) ndb(2) doc2txt(1) doctype(1) fmtinstall(2) idn(2) kill(1) games(1) dpic(1) quote(2)	797 694 946 82 945 1053 1061 51 595 1059 204 492 226 186 375 513 41 375 552 363 76 1000 554 77 78 466 514 160 109 79 590

add3, sub3, neg3, div3, mul3, eqpt3, closept3,	dot3, cross3, len3, dist3, unit3, midpt3,/	arith3(2)	375
- halt any local file systems and optionally shut	down or reboot the system /scram, reboot	fshalt(8)	956
authsrv, p9any, p9sk1,	dp9ik - authentication protocols	authsrv(6)	851
encoder	dpic, todpic – Doom picture decoder and	dpic(1)	79
troff, nroff,		troff(1)	314
at,		expect(1)	92
,	draw – screen graphics	draw(3)	685
graph -		graph(1)	114
histogram –		histogram(8)	974
replclipr, line, poly, fillpoly, bezier,/ Image,		draw(2)	432
map, mapdemo -	draw maps on various projections	map(7)	910
memimageline, memimagedraw, drawclip,	drawclipnorepl, memlinebbox,/ /memfillpoly,	memdraw(2)	536
/Cursor, initdraw, geninitdraw, newwindow,	drawerror, initdisplay, closedisplay,/	graphics(2)	492
/readmouse, closemouse, moveto, getrect,		5.	545
	drawgetrect, menuhit, setcursor, enter -/	mouse(2)	
grap – pic preprocessor for		grap(1)	112
	drawing pictures	pic(1)	218
/getmemdefont, memimagestring, hwdraw -	drawing routines for memory-resident/	memdraw(2)	536
timepic – troff preprocessor for	drawing timing diagrams	timepic(1)	305
device paint - create image files by	drawing with a mouse or other pointing	paint(1)	210
Image, draw, gendraw, drawreplxy,	drawrepl, replclipr, line, poly, fillpoly, bezier,/	draw(2)	432
fillpoly, bezier,/ Image, draw, gendraw,	drawreplxy, drawrepl, replclipr, line, poly,	draw(2)	432
/runestringbg, runestringnbg, _string, ARROW,	drawsetdebug - graphics functions PB L	draw(2)	432
os - interface to host OS commands	drawterm only)	os(1)	206
kbd – pc keyboard	driver	kbd(3)	707
pcc – APE C compiler		pcc(1)	216
opendevdata, openep, unstall – USB device	driver library /getdev, loaddevstr, opendev,	nusb(2)	560
kb, serial, ptp, usbd – Universal Serial Bus	drivers audio, disk, ether,	nusb(4)	797
Interface) SATA (Serial AT) storage device	drivers /- AHCI (Advanced Host Controller	sdahci(3)	725
genprime, gensafeprime, genstrongprime,	DSAprimes, probably_prime, smallprimetest -/	prime(2)	575
/dsaprivfree, dsasigalloc, dsasigfree,	dsaprivtopub – digital signature algorithm	dsa(2)	438
dsaprivfree,/ dsagen, dsasign, dsaverify,	dsapuballoc, dsapubfree, dsaprivalloc,	dsa(2)	438
/dsapubfree, dsaprivalloc, dsaprivfree,	dsasigalloc, dsasigfree, dsaprivtopub – digital/	dsa(2)	438
dsaprivalloc, dsaprivfree, / dsaprivalloc, dsaprivalloc, dsaprivfree, /	dsasign, dsaverify, dsapuballoc, dsapubfree,	dsa(2)	438
/itomp, uvtomp, mptouv, vtomp, mptov, mptod,			547
/itomp, uvtomp, mptouv, vtomp, mptov, mptou,	dtomp, mpdigdiv, mpadd, mpsub, mpleft,/	mp(2)	
	dtracy - dynamic tracing language	dtracy(1)	80
aufoCAu foCA coolord warms file commu	du – disk usage	du(1)	82
cwfs64x, fs64 - cached-worm file server,	dump cwfs, cwfs64,	f-(1)	770
fs – file server,	dump	fs(4)	776
history - print file names from the	dump	history(1)	147
xd – hex, octal, decimal, or ASCII	dump	xd(1)	341
yesterday, diffy - print file names from the	dump	yesterday(1)	344
image	dump9660, mk9660 - create an ISO-9660 CD .	mk9660(8)	992
blu-ray discs or restore/ backup, tobackup,	dumparenas, restore - backup venti arenas to .	backup(8)	932
ktrace – interpret kernel stack		ktrace(1)	161
	dup - duplicate an open file descriptor	dup(2)	440
	dup – dups of open files	dup(3)	689
cdfs, cddb - optical disc (CD,		cdfs(4)	755
/rectXrect, rectclip, combinerect, badrect, Dx,	Dy, Pt, Rect, Rpt - arithmetic on points and/	addpt(2)	363
dtracy –	dynamic tracing language	dtracy(1)	80
ARGBEGIN, ARGEND, ARGC, ARGF,	EARGF – process option letters from argv	arg(2)	373
/secp384r1, ecdominit, ecdomfree, ecassign,	ecadd, ecmul, strtoec, ecgen, ecverify,/	ec(2)	441
/eread, emouse, ekbd, ecanread, ecanmouse,	ecankbd, ereadmouse, eatomouse, eresized,/ .	event(2)	449
/secp256k1, secp384r1, ecdominit, ecdomfree,	ecassign, ecadd, ecmul, strtoec, ecgen,/	ec(2)	441
/ecdsasign, ecdsaverify, ecencodepub,	ecdecodepub, ecpubfree, X509toECpub,/	ec(2)	441
secp256r1, secp256k1, secp384r1, ecdominit,	ecdomfree, ecassign, ecadd, ecmul, strtoec,/ .	ec(2)	441
/ecmul, strtoec, ecgen, ecverify, ecpubverify,	ecdsasign, ecdsaverify, ecencodepub, /	ec(2)	441
,,, <u>-</u> , <u>-</u> ,, ,, ,, , ,, , ,, , ,, , ,, , ,, , ,, , ,, , ,, , ,, , ,, , ,,, ,,, ,,, ,,, ,,,,,,,,,,,,,,,,	echo – print arguments	echo(1)	83
udpecho –		udpecho(8)	1069
	ecp – fast copy, handling errors	ecp(1)	84
/ecdsaverify, ecencodepub, ecdecodepub,	ecpubfree, X509toECpub, X509ecdsaverify,/	ec(2)	441
/ecadd, ecmul, strtoec, ecgen, ecverify,	ecpubverify, ecdsasign, ecdsaverify, /	ec(2)	441
, ceaux, cennal, cercer, cegen, cereniy,	ed – text editor	ed(1)	85
floppies and flashes prep,		prep(8)	
tweak -		tweak(1)	318
	editor	ed(1)	85
	editor	hold(1)	149
	editor	sed(1)	267
			281
	editor	spred(1)	89
emacs –		emacs(1)	
sam, B, sam.save, samterm – screen	editor with structural regular expressions	sam(1)	258
/9boothyb, 9bootpxe, bootia32.efi, bootx64.efi,	efiboot.fat – PC bootloader for FAT, ISO and/	9boot(8)	921
/ecankbd, ereadmouse, eatomouse, eresized,	egetrect, edrawgetrect, emenuhit, eenter,/	event(2)	449
/egverify, egpuballoc, egpubfree, egprivalloc,	egprivfree, egsigalloc, egsigfree, egprivtopub/	elgamal(2)	443
egprivalloc,/ eggen, egencrypt, egdecrypt,	egsign, egverify, egpuballoc, egpubfree,	elgamal(2)	443

uart,	eia – serial communication control	uart(3)	740
ekbd, ecanread, ecanmouse, ecankbd,/ event,	einit, estart, estartfn, etimer, eread, emouse,	event(2)	449
parseipandmask, v4parseip, parseether,/ dossrv, 9660srv, dosmnt,	eipfmt, parseip, parseipmask,eipfmt, parseip, parseipmask,	ip(2)	519 765
/einit, estart, estartfn, etimer, eread, emouse,	ekbd, ecanread, ecanmouse, ecankbd,/	dossrv(4) event(2)	449
fplot – plot		fplot(1)	104
egsigalloc, egsigfree, egprivtopub –	elgamal encryption /egprivalloc, egprivfree,	elgamal(2)	443
/bezier, bezspline, fillbezier, fillbezspline,	ellipse, fillellipse, arc, fillarc, icossin,/	draw(2)	432
X509ecdsaverify, X509ecdsaverifydigest -	elliptic curve cryptography /X509toECpub,	ec(2)	441
	emacs - editor macros	emacs(1)	89
postmountsrv,/ Srv, chatty9p, dirread9p,	emalloc9p, erealloc9p, estrdup9p, listensrv,	9p(2)	349
event, einit, estart, estartfn, etimer, eread,	emouse, ekbd, ecanread, ecanmouse,/	event(2)	449
/egetrect, edrawgetrect, emenuhit, eenter,	emoveto, esetcursor, Event, Mouse, Menu -/	event(2)	449
vt – 5e – user–mode ARM	emulate a VT-100 or VT-220 terminal	vt(1) 5e(1)	333 10
realemu – software		realemu(8)	
2600 -	emulator	atari(1)	25
	emulator	blit(1)	39
mix - MIX assembler and	emulator	mix(1)	178
opl3 - OPL3 chip	emulator	opl3(1)	205
md –	emulator	sega(1)	271
gb, gba, nes, snes -	emulators	nintendo(1)	201
splhi, spllo, splx, islo –	enable and disable interrupts	splhi(9)	
intrenable, intrdisable - changeuser, convkeys, printnetkey, status,	enable (disable) an interrupt handler	intrenable(9) auth(8)	930
/dec644 chays /enc64 chr, dec32 chr, enc32 chr, dec16 chr,	enable, disable, authsrv, guard.srv, debug,/ enc16chr, encodefmt - encoding byte	encode(2)	445
sundec, wavdec, pcmconv, mixfs – decode and	encode audio files . /oggenc, flacdec, flacenc,	audio(1)	26
format pemdecode, pemencode -	encode files in Privacy Enhanced Mail (PE)	pem(8)	
/enc32chr, dec16chr, enc16chr,	·		
dpic, todpic - Doom picture decoder and	encoder	dpic(1)	79
	encrypt, decrypt, netcrypt – DES encryption	encrypt(2)	447
cryptsetup – setup bfECBencrypt, bfECBdecrypt – blowfish	encrypted partition	cryptsetup(8) blowfish(2)	942 393
ccpoly_encrypt, ccpoly_decrypt - chacha	encryption /chacha_encrypt2, hchacha,	chacha(2)	398
egsigalloc, egsigfree, egprivtopub – elgamal	encryption /egprivalloc, egprivfree,	elgamal(2)	443
encrypt, decrypt, netcrypt – DES	encryption	encrypt(2)	447
rc4, rc4skip, rc4back – alleged rc4	encryption setupRC4state,	rc4(2)	593
salsa_encrypt, salsa_encrypt2, hsalsa - salsa20	encryption /salsa_setblock, salsa_setiv,	salsa(2)	606
X509rsaverify, X509rsaverifydigest - RSA	encryption algorithm /X509rsareq,	rsa(2)	601
triple_block_cipher – single and triple digital /advanced	encryption standard /setupDES3state, encryption standard (rijndael)	des(2) aes(2)	425 365
pushssl – attach SSL version 2	encryption to a communication channel	pushssl(2)	582
/readcert, readcertchain – attach TLS1 or SSL3	encryption to a communication channel	pushtls(2)	583
pemencode – encode files in Privacy	Enhanced Mail (PE) format pemdecode,	pem(8)	1014
getrect, drawgetrect, menuhit, setcursor,	enter – mouse control . /closemouse, moveto,	mouse(2)	545
panic – abandon hope, all ye who	enter here	panic(9)	
actory putony accord	env – environment variables	env(3)	690 486
getenv, putenv – access plumbsendtext, plumblookup, plumbpack,/	environment variableseplumb, plumbfree, plumbopen, plumbsend,	getenv(2) plumb(2)	480 569
date (and time) to seconds since	epoch seconds – convert human–readable	seconds(1)	264
nsec – time in seconds and nanoseconds since	epoch time,	time(2)	642
	eqn – typeset mathematics	eqn(1)	90
unit3, midpt3,/ add3, sub3, neg3, div3, mul3,	eqpt3, closept3, dot3, cross3, len3, dist3,	arith3(2)	375
/rectsubpt, insetrect, canonrect, eqpt,	eqrect, ptinrect, rectinrect, rectXrect, rectclip,/	addpt(2)	363
/myipaddr, myetheraddr, maskip, equivip4,	equivip6, defmask, isv4, v4tov6, v6tov4,/	ip(2)	519
/ekbd, ecanread, ecanmouse, ecankbd, Srv, chatty9p, dirread9p, emalloc9p,	ereadmouse, eatomouse, eresized, egetrect,/ . erealloc9p, estrdup9p, listensrv,/	event(2) 9p(2)	449 349
/fmtstrflush, runefmtstrinit, runefmtstrflush,	errfmt – support for user-defined print/	fmtinstall(2)	466
rerrstr, werrstr – description of last system call	error errstr,	errstr(2)	448
	error - return an error	error(5)	836
error, nexterror, poperror, waserror -	error handling functions	error(9)	
perror, syslog, sysfatal – system	error messages	perror(2)	567
disk/smart - SMART handling functions	error monitoring error, nexterror, poperror, waserror – error	smart(8) error(9)	
vtmallocz, vtrealloc, vtstrdup, vtfree –	error-checking memory allocators . /vtmalloc,	venti-mem(2)	662
ecp – fast copy, handling	errors	ecp(1)	84
spell, sprog – find spelling	errors	spell(1)	277
system call error	errstr, rerrstr, werrstr - description of last	errstr(2)	448
/edrawgetrect, emenuhit, eenter, emoveto,	esetcursor, Event, Mouse, Menu – graphics/	event(2)	449
udp, il – network protocols over IP ip, attach, auth – messages to	esp, gre, icmp, icmpv6, ipmux, rudp, tcp, establish a connection	ip(3)	698 834
attach, auth - messages to swap -	establish a swap file	attach(5) swap(8)	
ecanread, ecanmouse,/ event, einit, estart,	estartfn, etimer, eread, emouse, ekbd,	event(2)	449
chatty9p, dirread9p, emalloc9p, erealloc9p,		9p(2)	349

	ada an Ethermatica	- the(2)	CO 1
Due duivere diele	ether – Ethernet device	ether(3)	691
Bus drivers audio, disk,	ether, kb, serial, ptp, usbd – Universal Serial	nusb(4)	797
	Ethernet (Ao) interface	aoe(3)	671
	Ethernet (Ao) storage device interface	sdaoe(3)	727
	Ethernet bridge	bridge(3)	678
cec – Coraid	Ethernet Console	cec(8)	937
ether –	Ethernet device	ether(3)	691
wol – send wake-on-lan	Ethernet packet	wol(8)	1081
ecanmouse,/ event, einit, estart, estartfn,		event(2)	449
hypot –	Euclidean distance	hypot(2)	513
,.el., \sim – command language		rc(1)	239
,.ei., ~ - command language			
	eve, iseve – privileged user	eve(9)	
	Event, Mouse, Menu – graphics events	event(2)	449
calendar – print upcoming		calendar(1)	43
derp –	examining recursive compare	derp(1)	73
- command language rc, cd, eval,	exec, exit, flag, rfork, shift, wait, whatis, ., ~	rc(1)	239
file exec,	execl, _privates, _nprivates, _tos - execute a	exec(2)	452
execution	execnet - network interface to program	execnet(4)	766
	executable	src(1)	282
leswav – machine-independent access to	executable files /beswav, leswab, leswal,	mach(2)	529
	executable files	size(1)	273
xargs – construct argument list and			340
		xargs(1)	
exec, execl, _privates, _nprivates, _tos -	execute a file	exec(2)	452
open, create - prepare a fid for I/O on an	existing or new file	open(5)	838
await, wait, waitpid - wait for a process to	exit	wait(2)	667
command language rc, cd, eval, exec,	exit, flag, rfork, shift, wait, whatis, ., ~	rc(1)	239
terminate process, process cleanup	exits, _exits, atexit, atexitdont, terminate	exits(2)	454
exponential, logarithm, power, square root	exp, log, log10, pow, pow10, sqrt	exp(2)	455
uncompress, zip, unzip - compress and	expand data /bzip2, bunzip2, compress,	gzip(1)	121
aliasmail -	expand system wide mail aliases	aliasmail(8)	926
at, drain,	expect, pass – dialer scripting tools	expect(1)	92
frexp, Idexp, modf – split into mantissa and	exponent	frexp(2)	480
exp, log, log10, pow, pow10, sqrt -	exponential, logarithm, power, square root	exp(2)	455
oexportfs – legacy		oexportfs(4)	799
	exportfs, srvfs – file server plumbing	exportfs(4)	767
regsub, rregexec, rregsub, regerror - regular		regexp(2)	597
regexp – regular	expression notation	regexp(6)	888
samterm - screen editor with structural regular	expressions sam, B, sam.save,	sam(1)	258
fs,	exsort – file server maintenance	fs(8)	947
	ext2srv – ext2 file system	ext2srv(4)	769
crtpre, crtin, crtout, crtprefree, crtresfree -	extended precision arithmetic /mpmagsub,	mp(2)	547
	extended precision arithmetic code generator .	mpc(1)	188
	extensible strings/s_putc, s_unique,	string(2)	630
	external format for fonts and subfonts	font(6)	859
	external format for images	image(6)	864
	extract a vac archive on Venti	vac(1)	324
	extract printable strings	strings(1)	286
	extract printable text from Microsoft/	doc2txt(1)	77
remainder, floor, ceiling functions	fabs, fmod, floor, ceil – absolute value,	floor(2)	465
	face – face files	face(6)	858
tweak - edit image files, subfont files,	face files, etc.	tweak(1)	318
mug – convert an image to a	face icon	mug(1)	191
- 0	faces, seemail, vwhois - mailbox interface	faces(1)	94
large primes	factor, primes - factor a number, generate	factor(1)	95
	factotum	delkey(1)	71
agent	factotum, fgui, userpasswd – authentication	factotum(4)	770
	fast copy, handling errors	ecp(1)	84
/srand, truerand, ntruerand, genrandom, prng,	fastrand, nfastrand – random number/	rand(2)	591
- kernel times and time/ seconds, ticks,			
		seconds(9)	
/bootx64.efi, efiboot.fat - PC bootloader for		9boot(8)	921
	fault	abort(2)	360
descriptor to a file server	fauth - set up authentication on a file	fauth(2)	456
/login, noworld, procsetuser, auth_proxy,		auth(2)	379
typesetter output files page - view		page(1)	208
telephone dialer network telco,		telco(4)	815
Fcall, convS2M, convD2M, convM2S, convM2D,	fcallfmt, dirfmt, dirmodefmt, read9pmsg,/	fcall(2)	457
setvbuf,/ fopen, freopen, fdopen, fileno,	fclose, sopenr, sopenw, sclose, fflush,	fopen(2)	469
cp,	fcp, mv – copy, move files	cp(1)	55
descriptor	fd2path - return file name associated with file	fd2path(2)	460
and flashes prep, edisk,	fdisk, format, mbr - prepare disks, floppies	prep(8)	
sclose, fflush, setvbuf,/ fopen, freopen,		fopen(2)	469
,,,,,,,,,,,,,	fedex, ups, usps – track shipments	fedex(1)	96
/sethuf faetnos ftell fsetnos fseek rewind	feof, ferror, clearerr – standard buffered/	fopen(2)	469
mandel,/ 4s, 5s, blabs, catclock, doom,		games(1)	109
$Harder_{i} \ldots T_{3}, J_{3}, J_{3}, J_{3}, Calciock, u_{0}OIII,$	icstoon, geigerstats, gienay, juggie, me,	games(1)	109

	fetch Associated Press news articles	ap(1)	22
points/ /pldist3, vdiv3, vrem3, pn2f3, pp2f3,	fetch return PC of current function	getcallerpc(2)	485
	fgetpos, ftell, fsetpos, fseek, rewind, feof,/	arith3(2) fopen(2)	375 469
	fgets, gets, fputs, puts, fread, fwrite – Stdio/	fgetc(2)	461
	fgui, userpasswd – authentication agent	factotum(4)	770
wpa –	Fi Protected Access setup	wpa(8)	1082
	fid	clunk(5)	835
	fid for I/O on an existing or new file	open(5)	838
closefid, lookupfid, removefid, Req,/ Fid,	fields getfields,	9pfid(2) getfields(2)	355
	file	access(2)	488 362
assemble a stream of bullshit from words in a		bullshit(1)	40
	file	dd(1)	69
	file exec,	exec(2)	452
	file	fortune(1)	103
	file	httpfile(4)	783
	file	namespace(6)	878
	file open, create, close file open, create	open(2) open(5)	566 838
	file	pr(1)	225
readn, write, pread, pwrite - read or write		read(2)	594
	file	read(5)	840
	file	remove(2)	599
	file sum, md5sum,	sum(1)	288
	file	swap(8)	
	file file	tail(1) touch(1)	291 310
	file	uniq(1)	321
	file	venti.conf(6)	900
	file – determine file type	file(1)	97
	file attributes	stat(5)	842
	file comparator	diff(1)	74
opendirfile,/ Tree, alloctree, freetree,	file control	swap(3)	736 357
	file descriptor	9pfile(2) dup(2)	440
	file descriptor	fd2path(2)	460
	file descriptor	iounit(2)	518
fauth - set up authentication on a	file descriptor to a file server	fauth(2)	456
grep, g – search a	file for a pattern	grep(1)	115
	file for PCs	plan9.ini(8)	
	file for reading or writing, create file file format	open(2) a.out(6)	566 847
	file format	ar(6)	850
	file formats	intro(6)	846
remove – remove a	file from a server	remove(5)	841
	file group	chgrp(1)	46
readdirfile, closedirfile, hasperm – in-memory	file hierarchy /walkfile, opendirfile,	9pfile(2)	357
pipefile - attach filter to obitraverse, isar, nextar, readar - object	file in name space	pipefile(1) object(2)	221 564
	file into pieces	split(1)	280
	file listing	proto(2)	581
mtime – print	file modification time	mtime(1)	190
	file name	mktemp(2)	544
	file name affixes	basename(1)	33
	file name associated with file descriptor file name completion	fd2path(2) complete(2)	460 402
	file name space	namespace(4)	402 791
	file names from the dump	history(1)	147
	file names from the dump	yesterday(1)	344
seek – change	file offset	seek(2)	616
sizeS2M, sizeD2M – interface to Plan 9	File protocol /read9pmsg, statcheck,	fcall(2)	457
intro - introduction to the Plan 9	File Protocol, 9Pfile server	intro(5) boot(8)	830 933
- set up authentication on a file descriptor to a	file server fauth	fauth(2)	955 456
	file server	fsconfig(8)	952
hjfs –	file server	hjfs(4)	782
	file server	upasfs(4)	819
- reboot the system upon loss of remote	file server connection reboot	reboot(8)	1038
	file server, dump cwfs,	$f_{c}(A)$	776
	file server, dump file server maintenance	fs(4) fs(8)	776 947
	file server maintenance	hjfs(8)	975
	file server plumbing	exportfs(4)	767
	· -		

	file server user list format	ucorc(E)	80F
	file servers	users(6) intro(4)	895 749
	file service	9p(2)	349
srv, srvtls, 9fs – start network		srv(4)	811
	file status /wstat, fwstat, dirstat, dirfstat,	stat(2)	626
disc (CD, DVD, B) track reader and writer	file system cdfs, cddb - optical	cdfs(4)	755
	file system	cfs(4)	757
ext2srv – ext2		ext2srv(4)	769
ftpfs - file transfer protocol (FT)		ftpfs(4)	778
hgfs – mercurial		hgfs(4)	780
Infs – long name		Infs(4)	789
mkfs, mkext - archive or update a		mkfs(8)	995
mkpaqfs - make a compressed read-only mksacfs - make a compressed		mkpaqfs(8) mksacfs(8)	996 997
	file system nntpfs	nntpfs(4)	997 796
pagfs – compressed read-only		paqfs(4)	800
plaqis compressed read only playlistfs – playlist		playlistfs(7)	914
ramfs – memory		ramfs(4)	803
ratfs - mail address ratification		ratfs(4)	804
rdbfs – remote kernel debugging	file system	rdbfs(4)	805
root – the root	file system	root(3)	721
sacfs – compressed		sacfs(4)	809
tftpfs - trivial file transfer protocol (TFT)		tftpfs(4)	817
truetypefs – TrueType font		truetypefs(4)	818
vacfs - a Venti-based		vacfs(4)	822
wadfs - WAD		wadfs(4)	823
webfs – world wide web		webfs(4) wikifs(4)	826
wikifs, wikipost – wiki	file system file system client	nfs(4)	828 794
	file system devices	fs(3)	695
	file system for console access	consolefs(4)	760
	file system for flash memory	flashfs(4)	775
mkflashfs – make a journalling	file system for flash memory	mkflashfs(8)	994
plumber –	file system for interprocess messaging	plumber(4)	801
iostats –	file system to measure I/O	iostats(4)	786
fstype – determine	file system type	fstype(1)	106
9660srv, dosmnt, eject - DOS and ISO9660	file systems dossrv,	dossrv(4)	765
	file systems mntgen	mntgen(4)	790
	file systems	tapefs(4)	814
reboot/ . fshalt, scram, reboot – halt any local		fshalt(8)	956
vmr remote login execution and XMODEM	file to unicode con, telnet, rx, hayes, xms,	uhtml(1) con(1)	320 53
sshfs – secure	file transfer protocol client	sshfs(4)	812
	file transfer protocol client	sshnet(4)	813
	file transfer protocol (FT) file system	ftpfs(4)	778
	file transfer protocol (TFT) file system	tftpfs(4)	817
	file type	file(1)	97
	file, with partitions	partfs(8)	
	fileelem, filesym, fileline, fnbound - symbol	symbol(2)	635
setvbuf, setbuf,/ fopen, freopen, fdopen,		fopen(2)	469
cat, read – catenate	files /flacdec, flacenc, sundec, wavdec, files	audio(1) cat(1)	26 44
cmp – compare two		cmp(1)	49
- select or reject lines common to two sorted		comm(1)	52
cp, fcp, mv – copy, move	files	cp(1)	55
dup – dups of open		dup(3)	689
face – face		face(6)	858
hgignore - syntax for Mercurial ignore		hgignore(8)	961
keyfs, warning - authentication database		keyfs(4)	787
	files . /beswal, beswav, leswab, leswal, leswav	mach(2)	529
mk, membername – maintain (make) related mothra – retrieve and display World-Wide Web		mk(1)	179
	files	mothra(1) page(1)	186 208
ger, rung – gueue management for spooled		qer(8)	
rio – window system		rio(4)	806
rm – remove		rm(1)	254
size - print size of executable		size(1)	273
sort - sort and/or merge		sort(1)	275
strip - remove symbols from binary		strip(1)	287
tmpfile, tmpnam - Stdio temporary		tmpfile(2)	647
	files	venti-file(2)	659
	files by drawing with a mouse or other files, face files, etc	paint(1) tweak(1)	210 318
	files for distribution	bundle(1)	41
		Sundie(1)	1 -

	files for Mercurial	hgrc(8)	963
	files for text windows	acme(4)	750
	files in Privacy Enhanced Mail (PE) format	pem(8)	
	files, subfont files, face files, etc.	tweak(1)	318
access/ /globalsym, textsym, file2pc, fileelem,		symbol(2)	635
	filesystem	bzfs(4)	754
	filesystem	kbdfs(8)	986
	filesystem client	cifs(4)	758
	fillarc, icossin, icossin2, border, string,/	draw(2)	432
/replclipr, line, poly, fillpoly, bezier, bezspline,		draw(2)	432
	filter	plot(1)	223
ptrap – plumber (4)	filter	ptrap(4)	802
	filter, list, deliver, token, vf - filtering mail	filter(1)	98
pipefile – attach	filter to file in name space	pipefile(1)	221
scanmail, testscan – spam	filters	scanmail(8)	
look –	find lines in a sorted list	look(1)	167
	find memory leaks	leak(1)	162
	find pages of this manual	man(1)	173
	find source code for executable	src(1)	282
	find spelling errors	spell(1)	277
/machbytype, machbyname, newmap, setmap,		mach(2)	529
/textseg, line2addr, lookup, findlocal, getauto,		symbol(2)	635
mp3dec, mp3enc, oggdec, oggenc, flacdec,		audio(1)	26
language rc, cd, eval, exec, exit,		rc(1)	239
flaakfa januariling fila avatam fan	flash – flash memory	flash(3)	692
	flash memory	flashfs(4)	775
	flash memory	mkflashfs(8)	994
· · · · · · · · ·	flashes prep, edisk, fdisk,	prep(8)	1029
memory	flashfs - journalling file system for flash	flashfs(4)	775
/inflatezlib, inflateblock, inflatezlibblock,		flate(2)	463
getfcr, setfcr, getfsr, setfsr – control		getfcr(2)	487
fmod, floor, ceil – absolute value, remainder,	floating point language	hoc(1)	148 465
prep, edisk, fdisk, format, mbr – prepare disks,	floor, ceiling functions fabs,	floor(2)	1029
prep, euisk, luisk, loimat, mbi – prepare uisks,	floppies and flashes floppy – floppy disk interface	prep(8) floppy(3)	694
	flush – abort a message	flush(5)	837
seaflush –		seqflush(2)	620
	flushimage, bufimage, lockdisplay,/	graphics(2)	492
floor, ceiling functions fabs,		floor(2)	465
	fmt, htmlfmt – simple text formatters	fmt(1)	100
venti/ /conf, fmtarenas, fmtbloom, fmtindex,	fmtisect, syncindex – prepare and maintain a	venti–fmt(8)	
/fmtrunestrcpy, fmtfdinit, fmtfdflush, fmtstrinit,		fmtinstall(2)	466
fmtfdinit,/ fmtinstall, dofmt, dorfmt, fmtprint,	fmtvprint, fmtrune, fmtstrcpy, fmtrunestrcpy,	fmtinstall(2)	466
/textsym, file2pc, fileelem, filesym, fileline,		symbol(2)	635
tap -	follow the pipes of a process	tap(1)	292
agefont, loadchar, Subfont, Fontchar,		cachechars(2)	395
	font file system	truetypefs(4)	818
subfonts		font(6)	859
	Fontchar, Font - font utilities	cachechars(2)	395
sopenw, sclose, fflush, setvbuf, setbuf, /		fopen(2)	469
	foreign character set HTML file to unicode	uhtml(1)	320
	fork, rfork - manipulate process resources	fork(2)	472
	format	a.out(6)	847
	format	ar(6)	850
	format	mdir(6)	872
	format memory	memory(8)	991
	format pemdecode, pemencode	pem(8)	
	format	splitmbox(8)	
	format	users(6)	895
	format	utf(6)	896
	format for fonts and subfonts	font(6)	859
	format for images	image(6)	864
flashes prep, edisk, fdisk,		prep(8)	
	format of plumb messages and rules	plumb(6)	884
	format rsa keys /rsa2asn1, rsa2pub,	rsa(8)	
	format tables for nroff or troff	tbl(1)	295
	formats	intro(6)	846
map - digitized map	formats	map(6)	871
	formats /vtrootpack, vtrootunpack,	venti-fcall(2)	657 466
	formats and output routines formatted input	fmtinstall(2) fscanf(2)	
	formatted output /printf, sprintf, snprintf,	fprintf(2)	481 474
	formatted output /printi, sprinti, suprinti, formatted output /vsmprint, runevsnprint,	print(2)	576
	formatters	fmt(1)	100

	formatting a document	doctype(1)	78
	formatting and sending mail	marshal(1)	174
	formatting and typesetting	htmlroff(1)	150
	formatting and typesetting	htmlroff(6)	861 314
	formatting and typesetting	troff(1) mhtml(6)	873
ms – macros for	formatting manuscripts	ms(6)	876
deroff – remove	formatting requests	deroff(1)	72
	forp – formula prover	forp(1)	101
	fortune, theo, troll - sample lines from a file	fortune(1)	103
trampoline -	forward incoming calls to another address	trampoline(8)	1068
/ciscframe, riscframe, localaddr, symoff,	fpformat, beieee80ftos, beieeesftos,/	debugger(2)	422
	fplot - plot elementary function	fplot(1)	104
runesprint, runesnprint, runeseprint,/ print,	fprint, sprint, snprint, seprint, smprint,	print(2)	576
vprintf, vsprintf, vsnprintf – print formatted/	fprintf, printf, sprintf, snprintf, vfprintf,	fprintf(2)	474
/fputc, putc, putchar, ungetc, fgets, gets,	fputs, puts, fread, fwrite – Stdio input and /	fgetc(2)	461
Network Computing (VN) . vncs, vncv – remote crop, iconv –	frame buffer server and viewer for Virtual frame, crop, and convert image	vnc(1) crop(1)	331 59
ntruerand, genrandom, prng,/ rand, Irand,	frand, nrand, Inrand, srand, truerand,	rand(2)	591
frselect,/ frinit, frsetrects, frinittick, frclear,	frcharofpt, frptofchar, frinsert, frdelete,	frame(2)	477
/frinsert, frdelete, frselect, frtick, frselectpaint,	frdrawsel, frdrawsel0, frgetmouse – frames of/	frame(2)	477
putc, putchar, ungetc, fgets, gets, fputs, puts,	fread, fwrite – Stdio input and output . /fputc,	fgetc(2)	461
malloc, mallocz, smalloc, realloc,	free, msize, secalloc, secfree, setmalloctag,/	malloc(9)	
setrealloctag,/ . malloc, mallocalign, mallocz,	free, realloc, calloc, msize, setmalloctag,	malloc(2)	532
blockalloclen, readblist,/ allocb, iallocb, freeb,	freeblist, BLEN, BALLOC, blocklen,	allocb(9)	1085
/ctlstrdup, ctlprint, deactivate, freectlfont,	freectlimage, initcontrols, namectlfont,/	control(2)	403
parsehtml, printitems, validitems, freeitems,	freedocinfo, dimenkind, dimenspec, targetid,/	html(2)	496
removefid, Req,/ Fid, Fidpool, allocfidpool,	freefidpool, allocfid, closefid, lookupfid,	9pfid(2)	355
/unlockdisplay, openfont, buildfont,	freefont, Pfmt, Rfmt, strtochan, chantostr,/	graphics(2)	492
setalpha,/ allocimage, allocimagemix,	freeimage, nameimage, namedimage,	allocimage(2)	367
bytesperline, wordsperline – allocating, parsehtml, printitems, validitems,	freeing, reading, writing images /writeimage, freeitems, freedocinfo, dimenkind,/	allocimage(2) html(2)	367 496
deletekey – integer to data/ Intmap, allocmap,	freemap, insertkey, caninsertkey, lookupkey,	intmap(2)	515
/creadmemimage, writememimage,	freememimage, memsetchan, loadmemimage,/	memdraw(2)	536
/allocmemsubfont, openmemsubfont,	freememsubfont, memsubfontwidth,/	memdraw(2)	536
/reject, netmkaddr, setnetmtpt, getnetconninfo,	freenetconninfo - make and break network/	dial(2)	427
/removefid, Req, Reqpool, allocreqpool,	freereqpool, allocreq, closereq, lookupreq,/	9pfid(2)	355
Screen, allocscreen, publicscreen,	freescreen, allocwindow, bottomwindow,/	window(2)	668
uninstallsubfont, subfontname,/ allocsubfont,	freesubfont, installsubfont, lookupsubfont,	subfont(2)	633
pushtls, tlsClient, tlsServer, initThumbprints,	freeThumbprints, okThumbprint,/	pushtls(2)	583
walkfile, opendirfile, / Tree, alloctree,	freetree, File, createfile, closefile, removefile,	9pfile(2)	357
sopenw, sclose, fflush, setvbuf,/ fopen,	freopen, fdopen, fileno, fclose, sopenr,	fopen(2)	469
frequenciesexponent	freq – print histogram of character frexp, Idexp, modf – split into mantissa and	freq(1) frexp(2)	105 480
frtick, frselectpaint, frdrawsel, frdrawsel0,	frgetmouse – frames of text /frselect,	frame(2)	477
frptofchar, frinsert, frdelete, frselect, frtick,/	frinit, frsetrects, frinittick, frclear, frcharofpt,	frame(2)	477
dimenkind, dimenspec, targetid, targetname,	fromStr, toStr - HTML parser /freedocinfo,	html(2)	496
frinit, frsetrects, frinittick, frclear, frcharofpt,	frptofchar, frinsert, frdelete, frselect, frtick,/ .	frame(2)	477
/frptofchar, frinsert, frdelete, frselect, frtick,	frselectpaint, frdrawsel, frdrawsel0,/	frame(2)	477
frptofchar, frinsert, frdelete, frselect,/ . frinit,		frame(2)	477
/frptofchar, frinsert, frdelete, frselect,	frtick, frselectpaint, frdrawsel, frdrawsel0,/	frame(2)	477
	fs – file server, dump fs – file system devices	fs(4)	776 695
	fs, exsort – file server maintenance	fs(3) fs(8)	947
/cwfs64, cwfs64x,		13(0)	547
input	fscanf, scanf, sscanf, vfscanf - scan formatted	fscanf(2)	481
P	fsconfig - configuring a file server	fsconfig(8)	952
/sclose, fflush, setvbuf, setbuf, fgetpos, ftell,	fsetpos, fseek, rewind, feof, ferror, clearerr -/	fopen(2)	469
systems and optionally shut down or reboot/ .	fshalt, scram, reboot - halt any local file	fshalt(8)	956
dirfwstat, nulldir - get and put file/ stat,	fstat, wstat, fwstat, dirstat, dirfstat, dirwstat,	stat(2)	626
	fstype – determine file system type	fstype(1)	106
	FT) file system	ftpfs(4)	778
/sclose, fflush, setvbuf, setbuf, fgetpos, daemons telnetd, rlogind, rexexec,	ftell, fsetpos, fseek, rewind, feof, ferror,/ ftpd, socksd, hproxy – Internet remote access	fopen(2)	469 984
uaemons temeta, nogina, rexexec,	ftpfs – file transfer protocol (FT) file system	ipserv(8) ftpfs(4)	778
runetochar, chartorune, runelen, runenlen,	fullrune, utfecpy, utflen, utfnlen, utfrune,/	rune(2)	603
negotiate version	fversion – initialize 9P connection and	fversion(2)	484
putchar, ungetc, fgets, gets, fputs, puts, fread,	fwrite - Stdio input and output /fputc, putc,	fgetc(2)	461
nulldir - get and put file/ stat, fstat, wstat,	fwstat, dirstat, dirfstat, dirwstat, dirfwstat,	stat(2)	626
grep,	g - search a file for a pattern	grep(1)	115
simulations	galaxy - representations of n-body	galaxy(6)	860
ready whitey pready provident	galaxy, mkgalaxy – galactic n-body simulator .	galaxy(1)	107
readv, writev, preadv, pwritev –	gather read and write	readv(2) nintendo(1)	596 201
gb,	yba, nes, snes - ennuators	millenuo(1)	201

4s, 5s, blabs, catclock, doom, festoon,	geigerstats, glendy, juggle, life, mandel,/	games(1)	109
poly, fillpoly, bezier, bezspline,/ Image, draw,	gendraw, drawreplxy, drawrepl, replclipr, line,	draw(2)	432
smallprimetest - prime number	generation /DSAprimes, probably_prime,	prime(2)	575
prng, fastrand, nfastrand - random number	generators /ntruerand, genrandom,	rand(2)	591
opendisk, Disk -	generic disk device interface	disk(2)	431
/closedisplay, getdefont, getwindow,	gengetwindow, flushimage, bufimage, /	graphics(2)	492
Display, Point, Rectangle, Cursor, initdraw,	geninitdraw, newwindow, drawerror,/	graphics(2)	492
dmid – MIDI to OPL3 converter using	GENMIDI-type instrument banks	dmid(1)	76
/nrand, Inrand, srand, truerand, ntruerand,	genrandom, prng, fastrand, nfastrand -/	rand(2)	591
probably_prime, smallprimetest -/ . genprime,	gensafeprime, genstrongprime, DSAprimes, Geometric transformations /rot, grot, scale,	prime(2)	575 534
move, xform, ixform, persp, look, viewport – put8,/ /unusemap, loadmap, attachproc, get1,	get2, get4, get8, geta, put1, put2, put4,	matrix(2) mach(2)	529
/pc2line, textseq, line2addr, lookup, findlocal,	getauto, findsym, localsym, globalsym,/	symbol(2)	635
function	getcallerpc – fetch return PC of current	getcallerpc(2)	485
gets, fputs, puts, fread, fwrite -/ . fgetc, getc,	getchar, fputc, putc, putchar, ungetc, fgets,	fgetc(2)	461
/drawerror, initdisplay, closedisplay,	getdefont, getwindow, gengetwindow,/	graphics(2)	492
/classname, closedev, configdev, devctl,	getdev, loaddevstr, opendev, opendevdata,/	nusb(2)	560
variables	getenv, putenv - access environment	getenv(2)	486
point	getfcr, setfcr, getfsr, setfsr - control floating	getfcr(2)	487
into fields	getfields, gettokens, tokenize - break a string	getfields(2)	488
shell scripts	getflags, usage - command-line parsing for	getflags(8)	957
getfcr, setfcr,	getfsr, setfsr - control floating point	getfcr(2)	487
calloc, msize, setmalloctag, setrealloctag,	getmalloctag, getrealloctag,/ /free, realloc,	malloc(2)	532
/secalloc, secfree, setmalloctag, setrealloctag,	getmalloctag, getrealloctag - kernel memory/ .	malloc(9)	
	getmap, colors - display color map	colors(1)	51
drawing/ /freememsubfont, memsubfontwidth,	getmemdefont, memimagestring, hwdraw –	memdraw(2)	536
/listen, accept, reject, netmkaddr, setnetmtpt,	getnetconninfo, freenetconninfo - make and/ .	dial(2)	427
getpid,	getppid – get process ids	getpid(2)	489 1095
/setmalloctag, setrealloctag, getmalloctag, /setmalloctag, setrealloctag, getmalloctag,	getrealloctag, malloctopoolblock – memory/	malloc(9) malloc(2)	532
initmouse, readmouse, closemouse, moveto,	getrect, drawgetrect, menuhit, setcursor,/	mouse(2)	545
/getchar, fputc, putc, putchar, ungetc, fgets,	gets, fputs, puts, fread, fwrite – Stdio input/	fgetc(2)	461
line2addr, lookup, findlocal,/ syminit,	getsym, symbase, pc2sp, pc2line, textseg,	symbol(2)	635
fields getfields,	gettokens, tokenize – break a string into	getfields(2)	488
	getuser, sysname - get user or system name	getuser(2)	490
	getwd – get current directory	getwd(2)	491
/drawerror, initdisplay, closedisplay, getdefont,	getwindow, gengetwindow, flushimage,/	graphics(2)	492
interpreter) gs - Aladdin	Ghostscript (PostScript and PDF language	gs(1)	116
tojpg, togeordi, togif, toppm, topng,/ jpg,	gif, png, tif, ppm, bmp, v210, yuv, ico, tga,	jpg(1)	156
blabs, catclock, doom, festoon, geigerstats,	glendy, juggle, life, mandel, mahjongg,/ /5s,	games(1)	109
shr –	global mountpoints	shr(3)	732
/lookup, findlocal, getauto, findsym, localsym,	globalsym, textsym, file2pc, fileelem, filesym,/	symbol(2)	635
date and time ctime, localtime,	gmtime, asctime, tm2sec, timezone – convert . go.fishing – mail and mailboxes	ctime(2)	419 172
mail, setjmp, longjmp, notejmp – non-local	goto	mail(1) setjmp(2)	622
Internet ping,		ping(8)	1015
	gpsevermore – GPS time and position service	qpsfs(8)	959
9533,	grap – pic preprocessor for drawing graphs	grap(1)	112
	graph – draw a graph	graph(1)	114
statusbar, statusmsg – display a bar	graph or status message window	statusbar(8)	1061
gview - interactive	graph viewer	gview(1)	119
output files page - view FAX, image,	graphic, PostScript, PDF, and typesetter	page(1)	208
newcontrolset, resizecontrolset - interactive	graphical controls /namectlimage,	control(2)	403
runestringwidth, runestringnwidth –	graphical size of strings /runestringsize,	stringsize(2)	632
draw – screen		draw(3)	685
strtochan, chantostr, chantodepth – interactive	graphics /buildfont, freefont, Pfmt, Rfmt,	graphics(2)	492
emoveto, esetcursor, Event, Mouse, Menu – – plot	graphics events /emenuhit, eenter, graphics filter	event(2) plot(1)	449 223
_string, ARROW, drawsetdebug -	graphics functions PB L /runestringnbg,	draw(2)	432
- string, Akkow, drawsetdebug	graphics interface	plot(6)	882
grap – pic preprocessor for drawing	graphs	grap(1)	112
stats – display		stats(8)	
network protocols over IP ip, esp,		ip(3)	698
	grep, g - search a file for a pattern	grep(1)	115
	group	chgrp(1)	46
postnote - send a note to a process or process	group	postnote(2)	574
cons – console, clocks, process/process	group ids, user, null, reboot, etc.	cons(3)	683
binalloc, bingrow, binfree -	grouped memory allocation	bin(2)	387
language interpreter)	gs - Aladdin Ghostscript (PostScript and PDF	gs(1)	116
/printnetkey, status, enable, disable, authsrv,		auth(8)	930
uncomprose zin unzin comprose and	gview – interactive graph viewer	gview(1)	119 121
uncompress, zip, unzip - compress and/ /HSPairs, hmydomain, hversion, htmlesc,	gzip, gunzip, bzip2, bunzip2, compress, halloc, hbodypush, hbuflen, hcheckcontent,/	gzip(1) httpd(2)	508
down or reboot the/ fshalt, scram, reboot -	halt any local file systems and optionally shut	fshalt(8)	956
asim of repose the ₁ · · · · · · · · · · · · · · · · · · ·	have any rocar me systems and optionary shut .	151141(0)	550

		······································	
intrdisable – enable (disable) an interrupt	handle asynchronous process notification handler intrenable,	notify(2) intrenable(9)	558
ecp – fast copy,	handling errors	ecp(1)	84
error, nexterror, poperror, waserror – error	handling functions	error(9)	
netmkaddr, setnetmtpt, getnetconninfo,/ dial,	hangup, announce, listen, accept, reject,	dial(2)	427
uptime – show how long the system	has been running	uptime(1)	323
poly1305 - cryptographically secure	hashes /hmac_sha2_384, hmac_sha2_512,	sechash(2)	614
/walkfile, opendirfile, readdirfile, closedirfile,	hasperm – in-memory file hierarchy	9pfile(2)	357
and XMODEM file transfer con, telnet, rx,	hayes, xms, xmr – remote login, execution,	con(1)	53
chacha/ /chacha_encrypt, chacha_encrypt2,	hchacha, ccpoly_encrypt, ccpoly_decrypt	chacha(2)	398
HFields, Hio, Htmlesc, HttpHead, HttpReq,/ /hbodypush, hbuflen, hcheckcontent, hclose,	HConnect, HContent, HContents, HETag, hdate2sec, hdatefmt, hfail, hflush, hgetc, /	httpd(2) httpd(2)	508 508
leak, kmem, umem -	help find memory leaks	leak(1)	162
panic – abandon hope, all ye who enter	here	panic(9)	
HttpReg,/ HConnect, HContent, HContents,	HETag, HFields, Hio, Htmlesc, HttpHead,	httpd(2)	508
xd -	hex, octal, decimal, or ASCII dump	xd(1)	341
/hcheckcontent, hclose, hdate2sec, hdatefmt,	hfail, hflush, hgetc, hgethead, hinit, hiserror,/	httpd(2)	508
HConnect, HContent, HContents, HETag,	HFields, Hio, Htmlesc, HttpHead, HttpReq,/	httpd(2)	508
hload,/ /hclose, hdate2sec, hdatefmt, hfail,	hflush, hgetc, hgethead, hinit, hiserror,	httpd(2)	508
system	hg – Mercurial source code management	hg(1)	123
post to a web page corresponding to a url /hdate2sec, hdatefmt, hfail, hflush, hgetc,	hget, hpost, webpaste, urlencode – retrieve,	hget(1) httpd(2)	145 508
/indatezsee, indaterint, inali, infusii, ligete,	hgfs – mercurial file system	hqfs(4)	780
	hgignore – syntax for Mercurial ignore files	hgignore(8)	961
	hgrc – configuration files for Mercurial	hqrc(8)	963
closedirfile, hasperm – in-memory file	hierarchy /walkfile, opendirfile, readdirfile,	9pfile(2)	357
walk - descend a directory	hierarchy	walk(5)	845
muldiv, umuldiv –	high-precision multiplication and division	muldiv(2)	552
/HContent, HContents, HETag, HFields,	Hio, Htmlesc, HttpHead, HttpReq, HRange,/	httpd(2)	508
/hdatefmt, hfail, hflush, hgetc, hgethead, hinit,	hiserror, hload, hlower, hmkcontent,/	httpd(2)	508
frog print	histogram – draw a histogram histogram of character frequencies	histogram(8) freq(1)	974 105
neq - princ	history – print file names from the dump	history(1)	147
	hjfs – file server	hjfs(4)	782
	hjfs – file server maintenance	hjfs(8)	975
hflush, hgetc, hgethead, hinit, hiserror, hload,	hlower, hmkcontent, hmkhfields,/ /hfail,	httpd(2)	508
hmac_md5, hmac_sha1, hmac_sha2_224,	hmac_sha2_256, hmac_sha2_384,/ . /hmac_x,	sechash(2)	614
secure/ /hmac_sha2_256, hmac_sha2_384,	hmac_sha2_512, poly1305 - cryptographically	sechash(2)	614
sha2_224, sha2_256, sha2_384, sha2_512,	hmac_x, hmac_md5, hmac_sha1,/ /sha1,	sechash(2)	614
/hgetc, hgethead, hinit, hiserror, hload, hlower,	hmkcontent, hmkhfields, hmkmimeboundary,/	httpd(2)	508
/hinit, hiserror, hload, hlower, hmkcontent, /hmkhfields, hmkmimeboundary, hmkspairs,	hmkhfields, hmkmimeboundary, hmkspairs,/	httpd(2) httpd(2)	508 508
Htmlesc, HttpHead, HttpReq, HRange, HSPairs,	hmydomain, hversion, htmlesc, halloc,/ /Hio,	httpd(2)	508
/nhgetv, nhgetl, nhgets, hnputv, hnputl,	hnputs, ptclbsum, readipifc – Internet/	ip(2)	519
,	hoc – interactive floating point language	hoc(1)	148
ping, gping, traceroute,	hogports – probe the Internet	ping(8)	1015
/hmkmimeboundary, hmkspairs, hmoved,	hokheaders, hparseheaders, hparsequery,/	httpd(2)	508
	hold – simple text editor	hold(1)	149
keys.who - biographic information for key	holders	keys.who(6)	868
	hope, all ye who enter here	panic(9)	741
storage device/ sdahci – AHCI (Advanced		usb(3) sdahci(3)	741
cmd – interface to	host operating system commands	cmd(3)	681
os – interface to		os(1)	206
uptime – show		uptime(1)	323
keyboard -	how to type characters	keyboard(6)	866
/hmoved, hokheaders, hparseheaders,	hparsequery, hparsereq, hprint, hputc,/	httpd(2)	508
a web page corresponding to a url hget,	hpost, webpaste, urlencode – retrieve, post to .	hget(1)	145
telnetd, rlogind, rexexec, ftpd, socksd,	hproxy – Internet remote access daemons	ipserv(8)	984
/HFields, Hio, Htmlesc, HttpHead, HttpReq, /hparsequery, hparsereq, hprint, hputc,	HRange, HSPairs, hmydomain, hversion,/ hreadbuf, hredirected, hregcleanup,/	httpd(2) httpd(2)	508 508
/hputc, hreadbuf, hredirected, hreqcleanup,	hrevhfields, hrevspairs, hstrdup, http11,/	httpd(2)	508
salsa_setiv, salsa_encrypt, salsa_encrypt2,	hsalsa – salsa20 encryption . /salsa_setblock,	salsa(2)	606
/hreqcleanup, hrevhfields, hrevspairs,	hstrdup, http11, httpfmt, httpunesc,/	httpd(2)	508
mhtml - macros for formatting	HTML	mhtml(6)	873
- convert between troff's ms macros and	html ms2html, html2ms	ms2html(1)	189
troff2html – convert troff output into	HTML	troff2html(1)	316
uhtml – convert foreign character set – htmlroff	HTML file to unicode	uhtml(1) htmlroff(1)	320 150
htmiroff –	HTML formatting and typesetting HTML formatting and typesetting	htmlroff(6)	861
targetid, targetname, fromStr, toStr –	HTML parser /dimenkind, dimenspec,	html(2)	496
and html ms2html,	html2ms - convert between troff's ms macros .	ms2html(1)	189
/HRange, HSPairs, hmydomain, hversion,	htmlesc, halloc, hbodypush, hbuflen,/	httpd(2)	508
/HContent, HContents, HETag, HFields, Hio,	Htmlesc, HttpHead, HttpReq, HRange,/	httpd(2)	508

¢ .		5 (1)	100
fmt,	htmlfmt – simple text formatters htmlroff – HTML formatting and typesetting	fmt(1) htmlroff(1)	100 150
	htmlroff – HTML formatting and typesetting	htmlroff(6)	861
webcookies -	HTTP cookie manager		825
/hreqcleanup, hrevhfields, hrevspairs, hstrdup,	http11, httpfmt, httpunesc, hunallowed,/	httpd(2)	508
	httpd – HTTP server	rc-httpd(8) httpd(8)	1035 977
HTTP server	httpfile – serve a single web file	httpfile(4)	783
/HContents, HETag, HFields, Hio, Htmlesc,	HttpHead, HttpReq, HRange, HSPairs,/	httpd(2)	508
/hrevspairs, hstrdup, http11, httpfmt,	httpunesc, hunallowed, hungetc, hunload,/	httpd(2)	508
since epoch seconds – convert	human-readable date (and time) to seconds	seconds(1)	264
memory – print memory statistics in /hstrdup, http11, httpfmt, httpunesc,	human-readable format	memory(8) httpd(2)	991 508
/http11, httpfmt, httpunesc, hunallowed,	hungetc, hunload, hurlfmt, hurlunesc,/	httpd(2)	508
/HttpReq, HRange, HSPairs, hmydomain,	hversion, htmlesc, halloc, hbodypush,/	httpd(2)	508
/hungetc, hunload, hurlfmt, hurlunesc,	hvprint, hwrite, hxferenc, - routines for/	httpd(2)	508
/getmemdefont, memimagestring,	hwdraw - drawing routines for	memdraw(2)	536
/hungetc, hunload, hurlfmt, hurlunesc, hvprint, sinh, cosh, tanh -	hwrite, hxferenc, – routines for creating an/ hyperbolic functions	httpd(2) sinh(2)	508 624
Sini, cosi, tani	hypot – Euclidean distance	hypot(2)	513
times and time/ seconds, ticks, fastticks,	HZ, MS2HZ, MS2TK, TK2MS, TK2SEC – kernel	seconds(9)	
scheddump, schedinit,/anyhigher, anyready,	hzsched, procpriority, procrestore, procsave,	sched(9)	
Interface Association (PCMCI) device blocklen, blockalloclen, readblist,/ allocb,	i82365 – Personal Computer Memory Card iallocb, freeb, freeblist, BLEN, BALLOC,	i82365(3) allocb(9)	697
interface (TWS) and inter–integrated circuit		twsi(3)	739
interface (1105) and inter-integrated encare	icanhasmsi – print MSI configuration	icanhasmsi(8)	979
cpuid,	icanhasvmx - print processor information	cpuid(8)	939
protocols over IP ip, esp, gre, icmp,	icmpv6, ipmux, rudp, tcp, udp, il – network	ip(3)	698
totif,/ jpg, gif, png, tif, ppm, bmp, v210, yuv, mug - convert an image to a face	ico, tga, tojpg, togeordi, togif, toppm, topng, .	jpg(1) mug(1)	156 191
crop,	iconv – frame, crop, and convert image	crop(1)	59
/ellipse, fillellipse, arc, fillarc, icossin,	icossin2, border, string, stringn, runestring,/ .	draw(2)	432
cap – capabilities for setting the user	id of processes	cap(3)	680
invertmat, xformpoint, xformpointd,/	ident, matmul, matmulr, determinant, adjoint, identify a PCMCIA card	matrix(2) pcmcia(8)	534
penicia -	idiff – interactive diff	idiff(1)	151
names to and from unicode utf2idn,	idn2utf - convert internationalized domain	idn(2)	514
/leieee80ftos, leieeesftos, leieeedftos,	ieeesftos, ieeedftos - machine-independent/ .	debugger(2)	422
hgignore – syntax for Mercurial esp, gre, icmp, icmpv6, ipmux, rudp, tcp, udp,	ignore filesin	hgignore(8)	961 698
crop, iconv – frame, crop, and convert	il – network protocols over IP ip, image	ip(3) crop(1)	59
dump9660, mk9660 - create an ISO-9660 CD	image	mk9660(8)	992
· · · · · · · · · · · · · · · · · · ·	image - external format for images	image(6)	864
replclipr, line, poly, fillpoly, bezier,/	Image, draw, gendraw, drawreplxy, drawrepl, .	draw(2)	432 210
pointing device paint - create tweak - edit	image files by drawing with a mouse or other . image files, subfont files, face files, etc.	paint(1) tweak(1)	318
typesetter output files page – view FAX,	image, graphic, PostScript, PDF, and	page(1)	208
mug – convert an	image to a face icon	mug(1)	191
httpd, save,	imagemap, man2html, webls - HTTP server	httpd(8)	977
 allocating, freeing, reading, writing image – external format for 	images /bytesperline, wordsperline images	allocimage(2) image(6)	367 864
- drawing routines for memory-resident		memdraw(2)	536
memltorearn - windows of memory-resident	images /memltofrontn, memltorear,	memlayer(2)	540
pop3,	imap4d - Internet mail servers		1026
oexportfs - legacy exportfs for cpu and system	import	oexportfs(4) import(4)	799 784
outsb, outss, outsl – programmed I/O	inb, ins, inl, outb, outs, outl, insb, inss, insl,	inb(9)	-
trampoline - forward	incoming calls to another address	trampoline(8)	
/wunlock, rsleep, rwakeup, rwakeupall,	incref, decref – spin locks, queueing/	lock(2)	526
/beswal, beswav, leswab, leswal, leswav - /leieeesftos, leieeedftos, ieeesftos, ieeedftos -	independent access to executable files	mach(2) debugger(2)	529 422
functions NaN,	Inf, isNaN, isInf – not–a–number and infinity	nan(2)	553
/deflatezlibblock, inflateinit, inflate, inflatezlib,	inflateblock, inflatezlibblock, flateerr,/	flate(2)	463
dns, dnstcp, dnsquery, dnsdebug, dnsgetip,	inform - network database /cs, csquery,		1000
astro – print astronomical	informationinformation	astro(7) cpuid(8)	905 939
cpuid, icanhasvmx – print processor sysinfo, sysupdate – report	information about, update the system	sysinfo(1)	290
arch – architecture–specific	information and control	arch(3)	675
keys.who - biographic	information for key holders	keys.who(6)	868
(Allowing departicute frequelle at frequelling and	init – initialize machine upon booting	init(8)	980
/ctlprint, deactivate, freectlfont, freectlimage, initdisplay,/ Display, Point, Rectangle, Cursor,	initcontrols, namectlfont, namectlimage,/ initdraw, geninitdraw, newwindow, drawerror, .	control(2) graphics(2)	403 492
fversion –	initialize 9P connection and negotiate version .	fversion(2)	484
init –	initialize machine upon booting	init(8)	980

keyboard control			
	initkeyboard, ctlkeyboard, closekeyboard	keyboard(2)	525
getrect, drawgetrect, menuhit, setcursor,/	initmouse, readmouse, closemouse, moveto,	mouse(2)	545
okThumbprint,/ . pushtls, tlsClient, tlsServer,	initThumbprints, freeThumbprints,	pushtls(2)	583
outss, outsl - programmed I/O inb, ins,	inl, outb, outs, outl, insb, inss, insl, outsb,	inb(9)	
fscanf, scanf, sscanf, vfscanf - scan formatted	input	fscanf(2)	481
fgets, gets, fputs, puts, fread, fwrite – Stdio	input and output /putc, putchar, ungetc,	fgetc(2)	461
zerotrunc – truncate	input on zero byte	zerotrunc(8)	
Bterm, Bbuffered, Blethal, Biofn – buffered	input/output . /Bprint, Bvprint, Bwrite, Bflush,	bio(2)	390
feof, ferror, clearerr – standard buffered	input/output package /fseek, rewind,	fopen(2)	469
stat, wstat –	inquire or change file attributes	stat(5)	842
programmed/ inb, ins, inl, outb, outs, outl,	insb, inss, insl, outsb, outss, outsl	inb(9)	
- integer to data/ Intmap, allocmap, freemap,	insertkey, caninsertkey, lookupkey, deletekey .	intmap(2)	515
/subpt, mulpt, divpt, rectaddpt, rectsubpt,	insetrect, canonrect, eqpt, eqrect, ptinrect,/	addpt(2)	363
I/O inb, ins, inl, outb, outs, outl, insb,	inss, insl, outsb, outss, outsl - programmed	inb(9)	1092
uninstallsubfont, / . allocsubfont, freesubfont,	installsubfont, lookupsubfont,	subfont(2)	633
seqflush – flush	instruction and data caches	segflush(2)	620
5i, ki, vi, qi -	instruction simulators	vi(1)	327
- MIDI to OPL3 converter using GENMIDI-type	instrument banks dmid	dmid(1)	76
twsi - two-wire serial interface (TWS) and	integrated circuit (I ² C) interface	twsi(3)	739
scheddump, schedinit, sched, yield – scheduler	interactions /procrestore, procsave,	sched(9)	1102
pnp – Plug 'n' Play ISA and PCI	Interfaces	pnp(3)	715
twsi - two-wire serial interface (TWS) and	inter-integrated circuit (I ² C) interface	twsi(3)	739
unicode utf2idn, idn2utf - convert	internationalized domain names to and from .	idn(2)	514
ping, gping, traceroute, hogports - probe the	Internet	ping(8)	1015
dhcpd, dhcp6d, dhcpleases, rarpd, tftpd -	Internet booting	dhcpd(8)	943
ipconfig, rip, linklocal –	Internet configuration and routing	ipconfig(8)	981
pop3, imap4d -	Internet mail servers	pop3(8)	
hnputv, hnputl, hnputs, ptclbsum, readipifc -	Internet Protocol addressing . /nhgetl, nhgets,	ip(2)	519
ircrc -	internet relay chat client	ircrc(1)	153
rlogind, rexexec, ftpd, socksd, hproxy -	Internet remote access daemons telnetd,	ipserv(8)	984
ascii. unicode -	interpret ASCII, Unicode characters	ascii(1)	24
ktrace –	interpret kernel stack dumps	ktrace(1)	161
objtraverse, isar, nextar, readar – object file		object(2)	564
programming language python – an	interpreted, interactive, object-oriented	python(1)	233
pipe - create an	interprocess channel	pipe(2)	568
pipe - two-way	interprocess communication	pipe(2)	714
plumber – file system for	interprocess messaging	plumber(4)	801
intrenable, intrdisable – enable (disable) an	interrupt handler	intrenable(9)	
- kernel process creation, termination and	interruption kproc, pexit, postnote	kproc(9)	
microdelay, addclock0link – small delays, clock	interrupts delay,	delay(9)	
splhi, spllo, splx, islo – enable and disable	interrupts		
caninsertkey, lookupkey, deletekey – integer/			1105
cannisenergy, noor apress, acherer = nilegen / .		•	1105
	Intmap, allocmap, freemap, insertkey,	intmap(2)	515
interrupt handler	intrenable, intrdisable - enable (disable) an	intmap(2) intrenable(9)	515 1093
interrupt handlerintro -	intrenable, intrdisable - enable (disable) an introduction to databases	intmap(2) intrenable(9) intro(7)	515 1093 904
interrupt handlerintro - intro - intro -	intrenable, intrdisable – enable (disable) an introduction to databases	intrenable(9) intrenable(7) intro(7) intro(6)	515 1093 904 846
interrupt handlerintro - intro - intro - intro -	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers	intmap(2) intrenable(9) intro(7) intro(6) intro(4)	515 1093 904 846 749
interrupt handlerintro - intro - intro - intro - intro - intro -	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(9)	515 1093 904 846 749 1084
interrupt handlerintro - intro - intro - intro - intro - intro - intro - intro -	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(9) intro(2)	515 1093 904 846 749 1084 346
interrupt handlerintro - intro - intro - intro - intro - intro - intro - intro - intro - intro -	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions introduction to Plan 9	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(9) intro(2) intro(1)	515 1093 904 846 749 1084 346 1
interrupt handlerintro – intro –	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions introduction to Plan 9 introduction to system administration	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(9) intro(2) intro(1) intro(8)	515 1093 904 846 749 1084 346 1 918
interrupt handlerintro - intro -	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions introduction to Plan 9 introduction to system administration introduction to the Plan 9 devices	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(9) intro(2) intro(1) intro(1) intro(8) intro(3)	515 1093 904 846 749 1084 346 1 918 670
interrupt handlerintro – intro –	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions introduction to Plan 9 introduction to system administration introduction to the Plan 9 devices introduction to the Plan 9 File Protocol, 9P	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(9) intro(2) intro(2) intro(1) intro(8) intro(3) intro(5)	515 1093 904 846 749 1084 346 1 918 670 830
interrupt handlerintro – intro –	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions introduction to Plan 9 introduction to system administration introduction to the Plan 9 devices introduction to the Plan 9 File Protocol, 9P intuit command line for formatting a	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(9) intro(2) intro(1) intro(1) intro(3) intro(5) doctype(1)	515 1093 904 846 749 1084 346 1 918 670 830 78
interrupt handler intro - intro - otro - intro -	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions introduction to Plan 9 introduction to system administration introduction to the Plan 9 devices introduction to the Plan 9 File Protocol, 9P intuction to the Plan 9 File Protocol, 9P intuction to the Plan 9 a	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(9) intro(2) intro(1) intro(8) intro(8) intro(3) doctype(1) assert(2)	515 1093 904 846 749 1084 346 1 918 670 830 78 377
interrupt handler intro – intro	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions introduction to Plan 9 introduction to system administration introduction to the Plan 9 devices introduction to the Plan 9 File Protocol, 9P introduction to the Plan 9 File Protocol, 9P intvariants invariants	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(9) intro(2) intro(1) intro(3) intro(3) intro(3) intro(5) doctype(1) assert(2) matrix(2)	515 1093 904 846 749 1084 346 1 918 670 830 78 377 534
interrupt handler intro – intro	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions introduction to Plan 9 introduction to system administration introduction to the Plan 9 devices introduction to the Plan 9 File Protocol, 9P intuction to the Plan 9 File Protocol, 9P intvariants invertmat, xformpoint, xformpointd,/ I/O inb, ins, inl, outb, outs, outl, insb,	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(9) intro(2) intro(1) intro(3) intro(3) intro(3) intro(5) doctype(1) assert(2) matrix(2) inb(9)	515 1093 904 846 749 1084 346 1 918 670 830 78 377 534 1092
interrupt handler intro – intro	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions introduction to Plan 9 introduction to Plan 9 introduction to the Plan 9 devices introduction to the Plan 9 File Protocol, 9P intuit command line for formatting a invariants invertmat, xformpoint, xformpointd,/ I/O inb, ins, inl, outb, outs, outl, insb, I/O	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(2) intro(2) intro(2) intro(3) intro(3) intro(5) doctype(1) assert(2) matrix(2) inb(9) iostats(4)	515 1093 904 846 749 1084 346 1 918 670 830 78 830 78 377 534 1092 786
interrupt handler intro – intro	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions introduction to Plan 9 introduction to system administration introduction to the Plan 9 devices introduction to the Plan 9 file Protocol, 9P intuit command line for formatting a invariants invertmat, xformpoint, xformpointd,/ I/O inb, ins, inl, outb, outs, outl, insb, I/O io - access PC I/O registers	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(9) intro(2) intro(1) intro(2) intro(3) intro(5) doctype(1) assert(2) matrix(2) inb(9) iostats(4) io(1)	515 1093 904 846 749 1084 1084 1918 670 830 78 377 534 1092 786 152
interrupt handler intro – intro	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions introduction to Plan 9 introduction to the Plan 9 devices introduction to the Plan 9 file Protocol, 9P intuit command line for formatting a invariants invertmat, xformpoint, xformpointd,/ I/O inb, ins, inl, outb, outs, outl, insb, I/O I/O on an existing or new file	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(2) intro(2) intro(1) intro(3) intro(3) intro(5) doctype(1) assert(2) matrix(2) inb(9) iostats(4) io(1) open(5)	515 1093 904 846 749 1084 346 1 918 670 830 78 377 534 1092 786 152 838
interrupt handler intro – intro	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions introduction to Plan 9 introduction to system administration introduction to the Plan 9 devices introduction to the Plan 9 File Protocol, 9P intuit command line for formatting a invariants invertmat, xformpoint, xformpointd,/ I/O inb, ins, inl, outb, outs, outl, insb, I/O io - access PC I/O registers I/O processes for threaded programs	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(2) intro(2) intro(1) intro(3) intro(3) intro(5) doctype(1) assert(2) matrix(2) inb(9) iostats(4) io(1) open(5) ioproc(2)	515 1093 904 846 749 1084 1084 1918 670 830 78 377 534 1092 786 152 838 516
interrupt handler intro – intro – assemt – check programmed iostats – file system to measure open, create – prepare a fid for /ioproc, ioread, ioreadn, iosleep, iowrite – slave na – assembler for the Symbios Logic PCI–SCSI	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions introduction to Plan 9 introduction to the Plan 9 devices introduction to the Plan 9 file Protocol, 9P intuit command line for formatting a invariants invertmat, xformpoint, xformpointd,/ io - access PC I/O registers I/O on an existing or new file I/O Processes for threaded programs	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(2) intro(2) intro(1) intro(3) intro(3) intro(5) doctype(1) assert(2) matrix(2) inb(9) iostats(4) io(1) open(5) ioproc(2) na(8)	515 1093 904 846 749 1084 1084 1918 670 830 78 377 534 1092 786 152 838 516 999
interrupt handler intro – intro – assert – check programmed iostats – file system to measure na – assembler for the Symbios Logic PCI–SCSI io – access PC	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions introduction to Plan 9 introduction to the Plan 9 devices introduction to the Plan 9 file Protocol, 9P intuit command line for formatting a invariants invertmat, xformpoint, xformpointd,/ io - access PC I/O registers I/O on an existing or new file I/O processes for threaded programs I/O registers	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(2) intro(2) intro(1) intro(3) intro(3) intro(5) doctype(1) assert(2) matrix(2) inb(9) iostats(4) iopen(5) ioproc(2) na(8) io(1)	515 1093 904 846 749 1084 346 1 918 670 830 78 377 534 1092 786 152 838 516 999 152
interrupt handler intro – intro – document	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions introduction to Plan 9 introduction to system administration introduction to the Plan 9 devices introduction to the Plan 9 File Protocol, 9P intuit command line for formatting a invariants invertmat, xformpoint, xformpointd,/ I/O inb, ins, inl, outb, outs, outl, insb, I/O inb, ins, inl, outb, outs, outl, insb, I/O on an existing or new file I/O processes for threaded programs I/O registers I/O unit for file descriptor	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(2) intro(2) intro(1) intro(3) intro(3) intro(3) intro(5) doctype(1) assert(2) matrix(2) inb(9) iostats(4) io(1) open(5) ioproc(2) na(8) io(1) iounit(2)	515 1093 904 846 749 1084 346 1 918 670 830 78 670 830 786 152 838 516 999 152 518
interrupt handler intro – intro – document doctype – doctype – doctype – doctype – doctype – doctype – doctype – doctype – assert – check program ident, matmul, matmulr, determinant, adjoint, inss, insl, outsb, outss, outsl – programmed iostats – file system to measure open, create – prepare a fid for /ioproc, ioread, ioreadn, iosleep, iowrite – slave na – assembler for the Symbios Logic PCI–SCSI io – access PC iounit – return size of atomic ioopen, ioproc, ioread, ioreadn,/ closeioproc,	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions introduction to Plan 9 introduction to the Plan 9 devices introduction to the Plan 9 devices introduction to the Plan 9 File Protocol, 9P intuit command line for formatting a invariants invertmat, xformpoint, xformpointd,/ io - access PC I/O registers I/O on an existing or new file I/O processes for threaded programs I/O registers I/O registers I/O unit for file descriptor iocall, ioclose, ioflush, iointerrupt, iodial,	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(2) intro(2) intro(2) intro(3) intro(3) intro(3) intro(5) doctype(1) assert(2) matrix(2) inb(9) iostats(4) io(1) open(5) ioproc(2) na(8) io(1) iounit(2) ioproc(2)	515 1093 904 846 749 1084 346 1 918 670 830 78 670 830 78 670 830 78 534 1092 786 152 838 516 999 152 518 516
interrupt handlerintro – intro – documentdoctype – assert – check program ident, matmul, matmulr, determinant, adjoint, inss, insl, outsb, outss, outsl – programmed iostats – file system to measure open, create – prepare a fid for /ioproc, ioread, ioreadn, iosleep, iowrite – slave na – assembler for the Symbios Logic PCI–SCSI io – access PC iounit – return size of atomic ioopen, ioproc, ioread, ioreadn,/ closeioproc, iocall,	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions introduction to Plan 9 introduction to the Plan 9 devices introduction to the Plan 9 devices introduction to the Plan 9 File Protocol, 9P introduction to the Plan 9 File Protocol, 9P invariants invertmat, xformpoint, xformpointd,/ I/O inb, ins, inl, outb, outs, outl, insb, I/O on an existing or new file I/O processes for threaded programs I/O Processors I/O registers I/O unit for file descriptor iocall, ioclose, ioflush, iointerrupt, iodial, ioclose, ioflush, iointerrupt, iodial, ioopen,	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(9) intro(2) intro(1) intro(2) intro(3) intro(3) intro(3) intro(3) intro(3) intro(3) intro(2) doctype(1) assert(2) matrix(2) inb(9) iostats(4) io(1) open(5) ioproc(2) na(8) io(1) iounit(2) ioproc(2)	515 1093 904 846 749 1084 346 1 918 670 830 78 830 783 377 534 1092 786 152 838 516 516 516
interrupt handler intro – intro – document doctype – doctype – doctype – doctype – doctype – doctype – doctype – doctype – assert – check program ident, matmul, matmulr, determinant, adjoint, inss, insl, outsb, outss, outsl – programmed iostats – file system to measure open, create – prepare a fid for /ioproc, ioread, ioreadn, iosleep, iowrite – slave na – assembler for the Symbios Logic PCI–SCSI io – access PC iounit – return size of atomic ioopen, ioproc, ioread, ioreadn,/ closeioproc,	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to kernel functions introduction to library functions introduction to Plan 9 introduction to the Plan 9 devices introduction to the Plan 9 File Protocol, 9P introduction to the Plan 9 File Protocol, 9P introduction to the Plan 9 File Protocol, 9P invariants invertmat, xformpoint, xformpointd,/ I/O inb, ins, inl, outb, outs, outl, insb, I/O io - access PC I/O registers I/O processes for threaded programs I/O registers I/O registers I/O unit for file descriptor iocall, ioclose, ioflush, iointerrupt, iodial, iosleep, iowrite – slave I/O processes for/	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(9) intro(2) intro(1) intro(2) intro(1) intro(3) intro(3) intro(3) intro(5) doctype(1) assert(2) matrix(2) ints(4) iostats(4) io(1) open(5) ioproc(2) na(8) io(1) iounit(2) ioproc(2) ioproc(2) ioproc(2)	515 1093 904 846 749 1084 670 830 78 670 830 783 77534 1092 786 152 838 516 516 516
interrupt handlerintro – intro – document	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to kernel functions introduction to Plan 9 introduction to Plan 9 introduction to the Plan 9 devices introduction to the Plan 9 File Protocol, 9P intuit command line for formatting a invertmat, xformpoint, xformpointd,/ I/O inb, ins, inl, outb, outs, outl, insb, I/O inb, ins, inl, outb, outs, outl, insb, I/O on an existing or new file I/O registers I/O registers I/O unit for file descriptor ioclose, ioflush, iointerrupt, iodial, ioopen, iosleep, iowrite – slave I/O processes for/ iostats – file system to measure I/O	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(2) intro(2) intro(1) intro(3) intro(3) intro(3) intro(5) doctype(1) assert(2) matrix(2) ints(4) iototats(4) iototats(4)	515 1093 904 846 749 1084 670 830 78 377 534 1092 786 152 838 516 999 152 518 516 516 516 786
interrupt handlerintro – intro – documentdoctype – assert – check program ident, matmul, matmulr, determinant, adjoint, inss, insl, outsb, outss, outsl – programmed iostats – file system to measure open, create – prepare a fid for /ioproc, ioread, ioreadn, iosleep, iowrite – slave na – assembler for the Symbios Logic PCI–SCSI io – access PC iounit – return size of atomic ioopen, ioproc, ioread, ioreadn,/ closeioproc, ioproc, ioread, ioreadn,/ closeioproc, iocall, /iodial, ioopen, ioproc, ioread, ioreadn,	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to kernel functions introduction to Plan 9 introduction to Plan 9 introduction to the Plan 9 devices introduction to the Plan 9 File Protocol, 9P intuit command line for formatting a invariants invertmat, xformpoint, xformpointd,/ I/O inb, ins, inl, outb, outs, outl, insb, I/O io – access PC I/O registers I/O processes for threaded programs I/O registers I/O unit for file descriptor iocall, ioclose, ioflush, iointerrupt, iodial, iosleep, iowrite – slave I/O processes for/ iounit – return size of atomic I/O unit for file	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(2) intro(2) intro(1) intro(3) intro(3) intro(3) intro(5) doctype(1) assert(2) matrix(2) inb(9) iostats(4) io(1) ioproc(2) ioproc(515 1093 904 846 749 1084 1084 1084 670 830 78 377 534 1092 786 516 516 516 518
interrupt handlerintro - intro - document	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to kernel functions introduction to Plan 9 introduction to Plan 9 introduction to the Plan 9 devices introduction to the Plan 9 File Protocol, 9P introduction to the Plan 9 File Protocol, 9P intvariants invertmat, xformpoint, xformpointd,/ I/O inb, ins, inl, outb, outs, outl, insb, I/O io - access PC I/O registers I/O processes for threaded programs I/O processes for threaded programs I/O unit for file descriptor iosleep, iowrite - slave I/O processes for / iounit - return size of atomic I/O unit for file	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(2) intro(2) intro(1) intro(3) intro(3) intro(3) intro(5) doctype(1) assert(2) matrix(2) intb(9) iostats(4) io(1) ioproc(2)	515 1093 904 846 749 1084 918 670 830 78 377 534 1092 786 516 516 516 516 516
interrupt handlerintro – intro – documentdoctype – assert – check program ident, matmul, matmulr, determinant, adjoint, inss, insl, outsb, outss, outsl – programmed iostats – file system to measure open, create – prepare a fid for /ioproc, ioread, ioreadn, iosleep, iowrite – slave na – assembler for the Symbios Logic PCI–SCSI io – access PC iounit – return size of atomic ioopen, ioproc, ioread, ioreadn,/ closeioproc, ioproc, ioread, ioreadn,/ closeioproc, iocall, /iodial, ioopen, ioproc, ioread, ioreadn, iosleep, udp, il – network protocols over IP	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions introduction to Plan 9 introduction to the Plan 9 devices introduction to the Plan 9 file Protocol, 9P introduction to the Plan 9 File Protocol, 9P intuit command line for formatting a invariants invertmat, xformpoint, xformpointd,/ I/O inb, ins, inl, outb, outs, outl, insb, I/O io - access PC I/O registers I/O processes for threaded programs I/O registers I/O registers I/O unit for file descriptor iocall, ioclose, ioflush, iointerrupt, iodial, ioopen, iostats - file system to measure I/O iowrite - slave I/O processes for threaded/ iowrite - slave I/O processes for threaded/	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(2) intro(2) intro(2) intro(2) intro(3) intro(3) intro(3) intro(3) intro(5) doctype(1) assert(2) matrix(2) inb(9) iostats(4) io(1) open(5) ioproc(2) i	515 1093 904 846 749 1084 346 1 918 670 830 786 152 838 516 516 516 516 516 516 516 698
interrupt handlerintro - intro - document	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions introduction to Plan 9 introduction to the Plan 9 devices introduction to the Plan 9 file Protocol, 9P introduction to the Plan 9 File Protocol, 9P introduction to the Plan 9 File Protocol, 9P invariants invertmat, xformpoint, xformpointd,/ I/O inb, ins, inl, outb, outs, outl, insb, I/O inb, ins, inl, outb, outs, outl, insb, I/O processes for threaded programs I/O processes for threaded programs I/O registers I/O rocesses for threaded programs iosleep, iowrite – slave I/O processes for/ iosleep, iowrite – slave I/O processes for/ iounit – return size of atomic I/O unit for file iowrite – slave I/O processes for threaded/ ip, esp, gre, icmp, icmpv6, ipmux, rudp, tcp, IP Ethernet bridge	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(2) intro(2) intro(2) intro(2) intro(3) intro(3) intro(3) intro(3) intro(5) doctype(1) assert(2) matrix(2) inb(9) iostats(4) io(1) open(5) ioproc(2) i	515 1093 904 846 749 1084 346 1 918 670 830 786 152 838 516 516 516 516 516 516 516 516 516 698 678
interrupt handlerintro - intro - documentdoctype - assert - check program ident, matmul, matmulr, determinant, adjoint, inss, insl, outsb, outss, outsl - programmed iostats - file system to measure open, create - prepare a fid for /ioproc, ioread, ioreadn, iosleep, iowrite - slave na - assembler for the Symbios Logic PCI-SCSI io - access PC iounit - return size of atomic ioopen, ioproc, ioread, ioreadn,/ closeioproc, ioproc, ioread, ioreadn,/ closeioproc, iocall, /iodial, ioopen, ioproc, ioread, ioreadn, iosleep, udp, il - network protocols over IP bridge - /ndbsearch, ndbsnext, ndbgetvalue, ndbfree,	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions introduction to Plan 9 introduction to the Plan 9 devices introduction to the Plan 9 devices introduction to the Plan 9 File Protocol, 9P introduction to the Plan 9 File Protocol, 9P introduction to the Plan 9 File Protocol, 9P invariants invertmat, xformpoint, xformpointd,/ I/O inb, ins, inl, outb, outs, outl, insb, I/O inb, ins, inl, outb, outs, outl, insb, I/O on an existing or new file I/O processes for threaded programs I/O Processors I/O registers I/O unit for file descriptor iocall, ioclose, ioflush, iointerrupt, iodial, ioopen, iosleep, iowrite - slave I/O processes for / iostats - file system to measure I/O iowrite - slave I/O processes for threaded / iowrite - slave I/O processes for threaded / iowrite - slave I/O processes for threaded / ip, esp, gre, icmp, icmpv6, ipmux, rudp, tcp, IP thernet bridge	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(9) intro(2) intro(1) intro(2) intro(3) intro(3) intro(3) intro(3) intro(3) intro(3) intro(3) intro(2) iotxts(4) io(1) open(5) ioproc(2) iop	515 1093 904 846 749 1084 346 1 918 670 830 783 377 534 1092 786 152 838 516 516 516 516 516 516 516 698 554
interrupt handlerintro - intro - document	intrenable, intrdisable – enable (disable) an introduction to databases introduction to file formats introduction to file servers introduction to kernel functions introduction to library functions introduction to Plan 9 introduction to the Plan 9 devices introduction to the Plan 9 file Protocol, 9P introduction to the Plan 9 File Protocol, 9P introduction to the Plan 9 File Protocol, 9P invariants invertmat, xformpoint, xformpointd,/ I/O inb, ins, inl, outb, outs, outl, insb, I/O inb, ins, inl, outb, outs, outl, insb, I/O processes for threaded programs I/O processes for threaded programs I/O registers I/O rocesses for threaded programs iosleep, iowrite – slave I/O processes for/ iosleep, iowrite – slave I/O processes for/ iounit – return size of atomic I/O unit for file iowrite – slave I/O processes for threaded/ ip, esp, gre, icmp, icmpv6, ipmux, rudp, tcp, IP Ethernet bridge	intmap(2) intrenable(9) intro(7) intro(6) intro(4) intro(2) intro(2) intro(2) intro(2) intro(3) intro(3) intro(3) intro(3) intro(5) doctype(1) assert(2) matrix(2) inb(9) iostats(4) io(1) open(5) ioproc(2) i	515 1093 904 846 749 1084 346 1 918 670 830 786 152 838 516 516 516 516 516 516 516 516 516 698 678

csquery, dns, dnstcp, dnsquery,/ query,		ndb(8)	
aescbc, and run automatic or manual tunnel of	ipso, secstore – secstore commands IPv6 through IPv4 6in4, ayiya – configure	secstore(1) 6in4(8)	265 919
and full automatic of manual tunnel of	ircrc – internet relay chat client	ircrc(1)	153
pnp – Plug 'n' Play	ISA and PCI Interfaces	pnp(3)	715
isalnum, isspace, ispunct, isprint, isgraph,/	isalpha, isupper, islower, isdigit, isxdigit,	ctype(2)	421
istitlerune, isupperrune, isdigitrune,/	isalpharune, islowerrune, isspacerune,		522
functions objtype, readobj, objtraverse,	isar, nextar, readar - object file interpretation	object(2)	564
/isspace, ispunct, isprint, isgraph, iscntrl,	isascii, toascii, _toupper, _tolower, toupper,/	ctype(2)	421
/isalnum, isspace, ispunct, isprint, isgraph, isprint, isgraph,/ isalpha, isupper, islower,	iscntrl, isascii, toascii, _toupper, _tolower,/ isdigit, isxdigit, isalnum, isspace, ispunct,	ctype(2) ctype(2)	421 421
/isspacerune, istitlerune, isupper, isoperrune,	isdigitrune, tolowerrune, totitlerune,/		522
eve.	iseve – privileged user	eve(9)	
/isxdigit, isalnum, isspace, ispunct, isprint,	isgraph, iscntrl, isascii, toascii, _toupper,/	ctype(2)	421
NaN, Inf, isNaN,	isInf - not-a-number and infinity functions	nan(2)	553
splhi, spllo, splx,	islo – enable and disable interrupts	splhi(9)	
ispunct, isprint, isgraph,/ isalpha, isupper,	islower, isdigit, isxdigit, isalnum, isspace,	ctype(2)	421
isupperrune, isdigitrune,/ isalpharune, functions NaN, Inf,	islowerrune, isspacerune, istitlerune, isNaN, isInf – not–a–number and infinity	nan(2)	522 553
efiboot.fat – PC bootloader for FAT,	ISO and PXE network booting /bootx64.efi,	9boot(8)	921
dump9660, mk9660 - create an	ISO-9660 CD image	mk9660(8)	992
dossrv, 9660srv, dosmnt, eject - DOS and	ISO9660 file systems	dossrv(4)	765
/islower, isdigit, isxdigit, isalnum, isspace,	ispunct, isprint, isgraph, iscntrl, isascii,/	ctype(2)	421
isalpharune, islowerrune, isspacerune,	istitlerune, isupperrune, isdigitrune,/		522
/maskip, equivip4, equivip6, defmask,	isv4, v4tov6, v6tov4, nhgetv, nhgetl, nhgets,/ .	ip(2)	519
isgraph,/ isalpha, isupper, islower, isdigit, /mptole, mptolel, mptoui, uitomp, mptoi,	isxdigit, isalnum, isspace, ispunct, isprint, itomp, uvtomp, mptouv, vtomp, mptov,/	ctype(2) mp(2)	421 547
tel.	iwhois – look in phone book	tel(1)	300
/popmat, rot, grot, scale, move, xform,	ixform, persp, look, viewport – Geometric/	matrix(2)	534
mnihongo – macros for typesetting	Japanese	mnihongo(6)	874
	join - relational database operator	join(1)	155
flashfs –	journalling file system for flash memory	flashfs(4)	775
mkflashfs - make a	journalling file system for flash memory	mkflashfs(8)	994
tga, tojpg, togeordi, togif, toppm, topng,/ jsonparse, jsonfree,	jpg, gif, png, tif, ppm, bmp, v210, yuv, ico, jsonbyname, jsonstr – JSON parser	jpg(1) json(2)	156 523
	juggle, life, mandel, mahjongg, memo, midi,/	games(1)	109
/ catchoon, accon, restoon, gengerstate, grendy,	juke – music jukebox	juke(7)	907
0a, 1a, 2a, 5a, 6a, 8a,	ka, qa, va – assemblers	2a(1)	4
drivers audio, disk, ether,	kb, serial, ptp, usbd – Universal Serial Bus	nusb(4)	797
file evente ve	kbd – pc keyboard driver	kbd(3)	707
filesystem	kbdfs, console - keyboard and console kbmap - show a list of available keyboard	kbdfs(8) kbmap(1)	986 159
0c, 1c, 2c, 5c, 6c, 7c, 8c,		2c(1)	5
rdbfs – remote		rdbfs(4)	805
intro – introduction to	kernel functions	intro(9)	
setrealloctag, getmalloctag, getrealloctag -	kernel memory allocator /setmalloctag,	malloc(9)	
- mouse, cursor - interruption kproc, pexit, postnote -	kernel mouse interface	mouse(3)	712
- kprof - kproc, pexit, positione - kprof -		kproc(9) kprof(3)	708
	kernel stack dumps	ktrace(1)	161
HZ, MS2HZ, MS2TK, TK2MS, TK2SEC -	kernel times and time conversions . /fastticks,	seconds(9)	
keys.who - biographic information for	key holders	keys.who(6)	868
securenet – Digital Pathways SecureNet		securenet(8)	
thumbprint – public	key thumbprints	thumbprint(6)	894 866
kbdfs, console –	keyboard and console filesystem	keyboard(6) kbdfs(8)	866 986
initkeyboard, ctlkeyboard, closekeyboard -	keyboard control	keyboard(2)	525
kbd – pc	keyboard driver	kbd(3)	707
kbmap - show a list of available	keyboard maps and switch between them	kbmap(1)	159
utilities bitsyload, light, pencal,	keyboard, params, prompter – bitsy–specific	bitsyload(1)	38
realyEOO realeer gamerate and format rea	keyfs, warning – authentication database files	keyfs(4)	787
rsa2x509, rsa2csr – generate and format rsa delkey – delete	keys . /asn12rsa, rsa2asn1, rsa2pub, rsa2ssh, keys from factotum	rsa(8) delkey(1)	1041 71
/des3ECBencrypt, des3ECBdecrypt,	key_setup, des56to64, des64to56,/	des(2)	425
holders	keys.who – biographic information for key	keys.who(6)	868
5i,	ki, vi, qi - instruction simulators	vi(1)	327
kill processes	kill, slay, broke, dontkill - print commands to	kill(1)	160
01, 11, 21, 51, 61, 81,	kl, ql, vl – loaders	2l(1)	8
leak, creation, termination and interruption	kmem, umem – help find memory leaks kproc, pexit, postnote – kernel process	leak(1) kproc(9)	162 1094
prof, tprof,		prof(1)	226
	kprof – kernel profiling	kprof(3)	708
	ktrace - interpret kernel stack dumps	ktrace(1)	161
ARROW, drawsetdebug - graphics functions PB	L /runestringbg, runestringnbg, _string,	draw(2)	432

ria.			250
rio, abs.	label, window, wloc – window system labs – integer absolute values	rio(1) abs(2)	250 361
wol – send	lan Ethernet packet	wol(8)	
- pattern-directed scanning and processing	language	awk(1)	29
bc – arbitrary–precision arithmetic	language	bc(1)	34
dtracy – dynamic tracing	language	dtracy(1)	80
hoc - interactive floating point	language	hoc(1)	148
interactive, object-oriented programming	language python - an interpreted,	python(1)	233
flag, rfork, shift, wait, whatis, ., ~ - command	language rc, cd, eval, exec, exit,	rc(1)	239
amlenum, amltake, amldrop – ACPI machine	language interpreter /amlwalk, amleval,	aml(2)	370
gs - Aladdin Ghostscript (PostScript and PDF	language interpreter)	gs(1)	116
cpp – C	language preprocessor	cpp(1)	56
ssl – SSL record tls – TLS and SSL3 record	layer	ssl(3)	734 737
lis – TES and SSES record	layerlayer	tls(3) ls(1)	170
exponent frexp,	Idexp, modf – split into mantissa and	frexp(2)	480
скронент некр,	leak, kmem, umem – help find memory leaks	leak(1)	162
oexportfs -	legacy exports for cpu and import	oexportfs(4)	799
/beieeedftos, leieee80ftos, leieeesftos,	leieeedftos, ieeesftos, ieeedftos -/	debugger(2)	422
	lens – interactive screen magnifier	lens(1)	164
/dot3, cross3, len3, dist3, unit3, midpt3,	lerp3, reflect3, nearseg3, pldist3, vdiv3,/	arith3(2)	375
/put8, puta beswab, beswal, beswav, leswab,	leswal, leswav - machine-independent access/	mach(2)	529
/mpfmt, mptoa, betomp, mptobe, mptober,	letomp, mptole, mptolel, mptoui, uitomp,/	mp(2)	547
ARGEND, ARGC, ARGF, EARGF – process option	letters from argv ARGBEGIN,	arg(2)	373
rendezvous – user semacquire, tsemacquire, semrelease – user	level process synchronization	rendezvous(2) semacquire(2)	600 621
semacquire, isemacquire, semielease – user	lex – generator of lexical analysis programs	lex(1)	165
openep, unstall – USB device driver	library /loaddevstr, opendev, opendevdata,	nusb(2)	560
ar – archive	library) file format	ar(6)	850
intro – introduction to	library functions	intro(2)	346
ar - archive and	library maintainer	ar(1)	23
/doom, festoon, geigerstats, glendy, juggle,	life, mandel, mahjongg, memo, midi, mole,/	games(1)	109
bitsy-specific utilities bitsyload,	light, pencal, keyboard, params, prompter	bitsyload(1)	38
doctype – intuit command	line for formatting a document	doctype(1)	78
– getflags, usage gendraw, drawreplxy, drawrepl, replclipr,	line parsing for shell scripts line, poly, fillpoly, bezier, bezspline,/ . /draw,	getflags(8) draw(2)	957 432
/getsym, symbase, pc2sp, pc2line, textseq,	line2addr, lookup, findlocal, getauto,/	symbol(2)	635
comm – select or reject	lines common to two sorted files	comm(1)	52
fortune, theo, troll – sample	lines from a file	fortune(1)	103
uniq – report repeated	lines in a file	uniq(1)	321
look – find		look(1)	167
loopback – network		loopback(3)	709
ipconfig, rip, look - find lines in a sorted	linklocal - Internet configuration and routing .	ipconfig(8) look(1)	981 167
	list and execute	xargs(1)	340
ls, lc -		ls(1)	170
filter,		filter(1)	98
	list format	users(6)	895
between them kbmap - show a		kbmap(1)	159
nm – name	list (symbol table)	nm(1)	203
getnetconninfo,/ dial, hangup, announce, tcp23, tcp25, tcp53, tcp110, tcp113, tcp143,/	listen, accept, reject, netmkaddr, setnetmtpt, listen, listen1, tcp7, tcp9, tcp19, tcp21,	dial(2) listen(8)	427 988
smtpd – SMTP	listener configuration	smtpd(6)	890
/dirread9p, emalloc9p, erealloc9p, estrdup9p,	listensrv, postmountsrv, postsharesrv,/	9p(2)	349
rdproto - parse and process a proto file	listing	proto(2)	581
ml, mlmgr, mlowner – unmoderated mailing	lists	mlmgr(1)	185
segment – long	lived memory segments	segment(3)	730
	Infs – long name file system	Infs(4)	789
genrandom, prng,/ rand, lrand, frand, nrand,	Inrand, srand, truerand, ntruerand, loadchar, Subfont, Fontchar, Font - font	rand(2)	591
utilities cachechars, agefont, unstall -/ /closedev, configdev, devctl, getdev,	loaddevstr, opendev, opendevdata, openep,	cachechars(2) nusb(2)	395 560
01, 11, 21, 51, 61, 81, k1, q1, v1 –	loaders	21(1)	8
/nameimage, namedimage, setalpha,	loadimage, cloadimage, unloadimage, /	allocimage(2)	367
geta,/ /newmap, setmap, findseg, unusemap,	loadmap, attachproc, get1, get2, get4, get8,	mach(2)	529
/writememimage, freememimage, memsetchan,	loadmemimage, cloadmemimage,/	memdraw(2)	536
cisctrace, risctrace, ciscframe, riscframe,	localaddr, symoff, fpformat, beieee80ftos,/	debugger(2)	422
/line2addr, lookup, findlocal, getauto, findsym,	localsym, globalsym, textsym, file2pc,/	symbol(2)	635
- convert date and time ctime,	localtime, gmtime, asctime, tm2sec, timezone lock - run a command under lock	ctime(2) lock(1)	419 166
/gengetwindow, flushimage, bufimage,	lockdisplay, unlockdisplay, openfont,/	graphics(2)	492
rwakeup, rwakeupall, incref, decref – spin	locks, queueing rendezvous locks,/ . /rsleep,	lock(2)	526
logarithm, power, square root exp, log,	log10, pow, pow10, sqrt - exponential,	exp(2)	455
na - assembler for the Symbios	Logic PCI–SCSI I/O Processors	na(8)	999
ssh – secure shell remote	login client	ssh(1)	284

con, telnet, rx, hayes, xms, xmr - remote	login, execution, and XMODEM file transfer	con(1)	53
/disable, authsrv, guard.srv, debug, wrkey,	login, newns, none, as - maintain or query/	auth(8)	930
fauth_proxy,/ amount, newns, addns,	login, noworld, procsetuser, auth_proxy,	auth(2)	379
vtlogremove, vtlogopen, ventilogging - Venti	logs /vtlognames, vtlogopen, vtlogprint,	venti-log(2)	661
setjmp,	longjmp, notejmp – non-local goto look – find lines in a sorted list	setjmp(2)	622
tal impoir	look in phone book	look(1) tel(1)	167 300
- tel, iwhois /rot, qrot, scale, move, xform, ixform, persp,	look, viewport – Geometric transformations	matrix(2)	534
manual man,	lookman, sig – print or find pages of this	man(1)	173
/symbase, pc2sp, pc2line, textseg, line2addr,	lookup, findlocal, getauto, findsym, localsym,/	symbol(2)	635
Cmdbuf, parsecmd, respondemderror,	lookupcmd – control message parsing	9pcmdbuf(2)	354
parsecmd, cmderror,	lookupcmd – parse device commands	parsecmd(9)	
/allocfidpool, freefidpool, allocfid, closefid,	lookupfid, removefid, Reg, Regpool,/	9pfid(2)	355
/allocmap, freemap, insertkey, caninsertkey,	lookupkey, deletekey - integer to data/	intmap(2)	515
/allocreqpool, freereqpool, allocreq, closereq,	lookupreg, removereg – 9P fid, request/	9pfid(2)	355
allocsubfont, freesubfont, installsubfont,	lookupsubfont, uninstallsubfont,/	subfont(2)	633
	loopback - network link simulation	loopback(3)	709
sdloop –	loopback storage device interface	sdloop(3)	728
reboot – reboot the system upon	loss of remote file server connection	reboot(8)	
	lp – PostScript preprocessors	lp(8)	990
	lp – printer output	lp(1)	168 710
ntruerand, genrandom, prng, fastrand,/ rand,	lpt – parallel port interface for PC's	lpt(3) rand(2)	591
intructand, genrandoni, pring, fastrand,/ Tand,	ls, Ic – list contents of directory	ls(1)	170
findseg, unusemap, loadmap,/ crackhdr,	machbytype, machbyname, newmap, setmap,	mach(2)	529
who, whois – who is using the	machine	who(1)	338
amleval, amlenum, amltake, amldrop – ACPI		aml(2)	370
init – initialize	machine upon booting	init(8)	980
files /beswal, beswav, leswab, leswal, leswav -	machine-independent access to executable	mach(2)	529
/leieeesftos, leieeedftos, ieeesftos, ieeedftos -	machine-independent debugger functions	debugger(2)	422
emacs – editor		emacs(1)	89
mpictures – picture inclusion	macros	mpictures(6)	875
html2ms – convert between troff's ms	macros and html	ms2html(1)	189
mhtml –	macros for formatting HTML	mhtml(6)	873
ms –	macros for formatting manuscripts	ms(6)	876
– mnihongo – man	macros for typesetting Japanesemacros to typeset manual	mnihongo(6) man(6)	874 869
lens – interactive screen	magnifier	lens(1)	164
/geigerstats, glendy, juggle, life, mandel,	mahjongg, memo, midi, mole, packet,/	games(1)	109
filter, list, deliver, token, vf – filtering	mail	filter(1)	98
marshal – formatting and sending	mail	marshal(1)	174
nedmail - reading	mail	nedmail(1)	193
ratfs –	mail address ratification file system	ratfs(4)	804
aliasmail - expand system wide	mail aliases	aliasmail(8)	926
mail, go.fishing -	mail and mailboxes	mail(1)	172
mdir –	mail directory format	mdir(6)	872
upasfs –	mail file server	upasfs(4)	819
nomencede , encode files in Privery Enhanced	mail, go.fishing – mail and mailboxes	mail(1)	172
pemencode – encode files in Privacy Enhanced rewrite –	Mail (PE) format pemdecode, mail rewrite rules	pem(8) rewrite(6)	889
send –	mail routing and delivery	send(8)	
pop3, imap4d – Internet		pop3(8)	
smtp, smtpd -	mail transport	smtp(8)	
faces, seemail, vwhois -	mailbox interface	faces(1)	94
splitmbox - split a		splitmbox(8)	1058
mail, go.fishing - mail and		mail(1)	172
ml, mlmgr, mlowner - unmoderated	mailing lists	mlmgr(1)	185
/chancreate, chanfree, chanclosing, chanprint,	mainstacksize, proccreate, procdata,/	thread(2)	638
ar – archive and library	maintainer	ar(1)	23 947
fs, exsort – file server hifs – file server	maintenancemaintenance	fs(8) hjfs(8)	947 975
mksacfs –		mksacfs(8)	975
mkpagfs –	make a compressed read-only file system	mkpaqfs(8)	996
mkdir -	make a directory	mkdir(1)	184
memory mkflashfs -	make a journalling file system for flash	mkflashfs(8)	994
, mktemp –	make a unique file name	mktemp(2)	544
/setnetmtpt, getnetconninfo, freenetconninfo -	make and break network connections	dial(2)	427
mk, membername – maintain	make) related files	mk(1)	179
/setrealloctag, getmalloctag, getrealloctag,	malloctopoolblock - memory allocator	malloc(2)	532
setmalloctag,/ malloc, mallocalign,	mallocz, free, realloc, calloc, msize,	malloc(2)	532
secalloc, secfree, setmalloctag,/ malloc,	mallocz, smalloc, realloc, free, msize,	malloc(9)	
this manual	man - macros to typeset manualman, lookman, sig - print or find pages of	man(6)	869 173
httpd, save, imagemap,	man2html, webls – HTTP server	man(1) httpd(8)	977
incpu, save, inageniap,		nupu(0)	511

	management /padblock, pullblock,	allocb(9)	
privalloc – per-process private storage	management	privalloc(2)	579
pull, push, scan - client-server replica		replica(1)	246
updatedb - simple client-server replica		replica(8)	
threadwaitchan, yield - thread and proc	management . /threadsetgrp, threadsetname,	thread(2)	638
topnwindows, originwindow – window	management /bottomnwindows, topwindow,	window(2) xalloc(9)	668
xspanalloc, xfree, xsummary – basic memory apm – Advanced Power	management xalloc, xallocz, Management 1.2 BIOS interface		674
apm – Advanced Power	Management 1.2 BIOS interface	apm(3) apm(8)	927
qer, runq – queue	management for spooled files	qer(8)	
poolblockcheck, pooldump – general memory	management routines	pool(2)	571
hg – Mercurial source code	management system	hq(1)	123
webcookies – HTTP cookie	manager		825
/festoon, geigerstats, glendy, juggle, life,	mandel, mahjongg, memo, midi, mole,/	games(1)	109
strsubfontwidth, mkfont – subfont	manipulation . /writesubfont, stringsubfont,	subfont(2)	633
frexp, Idexp, modf – split into	mantissa and exponent	frexp(2)	480
man, lookman, sig - print or find pages of this	manual	man(1)	173
man – macros to typeset	manual	man(6)	869
6in4, ayiya – configure and run automatic or	manual tunnel of IPv6 through IPv4	6in4(8)	919
ms - macros for formatting	manuscripts	ms(6)	876
getmap, colors - display color	map	colors(1)	51
readcolmap, writecolmap – access display color	map RGB,		595
	map – digitized map formats	map(6)	871
map,	mapdemo - draw maps on various projections	map(7)	910
cmap2rgba, rgb2cmap – colors and color deletekey – integer to data structure	maps cmap2rgb, maps /insertkey, caninsertkey, lookupkey,	color(2)	401 515
kbmap – show a list of available keyboard	maps and switch between them.	intmap(2) kbmap(1)	159
map, mapdemo – draw	maps on various projections	map(7)	910
segattach, segdetach, segfree –	map/unmap a segment in virtual memory	segattach(2)	617
segulacii, seguelacii, segiree	marshal – formatting and sending mail	marshal(1)	174
/v4parseip, parseether, myipaddr, myetheraddr,	maskip, equivip4, equivip6, defmask, isv4,/	ip(2)	519
eqn – typeset	mathematics	eqn(1)	90
xformpoint, xformpointd,/ ident, matmul,	matmulr, determinant, adjoint, invertmat,	matrix(2)	534
prep, edisk, fdisk, format,	mbr - prepare disks, floppies and flashes	prep(8)	1029
	mc – multicolumn print	mc(1)	176
	md - emulator	sega(1)	271
sha2_384, sha2_512, hmac_x,/ md4,		sechash(2)	614
a file sum,		sum(1)	288
	mdir – mail directory format	mdir(6)	872
splitmbox – split a mailbox into	mdir format	splitmbox(8)	
iostats – file system to tput –	measure I/Omeasure read throughput	iostats(4) tput(1)	786 311
/unloadmemimage, memfillcolor,		memdraw(2)	536
mk,	membername – maintain (make) related files	mk(1)	179
memset – memory operations memccpy,	memchr, memcmp, memcpy, memmove,	memory(2)	543
wordaddr, byteaddr,/ Memimage,	Memdata, Memdrawparam, memimageinit,	memdraw(2)	536
byteaddr,/ Memimage, Memdata,	Memdrawparam, memimageinit, wordaddr,	memdraw(2)	536
/memfillcolor, memarc, mempoly,	memellipse, memfillpoly, memimageline,/	memdraw(2)	536
memimageinit, wordaddr, byteaddr,/	Memimage, Memdata, Memdrawparam,	memdraw(2)	536
/memellipse, memfillpoly, memimageline,	memimagedraw, drawclip, drawclipnorepl,/	memdraw(2)	536
Memimage, Memdata, Memdrawparam,	memimageinit, wordaddr, byteaddr,/	memdraw(2)	536
/memarc, mempoly, memellipse, memfillpoly,	memimageline, memimagedraw, drawclip,/	memdraw(2)	536
/memimageinit, wordaddr, byteaddr,	memimagemove, allocmemimage,/	memdraw(2)	536
for/ /memsubfontwidth, getmemdefont, memlfree, memlhide, memline, / memdraw,	memimagestring, hwdraw – drawing routines . memlalloc, memldelete, memlexpose,	memdraw(2) memlayer(2)	536 540
/drawclip, drawclipnorepl, memlinebbox,	memlineendsize, allocmemsubfont,/	memdraw(2)	536
/memlexpose, memlfree, memlhide, memline,	memInorefresh, memIoad, memunIoad, /	memlayer(2)	540
/memload, memunload, memlorigin,	memlsetrefresh, memltofront, memltofrontn,/	memlayer(2)	540
/memlsetrefresh, memltofront, memltofrontn,	memltorear, memltorearn – windows of/	memlayer(2)	540
memccpy, memchr, memcmp, memcpy,	memmove, memset - memory operations	memory(2)	543
time/ /glendy, juggle, life, mandel, mahjongg,	memo, midi, mole, packet, sokoban, sudoku -	games(1)	109
flash – flash	memory	flash(3)	692
flashfs - journalling file system for flash	memory	flashfs(4)	775
- make a journalling file system for flash	memory mkflashfs	mkflashfs(8)	994
segfree - map/unmap a segment in virtual	memory segattach, segdetach,	segattach(2)	617
human-readable format	memory – print memory statistics in	memory(8)	991 387
binalloc, bingrow, binfree – grouped brk, sbrk – change	memory allocation memory allocation	bin(2) brk(2)	387 394
segbrk – change		segbrk(2)	619
getrealloctag, malloctopoolblock -	memory allocator	malloc(2)	532
getmalloctag, getrealloctag – kernel	memory allocator	malloc(9)	
vtrealloc, vtstrdup, vtfree – error-checking	memory allocators /vtmalloc, vtmallocz,	venti-mem(2)	662
device i82365 - Personal Computer	Memory Card Interface Association (PCMCI)	i82365(3)	697
opendirfile, readdirfile, closedirfile, hasperm -	memory file hierarchy /removefile, walkfile,	9pfile(2)	357

ramfs –	memory file system	ramfs(4)	803
leak, kmem, umem – help find	memory leaks	leak(1)	162
xallocz, xspanalloc, xfree, xsummary - basic	memory management	xalloc(9)	
poolblockcheck, pooldump – general	memory management routines /poolcheck,	pool(2)	571
memcmp, memcpy, memmove, memset -	memory operations memccpy, memchr,	memory(2)	543
segment – long lived	memory segments	segment(3)	730
	memory statistics in human-readable format	memory(8)	991
swap –	memory usage statistics and swap file control	swap(3)	736
hwdraw – drawing routines for	memory-resident images /memimagestring,	memdraw(2)	536
memltorear, memltorearn - windows of	memory-resident images /memltofrontn,	memlayer(2)	540
/unloadmemimage, memfillcolor, memarc,	mempoly, memellipse, memfillpoly,/	memdraw(2)	536
memchr, memcmp, memcpy, memmove,	memset - memory operations memccpy,	memory(2)	543
/writememimage, freememimage,	memsetchan, loadmemimage,/	memdraw(2)	536
/openmemsubfont, freememsubfont,	memsubfontwidth, getmemdefont,/	memdraw(2)	536
/memline, memlnorefresh, memload,	memunload, memlorigin, memlsetrefresh,/	memlayer(2)	540
eenter, emoveto, esetcursor, Event, Mouse,	Menu – graphics events /emenuhit,	event(2)	449
/closemouse, moveto, getrect, drawgetrect,	menuhit, setcursor, enter – mouse control	mouse(2)	545
hgrc – configuration files for	Mercurial	hgrc(8)	963
hgfs –	mercurial file system	hgfs(4)	780
	Mercurial ignore files	hgignore(8)	961
hg –	Mercurial source code management system	hg(1)	123
	merge files	sort(1)	275
tinc –	mesh peer to peer VPN	tinc(8)	
flush – abort a	5	flush(5)	837
respondemderror, lookupemd – control	message parsing Cmdbuf, parsecmd,	9pcmdbuf(2)	354
plumb – send	message to plumber	plumb(1)	224
statusmsg – display a bar graph or status	message window statusbar,	statusbar(8)	
perror, syslog, sysfatal – system error	messages	perror(2)	567
plumbunpackattr, Plumbmsg – plumb	messages/plumbunpackpartial,	plumb(2)	569
plumb – format of plumb	messages and rules	plumb(6)	884
attach, auth – plumber – file system for interprocess	messages to establish a connection	attach(5)	834 801
plumber - me system for merprocess	messaging	plumber(4) mhtml(6)	873
clock interrupts delay,	microdelay, addclock0link – small delays,	delay(9)	
msexceltables – extract printable text from	Microsoft documents . /olefs, mswordstrings,	doc2txt(1)	77
cifs –		cifs(4)	758
mus – MUS to	MIDI converter	mus(1)	192
/glendy, juggle, life, mandel, mahjongg, memo,	midi, mole, packet, sokoban, sudoku – time/	games(1)	109
instrument banks dmid -	MIDI to OPL3 converter using GENMIDI-type	dmid(1)	76
/closept3, dot3, cross3, len3, dist3, unit3,	midpt3, lerp3, reflect3, nearseg3, pldist3,/	arith3(2)	375
/ closepts, dots, closss, lells, dists, dilits,	mines – minesweeper	mines(1)	177
rotate – rotate or	mirror a picture	rotate(1)	255
Totale Totale of	mix – MIX assembler and emulator	mix(1)	178
/flacdec, flacenc, sundec, wavdec, pcmconv,	mixfs – decode and encode audio files	audio(1)	26
files	mk, membername – maintain (make) related	mk(1)	179
dump9660,	mk9660 – create an ISO–9660 CD image	mk9660(8)	992
/inflateblock, inflatezlibblock, flateerr,	mkcrctab, blockcrc, adler32 – deflate/	flate(2)	463
dnsquery,/ query, ipquery, mkhash,	mkdb, mkhosts, cs, csquery, dns, dnstcp,	ndb(8)	
$\cdots \cdots $	mkdir - make a directory	mkdir(1)	184
mkfs,	mkext - archive or update a file system	mkfs(8)	995
flash memory	mkflashfs - make a journalling file system for .	mkflashfs(8)	994
/writesubfont, stringsubfont, strsubfontwidth,	mkfont - subfont manipulation	subfont(2)	633
	mkfs, mkext - archive or update a file system	mkfs(8)	995
archfs - mount	mkfs-style archive	archfs(4)	753
galaxy,	mkgalaxy - galactic n-body simulator	galaxy(1)	107
dnsdebug,/ query, ipquery, mkhash, mkdb,	mkhosts, cs, csquery, dns, dnstcp, dnsquery, .	ndb(8)	1000
system	mkpaqfs - make a compressed read-only file .	mkpaqfs(8)	996
	mksacfs - make a compressed file system	mksacfs(8)	997
	mktemp - make a unique file name	mktemp(2)	544
ml,	mlmgr, mlowner - unmoderated mailing lists	mlmgr(1)	185
	mnihongo - macros for typesetting Japanese	mnihongo(6)	874
	mnt – attach to 9P servers	mnt(3)	711
points for file systems	mntgen - automatically generate mount	mntgen(4)	790
chmod – change	mode	chmod(1)	47
5e -	mode ARM emulation	5e(1)	10
spin – verification tool for		spin(1)	278
frexp, Idexp,	modf - split into mantissa and exponent modification date of a file	frexp(2)	480
touch – set mtime – print file	modification date of a file	touch(1)	310 190
/juggle, life, mandel, mahjongg, memo, midi,	mole, packet, sokoban, sudoku – time/	mtime(1)	109
yqadb – VGA controller and	mole, packet, sokoban, sudoku – time/ monitor database	games(1) vgadb(6)	901
- vgadb - vGA controller and winwatch -	monitor rio windows	winwatch(1)	339
disk/smart – SMART error		smart(8)	
Web files	mothra – retrieve and display World-Wide	mothra(1)	186

	22.fr	t = == = F = (A)	014
- cpiors, taprs, tarrs, tprs, vors, vijurs, ziprs - archfs	mount archival file systems	tapefs(4) archfs(4)	814 753
	mount point stubs	stub(8)	
mntgen – automatically generate	mount points for file systems	mntgen(4)	790
snap, snapfs - create and	mount process snapshots	snap(4)	810
bind,	mount, unmount - change name space	bind(1)	36
bind,	mount, unmount - change name space	bind(2)	388
shr - global	mountpoints	shr(3)	732
a port	mouse, aux/accupoint - configure a mouse to	mouse(8)	998
drawgetrect, menuhit, setcursor, enter -	mouse control /moveto, getrect,	mouse(2)	545 712
/emenuhit, eenter, emoveto, esetcursor, Event,	mouse, cursor – kernel mouse interface Mouse, Menu – graphics events	mouse(3) event(2)	449
paint – create image files by drawing with a	mouse or other pointing device	paint(1)	210
aux/mouse, aux/accupoint - configure a	mouse to a port	mouse(8)	998
cp, fcp, mv - copy,	move files	cp(1)	55
/xformplane, pushmat, popmat, rot, grot, scale,	move, xform, ixform, persp, look, viewport -/ .	matrix(2)	534
initmouse, readmouse, closemouse,	moveto, getrect, drawgetrect, menuhit,/	mouse(2)	545
sundec, wavdec, pcmconv, mixfs -/ . mp3dec,	mp3enc, oggdec, oggenc, flacdec, flacenc,	audio(1)	26
/vtomp, mptov, mptod, dtomp, mpdigdiv,	mpadd, mpsub, mpleft, mpright, mpmul,/	mp(2)	547
/mpnew, mpfree, mpbits, mpnorm, mpcopy,	mpassign, mprand, mpnrand, strtomp,/	mp(2)	547
generator	mpc – extended precision arithmetic code	mpc(1)	188
/mpmodadd, mpmodsub, mpmodmul, mpdiv,	mpcmp, mpsel, mpfactorial, mpextendedgcd,/	mp(2)	547 547
strtomp,/ /mpnew, mpfree, mpbits, mpnorm, /mptouv, vtomp, mptov, mptod, dtomp,	mpcopy, mpassign, mprand, mpnrand, mpdigdiv, mpadd, mpsub, mpleft, mpright,/	mp(2) mp(2)	547
mpmod, mpmodadd, mpmodsub, mpmodmul,	mpdigut, mpadd, mpsub, mplett, mplgtt,/ mpdiv, mpcmp, mpsel, mpfactorial,/ /mpexp,	mp(2)	547
/mpdiv, mpcmp, mpsel, mpfactorial,	mpextendedgcd, mpinvert, mpsignif,/	mp(2)	547
/mpassign, mprand, mpnrand, strtomp,	mpfmt, mptoa, betomp, mptobe, mptober, /	mp(2)	547
mprand, mpnrand, / mpsetminbits, mpnew,	mpfree, mpbits, mpnorm, mpcopy, mpassign,	mp(2)	547
	mpictures – picture inclusion macros	mpictures(6)	875
mpcmp, mpsel, mpfactorial, mpextendedgcd,	mpinvert, mpsignif, mplowbits0,/ /mpdiv,	mp(2)	547
/mptod, dtomp, mpdigdiv, mpadd, mpsub,	mpleft, mpright, mpmul, mpexp, mpmod,/	mp(2)	547
mpextendedgcd, mpinvert, mpsignif,	mplowbits0, mpvecdigmuladd,/ /mpfactorial,	mp(2)	547
/mpveccmp, mpvecmul, mpmagcmp,	mpmagadd, mpmagsub, crtpre, crtin, crtout,/	mp(2)	547
/mpsub, mpleft, mpright, mpmul, mpexp,	mpmod, mpmodadd, mpmodsub, mpmodmul,/	mp(2)	547
mpassign, mprand, mpnrand,/ mpsetminbits, dtomp, mpdigdiv, mpadd, mpsub, mpleft,	mpnew, mpfree, mpbits, mpnorm, mpcopy, mpright, mpmul, mpexp, mpmod, / . /mptod,	mp(2)	547 547
/mpmodsub, mpmodmul, mpdiv, mpcmp,	mpsel, mpfactorial, mpextendedgcd,/	mp(2) mp(2)	547
mpnorm, mpcopy, mpassign, mprand,/	mpsetminbits, mpnew, mpfree, mpbits,	mp(2)	547
/mpsel, mpfactorial, mpextendedgcd, mpinvert,	mpsignif, mplowbits0, mpvecdigmuladd,/	mp(2)	547
/mptov, mptod, dtomp, mpdigdiv, mpadd,	mpsub, mpleft, mpright, mpmul, mpexp,/	mp(2)	547
/mpassign, mprand, mpnrand, strtomp, mpfmt,	mptoa, betomp, mptobe, mptober, letomp,/	mp(2)	547
/mptoi, itomp, uvtomp, mptouv, vtomp, mptov,	mptod, dtomp, mpdigdiv, mpadd, mpsub,/	mp(2)	547
/mptoa, betomp, mptobe, mptober, letomp,	mptole, mptolel, mptoui, uitomp, mptoi,/	mp(2)	547
/mptoui, uitomp, mptoi, itomp, uvtomp,	mptouv, vtomp, mptov, mptod, dtomp,/	mp(2)	547
/mpvecdigmuladd, mpvecdigmulsub,	mpvecadd, mpvecsub, mpveccmp, mpvecmul,/	mp(2)	547
was was sured between	ms – macros for formatting manuscripts	ms(6)	
ms macros and html	ms2html, html2ms - convert between troff's MS2TK, TK2MS, TK2SEC - kernel times and	ms2html(1) seconds(9)	189
/wdoc2txt, xls2txt, olefs, mswordstrings,	msexceltables – extract printable text from/	doc2txt(1)	77
	MSI configuration	icanhasmsi(8)	979
malloc, mallocz, smalloc, realloc, free,	msize, secalloc, secfree, setmalloctag,/	malloc(9)	
mallocalign, mallocz, free, realloc, calloc,	msize, setmalloctag, setrealloctag, / malloc,	malloc(2)	532
doc2txt, doc2ps, wdoc2txt, xls2txt, olefs,	mswordstrings, msexceltables - extract/	doc2txt(1)	77
	mtime – print file modification time	mtime(1)	190
qinv, qlen, slerp, qmid, qsqrt -/ qtom,		quaternion(2)	588
	mug - convert an image to a face icon	mug(1)	191
dist3, unit3, midpt3,/ add3, sub3, neg3, div3,	mul3, eqpt3, closept3, dot3, cross3, len3,	arith3(2)	375
multiplication and division addpt, subpt,	muldiv, umuldiv – high-precision mulpt, divpt, rectaddpt, rectsubpt, insetrect,	muldiv(2)	552 363
mc –	multicolumn print	addpt(2) mc(1)	176
muldiv, umuldiv – high-precision	multiplication and division	muldiv(2)	552
malan, amalan mgn precision	mus – MUS to MIDI converter	mus(1)	192
juke –	music jukebox	juke(7)	907
cp, fcp,	mv – copy, move files	cp(1)	55
/parseipandmask, v4parseip, parseether,	myipaddr, myetheraddr, maskip, equivip4,/	ip(2)	519
PCI Interfaces pnp – Plug	'n' Play ISA and	pnp(3)	715
PCI–SCSI I/O Processors	na – assembler for the Symbios Logic	na(8)	999
cleanname - clean a path	name	cleanname(1)	48
cleanname - clean a path	name	cleanname(2)	400
getuser, sysname – get user or system mktemp – make a unique file	name	getuser(2) mktemp(2)	490 544
basename – strip file	name affixes	basename(1)	33
	name associated with file descriptor	fd2path(2)	460
	name completion	complete(2)	402
		· · · · · · · · · · · · · · · · · · ·	-

Infs – Iong	name file system	Infs(4)	789
nm –	name list (symbol table)	nm(1)	203
bind, mount, unmount - change	name space	bind(1)	36
bind, mount, unmount – change	name space	bind(2)	388
namespace - structure of conventional file	name space	namespace(4)	791 204
ns – display pipefile – attach filter to file in	name space	ns(1) pipefile(1)	204
namespace –	name space description file	namespace(6)	878
	name space from a remote system	import(4)	784
freectlimage, initcontrols, namectlfont,	namectlimage, newcontrolset,/ /freectlfont,	control(2)	403
	named segment	seg(1)	270
allocimage, allocimagemix, freeimage,	nameimage, namedimage, setalpha,/	allocimage(2)	367
	names from the dump	history(1)	147
yesterday, diffy - print file	names from the dump	yesterday(1)	344
idn2utf - convert internationalized domain	names to and from unicode utf2idn,	idn(2)	514
	namespace – name space description file	namespace(6)	878
name space	namespace – structure of conventional file	namespace(4)	791 553
infinity functions	NaN, Inf, isNaN, isInf - not-a-number and nanoseconds since epoch	nan(2) time(2)	555 642
nbrecv, nbrecvp, nbrecvul, nbsend, nbsendp,	nbsendul, threadcreate, threaddata,/ /sendul,	thread(2)	638
hbreev, hbreevp, hbreevul, hbseliu, hbseliup,	ndb – Network database	ndb(6)	879
ndbsearch, ndbsnext, ndbgetvalue,/ ndbopen,	ndbcat, ndbchanged, ndbclose, ndbreopen,	ndb(2)	554
ndbsearch, ndbsnext,/ ndbopen, ndbcat,	ndbchanged, ndbclose, ndbreopen,	ndb(2)	554
/csgetvalue, ndbfindattr, dnsquery, ndbdiscard,	ndbconcatenate, ndbreorder, ndbsubstitute,/	ndb(2)	554
ndbconcatenate, ndbreorder, ndbsubstitute,	ndbdedup - network database /ndbdiscard,	ndb(2)	554
/csipinfo, ndbhash, ndbparse, csgetvalue,	ndbfindattr, dnsquery, ndbdiscard,/	ndb(2)	554
csipinfo,/ /ndbsearch, ndbsnext, ndbgetvalue,	ndbfree, ipattr, ndbgetipaddr, ndbipinfo,	ndb(2)	554
/ipattr, ndbgetipaddr, ndbipinfo, csipinfo,		ndb(2)	554
ndbreopen, ndbsearch, ndbsnext,/ /ndbgetipaddr, ndbipinfo, csipinfo, ndbhash,	ndbopen, ndbcat, ndbchanged, ndbclose, ndbparse, csgetvalue, ndbfindattr, dnsguery,/	ndb(2) ndb(2)	554 554
ndbopen, ndbcat, ndbchanged, ndbclose,	ndbreopen, ndbsearch, ndbsnext,/	ndb(2)	554
/dnsquery, ndbdiscard, ndbconcatenate,	ndbreorder, ndbsubstitute, ndbdedup -/	ndb(2)	554
/ndbcat, ndbchanged, ndbclose, ndbreopen,	ndbsearch, ndbsnext, ndbgetvalue, ndbfree,/	ndb(2)	554
/ndbdiscard, ndbconcatenate, ndbreorder,	ndbsubstitute, ndbdedup – network database	ndb(2)	554
/len3, dist3, unit3, midpt3, lerp3, reflect3,	nearseg3, pldist3, vdiv3, vrem3, pn2f3,/	arith3(2)	375
	nedmail - reading mail	nedmail(1)	193
/quoterunestrfmt, quotefmtinstall, doquote,	needsrcquote - quoted character strings	quote(2)	590
cross3, len3, dist3, unit3,/ add3, sub3,		arith3(2)	375
version -	negotiate protocol version	version(5)	844
fversion – initialize 9P connection and gb, gba,	negotiate version	fversion(2) nintendo(1)	484 201
gb, gba,	netaudit – network configuration checker	netaudit(8)	
encrypt, decrypt,	netcrypt – DES encryption	encrypt(2)	447
passwd,	netkey – change or verify user password	passwd(1)	211
dial, hangup, announce, listen, accept, reject,	netmkaddr, setnetmtpt, getnetconninfo,/	dial(2)	427
	netstat - summarize network connections	netstat(1)	196
aan, aanuke – always available		aan(8)	924
fax, telcofax, telcodata – telephone dialer		telco(4)	815
- PC bootloader for FAT, ISO and PXE	network booting /bootx64.efi, efiboot.fat network buffers /packetsplit, packetstats,	9boot(8)	921
	Network Computing (VN) /vncv – remote	venti-packet(2) vnc(1)	663 331
netaudit –		netaudit(8)	
	network connections /getnetconninfo,	dial(2)	427
	network connections	netstat(1)	196
vtrecv, vtversion, vtdebug, vthangup - Venti	network connections /vtfreeconn, vtsend,	venti-conn(2)	655
	network daemon	cifsd(8)	938
ndbreorder, ndbsubstitute, ndbdedup -		ndb(2)	554
ndb -		ndb(6)	879
dnsquery, dnsdebug, dnsgetip, inform - tcp17019, tcp17020 - listen for calls on a	network database . /cs, csquery, dns, dnstcp, network device /tcp17010, tcp17013,	ndb(8)	988
	network file service	listen(8) srv(4)	811
	network file system client	nfs(4)	794
	network filesystem client	cifs(4)	758
execnet –		execnet(4)	766
loopback –	network link simulation	loopback(3)	709
newt -		newt(1)	198
system nntpfs –	network news transport protocol (NNT) file	nntpfs(4)	796
snoopy – spy on	network packets	snoopy(8)	
gre, icmp, icmpv6, ipmux, rudp, tcp, udp, il –	network protocols over IP ip, esp, new file open,	ip(3) open(5)	698 838
newuser – adding a	• •	newuser(8)	
/initcontrols, namectlfont, namectlimage,	newcontrolset, resizecontrolset – interactive/	control(2)	403
crackhdr, machbytype, machbyname,		mach(2)	529
auth_proxy, fauth_proxy,/ amount,		auth(2)	379

/authsrv, guard.srv, debug, wrkey, login,	newns, none, as - maintain or query/	auth(8)	930
	news – print news items	news(1)	197
	news articles	ap(1)	22
nntpfs – network	news transport protocol (NNT) file system newt – network news transport protocol (NNT)	nntpfs(4) newt(1)	796 198
	newuser – adding a new user	newuser(8)	
Point, Rectangle, Cursor, initdraw, geninitdraw,	newwindow, drawerror, initdisplay,/ . Display,	graphics(2)	492
functions objtype, readobj, objtraverse, isar, handling functions error,	nextar, readar – object file interpretation nexterror, poperror, waserror – error	object(2) error(9)	564
/ntruerand, genrandom, prng, fastrand,	nfastrand – random number generators	rand(2)	591
,, <u>g</u> , <u>F</u> <u>g</u> ,,	nfs – Sun network file system client	nfs(4)	794
(defined) in A And C Charles a party apprend	nfsserver, portmapper, ponfsd - NFS service	nfsserver(8)	
/defmask, isv4, v4tov6, v6tov4, nhgetv, nhgetl,	nhgets, hnputv, hnputl, hnputs, ptclbsum,/	ip(2) nietzsche(1)	519 200
	nm – name list (symbol table)	nm(1)	203
newt - network news transport protocol	NNT) client	newt(1)	198
(NNT) file system	nntpfs – network news transport protocol none, as – maintain or query authentication/ .	nntpfs(4) auth(8)	796 930
- setjmp, longjmp, notejmp	non-local goto	setjmp(2)	622
rtc - real-time clock and	non-volatile RAM	rtc(3)	722
NaN, Inf, isNaN, isInf –	not-a-number and infinity functions	nan(2)	553 888
regexp - regular expression alarm - ask for delayed	notation	regexp(6) alarm(1)	888 21
sleep, alarm – delay, ask for delayed	note	sleep(2)	625
postnote - send a		postnote(2)	574
setjmp, longjmp, process notification	notejmp – non-local goto	setjmp(2) notify(2)	622 558
fauth_proxy,/ . amount, newns, addns, login,	noworld, procsetuser, auth_proxy,	auth(2)	379
exec, execl, _privates,	_nprivates, _tos - execute a file	exec(2)	452
genrandom, prng,/ rand, Irand, frand,	nrand, Inrand, srand, truerand, ntruerand,	rand(2)	591 314
troff, tbl - format tables for	nroff, dpost - text formatting and typesetting . nroff or troff	troff(1) tbl(1)	295
	ns – display name space	ns(1)	204
since epoch time,		time(2)	642
/Irand, frand, nrand, Inrand, srand, truerand, clocks, process/process group ids, user,	ntruerand, genrandom, prng, fastrand,/ null, reboot, etc cons - console,	rand(2) cons(3)	591 683
fwstat, dirstat, dirfstat, dirwstat, dirfwstat,	nulldir – get and put file status . /fstat, wstat,	stat(2)	626
NaN, Inf, isNaN, isInf -	number and infinity functions	nan(2)	553
factor, primes - factor a probably_prime, smallprimetest - prime	number, generate large primes	factor(1) prime(2)	95 575
prng, fastrand, nfastrand – random	number generation /DSAprines, number generators . /ntruerand, genrandom,	rand(2)	591
strtol, strtoll, strtoul, strtoull - convert text to	numbers /atoi, atol, atoll, charstod, strtod,	atof(2)	378
seq – print sequences of	numbers	seq(1) nusbrc(8)	272
convTR2M, convM2TR,/ . authdial, passtokey,	nvcsum, readnvram, convT2M, convM2T,	authsrv(2)	382
a.out -	object file format	a.out(6)	847
python – an interpreted, interactive,	object-oriented programming language	python(1)	233
interpretation functions objtype, readobj, xd - hex,	objtraverse, isar, nextar, readar – object file octal, decimal, or ASCII dump	object(2) xd(1)	564 341
import	oexportfs - legacy exportfs for cpu and	oexportfs(4)	799
seek - change file		seek(2)	616
pcmconv, mixfs -/ mp3dec, mp3enc, oggdec, /tlsServer, initThumbprints, freeThumbprints,	oggenc, flacdec, flacenc, sundec, wavdec, okThumbprint, okCertificate, readcert,/	audio(1) pushtls(2)	26 583
printable/ doc2txt, doc2ps, wdoc2txt, xls2txt,	olefs, mswordstrings, msexceltables – extract	doc2txt(1)	77
thesaurus – search	online thesaurus	thesaurus(1)	303
os – interface to host OS commands (drawterm mkpaqfs – make a compressed	only)	os(1) mkpaqfs(8)	206 996
paqfs – compressed	only file system	paqfs(4)	800
existing or new file	open, create - prepare a fid for I/O on an	open(5)	838
or writing, create file dup – duplicate an	open, create, close – open a file for reading open file descriptor	open(2) dup(2)	566 440
dup – dupicate an dup – dups of		dup(2) dup(3)	689
/configdev, devctl, getdev, loaddevstr, opendev,	opendevdata, openep, unstall – USB device/	nusb(2)	560
/File, createfile, closefile, removefile, walkfile,	opendirfile, readdirfile, closedirfile, hasperm/ . opendisk, Disk – generic disk device interface .	9pfile(2) disk(2)	357 431
/getdev, loaddevstr, opendev, opendevdata,	openep, unstall – USB device driver library	nusb(2)	560
/bufimage, lockdisplay, unlockdisplay,	openfont, buildfont, freefont, Pfmt, Rfmt,/	graphics(2)	492
/memlineendsize, allocmemsubfont, scsierror – SCSI device operations	openmemsubfont, freememsubfont,/	memdraw(2)	536 612
cmd – interface to host	openscsi, closescsi, scsiready, scsi, scsicmd, operating system commands	scsi(2) cmd(3)	681
	opl3 - OPL3 chip emulator	opl3(1)	205
instrument banks dmid - MIDI to		dmid(1)	76 755
writer file system cdfs, cddb – ARGEND, ARGC, ARGF, EARGF – process	optical disc (CD, DVD, B) track reader and option letters from argv ARGBEGIN,	cdfs(4) arg(2)	755 373
,,,,p.00000	,	5(=)	

/scram, reboot - halt any local file systems and	optionally shut down or reboot the system	fshalt(8)	956
python – an interpreted, interactive,	oriented programming language	python(1)	233
/bottomnwindows, topwindow, topnwindows,	originwindow - window management	window(2)	668
(drawterm only)	os - interface to host OS commands	os(1)	206
programmed I/O inb, ins, inl, outb, outs,	outl, insb, inss, insl, outsb, outss, outsl –	inb(9)	
Bterm, Bbuffered, Blethal, Biofn – buffered	output /Bprint, Bvprint, Bwrite, Bflush,	• •	390
			461
fputs, puts, fread, fwrite - Stdio input and	output /putc, putchar, ungetc, fgets, gets,		
vprintf, vsprintf, vsnprintf - print formatted	output /printf, sprintf, snprintf, vfprintf,		474
lp – printer	output	lp(1)	168
runevseprint, runevsmprint - print formatted	output /vseprint, vsmprint, runevsnprint,		576
image, graphic, PostScript, PDF, and typesetter	output files page - view FAX,		208
proof – troff	output interpreter	proof(1)	228
troff2html – convert troff	output into HTML	troff2html(1)	316
feof, ferror, clearerr - standard buffered	output package . /ftell, fsetpos, fseek, rewind,	fopen(2)	469
- support for user-defined print formats and	output routines /runefmtstrflush, errfmt		466
inb, ins, inl, outb, outs, outl, insb, inss, insl,	outsb, outss, outsl - programmed I/O	inb(9)	1092
	p – paginate	p(1)	207
authsrv, p9any,	p9sk1, dp9ik – authentication protocols	authsrv(6)	851
clearerr – standard buffered input/output	package . /fsetpos, fseek, rewind, feof, ferror,		469
/readblist, concatblock, copyblock, trimblock,	packblock, padblock, pullblock, pullupblock,/		
wol - send wake-on-lan Ethernet	packet		
packetasize, packetcmp, packetconcat,/	Packet, packetalloc, packetappend,		663
/life, mandel, mahjongg, memo, midi, mole,	packet, sokoban, sudoku - time wasters		109
packetcmp, packetconcat,/ Packet,	packetalloc, packetappend, packetasize,		663
/packetasize, packetcmp, packetconcat,	packetconsume, packetcopy, packetdup,/		663
/packetconsume, packetcopy, packetdup,	packetforeign, packetfragments, packetfree,/ .	venti-packet(2)	663
/packetforeign, packetfragments, packetfree,	packetheader, packetpeek, packetprefix,/	venti-packet(2)	663
snoopy – spy on network	packets	snoopy(8)	1056
udpecho – echo UDP	packets	udpecho(8)	1069
/packetheader, packetpeek, packetprefix,	packetsha1, packetsize, packetsplit,/		663
/packetpeek, packetprefix, packetsha1,	packetsize, packetsplit, packetstats,/		663
buffers . /packetsize, packetsplit, packetstats,	packettrailer, packettrim – zero-copy network		663
/concatblock, copyblock, trimblock, packblock,	padblock, pullblock, pullupblock, adjustblock,/	allocb(9)	
PDF, and typesetter output files	page – view FAX, image, graphic, PostScript,		208
webpaste, urlencode – retrieve, post to a web	page corresponding to a url hget, hpost,	page(1)	
			145
man, lookman, sig - print or find	pages of this manual		173
p –	paginate	p(1)	207
mouse or other pointing device	paint - create image files by drawing with a	paint(1)	210
	panic - abandon hope, all ye who enter here	panic(9)	
	paqfs - compressed read-only file system	paqfs(4)	800
lpt –	parallel port interface for PC's	lpt(3)	710
bitsyload, light, pencal, keyboard,	params, prompter - bitsy-specific utilities	bitsyload(1)	38
rdproto –	parse and process a proto file listing	proto(2)	581
device commands	parsecmd, cmderror, lookupcmd - parse	parsecmd(9)	1098
control message parsing Cmdbuf,	parsecmd, respondemderror, lookupemd	9pcmdbuf(2)	354
freedocinfo, dimenkind, dimenspec, targetid,/	parsehtml, printitems, validitems, freeitems,	html(2)	496
v4parseip, parseether, myipaddr,/ eipfmt,	parseip, parseipmask, parseipandmask,	ip(2)	519
targetid, targetname, fromStr, toStr - HTML	parser . /freedocinfo, dimenkind, dimenspec,		496
jsonfree, jsonbyname, jsonstr – JSON	parser jsonparse,	json(2)	523
lookupcmd – control message	parsing /parsecmd, respondemderror,		354
getflags, usage – command-line	parsing for shell scripts		957
gettiags, usage - command-ime		getflags(8)	
chine chine contractions	partfs – serve file, with partitions	partfs(8)	
cryptsetup – setup encrypted		cryptsetup(8)	942
at, drain, expect,		expect(1)	92
convM2T, convTR2M, convM2TR,/ authdial,	passtokey, nvcsum, readnvram, convT2M,	authsrv(2)	382
password	passwd, netkey - change or verify user	passwd(1)	211
system	patch - simple patch creation and tracking	patch(1)	212
walk – walk a		walk(1)	334
cleanname – clean a		cleanname(1)	48
cleanname - clean a		cleanname(2)	400
authentication box securenet - Digital		securenet(8)	1051
grep, g - search a file for a		grep(1)	115
language	pattern-directed scanning and processing	awk(1)	29
ARROW, drawsetdebug - graphics functions	PB L /runestringbg, runestringnbg, _string,	draw(2)	432
pwd,	pbd – working directory	pwd(1)	232
vmx – virtual		vmx(1)	329
	pc – programmer's calculator	pc(1)	214
/bootia32.efi, bootx64.efi, efiboot.fat -		9boot(8)	921
	PC I/O registers	io(1)	152
bhd _	pc keyboard driver	kbd(3)	707
getcallerpc – fetch return	PC of current function		485
findlocal, getauto,/ syminit, getsym, symbase,		symbol(2)	635
maiocai, gelaulo,/ symmit, gelsym, symbase,	pc2sp, pc2line, textseg, intezadur, lookup, pcc – APE C compiler driver		216
		pcc(1)	
	pci – print PCI bus configuration	pci(8)	1012

	PCI Interfaces	pnp(3)	715
na – assembler for the Symbios Logic	PCI–SCSI I/O Processors	na(8)	999
Computer Memory Card Interface Association	PCMCI) device i82365 - Personal	i82365(3)	
	pcmcia - identify a PCMCIA card	pcmcia(8)	
/oggenc, flacdec, flacenc, sundec, wavdec,	pcmconv, mixfs - decode and encode audio/ .	audio(1)	26
nfsserver, portmapper,	pcnfsd – NFS service	nfsserver(8)	
lpt – parallel port interface for	PC's	lpt(3)	710
plan9.ini – configuration file for	PCs	plan9.ini(8)	1017
pdf2ps - convert between PostScript and	PDF ps2pdf,	ps2pdf(1)	230
page – view FAX, image, graphic, PostScript,	PDF, and typesetter output files	page(1)	208
gs - Aladdin Ghostscript (PostScript and	PDF language interpreter)	gs(1)	116
ps2pdf,	pdf2ps - convert between PostScript and PDF .	ps2pdf(1)	230
/pldist3, vdiv3, vrem3, pn2f3, ppp2f3, fff2p3,	pdiv4, add4, sub4 - operations on 3-d points/	arith3(2)	375
tinc – mesh peer to	peer VPN	tinc(8)	1065
Mail (PE) format pemdecode,	pemencode - encode files in Privacy Enhanced	pem(8)	1014
bitsy-specific utilities bitsyload, light,	pencal, keyboard, params, prompter	bitsyload(1)	38
privalloc -	per-process private storage management	privalloc(2)	579
messages	perror, syslog, sysfatal – system error	perror(2)	567
Association (PCMCI) device i82365 -	Personal Computer Memory Card Interface	i82365(3)	697
popmat, rot, grot, scale, move, xform, ixform,	persp, look, viewport - Geometric/ /pushmat,	matrix(2)	534
termination and interruption kproc,	pexit, postnote – kernel process creation,	kproc(9)	
/unlockdisplay, openfont, buildfont, freefont,	Pfmt, Rfmt, strtochan, chantostr, chantodepth/	graphics(2)	492
tel, iwhois – look in	phone book	tel(1)	300
timmy –	physics sandbox	timmy(1)	306
chiniy	pic – troff preprocessor for drawing pictures	pic(1)	218
grap -	pic preprocessor for drawing graphs	grap(1)	112
resample, resize – resample a		resample(1)	249
rotate – rotate or mirror a		rotate(1)	249
dpic, todpic – Doom	picture decoder and encoder		79
· · · ·	picture inclusion macros	dpic(1) mpictures(6)	875
mpictures -			
toppm, topng, totif, toico – view and convert pic – troff preprocessor for drawing	pictures . /yuv, ico, tga, tojpg, togeordi, togif,	jpg(1)	156
	pictures	pic(1)	218
Internet	ping, gping, traceroute, hogports – probe the .	ping(8)	
	pipe - create an interprocess channel	pipe(2)	568
	pipe - two-way interprocess communication	pipe(3)	714
tee –		tee(1)	299
	pipefile - attach filter to file in name space	pipefile(1)	221
tap - follow the		tap(1)	292
	pixels and colors	color(6)	856
intro – introduction to	Plan 9	intro(1)	1
style –	Plan 9 coding conventions for C	style(6)	893
intro – introduction to the	Plan 9 devices	intro(3)	670
statcheck, sizeS2M, sizeD2M - interface to	Plan 9 File protocol /read9pmsg,	fcall(2)	457
intro – introduction to the		intro(5)	830
	plan9.ini - configuration file for PCs	plan9.ini(8)	
add4, sub4 - operations on 3-d points and		arith3(2)	375
	play – simple audio player	play(1)	222
pnp – Plug 'n'		pnp(3)	715
	playlistfs – playlist file system	playlistfs(7)	914
/dist3, unit3, midpt3, lerp3, reflect3, nearseg3,	pldist3, vdiv3, vrem3, pn2f3, ppp2f3, fff2p3,/	arith3(2)	375
	plot – graphics filter	plot(1)	223
	plot – graphics interface	plot(6)	882
fplot –	plot elementary function	fplot(1)	104
pnp –		pnp(3)	715
	plumb – format of plumb messages and rules .	plumb(6)	884
	plumb – send message to plumber	plumb(1)	224
/plumblookup, plumbpack, plumbpackattr,	plumbaddattr, plumbdelattr, plumbrecv,/	plumb(2)	569
messaging	plumber – file system for interprocess	plumber(4)	801
ptrap –	plumber (4) filter	ptrap(4)	802
plumbsendtext, plumblookup,/ eplumb,	plumbfree, plumbopen, plumbsend,	plumb(2)	569
exportfs, srvfs – file server	plumbing	exportfs(4)	767
/plumbopen, plumbsend, plumbsendtext,	plumblookup, plumbpack, plumbpackattr,/	plumb(2)	569
plumbunpackpartial, plumbunpackattr,	Plumbmsg – plumb messages /plumbunpack,	plumb(2)	569
plumblookup,/ eplumb, plumbfree,	plumbopen, plumbsend, plumbsendtext,	plumb(2)	569
/plumbsend, plumbsendtext, plumblookup,	plumbpack, plumbpackattr, plumbaddattr,/	plumb(2)	569
plumbpackattr, plumbaddattr, plumbdelattr,	plumbrecv, plumbunpack, / /plumbpack,	plumb(2)	569
plumbpack,/ eplumb, plumbfree, plumbopen,	plumbsend, plumbsendtext, plumblookup,	plumb(2)	569
/plumbaddattr, plumbdelattr, plumbrecv,	plumbunpack, plumbunpackpartial,/	plumb(2)	569
/plumbrecv, plumbunpack, plumbunpackpartial,	plumbunpackattr, Plumbmsg – plumb/	plumb(2)	569
/reflect3, nearseg3, pldist3, vdiv3, vrem3,	pn2f3, ppp2f3, fff2p3, pdiv4, add4, sub4 -/	arith3(2)	375
togeordi, togif, toppm, topng, totif,/ . jpg, gif,	png, tif, ppm, bmp, v210, yuv, ico, tga, tojpg,	jpg(1)	156
	pnp - Plug 'n' Play ISA and PCI Interfaces	pnp(3)	715
getfcr, setfcr, getfsr, setfsr - control floating	point	getfcr(2)	487
hoc – interactive floating	point language	hoc(1)	148
		/	-

ppp, pppoe, pptp, pptpd –	point protocol	ppp(8)	
geninitdraw, newwindow, drawerror,/ Display,	Point, Rectangle, Cursor, initdraw,	graphics(2)	492
stub – provide mount	point stubs	stub(8)	
image files by drawing with a mouse or other	pointing device paint - create	paint(1)	210
fff2p3, pdiv4, add4, sub4 - operations on 3-d badrect, Dx, Dy, Pt, Rect, Rpt - arithmetic on	points and planes /vrem3, pn2f3, ppp2f3, points and rectangles . /rectclip, combinerect,	arith3(2) addpt(2)	375 363
locks, reader–writer locks, rendezvous	points and reference counts /rendezvous	lock(2)	526
mntgen – automatically generate mount	points for file systems	mntgen(4)	790
ppp, pppoe, pptp, pptpd -	point-to-point protocol	ppp(8)	
/gendraw, drawreplxy, drawrepl, replclipr, line,	poly, fillpoly, bezier, bezspline, fillbezier,/	draw(2)	432
/hmac_sha2_384, hmac_sha2_512,	poly1305 - cryptographically secure hashes	sechash(2)	614
/poolrealloc, poolcompact, poolcheck,	poolblockcheck, pooldump – general memory/	pool(2)	571
poolrealloc,/ poolalloc, poolallocalign,	poolfree, poolmsize, poolisoverlap,	pool(2)	571
	pop3, imap4d - Internet mail servers	pop3(8)	
error, nexterror,	poperror, waserror - error handling functions .	error(9)	
ixform,/ /xformpointd, xformplane, pushmat,	popmat, rot, qrot, scale, move, xform,	matrix(2)	534
aux/accupoint - configure a mouse to a	port aux/mouse,	mouse(8)	998
lpt – parallel	port interface for PC's	lpt(3)	710
nfsserver, gpsfs, gpsevermore – GPS time and	portmapper, pcnfsd – NFS service	nfsserver(8)	1008 959
hget, hpost, webpaste, urlencode – retrieve,	position service	gpsfs(8) hget(1)	145
/emalloc9p, erealloc9p, estrdup9p, listensrv,	postrio a web page corresponding to a un	9p(2)	349
termination and interruption kproc, pexit,	postnote – kernel process creation,	kproc(9)	
process group	postnote – send a note to a process or	postnote(2)	574
ps2pdf, pdf2ps - convert between	PostScript and PDF	ps2pdf(1)	230
gs – Aladdin Ghostscript		gs(1)	116
page – view FAX, image, graphic,	PostScript, PDF, and typesetter output files	page(1)	208
lp –	PostScript preprocessors	lp(8)	990
/estrdup9p, listensrv, postmountsrv,	postsharesrv, readbuf, readstr, respond,/	9p(2)	349
square root exp, log, log10, pow,	pow10, sqrt - exponential, logarithm, power,	exp(2)	455
acpi - Advanced Configuration and	Power Interface	acpi(8)	925
apm – Advanced	Power Management 1.2 BIOS interface	apm(3)	674
apm – Advanced	Power Management 1.2 BIOS interface power, square root exp, log, log10,	apm(8)	927 455
pow, pow10, sqrt – exponential, logarithm, togeordi, togif, toppm,/ jpg, gif, png, tif,	ppm, bmp, v210, yuv, ico, tga, tojpg,	exp(2) jpg(1)	156
/nearseg3, pldist3, vdiv3, vrem3, pn2f3,	ppp2f3, fff2p3, pdiv4, add4, sub4 -/	arith3(2)	375
ppp,		ppp(8)	
PPP;	pr – print file	pr(1)	225
read, readn, write,		read(2)	594
write readv, writev,	pready, pwritey - scatter/gather read and	readv(2)	596
crtin, crtout, crtprefree, crtresfree – extended	precision arithmetic /mpmagsub, crtpre,	mp(2)	547
mpc – extended	precision arithmetic code generator	mpc(1)	188
bc –	precision arithmetic language	bc(1)	34
muldiv, umuldiv -	precision multiplication and division	muldiv(2)	552
disks, floppies and flashes	prep, edisk, fdisk, format, mbr - prepare	prep(8)	
cpp - C language grap - pic	preprocessor	cpp(1)	56 112
pic – troff	preprocessor for drawing pictures	grap(1) pic(1)	218
timepic – troff		timepic(1)	305
	preprocessors	lp(8)	990
ap – fetch Associated	Press news articles	ap(1)	22
DSAprimes, probably_prime, smallprimetest -	prime number generation . /genstrongprime,	prime(2)	575
primes		factor(1)	95
	print	mc(1)	176
echo –	print arguments	echo(1)	83
astro –	print astronomical information	astro(7)	905
- cal kill slav broke dontkill	print calendar	cal(1)	42
kill, slay, broke, dontkill – stop, start –	print commands to kill processesprint commands to stop and start processes	kill(1)	160 285
pr –	print file	stop(1) pr(1)	225
mtime –	print file modification time	mtime(1)	190
history –	print file names from the dump	history(1)	147
yesterday, diffy –	print file names from the dump	yesterday(1)	344
/errfmt - support for user-defined	print formats and output routines	fmtinstall(2)	466
snprintf, vfprintf, vprintf, vsprintf, vsnprintf -	print formatted output /printf, sprintf,	fprintf(2)	474
runesprint, runesnprint, runeseprint,/	print, fprint, sprint, snprint, seprint, smprint,	print(2)	576
freq -	print histogram of character frequencies	freq(1)	105
format memory -	print memory statistics in human-readable	memory(8)	991
icanhasmsi – news –	print MSI configuration	icanhasmsi(8)	979 197
man, lookman, sig –	print or find pages of this manual	news(1) man(1)	173
nietzsche –	print out Nietzsche quote	nietzsche(1)	200
pci –	print PCI bus configuration	pci(8)	
cpuid, icanhasvmx –	print processor information	cpuid(8)	939
• •		•	

50g	print coquences of numbers	cod(1)	272
seq – size –	print sequences of numbers print size of executable files	seq(1) size(1)	272
calendar –	print upcoming events	calendar(1)	43
weather –	print weather report	weather(1)	337
strings – extract	printable strings	strings(1)	286
/olefs, mswordstrings, msexceltables - extract	printable text from Microsoft documents	doc2txt(1)	77
lp –	printer output	lp(1)	168
vsprintf, vsnprintf - print formatted/ . fprintf,	printf, sprintf, snprintf, vfprintf, vprintf,	fprintf(2)	474
dimenkind, dimenspec, targetid,/ parsehtml,	printitems, validitems, freeitems, freedocinfo,	html(2)	496
guard.srv, debug,/ changeuser, convkeys,	printnetkey, status, enable, disable, authsrv,	auth(8)	930
pemdecode, pemencode – encode files in	Privacy Enhanced Mail (PE) format	pem(8)	
management	privalloc – per-process private storage	privalloc(2)	579
exec, execl,	_privates, _nprivates, _tos - execute a file	exec(2) eve(9)	452
eve, iseve - /srand, truerand, ntruerand, genrandom,	privileged userprng, fastrand, nfastrand - random number/ .	rand(2)	591
/gensafeprime, genstrongprime, DSAprimes,	probably_prime, smallprimetest – prime/	prime(2)	575
ping, gping, traceroute, hogports -	probe the Internet	ping(8)	
	proc – running processes	proc(3)	717
/chanclosing, chanprint, mainstacksize,	proccreate, procdata, procexec, procexecl,/	thread(2)	638
booting - bootstrapping	procedures	booting(8)	935
tap – follow the pipes of a	process	tap(1)	292
rdproto – parse and	process a proto file listing	proto(2)	581
cputime, times, cycles – cpu time in this	process and children	cputime(2)	418
procsetname – set	process arguments	•	580
trace - show (real-time)	process behavior	trace(1)	313
atexitdont, terminate – terminate process,	process cleanup exits, _exits, atexit,	exits(2)	454
interruption kproc, pexit, postnote - kernel	process creation, termination and	kproc(9)	574
postnote - send a note to a process or cons - console, clocks,	process group process group ids, user, null, reboot, etc.	postnote(2) cons(3)	683
getpid, getppid – get	process ids	getpid(2)	489
notify, noted, atnotify – handle asynchronous	process notification	notify(2)	558
ARGBEGIN, ARGEND, ARGC, ARGF, EARGF -	process option letters from argy	arg(2)	373
postnote - send a note to a	process or process group	postnote(2)	574
privalloc –	process private storage management	privalloc(2)	579
_exits, atexit, atexitdont, terminate - terminate	process, process cleanup exits,	exits(2)	454
fork, rfork - manipulate	process resources	fork(2)	472
snap, snapfs - create and mount	process snapshots	snap(4)	810
snap –	process snapshots	snap(6)	892
ps, psu, pstree –	process status	ps(1)	229
sleep, wakeup, tsleep, return0 – rendezvous – user level	process synchronisation	sleep(9)	600
ratrace – trace	process synchronizationprocess system calls	rendezvous(2) ratrace(1)	238
await, wait, waitpid – wait for a	process to exit	wait(2)	667
cap - capabilities for setting the user id of	processes	cap(3)	680
slay, broke, dontkill - print commands to kill	processes kill,	kill(1)	160
proc – running	processes	proc(3)	717
stop, start - print commands to stop and start	processes	stop(1)	285
ioread, ioreadn, iosleep, iowrite - slave I/O	processes for threaded programs /ioproc,	ioproc(2)	516
awk - pattern-directed scanning and	processing language	awk(1)	29
reqqueuepush, reqqueueflush – deferred	processing of 9P requests /requeuecreate,	9pqueue(2)	359
troff2png, troff2gif - miscellaneous text cpuid, icanhasvmx - print	processing tools processor information	troff2png(1)	317 939
- assembler for the Symbios Logic PCI–SCSI I/O	Processors na	cpuid(8) na(8)	999
etc cons – console, clocks,	process/process group ids, user, null, reboot,	cons(3)	683
anyhigher, anyready, hzsched, procpriority,	procrestore, procsave, scheddump, schedinit,/	sched(9)	
/proccreate, procdata, procexec, procexecl,	procrfork, recv, recvp, recvul, send, sendp,/	thread(2)	638
	procsetname - set process arguments	procsetname(2)	580
amount, newns, addns, login, noworld,	procsetuser, auth_proxy, fauth_proxy,/	auth(2)	379
	prof, tprof, kprof – display profiling data	prof(1)	226
kprof – kernel		kprof(3)	708
units – conversion		units(1)	322
cb - C	program beautifier	cb(1)	45
execnet – network interface to assert – check	program executionprogram invariants	execnet(4) assert(2)	766 377
outs, outl, insb, inss, insl, outsb, outss, outsl -	programmed I/O inb, ins, inl, outb,	inb(9)	
pc -	programmer's calculator	pc(1)	214
- an interpreted, interactive, object-oriented	programming language python	python(1)	233
iowrite - slave I/O processes for threaded	programs /ioproc, ioread, ioreadn, iosleep,	ioproc(2)	516
lex - generator of lexical analysis	programs	lex(1)	165
map, mapdemo - draw maps on various	projections	map(7)	910
bitsyload, light, pencal, keyboard, params,	prompter – bitsy–specific utilities	bitsyload(1)	38
	proof – troff output interpreter	proof(1)	228
	Protected Access setup	wpa(8) proto(2)	581
Tupioto – parse anu process a		μιστο(2)	100

sizeS2M, sizeD2M - interface to Plan 9 File	protocol /read9pmsg, statcheck,	fcall(2)	457
ppp, pppoe, pptp, pptpd – point-to-point	protocol	ppp(8)	1027
sdp – secure datagram	protocol	sdp(3)	729
intro – introduction to the Plan 9 File	Protocol, 9P	intro(5)	830
hnputl, hnputs, ptclbsum, readipifc - Internet	Protocol addressing . /nhgetl, nhgets, hnputv,	ip(2)	519
sshfs – secure file transfer	protocol client	sshfs(4)	812
sshnet – secure file transfer	protocol client	sshnet(4)	813
ftpfs – file transfer	protocol (FT) file system	ftpfs(4)	778
newt – network news transport	protocol (NNT) client	newt(1)	198
nntpfs – network news transport	protocol (NNT) file system	nntpfs(4)	796
tftpfs – trivial file transfer	protocol (TFT) file system	tftpfs(4)	817
version – negotiate	protocol version	version(5)	844
authsrv, p9any, p9sk1, dp9ik - authentication	protocols	authsrv(6)	851
icmpv6, ipmux, rudp, tcp, udp, il – network	protocols over IP ip, esp, gre, icmp,	ip(3)	698
forp – formula	prover	forp(1)	101
and PDF	ps2pdf, pdf2ps - convert between PostScript	ps2pdf(1)	230
ps, psu,	pstree – process status	ps(1)	229
/rectclip, combinerect, badrect, Dx, Dy,	Pt, Rect, Rpt – arithmetic on points and /	addpt(2)	363
/nhgetl, nhgets, hnputv, hnputl, hnputs,	ptclbsum, readipifc – Internet Protocol/	ip(2)	519
/rectsubpt, insetrect, canonrect, eqpt, eqrect,	ptinrect, rectinrect, rectXrect, rectclip,/	addpt(2)	363
audio, disk, ether, kb, serial,	ptp, usbd – Universal Serial Bus drivers	nusb(4)	797
	ptrap – plumber (4) filter	ptrap(4)	802
thumbprint –	public key thumbprints	thumbprint(6)	894
bottomwindow,/ Screen, allocscreen,	publicscreen, freescreen, allocwindow,	window(2)	668
management changes,	pull, push, scan - client-server replica	replica(1)	246
/trimblock, packblock, padblock, pullblock,	pullupblock, adjustblock, checkb – data block/	allocb(9)	
circular buffer	pump - copy asynchronously via a large	pump(1)	231
management	push, scan - client-server replica	replica(1)	246
/xformpoint, xformpointd, xformplane,	pushmat, popmat, rot, qrot, scale, move,/	matrix(2)	534
communication channel	pushssl – attach SSL version 2 encryption to a .	pushssl(2)	582
freeThumbprints, okThumbprint,/	pushtls, tlsClient, tlsServer, initThumbprints, .	pushtls(2)	583
dirfstat, dirwstat, dirfwstat, nulldir - get and	put file status /fstat, wstat, fwstat, dirstat,	stat(2)	626
/attachproc, get1, get2, get4, get8, geta, put1,	put2, put4, put8, puta beswab, beswal,/	mach(2)	529
fread, fwrite/ fgetc, getc, getchar, fputc, putc,	putchar, ungetc, fgets, gets, fputs, puts,	fgetc(2)	461
getenv,	putenv - access environment variables	getenv(2)	486
	pwd, pbd – working directory	pwd(1)	232
read, readn, write, pread,	pwrite - read or write file	read(2)	594
readv, writev, preadv,	pwritev - scatter/gather read and write	readv(2)	596
efiboot.fat - PC bootloader for FAT, ISO and	PXE network booting /bootx64.efi,	9boot(8)	921
object-oriented programming language	python - an interpreted, interactive,	python(1)	233
0a, 1a, 2a, 5a, 6a, 8a, ka,	qa, va – assemblers	2a(1)	4
qlen, slerp, qmid, qsqrt -/ qtom, mtoq,	qadd, qsub, qneg, qmul, qdiv, qunit, qinv,	quaternion(2)	588
	qball - 3-d rotation controller	qball(2)	586
0c, 1c, 2c, 5c, 6c, 7c, 8c, kc,		2c(1)	5
qtom, mtoq, qadd, qsub, qneg, qmul,	qdiv, qunit, qinv, qlen, slerp, qmid, qsqrt -/	quaternion(2)	588
files	qer, runq - queue management for spooled	qer(8)	
5i, ki, vi,		vi(1)	327
	ql, vl – loaders	21(1)	8
qadd, qsub, qneg, qmul, qdiv, qunit, qinv,	qlen, slerp, qmid, qsqrt - Quaternion/ /mtoq,		588
runlock, wlock, / lock, canlock, unlock,		lock(2)	526
wlock, wunlock - serial synchronisation	qlock, qunlock, canqlock, rlock, runlock,	qlock(9)	
qsqrt -/ qtom, mtoq, qadd, qsub, qneg,	qmul, qdiv, qunit, qinv, qlen, slerp, qmid,	quaternion(2)	588
viewport/ /xformplane, pushmat, popmat, rot,	qr – generate QR code	qr(1) matrix(2)	237 534
viewport/ / xioimpiane, pusimiat, popinat, rot,			587
slerp, gmid, gsgrt -/ gtom, mtog, gadd,	qsort – quicker sort	qsort(2) quaternion(2)	588
wrkey, login, newns, none, as – maintain or	query authentication databases /debug,	auth(8)	930
csquery, dns, dnstcp, dnsquery, dnsdebug,/	query, ipquery, mkhash, mkdb, mkhosts, cs,	ndb(8)	
esquery, ans, anstep, ansquery, ansuebug,/	queue management for spooled files	qer(8)	
locks,/ /rwakeupall, incref, decref – spin locks,	queueing rendezvous locks, reader-writer	lock(2)	526
qtom, mtoq, qadd, qsub, qneg, qmul, qdiv,	qunit, qinv, qlen, slerp, qmid, qsqrt -/	quaternion(2)	588
wunlock – serial synchronisation glock,	quillock, canglock, rlock, runlock, wlock,	qlock(9)	
lock, canlock, unlock, glock, canglock,	quillock, rlock, canrlock, runlock, wlock, /	lock(2)	526
nietzsche – print out Nietzsche	quote	nietzsche(1)	200
quoted/ /quotestrfmt, quoterunestrfmt,	quotefmtinstall, doquote, needsrcquote –	quote(2)	590
unquoterunestrdup,/ quotestrdup,	quoterunestrdup, unquotestrdup,	quote(2)	590
/unquoterunestrdup, quotestrdup,	quoterunestrfmt, quotefmtinstall, doquote,/	quote(2)	590
unquotestrdup, unquoterunestrdup, /	quotestrdup, quoterunestrdup,	quote(2)	590
/unquotestrdup, unquoterunestrdup,	quotestrfmt, quoterunestrfmt,/	quote(2)	590
rtc – real-time clock and non-volatile	RAM	rtc(3)	722
bzfs – compressed read-write		bzfs(4)	754
	ramfs – memory file system	ramfs(4)	803
truerand, ntruerand, genrandom, prng,/	rand, Irand, frand, nrand, Inrand, srand,	rand(2)	591
dhcpd, dhcp6d, dhcpleases,	rarpd, tftpd – Internet booting	dhcpd(8)	943
······································		-1	-

	ratfs - mail address ratification file system	ratfs(4)	804
	ratrace - trace process system calls	ratrace(1)	238
dumparenas, restore – backup venti arenas to	ray discs or restore from them /tobackup,	backup(8)	932
whatis, ., ~ - command languagesetupRC4state,	rc, cd, eval, exec, exit, flag, rfork, shift, wait, . rc4, rc4skip, rc4back – alleged rc4 encryption .	rc(1) rc4(2)	239 593
setuphe4state,	rc-httpd - HTTP server	rc-httpd(8)	
to CPU server	rcpu, rimport, rexport, rconnect – connection	rcpu(1)	245
servers	rdarena, wrarena – copy arenas between venti . v		
	rdbfs - remote kernel debugging file system	rdbfs(4)	805
listing	rdproto - parse and process a proto file	proto(2)	581
cat,		cat(1)	44
readv, writev, preadv, pwritev – scatter/gather dirread, dirreadall –	read and writeread directory	readv(2) dirread(2)	596 430
write file	read, readn, write, pread, pwrite – read or	read(2)	594
	read routines	readnum(9)	
	read throughput	tput(1)	311
	read, write - transfer data from and to a file	read(5)	840
	read, write, copy - simple Venti clients	venti(1)	326
/convM2D, fcallfmt, dirfmt, dirmodefmt,	read9pmsg, statcheck, sizeS2M, sizeD2M -/	fcall(2)	457
epoch seconds – convert memory – print memory statistics in	readable date (and time) to seconds since readable format	seconds(1) memory(8)	264 991
objtype, readobj, objtraverse, isar, nextar,	readar – object file interpretation functions	object(2)	564
/BLEN, BALLOC, blocklen, blockalloclen,	readblist, concatblock, copyblock, trimblock,/	allocb(9)	
/listensrv, postmountsrv, postsharesrv,	readbuf, readstr, respond, responderror,/	9p(2)	349
/okThumbprint, okCertificate, readcert,	readcertchain - attach TLS1 or SSL3/	pushtls(2)	583
color map RGB,	readcolmap, writecolmap - access display	readcolmap(2)	595
file/ /closefile, removefile, walkfile, opendirfile,	readdirfile, closedirfile, hasperm – in-memory	9pfile(2)	357
cdfs, cddb – optical disc (CD, DVD, B) track /- spin locks, queueing rendezvous locks,	reader and writer file system reader-writer locks, rendezvous points, and/ .	cdfs(4) lock(2)	755 526
/loadimage, cloadimage, unloadimage,	readimage, writeimage, bytesperline,/	allocimage(2)	367
- nedmail	reading mail	nedmail(1)	193
open, create, close - open a file for	reading or writing, create file	open(2)	566
wordsperline - allocating, freeing,	reading, writing images /bytesperline,	allocimage(2)	367
/nhgets, hnputv, hnputl, hnputs, ptclbsum,	readipifc - Internet Protocol addressing	ip(2)	519
/allocmemimage, allocmemimaged,	readmemimage, creadmemimage,/	memdraw(2)	536
drawgetrect, menuhit, setcursor,/ . initmouse, read.	readmouse, closemouse, moveto, getrect, readn, write, pread, pwrite - read or write file .	mouse(2) read(2)	545 594
Teau,	readnum, readstr – device read routines	readnum(9)	
convM2TR,/ authdial, passtokey, nvcsum,	readnyram, convT2M, convM2T, convTR2M,	authsrv(2)	382
object file interpretation functions objtype,	readobj, objtraverse, isar, nextar, readar	object(2)	564
mkpaqfs - make a compressed	read-only file system	mkpaqfs(8)	996
paqfs – compressed	read-only file system	paqfs(4)	800
readnum, /postmountsrv, postsharesrv, readbuf,	readstr – device read routines readstr, respond, responderror, srvacquire,/	readnum(9) 9p(2)	1101 349
/uninstallsubfont, subfontname, readsubfont,	readsubfonti, writesubfont, stringsubfont,/	subfont(2)	633
scatter/gather read and write	ready, writey, pready, pwritey –	readv(2)	596
bzfs – compressed	read-write ram filesystem	bzfs(4)	754
/dev/realmode	realemu - software emulation of	realemu(8)	
	realloc, calloc, msize, setmalloctag,/	malloc(2)	
setmalloctag,/ malloc, mallocz, smalloc, realemu – software emulation of	realloc, free, msize, secalloc, secfree,	malloc(9) realemu(8)	
rtc -		rtc(3)	722
	real-time) process behavior	trace(1)	313
optionally shut down or reboot/ fshalt, scram,		fshalt(8)	956
remote file server connection	reboot – reboot the system upon loss of	reboot(8)	
clocks, process/process group ids, user, null,		cons(3)	683
<i>i i i</i>	reboot the system . /scram, reboot – halt any	fshalt(8)	956
server connection reboot -	reboot the system upon loss of remote file recognize – character recognition	reboot(8) scribble(2)	610
	record layer	ssl(3)	734
tls - TLS and SSL3	record layer	tls(3)	737
/rectclip, combinerect, badrect, Dx, Dy, Pt,	Rect, Rpt - arithmetic on points and /	addpt(2)	363
eqpt, eqrect,/ addpt, subpt, mulpt, divpt,	rectaddpt, rectsubpt, insetrect, canonrect,	addpt(2)	363
newwindow, drawerror, / Display, Point,	Rectangle, Cursor, initdraw, geninitdraw,	graphics(2)	492
/insetrect, canonrect, eqpt, eqrect, ptinrect, addpt, subpt, mulpt, divpt, rectaddpt,	rectinrect, rectXrect, rectclip, combinerect,/ rectsubpt, insetrect, canonrect, eqpt, eqrect,/ .	addpt(2) addpt(2)	363 363
/canonrect, eqpt, eqrect, ptinrect, rectandpt,	rectXrect, rectclip, combinerect, badrect, Dx,/	addpt(2)	363
derp – directory–examining	recursive compare	derp(1)	73
/procdata, procexec, procexecl, procrfork, recv,	recvp, recvul, send, sendp, sendul, nbrecv,/	thread(2)	638
reader-writer locks, rendezvous points, and	reference counts /rendezvous locks,	lock(2)	526
/dot3, cross3, len3, dist3, unit3, midpt3, lerp3,	reflect3, nearseg3, pldist3, vdiv3, vrem3,/	arith3(2)	375
rregexec, rregsub, regerror -/ regcomp,	regcomplit, regcompnl, regexec, regsub,	regexp(2)	597
in - access PC 1/0	regexp - regular expression notation	regexp(6) io(1)	888 152
10 - access FC I/O	registers	10(1)	172

srv – server		srv(3)	733
regcomp, regcomplit, regcompnl, regexec,	regsub, rregexec, rregsub, regerror - regular/	regexp(2)	597
- regexp samterm - screen editor with structural	regular expression notation sam, B, sam.save,	regexp(6) sam(1)	888 258
comm – select or	5 1	comm(1)	52
dial, hangup, announce, listen, accept,	reject, netmkaddr, setnetmtpt,/	dial(2)	427
join –	relational database operator	join(1)	155
ircrc – internet	· · · · ·	ircrc(1)	153
fabs, fmod, floor, ceil - absolute value,	remainder, floor, ceiling functions	floor(2)	465
rexexec, ftpd, socksd, hproxy – Internet		ipserv(8)	984
securenet – Digital Pathways SecureNet Key		securenet(8)	
reboot – reboot the system upon loss of		reboot(8)	
Virtual Network Computing (VN) . vncs, vncv –		vnc(1)	331
- rdbfs ssh – secure shell	· · · · · · · · · · · · · · · · · · ·	rdbfs(4) ssh(1)	805 284
transfer con, telnet, rx, hayes, xms, xmr -	remote login, execution, and XMODEM file	con(1)	284 53
import – import a name space from a	5	import(4)	784
rwd, conswdir – maintain	remote working directory	rwd(1)	256
	remove – remove a file	remove(2)	599
	remove - remove a file from a server	remove(5)	841
rm –		rm(1)	254
deroff –	J J J J J J J J J J	deroff(1)	72
strip –	, ,	strip(1)	287
/freefidpool, allocfid, closefid, lookupfid,	removefid, Req, Reqpool, allocreqpool, /	9pfid(2)	355
/alloctree, freetree, File, createfile, closefile, /freeregpool, allocreg, closereg, lookupreg,	removefile, walkfile, opendirfile, readdirfile, / .	9pfile(2)	357 355
ttfnewbitmap, ttffreebitmap, ttfblit – TrueType	removereq – 9P fid, request tracking renderer /ttfrender, ttfrunerender,	9pfid(2) ttf(2)	648
synchronization	rendezvous – user level process		600
/rendezvous locks, reader-writer locks,	rendezvous points, and reference counts	lock(2)	526
uniq – report		uniq(1)	321
Image, draw, gendraw, drawreplxy, drawrepl,	replclipr, line, poly, fillpoly, bezier, bezspline,/	draw(2)	432
changes, pull, push, scan - client-server	replica management	replica(1)	246
compactdb, updatedb - simple client-server weather - print weather		replica(8) weather(1)	1039 337
sysinfo, sysupdate –	report	sysinfo(1)	290
uniq –	report repeated lines in a file	uniq(1)	321
color –	representation of pixels and colors	color(6)	856
galaxy –	representations of n-body simulations	galaxy(6)	860
/allocfid, closefid, lookupfid, removefid, Req,	Reqpool, allocreqpool, freereqpool, allocreq,/	9pfid(2)	355
reqqueueflush - deferred/ Reqqueue,	requeuecreate, requeuepush,	9pqueue(2)	359
closereq, lookupreq, removereq – 9P fid, deroff – remove formatting	request tracking /freereqpool, allocreq, requests	9pfid(2) deroff(1)	355 72
call error errstr,		errstr(2)	448
	resample, resize - resample a picture	resample(1)	249
hwdraw - drawing routines for		memdraw(2)	536
memltorear, memltorearn - windows of		memlayer(2)	540
resample, /namectlfont, namectlimage, newcontrolset,	resize – resample a picture	resample(1) control(2)	249 403
fork, rfork – manipulate process	resizecontrolset - interactive graphical/ resources	fork(2)	403
message parsing Cmdbuf, parsecmd,	responderderror, lookupcmd – control	9pcmdbuf(2)	354
/postsharesrv, readbuf, readstr, respond,	responderror, srvacquire, srvrelease,/	9p(2)	349
or restore/ backup, tobackup, dumparenas,	restore - backup venti arenas to blu-ray discs .	backup(8)	932
mothra –	retrieve and display World-Wide Web files	mothra(1)	186
a url hget, hpost, webpaste, urlencode -	retrieve, post to a web page corresponding to .	hget(1)	145
error – descriptor fd2path –	return an error	error(5)	836
getcallerpc – fetch	return file name associated with file	fd2path(2) getcallerpc(2)	460 485
descriptor iounit -		iounit(2)	518
sleep, wakeup, tsleep,	return0 – process synchronisation	sleep(9)	
/setvbuf, setbuf, fgetpos, ftell, fsetpos, fseek,	rewind, feof, ferror, clearerr - standard/	fopen(2)	469
	rewrite – mail rewrite rules	rewrite(6)	889
remote access daemons telnetd, rlogind, rcpu, rimport,		ipserv(8) rcpu(1)	984 245
/openfont, buildfont, freefont, Pfmt,	Rfmt, strtochan, chantostr, chantodepth -/	graphics(2)	492
fork,	rfork - manipulate process resources	fork(2)	472
language rc, cd, eval, exec, exit, flag,	rfork, shift, wait, whatis, ., ~ - command	rc(1)	239
display color map	RGB, readcolmap, writecolmap - access	readcolmap(2)	595
cmap2rgb, cmap2rgba,	rgb2cmap - colors and color maps	color(2)	401
advanced encryption standard CPU server	rijndael) /aesgcm_decrypt - rimport, rexport, rconnect - connection to	aes(2) rcpu(1)	365 245
сто зениен полити пори,	rio – window system files	rio(4)	806
	rio, label, window, wloc – window system	rio(1)	250
winwatch - monitor		winwatch(1)	339
routing ipconfig,	rip, linklocal - Internet configuration and	ipconfig(8)	981

	ripemd160, sha1, sha2_224, sha2_256,	sechash(2)	614
symoff, fpformat, beieee80ftos,/ cisctrace,	risctrace, ciscframe, riscframe, localaddr,	debugger(2)	422
/canlock, unlock, qlock, canqlock, qunlock,	rlock, canrlock, runlock, wlock, canwlock,/	lock(2)	526
synchronisation glock, gunlock, canglock,	rlock, runlock, wlock, wunlock – serial	glock(9)	1099
Internet remote access daemons telnetd,	rlogind, rexexec, ftpd, socksd, hproxy	ipserv(8)	984
	rm – remove files	rm(1)	254
sart – exponential, logarithm, power, square	root exp, log, log10, pow, pow10,	exp(2)	455
	root – the root file system	root(3)	721
hoot hootre - connect to the	root file server	boot(8)	933
/xformpointd, xformplane, pushmat, popmat,		matrix(2)	534
/xioimpointa, xioimpiane, pusimiat, popinat,	rotate – rotate or mirror a picture	rotate(1)	255
aball 2 d	· · ·	gball(2)	586
qball – 3-d rip, linklocal – Internet configuration and			
		ipconfig(8)	981
send – mail	5 , , , , , , , , , , , , , , , , , , ,	send(8)	
/combinerect, badrect, Dx, Dy, Pt, Rect,		addpt(2)	363
/regcompnl, regexec, regsub, rregexec,	rregsub, regerror - regular expression	regexp(2)	597
/asn1encodeRSApub, decodePEM, rsadecrypt,		rsa(2)	601
rsa2ssh, rsa2x509, rsa2csr - generate and/	rsagen, rsafill, asn12rsa, rsa2asn1, rsa2pub,	rsa(8)	
/rsagen, rsaprivalloc, rsaprivfree, rsaprivtopub,		rsa(2)	601
/canrlock, runlock, wlock, canwlock, wunlock,		lock(2)	526
	rtc - real-time clock and non-volatile RAM	rtc(3)	722
ip, esp, gre, icmp, icmpv6, ipmux,	rudp, tcp, udp, il – network protocols over IP .	ip(3)	698
plumb – format of plumb messages and	rules	plumb(6)	884
rewrite – mail rewrite	rules	rewrite(6)	889
lock –	run a command under lock	lock(1)	166
through IPv4 6in4, ayiya - configure and		6in4(8)	919
ÚŤF, Unicode, ASCII,		utf(6)	896
runestrrchr, runestrdup, runestrstr –		runestrcat(2)	605
/fmtfdinit, fmtfdflush, fmtstrinit, fmtstrflush,		fmtinstall(2)	466
utfrune,/ runetochar, chartorune, runelen,	runenlen, fullrune, utfecpy, utflen, utfnlen,	rune(2)	603
/smprint, runesprint, runesprint, runeseprint,	runesmprint, vfprint, vsnprint, vseprint,/	print(2)	576
runestrncpy,/ runestrcat, runestrncat,	runestrcmp, runestrncmp, runestrcpy,	runestrcat(2)	605
/runestrlen, runestrchr, runestrrchr,	runestrdup, runestrstr – rune string/	runestrcat(2)	605
/runestrncmp, runestrcpy, runestrncpy,	runestrecpy, runestrlen, runestrchr,/	runestrcat(2)	605
/runestring, runestringn, stringbg, stringnbg,	runestringbg, runestringnbg, _string, ARROW,/	draw(2)	432
/stringnwidth, runestringsize, runestringwidth,		stringsize(2)	632
stringsize, stringwidth, stringnwidth,	runestringsize, runestringwidth,/	stringsize(2)	632
runestrcpy, runestrncpy,/ runestrcat,		runestrcat(2)	605
string/ . /runestrecpy, runestrlen, runestrchr,	runestrrchr, runestrdup, runestrstr – rune	runestrcat(2)	605
fullrune, utfecpy, utflen, utfnlen, utfrune,/	runetochar, chartorune, runelen, runenlen,	rune(2)	603
utflen, utfnlen, utfrune, utfrrune, utfutf -	rune/UTF conversion /fullrune, utfecpy,	rune(2)	603
/vseprint, vsmprint, runevsnprint, runevseprint,	runevsmprint – print formatted output	print(2)	576
/qlock, canqlock, qunlock, rlock, canrlock,		lock(2)	526
qlock, qunlock, canqlock, rlock,		qlock(9)	1099
uptime – show how long the system has been		uptime(1)	323
proc –	J	proc(3)	717
qer,		qer(8)	
/wlock, canwlock, wunlock, rsleep, rwakeup,		lock(2)	526
directory	rwd, conswdir – maintain remote working	rwd(1)	256
execution, and XMODEM file/ con, telnet,		con(1)	53
satval, satreset, satfree – boolean satisfiability		sat(2)	607
	sacfs – compressed file system	sacfs(4)	809
s_free, s_incref, s_memappend, s_nappend,/ .	s_alloc, s_append, s_array, s_copy, s_error,	string(2)	630
setupSalsastate, salsa_setblock, salsa_setiv,	- ,, , _ ,, , ,	salsa(2)	606
ssam – stream interface to		ssam(1)	283
fortune, theo, troll –		fortune(1)	103
structural regular expressions sam, B,		sam(1)	258
timmy – physics		timmy(1)	306
s_memappend,/ s_alloc, s_append,		string(2)	630
/- AHCI (Advanced Host Controller Interface)		sdahci(3)	725
/satrangev, satsolve, satmore, satval, satreset,		sat(2)	607
satrangev, satsolve, satmore, satval, satreset,/	satnew, satadd1, sataddv, satrange1,	sat(2)	607
server httpd,		httpd(8)	977
brk,	5 1	brk(2)	394
/xformplane, pushmat, popmat, rot, qrot,		matrix(2)	534
changes, pull, push,		replica(1)	246
fscanf,		fscanf(2)	481
li	scanmail, testscan – spam filters	scanmail(8)	
awk – pattern–directed	scanning and processing language	awk(1)	29
	scat – sky catalogue and Digitized Sky Survey .	scat(7)	915
ready, writev, pready, pwritev -		readv(2)	596
/hzsched, procpriority, procrestore, procsave,		sched(9)	
<pre>/fdopen, fileno, fclose, sopenr, sopenw, s_memappend,/ s_alloc, s_append, s_array,</pre>		fopen(2)	469 630
s_memappend,/ s_anoc, s_append, s_allay,	s_copy, s_error, s_free, s_incref,	string(2)	020

and optionally shut down or reboot/ fshalt,	scram, reboot - halt any local file systems	fshalt(8)	956
allocwindow, bottomwindow,/	Screen, allocscreen, publicscreen, freescreen,	window(2)	668
expressions sam, B, sam.save, samterm -	screen editor with structural regular	sam(1)	258
draw -	screen graphics	draw(3)	685
lens – interactive	screen magnifier	lens(1)	164
	screenlock - disable access to a terminal	screenlock(8)	1046
recognition	scribblealloc, recognize – character	scribble(2)	610
nusbrc – Universal Serial Bus startup	script	nusbrc(8)	1010
at, drain, expect, pass - dialer	scripting tools	expect(1)	92
	scripts	cpurc(8)	940
usage - command-line parsing for shell	scripts getflags,	getflags(8)	957
na – assembler for the Symbios Logic	SCSI I/O Processors	na(8)	999
openscsi, closescsi, scsiready, scsi, scsicmd,		scsi(2)	612
	scuzz – SCSI target control	scuzz(8)	1047
	sd – storage device interface	sd(3)	723
Interface) SATA (Serial AT) storage device/	sdahci - AHCI (Advanced Host Controller	sdahci(3)	725
device interface	sdaoe – ATA-over-Ethernet (Ao) storage	sdaoe(3)	727
	sdloop – loopback storage device interface	sdloop(3)	728
	sdp – secure datagram protocol	sdp(3)	729
grep, g -		grep(1)	115
thesaurus -		thesaurus(1)	303
avllookup, avlnext, avlprev – Balanced binary		avl(2)	385
mallocz, smalloc, realloc, free, msize, secalloc,		malloc(9)	1095
time) to seconds since epoch	seconds - convert human-readable date (and .	seconds(1)	264
time, nsec – time in		time(2)	642
TK2MS, TK2SEC - kernel times and time/	seconds, ticks, fastticks, HZ, MS2HZ, MS2TK,	seconds(9)	
ecdominit, ecdomfree, ecassign, ecadd,/	secp256r1, secp256k1, secp384r1,	ec(2)	441
aescbc. ipso.		secstore(1)	265
	secstored, secuser - secstore commands	secstore(8)	
- dp	secure datagram protocol	sdp(3)	729
	secure file transfer protocol client	sshfs(4)	812
	secure file transfer protocol client	sshnet(4)	813
	secure hashes	sechash(2)	614
ssh –	secure shell remote login client	ssh(1)	284
remote authentication box	securenet – Digital Pathways SecureNet Key	securenet(8)	1051
secstored,		secstore(8)	
,	sed - stream editor	sed(1)	267
	seek – change file offset	seek(2)	616
faces,		faces(1)	94
,	seg – access a named segment		
	sey - access a nameu seyment	seq(1)	270
	segbrk – change memory allocation	seg(1) segbrk(2)	270 619
memory segattach, segdetach,	segbrk - change memory allocation	segbrk(2)	619
memory segattach, segdetach, seg - access a named	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual	segbrk(2) segflush(2)	619 620
	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual	segbrk(2) segflush(2) segattach(2)	619 620 617
seg – access a named	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment	segbrk(2) segflush(2) segattach(2) seg(1)	619 620 617 270
seg – access a named	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment segment - long lived memory segments	segbrk(2) segflush(2) segattach(2) seg(1) segment(3)	619 620 617 270 730
seg – access a named segattach, segdetach, segfree – map/unmap a	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment segment - long lived memory segments segment in virtual memory select or reject lines common to two sorted semrelease - user level semaphores	segbrk(2) segflush(2) segattach(2) segment(3) segattach(2) comm(1) semacquire(2)	619 620 617 270 730 617 52 621
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire,	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment segment - long lived memory segments segment in virtual memory select or reject lines common to two sorted semrelease - user level semaphores send - mail routing and delivery	segbrk(2) segflush(2) segattach(2) seg(1) segment(3) segattach(2) comm(1)	619 620 617 270 730 617 52 621
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire,	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment segment - long lived memory segments segment in virtual memory select or reject lines common to two sorted semrelease - user level semaphores send - mail routing and delivery send a note to a process or process group	segbrk(2) segflush(2) segattach(2) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2)	619 620 617 270 730 617 52 621 1052 574
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb –	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment segment - long lived memory segments segment in virtual memory select or reject lines common to two sorted semrelease - user level semaphores send - mail routing and delivery send a note to a process or process group send message to plumber	segbrk(2) segflush(2) segattach(2) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1)	619 620 617 270 730 617 52 621 1052 574 224
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul,	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment segment in virtual memory segments select or reject lines common to two sorted semrelease - user level semaphores send - mail routing and delivery send a note to a process or process group send, sendp, sendul, nbrecv, nbrecvp,/	segbrk(2) segflush(2) segattach(2) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2)	619 620 617 270 730 617 52 621 1052 574 224 638
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul, wol –	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment segment in virtual memory segments segment in virtual memory select or reject lines common to two sorted semrelease - user level semaphores send - mail routing and delivery send a note to a process or process group send message to plumber send, sendp, sendul, nbrecv, nbrecvp,/ send wake-on-lan Ethernet packet	segbrk(2) segflush(2) segattach(2) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2) wol(8)	619 620 617 270 730 617 52 621 1052 574 224 638 1081
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul, wol – marshal – formatting and	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment segment in virtual memory segments segment in virtual memory select or reject lines common to two sorted semrelease - user level semaphores send - mail routing and delivery send a note to a process or process group send message to plumber send, sendp, sendul, nbrecv, nbrecvp,/ send wake-on-lan Ethernet packet sending mail	segbrk(2) segflush(2) segattach(2) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2) wol(8) marshal(1)	619 620 617 270 730 617 52 621 1052 574 224 638 1081 174
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul, wol – marshal – formatting and /procrfork, recv, recvp, recvul, send, sendp,	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment segment in virtual memory segments segment in virtual memory select or reject lines common to two sorted semrelease - user level semaphores send - mail routing and delivery send a note to a process or process group send message to plumber send, sendp, sendul, nbrecv, nbrecvp,/ sendul, nbrecv, nbrecvul, nbsend,/	segbrk(2) segflush(2) segattach(2) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2) wol(8) marshal(1) thread(2)	619 620 617 270 730 617 52 621 1052 574 224 638 1081 174 638
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul, wol – marshal – formatting and	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment segment - long lived memory segments segment in virtual memory select or reject lines common to two sorted semrelease - user level semaphores send - mail routing and delivery send a note to a process or process group send message to plumber send message to plumber send wake-on-lan Ethernet packet sending mail sendul, nbrecv, nbrecvpl, nbsend,/ seprint, smprint, runesprint, runesnprint,	segbrk(2) segflush(2) segattach(2) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2) wol(8) marshal(1) thread(2) print(2)	619 620 617 270 730 617 52 621 1052 574 224 638 1081 174 638 576
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul, wol – marshal – formatting and /procrfork, recv, recvp, recvul, send, sendp, runeseprint,/ print, fprint, sprint, snprint,	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment segment - long lived memory segments segment in virtual memory select or reject lines common to two sorted semrelease - user level semaphores send - mail routing and delivery send a note to a process or process group send message to plumber send, sendp, sendul, nbrecv, nbrecvp,/ send wake-on-lan Ethernet packet sending mail seprint, smprint, runesprint, runesnprint, seq - print sequences of numbers	segbrk(2) segflush(2) segattach(2) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2) wol(8) marshal(1) thread(2) print(2) seq(1)	619 620 617 270 730 617 52 621 1052 574 224 638 1081 174 638 576 272
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul, wol – marshal – formatting and /procrfork, recv, recvp, recvul, send, sendp, runeseprint,/ print, fprint, sprint, snprint, (Advanced Host Controller Interface) SATA	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment segment - long lived memory segments segment in virtual memory select or reject lines common to two sorted semrelease - user level semaphores send - mail routing and delivery send a note to a process or process group send message to plumber send, sendp, sendul, nbrecv, nbrecvp,/ send wake-on-lan Ethernet packet sending mail seprint, smprint, runesprint, runesprint, serial AT) storage device drivers/- AHCI	segbrk(2) segflush(2) segattach(2) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2) wol(8) marshal(1) thread(2) print(2) seq(1) sdahci(3)	619 620 617 270 730 617 52 621 1052 574 224 638 1081 174 638 576 272 725
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul, wol – marshal – formatting and /procrfork, recv, recvp, recvul, send, sendp, runeseprint,/ print, fprint, sprint, snprint, (Advanced Host Controller Interface) SATA disk, ether, kb, serial, ptp, usbd – Universal	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment segment - long lived memory segments segment in virtual memory select or reject lines common to two sorted semrelease - user level semaphores send - mail routing and delivery send a note to a process or process group send message to plumber send, sendp, sendul, nbrecv, nbrecvp,/ send wake-on-lan Ethernet packet sending mail seprint, smprint, runesprint, runesprint, serial AT) storage device drivers/- AHCI Serial Bus driversaudio,	segbrk(2) segflush(2) segattach(2) segattach(2) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2) wol(8) marshal(1) thread(2) print(2) seq(1) sdahci(3) nusb(4)	619 620 617 270 730 617 52 621 1052 574 224 638 1081 174 638 576 272 725 797
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul, wol – marshal – formatting and /procrfork, recv, recvp, recvul, send, sendp, runeseprint,/ print, fprint, sprint, snprint, (Advanced Host Controller Interface) SATA disk, ether, kb, serial, ptp, usbd – Universal nusbrc – Universal	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment segment - long lived memory segments segment in virtual memory select or reject lines common to two sorted semrelease - user level semaphores send - mail routing and delivery send a note to a process or process group send message to plumber send, sendp, sendul, nbrecv, nbrecvp,/ send wake-on-lan Ethernet packet sending mail seprint, smprint, runesprint, runesnprint, serial AT) storage device drivers/- AHCI Serial Bus startup scriptaudition	segbrk(2) segflush(2) segattach(2) segattach(2) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2) wol(8) marshal(1) thread(2) print(2) seq(1) sdahci(3) nusb(4) nusbrc(8)	619 620 617 270 730 617 52 621 1052 574 224 638 1081 174 638 1081 174 638 576 272 725 797 1010
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul, wol – marshal – formatting and /procrfork, recv, recvp, recvul, send, sendp, runeseprint,/ print, fprint, sprint, snprint, (Advanced Host Controller Interface) SATA disk, ether, kb, serial, ptp, usbd – Universal nusbrc – Universal uart, eia –	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment segment - long lived memory segments segment in virtual memory select or reject lines common to two sorted semrelease - user level semaphores send - mail routing and delivery send a note to a process or process group send message to plumber send, sendp, sendul, nbrecv, nbrecvp,/ send wake-on-lan Ethernet packet sending mail seprint, smprint, runesprint, runesprint, seq - print sequences of numbers Serial AT) storage device drivers/- AHCI Serial Bus drivers serial communication control	segbrk(2) segflush(2) segattach(2) segattach(2) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2) wol(8) marshal(1) thread(2) print(2) seq(1) sdahci(3) nusb(4) nusbrc(8) uart(3)	619 620 617 270 730 617 52 621 1052 574 224 638 1081 174 638 576 272 725 797 1010 740
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul, wol – marshal – formatting and /procrfork, recv, recvp, recvul, send, sendp, runeseprint,/ print, fprint, sprint, snprint, (Advanced Host Controller Interface) SATA disk, ether, kb, serial, ptp, usbd – Universal nusbrc – Universal uart, eia – circuit (I ² C) interface twsi – two-wire	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment segment in virtual memory segments segment in virtual memory select or reject lines common to two sorted semrelease - user level semaphores send - mail routing and delivery send a note to a process or process group send message to plumber send, sendp, sendul, nbrecv, nbrecvp,/ send wake-on-lan Ethernet packet sending mail seprint, smprint, runesprint, runesprint, serial AT) storage device drivers/- AHCI Serial Bus drivers serial communication control serial interface (TWS) and inter-integrated	segbrk(2) segflush(2) segattach(2) segattach(2) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2) wol(8) marshal(1) thread(2) print(2) seq(1) sdahci(3) nusb(4) nusbr(8) uart(3) twsi(3)	619 620 617 270 617 52 621 1052 574 224 638 1081 174 638 576 272 725 797 1010 740 739
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul, wol – marshal – formatting and /procrfork, recv, recvp, recvul, send, sendp, runeseprint,/ print, fprint, sprint, snprint, (Advanced Host Controller Interface) SATA disk, ether, kb, serial, ptp, usbd – Universal nusbrc – Universal uart, eia – circuit (I ² C) interface twsi – two-wire audio, disk, ether, kb,	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment	segbrk(2) segflush(2) segattach(2) segment(3) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2) wol(8) marshal(1) thread(2) print(2) seq(1) sdahci(3) nusb(4) nusbr(4)	619 620 617 270 730 617 52 621 1052 574 224 638 1081 174 638 576 272 725 797 1010 740 739 797
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul, wol – marshal – formatting and /procrfork, recv, recvp, recvul, send, sendp, runeseprint,/ print, fprint, sprint, snprint, (Advanced Host Controller Interface) SATA disk, ether, kb, serial, ptp, usbd – Universal nusbrc – Universal uart, eia – circuit (I ² C) interface twsi – two-wire audio, disk, ether, kb, canqlock, rlock, runlock, wlock, wunlock –	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment	segbrk(2) segflush(2) segattach(2) segment(3) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2) wol(8) marshal(1) thread(2) print(2) seq(1) sdahci(3) nusb(4) nusbr(4) qlock(9)	619 620 617 270 730 617 52 621 1052 574 224 638 1081 174 638 576 272 725 797 1010 740 739 797 1099
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul, wol – marshal – formatting and /procrfork, recv, recvp, recvul, send, sendp, runeseprint,/ print, fprint, sprint, snprint, (Advanced Host Controller Interface) SATA disk, ether, kb, serial, ptp, usbd – Universal uart, eia – circuit (I ² C) interface twsi – two-wire audio, disk, ether, kb, canqlock, rlock, runlock, wlock, wunlock – s_alloc, s_append, s_array, s_copy,	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment	segbrk(2) segflush(2) segattach(2) segattach(2) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2) wol(8) marshal(1) thread(2) print(2) seq(1) sdahci(3) nusb(4) nusbr(8) uart(3) twsi(3) nusb(4) qlock(9) string(2)	619 620 617 270 730 617 52 621 1052 574 224 638 1081 174 638 576 272 725 797 1010 749 797 1099 630
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul, wol – marshal – formatting and /procrfork, recv, recvp, recvul, send, sendp, runeseprint,/ print, fprint, sprint, snprint, (Advanced Host Controller Interface) SATA disk, ether, kb, serial, ptp, usbd – Universal uart, eia – circuit (I ² C) interface twsi – two-wire audio, disk, ether, kb, canqlock, rlock, runlock, wlock, wunlock – s_alloc, s_append, s_array, s_copy, httpfile –	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment	segbrk(2) segflush(2) segattach(2) segattach(2) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2) wol(8) marshal(1) thread(2) print(2) seq(1) sdahci(3) nusb(4) nusbrc(8) uart(3) twsi(3) nusb(4) qlock(9) string(2) httpfile(4)	619 620 617 270 730 617 52 621 1052 574 224 638 1081 174 638 576 272 725 797 1010 740 739 797 1099 630 783
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul, wol – marshal – formatting and /procrfork, recv, recvp, recvul, send, sendp, runeseprint,/ print, fprint, sprint, snprint, (Advanced Host Controller Interface) SATA disk, ether, kb, serial, ptp, usbd – Universal uart, eia – circuit (I ² C) interface twsi – two-wire audio, disk, ether, kb, canqlock, rlock, runlock, wlock, wunlock – s_alloc, s_append, s_array, s_copy, httpfile – partfs –	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment	segbrk(2) segflush(2) segattach(2) segattach(2) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2) wol(8) marshal(1) thread(2) print(2) seq(1) sdahci(3) nusb(4) nusbrc(8) uart(3) twsi(3) nusb(4) qlock(9) string(2) httpfile(4) partfs(8)	619 620 617 270 730 617 52 621 1052 574 224 638 1081 174 638 576 272 725 797 1010 740 739 797 1099 630 783 1011
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul, wol – marshal – formatting and /procrfork, recv, recvp, recvul, send, sendp, runeseprint,/ print, fprint, sprint, snprint, (Advanced Host Controller Interface) SATA disk, ether, kb, serial, ptp, usbd – Universal uart, eia – circuit (I ² C) interface twsi – two-wire audio, disk, ether, kb, canqlock, rlock, runlock, wlock, wunlock – s_alloc, s_append, s_array, s_copy, httpfile – partfs – boot, bootrc – connect to the root file	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment	segbrk(2) segflush(2) segattach(2) segattach(2) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2) wol(8) marshal(1) thread(2) print(2) seq(1) sdahci(3) nusb(4) nusbrc(8) uart(3) twsi(3) nusb(4) qlock(9) string(2) httpfile(4) partfs(8) boot(8)	619 620 617 270 730 617 52 621 1052 574 224 638 1081 174 638 1081 174 638 1081 174 638 576 272 725 797 1010 740 739 797 1010 740 739 797 1099 630 783 1011 933
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul, wol – marshal – formatting and /procrfork, recv, recvp, recvul, send, sendp, runeseprint,/ print, fprint, sprint, snprint, (Advanced Host Controller Interface) SATA disk, ether, kb, serial, ptp, usbd – Universal uart, eia – circuit (I ² C) interface twsi – two-wire audio, disk, ether, kb, canqlock, rlock, runlock, wlock, wunlock – s_alloc, s_append, s_array, s_copy, httpfile – partfs – boot, bootrc – connect to the root file cpu – connection to CPU	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment	segbrk(2) segflush(2) segattach(2) segattach(2) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2) wol(8) marshal(1) thread(2) print(2) seq(1) sdahci(3) nusb(4) nusbrc(8) uart(3) twsi(3) nusb(4) qlock(9) string(2) httpfile(4) partfs(8) boot(8) cpu(1)	619 620 617 270 730 617 52 621 1052 574 224 638 1081 174 638 576 272 797 1010 740 739 797 1090 797 1090 630 783 1011 933 57
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul, wol – marshal – formatting and /procrfork, recv, recvp, recvul, send, sendp, runeseprint,/ print, fprint, sprint, snprint, (Advanced Host Controller Interface) SATA disk, ether, kb, serial, ptp, usbd – Universal uart, eia – circuit (I ² C) interface twsi – two-wire audio, disk, ether, kb, canqlock, rlock, runlock, wlock, wunlock – s_alloc, s_append, s_array, s_copy, httpfile – partfs – boot, bootrc – connect to the root file cpu – connection to CPU up authentication on a file descriptor to a file	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment segment - long lived memory segments segment in virtual memory select or reject lines common to two sorted semand a note to a process or process group send a note to a process or process group send wake-on-lan Ethernet packet segment, smprint, runesprint, runesnprint, segrial AT) storage device drivers Serial Bus startup script	segbrk(2) segflush(2) segattach(2) segment(3) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2) wol(8) marshal(1) thread(2) print(2) seq(1) sdahci(3) nusbr(4) nusbrc(8) uart(3) twsi(3) nusb(4) qlock(9) string(2) httpfile(4) partfs(8) boot(8) cpu(1) fauth(2)	619 620 617 270 730 617 52 621 1052 574 224 638 1081 174 638 576 272 725 797 1010 740 739 797 1099 630 783 1011 933 57 456
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul, wol – marshal – formatting and /procrfork, recv, recvp, recvul, send, sendp, runeseprint,/ print, fprint, sprint, snprint, (Advanced Host Controller Interface) SATA disk, ether, kb, serial, ptp, usbd – Universal uart, eia – circuit (I²C) interface twsi – two-wire audio, disk, ether, kb, canqlock, rlock, runlock, wlock, wunlock – s_alloc, s_append, s_array, s_copy, httpfile – partfs – boot, bootrc – connect to the root file cpu – connection to CPU up authentication on a file descriptor to a file fsconfig – configuring a file	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment	segbrk(2) segflush(2) segattach(2) segment(3) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2) wol(8) marshal(1) thread(2) print(2) seq(1) sdahci(3) nusb(4) nusbrc(8) uart(3) twsi(3) nusb(4) qlock(9) string(2) httpfile(4) partfs(8) boot(8) cpu(1) fauth(2) fsconfig(8)	619 620 617 270 730 617 52 621 1052 574 224 638 1081 174 638 576 272 725 797 1010 740 739 797 1099 630 783 1011 933 57 456 952
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul, wol – marshal – formatting and /procrfork, recv, recvp, recvul, send, sendp, runeseprint,/ print, fprint, sprint, snprint, (Advanced Host Controller Interface) SATA disk, ether, kb, serial, ptp, usbd – Universal uart, eia – circuit (I ² C) interface twsi – two-wire audio, disk, ether, kb, canqlock, rlock, runlock, wlock, wunlock – s_alloc, s_append, s_array, s_copy, httpfile – partfs – boot, bootrc – connect to the root file cpu – connection to CPU up authentication on a file descriptor to a file fsconfig – configuring a file hjfs – file	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment	segbrk(2) segflush(2) segattach(2) segment(3) segment(3) segment(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2) wol(8) marshal(1) thread(2) print(2) seq(1) sdahci(3) nusb(4) nusbr(8) uart(3) twsi(3) nusb(4) qlock(9) string(2) httpfile(4) partfs(8) boot(8) cpu(1) fauth(2) fsconfig(8) hjfs(4)	619 620 617 270 730 617 52 621 1052 574 224 638 1081 174 638 576 272 725 797 1010 740 739 797 1099 630 783 1011 933 57 456 952 782
seg – access a named segattach, segdetach, segfree – map/unmap a files comm – semacquire, tsemacquire, postnote – plumb – /procexecl, procrfork, recv, recvp, recvul, wol – marshal – formatting and /procrfork, recv, recvp, recvul, send, sendp, runeseprint,/ print, fprint, sprint, snprint, (Advanced Host Controller Interface) SATA disk, ether, kb, serial, ptp, usbd – Universal uart, eia – circuit (I ² C) interface twsi – two-wire audio, disk, ether, kb, canqlock, rlock, runlock, wlock, wunlock – s_alloc, s_append, s_array, s_copy, httpfile – partfs – boot, bootrc – connect to the root file cpu – connection to CPU up authentication on a file descriptor to a file hjfs – file hxferenc, – routines for creating an http	segbrk - change memory allocation segflush - flush instruction and data caches segfree - map/unmap a segment in virtual segment	segbrk(2) segflush(2) segattach(2) segment(3) segment(3) segattach(2) comm(1) semacquire(2) send(8) postnote(2) plumb(1) thread(2) wol(8) marshal(1) thread(2) print(2) seq(1) sdahci(3) nusb(4) nusbrc(8) uart(3) twsi(3) nusb(4) qlock(9) string(2) httpfile(4) partfs(8) boot(8) cpu(1) fauth(2) fsconfig(8)	619 620 617 270 730 617 52 621 1052 574 224 638 1081 174 638 576 272 725 797 1010 740 739 797 1099 630 783 1011 933 57 456 952

rc httpd UTTD	contor	rc httpd(8)	1025
rc-httpd - HTTP	server rcpu,	rc-httpd(8) rcpu(1)	245
	server	remove(5)	841
upasfs – mail file	server	upasfs(4)	819
	server	venti(2)	650
venti – archival storage	server	venti(6)	897
venti – archival storage		venti(8)	
	server /fmtbloom, fmtindex, fmtisect,	venti-fmt(8)	
	server		665
Computing/ vncs, vncv – remote frame buffer	server and client	tlssrv(8) vnc(1)	331
	server connection reboot	reboot(8)	
	server, dump cwfs, cwfs64,	cwfs(4)	762
fs – file	server, dump	fs(4)	776
fs, exsort – file	server maintenance	fs(8)	947
hjfs – file	server maintenance	hjfs(8)	975
	server plumbing	exportfs(4)	767
srv –		srv(3)	733
changes, pull, push, scan -		replica(1)	246
	server replica management applychanges,	replica(8) users(6)	895
	server user list format	authsrv(2)	382
intro – introduction to file		intro(4)	749
mnt – attach to 9P	servers	mnt(3)	711
pop3, imap4d - Internet mail		pop3(8)	
rdarena, wrarena – copy arenas between venti			
threadpostsharesrv, srv – 9P file	service/threadpostmountsrv,	9p(2)	349
gpsfs, gpsevermore - GPS time and position	service	gpsfs(8)	959
nfsserver, portmapper, pcnfsd - NFS	service	nfsserver(8)	1008
srv, srvtls, 9fs - start network file	service	srv(4)	811
/freeimage, nameimage, namedimage,	setalpha, loadimage, cloadimage, /	allocimage(2)	367
/fclose, sopenr, sopenw, sclose, fflush, setvbuf,	setbuf, fgetpos, ftell, fsetpos, fseek, rewind,/	fopen(2)	469
/moveto, getrect, drawgetrect, menuhit,	setcursor, enter – mouse control	mouse(2)	545
getfcr, setfcr, getfsr,	setfsr – control floating point	getfcr(2)	487
mallocz frog realloc calloc meizo	setjmp, longjmp, notejmp – non-local goto	setjmp(2)	622 532
/mallocz, free, realloc, calloc, msize, /smalloc, realloc, free, msize, secalloc, secfree,	setmalloctag, setrealloctag, getmalloctag,/ setmalloctag, setrealloctag, getmalloctag,/	malloc(2) malloc(9)	
crackhdr, machbytype, machbyname, newmap,	setmap, findseg, unusemap, loadmap,/	mach(2)	529
/announce, listen, accept, reject, netmkaddr,	setnetmtpt, getnetconninfo, freenetconninfo/	dial(2)	427
/free, realloc, calloc, msize, setmalloctag,	setrealloctag, getmalloctag, getrealloctag,/	malloc(2)	532
/free, msize, secalloc, secfree, setmalloctag,	setrealloctag, getmalloctag, getrealloctag -/	malloc(9)	
cap – capabilities for	setting the user id of processes	cap(3)	680
wpa – Wi–Fi Protected Access	setup	wpa(8)	1082
cryptsetup –	setup encrypted partition	cryptsetup(8)	942
aesgcm_encrypt, aesgcm_decrypt – advanced en			
aesCBCdecrypt, aesCFBencrypt, /	setupAESstate, aesCBCencrypt,	aes(2)	365
bfECBencrypt, bfECBdecrypt – blowfish/	setupBFstate, bfCBCencrypt, bfCBCdecrypt,	blowfish(2)	393
chacha_setiv, chacha_encrypt,/	setupChachastate, chacha_setblock,	chacha(2)	398
and triple/ /key_setup, des56to64, des64to56,	setupDES3state, triple_block_cipher - single	des(2)	425
desCBCencrypt, desCBCdecrypt,/alleged rc4 encryption	setupDESstate, des_key_setup, block_cipher, setupRC4state, rc4, rc4skip, rc4back –	des(2) rc4(2)	425 593
salsa_encrypt, salsa_encrypt2, hsalsa -/	setupSalsastate, salsa_setblock, salsa_setiv,	salsa(2)	606
/fileno, fclose, sopenr, sopenw, sclose, fflush,	setvbuf, setbuf, fgetpos, ftell, fsetpos, fseek,/	fopen(2)	469
s_alloc, s_append, s_array, s_copy, s_error,	s_free, s_incref, s_memappend, s_nappend,/	string(2)	630
s_putc, s_unique, s_grow, s_read, s_read_line,	s_getline - extensible strings /s_tolower,	string(2)	630
sum, md5sum,	shalsum - sum and count blocks in a file	sum(1)	288
hmac_x,/ md4, md5, ripemd160, sha1,	sha2_224, sha2_256, sha2_384, sha2_512,	sechash(2)	614
ssh – secure	shell remote login client	ssh(1)	284
getflags, usage - command-line parsing for		getflags(8)	957
rc, cd, eval, exec, exit, flag, rfork,	shift, wait, whatis, ., ~ - command language	rc(1)	239
fedex, ups, usps – track		fedex(1)	96
switch between them kbmap -	show a list of available keyboard maps and	kbmap(1)	159
uptime – trace –		uptime(1) trace(1)	323 313
trace -	show (real-time) process behavior	shr(3)	732
tinyurl –		tinyurl(1)	307
- halt any local file systems and optionally		fshalt(8)	956
man, lookman,	sig – print or find pages of this manual	man(1)	173
dsasigalloc, dsasigfree, dsaprivtopub - digital	signature algorithm /dsaprivfree,	dsa(2)	438
loopback – network link	simulation	loopback(3)	709
galaxy - representations of n-body		galaxy(6)	860
	simulator	disksim(8)	946
	simulator	galaxy(1)	107
ы, кі, vi, qi – instruction	simulators	vi(1)	327

trigonometric functions	sin, cos, tan, asin, acos, atan, atan2	sin(2)	623
human-readable date (and time) to seconds	since epoch seconds - convert	seconds(1)	264
time. nsec – time in seconds and nanoseconds	since epoch	time(2)	642
,	s_incref, s_memappend, s_nappend, s_new,/		630
/s_append, s_array, s_copy, s_error, s_free,		string(2)	
/setupDES3state, triple_block_cipher -	single and triple digital encryption standard	des(2)	425
httpfile – serve a	single web file	httpfile(4)	783
	sinh, cosh, tanh - hyperbolic functions	sinh(2)	624
	size – print size of executable files	size(1)	273
iounit – return	size of atomic I/O unit for file descriptor	iounit(2)	518
runestringwidth, runestringnwidth - graphical		stringsize(2)	632
/dirfmt, dirmodefmt, read9pmsg, statcheck,	sizeS2M, sizeD2M – interface to Plan 9 File/	fcall(2)	457
scat – sky catalogue and Digitized	Sky Survey	scat(7)	915
/ioproc, ioread, ioreadn, iosleep, iowrite -	slave I/O processes for threaded programs	ioproc(2)	516
	slave 1/0 processes for threaded programs	· · · · · · · · · · · · · · · · · · ·	
processes kill,		kill(1)	160
	sleep - suspend execution for an interval	sleep(1)	274
	sleep, alarm - delay, ask for delayed note	sleep(2)	625
synchronisation	sleep, wakeup, tsleep, return0 - process	sleep(9)	
/qsub, qneg, qmul, qdiv, qunit, qinv, qlen,	slerp, qmid, qsqrt - Quaternion arithmetic	quaternion(2)	588
delay, microdelay, addclock0link -	small delays, clock interrupts	delay(9)	
secfree, setmalloctag,/ malloc, mallocz,	smalloc, realloc, free, msize, secalloc,	malloc(9)	1095
/genstrongprime, DSAprimes, probably_prime,	smallprimetest - prime number generation	prime(2)	575
	smart - SMART error monitoring	smart(8)	1053
cifsd –	SMB network daemon	cifsd(8)	938
/s_array, s_copy, s_error, s_free, s_incref,	s_memappend, s_nappend, s_new,/	string(2)	630
print, fprint, sprint, snprint, seprint,	smprint, runesprint, runesnprint, runeseprint,/	print(2)	576
smtp,	smtpd – mail transport	smtp(8)	
Sintp,	smtpd – Mail transport	smtpd(6)	890
	snap – process snapshots	snap(6)	892
snap,	snapfs - create and mount process snapshots .	snap(4)	810
<pre>/s_error, s_free, s_incref, s_memappend,</pre>	s_nappend, s_new, s_newalloc, s_parse,/	string(2)	630
snap – process	snapshots	snap(6)	892
gb, gba, nes,	snes – emulators	nintendo(1)	201
<pre>/s_incref, s_memappend, s_nappend, s_new,</pre>	s_newalloc, s_parse, s_reset, s_restart,/	string(2)	630
	snoopy – spy on network packets	snoopy(8)	1056
runesnprint, runeseprint,/ print, fprint, sprint,	snprint, seprint, smprint, runesprint,	print(2)	576
print formatted output . fprintf, printf, sprintf,	snprintf, vfprintf, vprintf, vsprintf, vsnprintf -	fprintf(2)	474
daemons telnetd, rlogind, rexexec, ftpd,	socksd, hproxy - Internet remote access	ipserv(8)	984
realemu -	software emulation of /dev/realmode	realemu(8)	
mandel, mahjongg, memo, midi, mole, packet,	sokoban, sudoku – time wasters . /juggle, life,	games(1)	109
satreset, satfree – boolean satisfiability (SA)	solver . /satrangev, satsolve, satmore, satval,	sat(2)	607
fopen, freopen, fdopen, fileno, fclose, sopenr,	sopenw, sclose, fflush, setvbuf, setbuf, /	fopen(2)	469
qsort – quicker			587
ysoit - quicker	sortsort and/or merge files	qsort(2)	
and the second sec		sort(1)	275
	sorted files	comm(1)	52
	sorted list	look(1)	167
- synchronize the system clock to a time		timesync(8)	
src, Bfn – find	source code for executable	src(1)	282
hg – Mercurial	source code management system	hg(1)	123
bind, mount, unmount – change name	space	bind(1)	36
bind, mount, unmount - change name	space	bind(2)	388
- structure of conventional file name	space namespace		791
ns – display name	space	ns(1)	204
pipefile - attach filter to file in name	space	pipefile(1)	221
namespace – name	space description file	namespace(6)	878
import – import a name		import(4)	784
scanmail, testscan –	spam filters	scanmail(8)	
/s_memappend, s_nappend, s_new, s_newalloc,	s_parse, s_reset, s_restart, s_terminate,/	string(2)	630
arch -	specific information and control	arch(3)	675
light, pencal, keyboard, params, prompter –	specific utilities bitsyload,	bitsyload(1)	38
ngin, pencai, keyboaru, paranis, prompter -	spell, sprog – find spelling errors		
concurrent systems	spin – verification tool for models of	spell(1)	277
concurrent systems		spin(1)	278
/rsleep, rwakeup, rwakeupall, incref, decref -	spin locks, queueing rendezvous locks,/	lock(2)	526
interrupts	splhi, spllo, splx, islo - enable and disable	splhi(9)	
	split – split a file into pieces	split(1)	280
frexp, ldexp, modf -		frexp(2)	480
	splitmbox - split a mailbox into mdir format	splitmbox(8)	
splhi, spllo,		splhi(9)	
qer, runq - queue management for	spooled files	qer(8)	
	spred – sprite editor	spred(1)	281
runesnprint, runeseprint,/ print, fprint,		print(2)	576
vsnprintf - print formatted/ fprintf, printf,	sprintf, snprintf, vfprintf, vprintf, vsprintf,	fprintf(2)	474
spred –	sprite editor	spred(1)	281
spell,	• • • • • • • • • • • • • • • • • • • •	spell(1)	277
/s_reset, s_restart, s_terminate, s_tolower,		string(2)	630
. , _ , _ , _ , , , , , , , , , , , , ,		5.7	

			1050
snoopy -		snoopy(8)	
root exp, log, log10, pow, pow10,	sqrt - exponential, logarithm, power, square	exp(2)	455
fastrand,/ rand, Irand, frand, nrand, Inrand,	srand, truerand, ntruerand, genrandom, prng, src, Bfn – find source code for executable	rand(2)	591 282
strings /s tolower s puts s unique s grow		src(1)	630
<pre>strings . /s_tolower, s_putc, s_unique, s_grow, /s_tolower, s_putc, s_unique, s_grow, s_read,</pre>	s_read, s_read_line, s_getline - extensible s_read_line, s_getline - extensible strings	string(2)	630
		string(2)	
/s_nappend, s_new, s_newalloc, s_parse,		string(2)	630
	srv – server registry	srv(3)	733
erealloc9p, estrdup9p, listensrv,/	Srv, chatty9p, dirread9p, emalloc9p,	9p(2)	349
	srv, srvtls, 9fs – start network file service	srv(4)	811
exportfs,		exportfs(4)	767
readstr, respond, responderror, srvacquire,	srvrelease, threadlistensrv,/ /readbuf,	9p(2)	349
srv,	· · · · · · · · · · · · · · · · · · ·	srv(4)	811
	ssam - stream interface to sam	ssam(1)	283
tscant, scant,	sscanf, vfscanf - scan formatted input	fscanf(2)	481
	ssh – secure shell remote login client	ssh(1)	284
	sshfs – secure file transfer protocol client	sshfs(4)	812
	sshnet – secure file transfer protocol client	sshnet(4)	813
	ssl – SSL record layer	ssl(3)	734
	SSL version 2 encryption to a communication .	pushssl(2)	582
	SSL3 encryption to a communication channel .	pushtls(2)	583
	SSL3 record layer	tls(3)	737
ktrace – interpret kernel	stack dumps	ktrace(1)	161
 single and triple digital encryption 	standard/triple_block_cipher	des(2)	425
/fsetpos, fseek, rewind, feof, ferror, clearerr -	standard buffered input/output package	fopen(2)	469
/advanced encryption	standard (rijndael)	aes(2)	365
processes stop,	start - print commands to stop and start	stop(1)	285
srv, srvtls, 9fs –	start network file service	srv(4)	811
nusbrc – Universal Serial Bus	startup script	nusbrc(8)	1010
dirwstat, dirfwstat, nulldir - get and put file/ .	stat, fstat, wstat, fwstat, dirstat, dirfstat,	stat(2)	626
, , , , , , , , , , , , , , , , , , , ,	stat, wstat - inquire or change file attributes	stat(5)	842
/fcallfmt, dirfmt, dirmodefmt, read9pmsg,	statcheck, sizeS2M, sizeD2M - interface to/	fcall(2)	457
swap – memory usage	statistics and swap file control	swap(3)	736
memory – print memory		memory(8)	991
	stats – display graphs of system activity	stats(8)	1059
ps. psu. pstree – process	status	ps(1)	229
	status /fstat, wstat, fwstat, dirstat, dirfstat,	stat(2)	626
test – set	status according to condition	test(1)	301
debug,/ . changeuser, convkeys, printnetkey,		auth(8)	930
status message window	statusbar, statusmsg – display a bar graph or	statusbar(8)	
ungetc, fgets, gets, fputs, puts, fread, fwrite -	Stdio input and output . /fputc, putc, putchar,	fgetc(2)	461
tmpfile, tmpnam -	Stdio temporary files	tmpfile(2)	647
	s_tolower, s_putc, s_unique, s_grow, s_read,/	string(2)	630
processes	stop, start – print commands to stop and start	stop(1)	285
Host Controller Interface) SATA (Serial AT)	storage device drivers /- AHCI (Advanced	sdahci(3)	725
	storage device interface	sd(3)	723
sdaoe - ATA-over-Ethernet (Ao)		sdaoe(3)	727
	storage device interface	sdloop(3)	728
	storage management	privalloc(2)	579
	storage server	venti(2)	650
venti – archival		venti(6)	897
venti – archival	storage server	venti(8)	
strncpy, strecpy, strlen, / strcat, strncat,	strcmp, strncmp, cistrcmp, cistrncmp, strcpy,	strcat(2)	628
/strecpy, strlen, strchr, strrchr, strpbrk, strspn,	strcspn, strtok, strdup, strstr, cistrstr – string/	strcat(2)	628
- succepy, succes, succes, succes, supply, supply, succes, suc	stream editor	sed(1)	267
ssam –	stream interface to sam	ssam(1)	283
bullshit – assemble a	stream of bullshit from words in a file	bullshit(1)	40
/strncmp, cistrcmp, cistrncmp, strcpy, strncpy,	strecpy, strlen, strchr, strrchr, strpbrk,/	strcat(2)	628
/stringnbg, runestringbg, runestringnbg,	_string, ARROW, drawsetdebug - graphics/	draw(2)	432
getfields, gettokens, tokenize – break a		getfields(2)	488
runestrrchr, runestrdup, runestrstr – rune	string operations /runestrlen, runestrchr,	runestrcat(2)	605
strspn, strcspn, strtok, strdup, strstr, cistrstr -	string operations /strchr, strrchr, strpbrk,	strcat(2)	628
string, stringn, runestring, runestringn,	stringbg, stringnbg, runestringbg, / . /border,	draw(2)	432
runestringnwidth -/ stringsize, stringwidth,	stringnwidth, runestringsize, runestringwidth,	stringsize(2)	632
encodefmt – encoding byte arrays as	strings /enc32chr, dec16chr, enc16chr,	encode(2)	445
doquote, needsrcquote – quoted character	strings /quoterunestrfmt, quotefmtinstall,	quote(2)	590
s_read, s_read_line, s_getline - extensible	strings . /s_tolower, s_putc, s_unique, s_grow,	string(2)	630
5_read, 5_read_inte, 5_gettine extensible	strings – extract printable strings	strings(1)	286
runestringsize, runestringwidth,/	stringsize, stringwidth, stringnwidth,	stringsize(2)	632
/readsubfont, readsubfonti, writesubfont,	stringsubfont, strsubfontwidth, mkfont -/	subfont(2)	633
readsubione, readsubioner, whitesubioner,	strip – remove symbols from binary files	strip(1)	287
basename -	strip file name affixes	basename(1)	33
cistrncmp, strcpy, strncpy, strecpy, / strcat,	strncat, strcmp, strncmp, cistrcmp,	strcat(2)	628
/strcpy, strncpy, strecpy, strecpy, strecpy, strecht,		strcat(2)	628
,,,,,,,, .	, , ,		

/readsubfonti, writesubfont, stringsubfont,	strsubfontwidth, mkfont – subfont/	subfont(2)	633
/openfont, buildfont, freefont, Pfmt, Rfmt,	strtochan, chantostr, chantodepth -/	graphics(2)	492
text to/ atof, atoi, atol, atoll, charstod,	strtod, strtol, strtoll, strtoul, strtoull - convert	atof(2)	378
/ecdominit, ecdomfree, ecassign, ecadd, ecmul,	strtoec, ecgen, ecverify, ecpubverify,	ec(2)	441
/strlen, strchr, strrchr, strpbrk, strspn, strcspn,	strtok, strdup, strstr, cistrstr – string/	strcat(2)	628
atof, atoi, atol, atoll, charstod, strtod, strtol,	strtoll, strtoul, strtoull - convert text to/	atof(2)	378
/mpcopy, mpassign, mprand, mpnrand,	strtomp, mpfmt, mptoa, betomp, mptobe,/	mp(2)	547
B, sam.save, samterm – screen editor with	structural regular expressions sam,	sam(1)	258
lookupkey, deletekey – integer to data	structure maps /insertkey, caninsertkey,	intmap(2)	515
namespace –	structure of conventional file name space	namespace(4)	791
namespace -			1062
	stub – provide mount point stubs	stub(8)	
and farmer and	style - Plan 9 coding conventions for C	style(6)	893
	style archive	archfs(4)	753
dot3, cross3, len3, dist3, unit3,/ add3,		arith3(2)	375
/vrem3, pn2f3, ppp2f3, fff2p3, pdiv4, add4,	sub4 - operations on 3-d points and planes	arith3(2)	375
subfonts font,	subfont - external format for fonts and	font(6)	859
tweak - edit image files,	subfont files, face files, etc.	tweak(1)	318
cachechars, agefont, loadchar,	Subfont, Fontchar, Font – font utilities	cachechars(2)	395
/lookupsubfont, uninstallsubfont,	subfontname, readsubfont, readsubfonti,/	subfont(2)	633
font, subfont - external format for fonts and	subfonts	font(6)	859
insetrect, canonrect, eqpt, eqrect,/ addpt,	subpt, mulpt, divpt, rectaddpt, rectsubpt,	addpt(2)	363
memo, midi, mole, packet, sokoban,	sudoku - time wasters /mandel, mahjongg,	games(1)	109
blocks in a file	sum, md5sum, sha1sum - sum and count	sum(1)	288
nfs –	Sun network file system client	nfs(4)	794
/mp3enc, oggdec, oggenc, flacdec, flacenc,	sundec, wavdec, pcmconv, mixfs - decode/	audio(1)	26
/s_restart, s_terminate, s_tolower, s_putc,	s_unique, s_grow, s_read, s_read_line,/	string(2)	630
/runefmtstrinit, runefmtstrflush, errfmt -	support for user-defined print formats and/	fmtinstall(2)	466
scat – sky catalogue and Digitized Sky	Survey	scat(7)	915
sleep –	suspend execution for an interval	sleep(1)	274
	swap – establish a swap file	swap(8)	1063
control	swap - memory usage statistics and swap file .	swap(3)	736
- show a list of available keyboard maps and	switch between them kbmap	kbmap(1)	159
lookup, findlocal, getauto,/ . syminit, getsym,	symbase, pc2sp, pc2line, textseg, line2addr,	symbol(2)	635
na - assembler for the	Symbios Logic PCI–SCSI I/O Processors	na(8)	999
nm – name list	symbol table)	nm(1)	203
strip – remove	symbols from binary files	strip(1)	287
textseg, line2addr, lookup, findlocal,/	syminit, getsym, symbase, pc2sp, pc2line,	symbol(2)	635
/risctrace, ciscframe, riscframe, localaddr,	symoff, fpformat, beieee80ftos, beieeesftos,/	debugger(2)	422
rlock, runlock, wlock, wunlock - serial	synchronisation qlock, qunlock, canqlock,		1099
sleep, wakeup, tsleep, return0 - process	synchronisation	sleep(9)	1104
rendezvous – user level process	synchronization	rendezvous(2)	600
source timesync -	synchronize the system clock to a time	timesync(8)	1064
/conf, fmtarenas, fmtbloom, fmtindex, fmtisect,	syncindex - prepare and maintain a venti/	venti–fmt(8)	1076
hgignore –	syntax for Mercurial ignore files	hgignore(8)	961
	syscall - test a system call	syscall(1)	289
about, update the system	sysinfo, sysupdate - report information	sysinfo(1)	290
perror,		perror(2)	567
getuser,		getuser(2)	490
	system cdfs, cddb - optical	cdfs(4)	755
	system	cfs(4)	757
	system	ext2srv(4)	769
	system /reboot - halt any local file systems	fshalt(8)	956
	system	ftpfs(4)	778
hg - Mercurial source code management hgfs - mercurial file		hg(1) hgfs(4)	123 780
	systemsystem		
Infs – long name file		import(4) Infs(4)	784 789
mkfs, mkext – archive or update a file		mkfs(8)	995
mkpagfs – make a compressed read-only file		mkpaqfs(8)	996
mksacfs – make a compressed read-only me		mksacfs(8)	990 997
- network news transport protocol (NNT) file		nntpfs(4)	796
pagfs – compressed read-only file		paqfs(4)	800
patch – simple patch creation and tracking	SVSIEIII		212
pater simple pater eleation and ducking			
plavlistfs – plavlist file	system	patch(1)	914
playlistfs – playlist file ramfs – memory file	sýstemsystem	patch(1) playlistfs(7)	914 803
ramfs - memory file	systemsystemsystem	patch(1) playlistfs(7) ramfs(4)	
ramfs - memory file ratfs - mail address ratification file	system	patch(1) playlistfs(7)	803
ramfs – memory file ratfs – mail address ratification file rdbfs – remote kernel debugging file	system	patch(1) playlistfs(7) ramfs(4) ratfs(4)	803 804
ramfs – memory file ratfs – mail address ratification file rdbfs – remote kernel debugging file rio, label, window, wloc – window root – the root file	system	patch(1) playlistfs(7) ramfs(4) ratfs(4) rdbfs(4)	803 804 805
ramfs – memory file ratfs – mail address ratification file rdbfs – remote kernel debugging file rio, label, window, wloc – window root – the root file	system	patch(1) playlistfs(7) ramfs(4) ratfs(4) rdbfs(4) rio(1)	803 804 805 250
ramfs – memory file ratfs – mail address ratification file rdbfs – remote kernel debugging file rio, label, window, wloc – window root – the root file sacfs – compressed file	system	patch(1) playlistfs(7) ramfs(4) ratfs(4) rdbfs(4) rio(1) root(3)	803 804 805 250 721
ramfs – memory file ratfs – mail address ratification file rdbfs – remote kernel debugging file rio, label, window, wloc – window root – the root file sacfs – compressed file – report information about, update the	system	patch(1) playlistfs(7) ramfs(4) rdbfs(4) rio(1) root(3) sacfs(4) sysinfo(1) tftpfs(4)	803 804 805 250 721 809
ramfs - memory file ratfs - mail address ratification file rdbfs - remote kernel debugging file rio, label, window, wloc - window root - the root file sacfs - compressed file - report information about, update the tftpfs - trivial file transfer protocol (TFT) file truetypefs - TrueType font file	system system	patch(1) playlistfs(7) ramfs(4) rdbfs(4) rio(1) root(3) sacfs(4) sysinfo(1)	803 804 805 250 721 809 290
ramfs - memory file ratfs - mail address ratification file rdbfs - remote kernel debugging file rio, label, window, wloc - window root - the root file sacfs - compressed file - report information about, update the tftpfs - trivial file transfer protocol (TFT) file truetypefs - TrueType font file	system system	patch(1) playlistfs(7) ramfs(4) rdbfs(4) rio(1) root(3) sacfs(4) sysinfo(1) tftpfs(4)	803 804 805 250 721 809 290 817

			000
	system	wadfs(4)	823
	systemsystem	webfs(4) wikifs(4)	826 828
stats – display graphs of	system activity	stats(8)	
intro – introduction to	system administration	intro(8)	918
	system call	syscall(1)	289
· · ·	system call error	errstr(2)	448
	system calls	ratrace(1)	238
	system client	nfs(4)	794
	system clock to a time source	timesync(8) cmd(3)	681
	system devices	fs(3)	695
perror, syslog, sysfatal –		perror(2)	567
	system files	rio(4)	806
	system for console access	consolefs(4)	760
	system for flash memory	flashfs(4)	775
mkflashfs – make a journalling file	system for flash memory	mkflashfs(8)	994
untime – show how long the	system for interprocess messaging	plumber(4) uptime(1)	801 323
aetuser, sysname – get user or	system name	getuser(2)	490
	system to measure I/O	iostats(4)	786
fstype – determine file	system type	fstype(1)	106
connection reboot - reboot the		reboot(8)	
aliasmail – expand		aliasmail(8)	926
	systems dossrv, systems mntgen	dossrv(4)	765 790
	systems	mntgen(4) spin(1)	278
	systems	tapefs(4)	814
	systems and optionally shut down or reboot	fshalt(8)	956
the system sysinfo,	sysupdate - report information about, update .	sysinfo(1)	290
	table)	nm(1)	203
	table access functions /textsym, file2pc,	symbol(2)	635
tbi – format	tables for nroff or trofftables for nroff or trofftables for nroff or troff a file	tbl(1) tail(1)	295 291
functions sin, cos,		sin(2)	623
	tanh – hyperbolic functions	sinh(2)	624
- , ,	tap – follow the pipes of a process	tap(1)	292
	tar, dircp – archiver	tar(1)	293
file systems 32vfs, cpiofs, tapfs,	tarfs, tpfs, v6fs, v10fs, zipfs - mount archival .	tapefs(4)	814
	target	vblade(8)	
scuzz - SCSI	target control target control	atazz(8) scuzz(8)	928 1047
/freedocinfo, dimenkind, dimenspec, targetid,		html(2)	496
,, .,,,,,, .	tbl - format tables for nroff or troff	tbl(1)	295
ip, esp, gre, icmp, icmpv6, ipmux, rudp,		ip(3)	698
/tcp7, tcp9, tcp19, tcp21, tcp23, tcp25, tcp53,		listen(8)	988
	tcp113, tcp143, tcp445, tcp513, tcp515,/	listen(8)	988
/tcp566, tcp567, tcp993, tcp995, tcp1723, /tcp17007, tcp17008, tcp17009, tcp17010,		listen(8) listen(8)	988 988
/tcp565, tcp566, tcp567, tcp993, tcp995,	tcp1723, tcp17007, tcp17008, tcp17009,/	listen(8)	988
tcp113, tcp143,/ listen, listen1, tcp7, tcp9,	tcp19, tcp21, tcp23, tcp25, tcp53, tcp110,	listen(8)	988
/tcp23, tcp25, tcp53, tcp110, tcp113, tcp143,	tcp445, tcp513, tcp515, tcp564, tcp565,/	listen(8)	988
/tcp445, tcp513, tcp515, tcp564, tcp565,	tcp566, tcp567, tcp993, tcp995, tcp1723,/	listen(8)	988
tcp110, tcp113, tcp143,/ listen, listen1, /tcp515, tcp564, tcp565, tcp566, tcp567,	tcp7, tcp9, tcp19, tcp21, tcp23, tcp25, tcp53, . tcp993, tcp995, tcp1723, tcp17007,/	listen(8) listen(8)	988 988
/ (cp313, (cp304, (cp303, (cp300, (cp307,	tcs – translate character sets	tcs(1)	297
	tee – pipe fitting	tee(1)	299
	tel, iwhois – look in phone book	tel(1)	300
telco, faxreceive, faxsend, fax, telcofax,		telco(4)	815
execution, and XMODEM file transfer con,		con(1)	53
hproxy – Internet remote access daemons	telnetd, rlogind, rexexec, ftpd, socksd,	ipserv(8)	984 647
	terminal	tmpfile(2) screenlock(8)	647 1046
vt – emulate a VT–100 or VT–220	terminal	vt(1)	333
exits, _exits, atexit, atexitdont, terminate -	terminate process, process cleanup	exits(2)	454
pexit, postnote - kernel process creation,	termination and interruption kproc,	kproc(9)	
cpurc, cpurc.local, termrc,	termrc.local – boot scripts	cpurc(8)	940
eve coll	test – set status according to condition	test(1)	301
	test a system call	syscall(1) scanmail(8)	289 1043
	text /frdelete, frselect, frtick, frselectpaint,	frame(2)	477
ed –	text editor	ed(1)	85
hold – simple	text editor	hold(1)	149
fmt, htmlfmt – simple	text formatters	fmt(1)	100

	text formatting and typesetting	troff(1)	314
	text from Microsoft documents	doc2txt(1)	77
	text processing tools	troff2png(1)	317
	text to numbers /atoi, atol, atoll, charstod,	atof(2)	378
	text translatortext windows	9pcon(8)	923 16
	text windows	acme(1) acme(4)	750
syminit, getsym, symbase, pc2sp, pc2line,		symbol(2)	635
/getauto, findsym, localsym, globalsym,	textsym, file2pc, fileelem, filesym, fileline,/	symbol(2)	635
dhcpd, dhcp6d, dhcpleases, rarpd,		dhcpd(8)	943
system	tftpfs - trivial file transfer protocol (TFT) file	tftpfs(4)	817
jpg, gif, png, tif, ppm, bmp, v210, yuv, ico,		jpg(1)	156
venti arenas to blu-ray discs or restore from		backup(8)	932
available keyboard maps and switch between	them kbmap - show a list of	kbmap(1)	159
fortune,	· · · · · · · · · · · · · · · · · · ·	fortune(1)	103
(above and above dealers dealers dealers)	thesaurus - search online thesaurus	thesaurus(1)	303
/nbrecvul, nbsend, nbsendp, nbsendul,		thread(2)	638
iosleep, iowrite - slave I/O processes for /threadcreate, threaddata, threadexits,	threaded programs . /ioproc, ioread, ioreadn, threadexitsall, threadgetgrp, threadgetname,/	ioproc(2) thread(2)	516 638
/threadkillgrp, threadmain, threadnotify,	threadid, threadpid, threadsetgrp, /	thread(2)	638
/threadexitsall, threadgetgrp, threadgetname,	threadint, threadintgrp, threadkill,	thread(2)	638
threadid, / /threadint, threadintgrp, threadkill,	threadkillgrp, threadmain, threadnotify,	thread(2)	638
/threadlistensry, threadpostmountsry,	threadpostsharesrv, srv – 9P file service	9p(2)	349
thread/ /threadid, threadpid, threadsetgrp,	threadsetname, threadwaitchan, yield	thread(2)	638
and run automatic or manual tunnel of IPv6	through IPv4 6in4, ayiya - configure	6in4(8)	919
tput – measure read		tput(1)	311
	thumbprint – public key thumbprints	thumbprint(6)	894
TK2SEC - kernel times and time/ seconds,	ticks, fastticks, HZ, MS2HZ, MS2TK, TK2MS,	seconds(9)	
togeordi, togif, toppm, topng, / . jpg, gif, png,	tif, ppm, bmp, v210, yuv, ico, tga, tojpg, time ctime, localtime, gmtime,	jpg(1)	156
asctime, tm2sec, timezone - convert date and date, clock - date and		ctime(2) date(1)	419 60
mtime – print file modification		mtime(1)	190
tmparse, tmfmt, tmnorm – convert date and		tmdate(2)	643
	time – time a command	time(1)	304
gpsfs, gpsevermore – GPS	time and position service	gpsfs(8)	959
rtc –		rtc(3)	722
MS2TK, TK2MS, TK2SEC - kernel times and		seconds(9)	
cputime, times, cycles – cpu		cputime(2)	418
nanoseconds since epoch	time, nsec – time in seconds and	time(2)	642
timesync – synchronize the system clock to a	time) process behavior	trace(1) timesync(8)	313 1064
seconds – convert human-readable date (and		seconds(1)	264
memo, midi, mole, packet, sokoban, sudoku –	time wasters	games(1)	109
timing diagrams	timepic – troff preprocessor for drawing	timepic(1)	305
HŽ, MŠŽHZ, MŠŽTK, TK2MS, TK2SEC – kernel	times and time conversions . /ticks, fastticks,	seconds(9)	1103
children cputime,		cputime(2)	418
time source	timesync - synchronize the system clock to a .	timesync(8)	
ctime, localtime, gmtime, asctime, tm2sec,		ctime(2)	419
timepic - troff preprocessor for drawing	timing diagrams timmy – physics sandbox	timepic(1)	305
	tinc – mesh peer to peer VPN	timmy(1)	
	tinyurl – shrink a URL	tinc(8) tinyurl(1)	307
/ticks, fastticks, HZ, MS2HZ, MS2TK, TK2MS,	TK2SEC - kernel times and time conversions	seconds(9)	
, cience, i accience, i iii, i iiiiiiiii, iiiiiiiii, iiiiiii	tls – TLS and SSL3 record layer	tls(3)	737
tlssrv, tlsclient, tlssrvtunnel,	tlsclienttunnel - TLS server and client	tlssrv(8)	1066
okThumbprint,/ pushtls, tlsClient,		pushtls(2)	583
ctime, localtime, gmtime, asctime,	,	ctime(2)	419
tmpfile,		tmpfile(2)	647
date and time		tmdate(2)	643
ASCII/ /ispunct, isprint, isgraph, iscntrl, isascii, venti arenas to blu-ray discs or/ backup,	toascii, _toupper, _tolower, toupper, tolower - tobackup, dumparenas, restore - backup	ctype(2) backup(8)	421 932
dpic,		dpic(1)	79
/ppm, bmp, v210, yuv, ico, tga, tojpg, togeordi,		ipq(1)	156
filter, list, deliver,		filter(1)	98
getfields, gettokens,	tokenize - break a string into fields	getfields(2)	488
/isgraph, iscntrl, isascii, toascii, _toupper,	_tolower, toupper, tolower - ASCII character/ .	ctype(2)	421
Unicode/ /istitlerune, isupperrune, isdigitrune,		isalpharune(2)	522
spin – verification		spin(1)	278
at, drain, expect, pass - dialer scripting	tools	expect(1)	92 317
troff2gif - miscellaneous text processing /bmp, v210, yuv, ico, tga, tojpg, togeordi, togif,	tools troff2png, toppm, topng, totif, toico – view and convert/	troff2png(1) jpg(1)	317 156
window/ . /bottomwindow, bottomnwindows,	topwindow, topnwindows, originwindow	window(2)	668
	torrent – bittorrent client	torrent(1)	308
exec, execl, _privates, _nprivates,	_tos - execute a file	exec(2)	452

	toStr - HTML parser /freedocinfo, dimenkind,	html(2)	496
ico, tga, tojpg, togeordi, togif, toppm, topng,	totif, toico - view and convert pictures . /yuv,	jpg(1)	156
/isupperrune, isdigitrune, tolowerrune,		isalpharune(2)	522
	touch – set modification date of a file	touch(1)	310
/ispunct, isprint, isgraph, iscntrl, isascii, toascii,	_toupper, _tolower, toupper, tolower – ASCII/ .	ctype(2)	421
cases . /isdigitrune, tolowerrune, totitlerune,	toupperrune - Unicode character classes and	isalpharune(2)	522
systems	tpfs, v6fs, v10fs, zipfs - mount archival file	tapefs(4)	814
prof,	tprof, kprof – display profiling data	prof(1)	226
	tput – measure read throughput	tput(1)	311
	tr – translate characters	tr(1)	312
	trace – show (real-time) process behavior	trace(1)	313
ratrace -	trace process system calls	ratrace(1)	238
ping, gping,		ping(8)	
	tracing language	dtracy(1)	80
cdfs, cddb – optical disc (CD, DVD, B)		cdfs(4)	755
fedex, ups, usps –		fedex(1)	96
	tracking /freereqpool, allocreq, closereq,	9pfid(2)	355
	tracking system	patch(1)	212
another address	trampoline - forward incoming calls to	trampoline(8)	
	transfer con, telnet, rx, hayes, xms, xmr	con(1)	53
	transfer data from and to a file	read(5)	840
	transfer protocol client	sshfs(4)	812
	transfer protocol client	sshnet(4)	813
	transfer protocol (FT) file system	ftpfs(4)	778
	transfer protocol (TFT) file system	tftpfs(4)	817
	transformations /qrot, scale, move, xform,	matrix(2)	534
tcs –	translate character sets	tcs(1)	297
tr –	translate characters	tr(1)	312
9pcon – 9P to text	translator	9pcon(8)	923
closefile, removefile, walkfile, opendirfile,/	Tree, alloctree, freetree, File, createfile,	9pfile(2)	357
avlnext, avlprev - Balanced binary search	tree routines . /avlinsert, avldelete, avllookup,	avl(2)	385
sin, cos, tan, asin, acos, atan, atan2 -	trigonometric functions	sin(2)	623
/readblist, concatblock, copyblock,	trimblock, packblock, padblock, pullblock, /	allocb(9)	1085
	triple_block_cipher - single and triple digital/ .	des(2)	425
tftpfs –		tftpfs(4)	817
	troff	tbl(1)	295
typesetting		troff(1)	314
	troff output interpreter	proof(1)	228
	troff output into HTML	troff2html(1)	316
pic -		pic(1)	218
diagrams timepic -		timepic(1)	305
ulugiants antepic	troff2html – convert troff output into HTML	troff2html(1)	316
processing tools	troff2png, troff2gif - miscellaneous text	troff2png(1)	317
	troff's ms macros and html	ms2html(1)	189
fortune, theo,		fortune(1)	103
rand, Irand, frand, nrand, Inrand, srand,		rand(2)	591
ttfnewbitmap, ttffreebitmap, ttfblit –	TrueType renderer . /ttfrender, ttfrunerender,	ttf(2)	648
timewoninap, timeeoninap, tiont -	truetypefs – TrueType font file system	truetypefs(4)	818
acid truss	trump – debugger		12
		acid(1)	
	truncate input on zero byte vtzerotruncate,	zerotrunc(8)	
· · · · · · · · · · · · · · · · · · ·		venti-zero(2)	666
acid,		acid(1)	12
semaphores semacquire, sleep, wakeup,	tsemacquire, semrelease – user level tsleep, return0 – process synchronisation	semacquire(2) sleep(9)	621
ttfrunerender, ttfnewbitmap, ttffreebitmap, ttfputglyph, ttfgetcontour,/ttfopen, ttfscale,	ttfblit – TrueType renderer /ttfrender, ttfclose, ttffindchar, ttfenumchar, ttfgetglyph, .	ttf(2)	648 648
		ttf(2)	
/ttfrender, ttfrunerender, ttfnewbitmap,		ttf(2)	648
/ttfenumchar, ttfgetglyph, ttfputglyph,	ttfgetcontour, ttfrender, ttfrunerender, /	ttf(2)	648
/ttfgetcontour, ttfrender, ttfrunerender,	ttfnewbitmap, ttffreebitmap, ttfblit -/	ttf(2)	648
ttfenumchar, ttfgetglyph, ttfputglyph,/	ttfopen, ttfscale, ttfclose, ttffindchar,	ttf(2)	648
/ttfgetglyph, ttfputglyph, ttfgetcontour,	ttfrender, ttfrunerender, ttfnewbitmap,/	ttf(2)	648
ttfgetglyph, ttfputglyph,/ ttfopen,	ttfscale, ttfclose, ttffindchar, ttfenumchar,	ttf(2)	648
ayiya - configure and run automatic or manual	tunnel of IPv6 through IPv4 6in4,	6in4(8)	919
files, etc.	tweak – edit image files, subfont files, face	tweak(1)	318
inter-integrated circuit (I ² C) interface	twsi - two-wire serial interface (TWS) and	twsi(3)	739
file – determine file	type	file(1)	97
fstype – determine file system	type	fstype(1)	106
keyboard - how to	type characters	keyboard(6)	866
dmid – MIDI to OPL3 converter using	type instrument banks	dmid(1)	76
man – macros to	typeset manual	man(6)	869
eqn –	typeset mathematics	eqn(1)	90
view FAX, image, graphic, PostScript, PDF, and	typesetter output files page -	page(1)	208
htmlroff - HTML formatting and	typesetting	htmlroff(1)	150
htmlroff - HTML formatting and	typesetting	htmlroff(6)	861

troff, nroff, dpost - text formatting and	typesetting	troff(1)	314
mnihongo – macros for		mnihongo(6)	874
convert date and time tmnow,	tzload, tmtime, tmparse, tmfmt, tmnorm – uart, eia – serial communication control	tmdate(2)	643 740
ip, esp, gre, icmp, icmpv6, ipmux, rudp, tcp,	udp, il – network protocols over IP	uart(3) ip(3)	698
ip, csp, gre, iemp, iempvo, ipmux, ruup, iep,	udpecho – echo UDP packets	udpecho(8)	
file to unicode	uhtml – convert foreign character set HTML	uhtml(1)	320
/mptober, letomp, mptole, mptolel, mptoui,	uitomp, mptoi, itomp, uvtomp, mptouv,/	mp(2)	547
leak, kmem,	umem - help find memory leaks	leak(1)	162
division muldiv,	umuldiv - high-precision multiplication and	muldiv(2)	552
gzip, gunzip, bzip2, bunzip2, compress, lock – run a command	uncompress, zip, unzip - compress and/	gzip(1) lock(1)	121 166
fgetc, getc, getchar, fputc, putc, putchar,	under lock	fgetc(2)	461
internationalized domain names to and from	unicode utf2idn, idn2utf – convert	idn(2)	514
- convert foreign character set HTML file to	unicode uhtml	uhtml(1)	320
ascii,	unicode - interpret ASCII, Unicode characters .	ascii(1)	24
format UTF,	Unicode, ASCII, rune - character set and	utf(6)	896
/tolowerrune, totitlerune, toupperrune -	Unicode character classes and cases	isalpharune(2)	522
ascii, unicode – interpret ASCII, /freesubfont, installsubfont, lookupsubfont,	Unicode charactersuninstallsubfont, subfontname, readsubfont,	ascii(1) subfont(2)	24 633
	uniq – report repeated lines in a file	uniq(1)	321
mktemp – make a	unique file name	mktemp(2)	544
iounit - return size of atomic I/O	unit for file descriptor	iounit(2)	518
/eqpt3, closept3, dot3, cross3, len3, dist3,		arith3(2)	375
	units - conversion program	units(1)	322
audio, disk, ether, kb, serial, ptp, usbd –	Universal Serial Bus drivers	nusb(4)	797
– nusbrc /setalpha, loadimage, cloadimage,	Universal Serial Bus startup scriptunloadimage, readimage, writeimage,/	nusbrc(8) allocimage(2)	1010 367
mempoly,/ /loadmemimage, cloadmemimage,	unloadmemimage, memfillcolor, memarc,	memdraw(2)	536
canrlock, runlock, wlock, / lock, canlock,	unlock, glock, canglock, gunlock, rlock,	lock(2)	526
Pfmt,/ /flushimage, bufimage, lockdisplay,	unlockdisplay, openfont, buildfont, freefont,	graphics(2)	492
segattach, segdetach, segfree -	unmap a segment in virtual memory	segattach(2)	617
ml, mlmgr, mlowner –	unmoderated mailing lists	mlmgr(1)	185
bind, mount,	5 1	bind(1)	36 388
bind, mount, quotestrfmt,/ quotestrdup, quoterunestrdup,	unmount – change name space	bind(2) quote(2)	590
loaddevstr, opendev, opendevdata, openep,	unstall – USB device driver library /getdev,	nusb(2)	560
/machbyname, newmap, setmap, findseg,	unusemap, loadmap, attachproc, get1, get2,/	mach(2)	529
vac,	unvac - create, extract a vac archive on Venti .	vac(1)	324
bzip2, bunzip2, compress, uncompress, zip,	unzip - compress and expand data . /gunzip,	gzip(1)	121
milite miliout archive or	upasfs – mail file server	upasfs(4)	819 995
mkfs, mkext - archive or sysinfo, sysupdate - report information about,	update a file system	mkfs(8) sysinfo(1)	290
applychanges, applylog, compactdb,	updatedb – simple client-server replica/	replica(8)	
init – initialize machine	upon booting	init(8)	980
reboot – reboot the system	upon loss of remote file server connection	reboot(8)	
. fedex,		fedex(1)	96
running	uptime - show how long the system has been .	uptime(1)	323
corresponding to a/ hget, hpost, webpaste,		tinyurl(1) hget(1)	307 145
du – disk	usage	du(1)	82
scripts getflags,		getflags(8)	957
swap – memory	usage statistics and swap file control	swap(3)	736
dougt gotdou logidiousty suggestions (usb – USB Host Controller Interface	usb(3)	741
devctl, getdev, loaddevstr, opendev,/ audio, disk, ether, kb, serial, ptp,	usbcmd, classname, closedev, configdev, usbd – Universal Serial Bus drivers	nusb(2) nusb(4)	560 797
eve, iseve – privileged		eve(9)	
	user	newuser(8)	
cap – capabilities for setting the	user id of processes	cap(3)	680
rendezvous –	user level process synchronization		600
semacquire, tsemacquire, semrelease –	user level semaphores		621
- console clocks process/process group ide	user list format	users(6) cons(3)	895 683
	user or system name	getuser(2)	490
passwd, netkey - change or verify	user password	passwd(1)	211
/runefmtstrflush, errfmt - support for	user-defined print formats and output/	fmtinstall(2)	466
5e -		5e(1)	10
,factotum, fgui auth_getinfo - routines for authenticating	userpasswd - authentication agent	factotum(4)	770 379
auti-gettino - routines for authenticaling	users – file server user list format	auth(2) users(6)	895
dmid – MIDI to OPL3 converter	using GENMIDI-type instrument banks	dmid(1)	76
who, whois – who is	using the machine	who(1)	338
	usps - track shipments	fedex(1)	96
uttlen, uttnlen, uttrune, uttrrune, utfutf -	UTF conversion . /runenlen, fullrune, utfecpy,	rune(2)	603

_			
format	UTF, Unicode, ASCII, rune - character set and .	utf(6)	896
domain names to and from unicode	utf2idn, idn2utf - convert internationalized	idn(2)	514
/runelen, runenlen, fullrune, utfecpy,	utflen, utfnlen, utfrune, utfrrune, utfutf -/	rune(2)	603
keyboard, params, prompter - bitsy-specific		bitsyload(1)	38
loadchar, Subfont, Fontchar, Font - font	utilities cachechars, agefont,		395
/mptolel, mptoui, uitomp, mptoi, itomp,	uvtomp, mptouv, vtomp, mptov, mptod,/	mp(2)	547
32vfs, cpiofs, tapfs, tarfs, tpfs, v6fs,	v10fs, zipfs – mount archival file systems	tapefs(4)	814
toppm, topng,/ . jpg, gif, png, tif, ppm, bmp,	v210, yuv, ico, tga, tojpg, togeordi, togif,	jpg(1)	156
parseip, parseipmask, parseipandmask, /maskip, equivip4, equivip6, defmask, isv4,	v4parseip, parseether, myipaddr,/ eipfmt, v4tov6, v6tov4, nhgetv, nhgetl, nhgets,/	ip(2)	519 519
systems 32vfs, cpiofs, tapfs, tarfs, tpfs,	v6fs, v10fs, zipfs – mount archival file	ip(2) tapefs(4)	814
/equivip4, equivip6, defmask, isv4, v4tov6,	v6tov4, nhgetv, nhgetl, nhgets, hnputv,/	ip(2)	519
0a, 1a, 2a, 5a, 6a, 8a, ka, qa,	va – assemblers	2a(1)	4
Venti	vac, unvac – create, extract a vac archive on	vac(1)	324
	vacfs – a Venti-based file system	vacfs(4)	822
dimenspec, targetid,/ . parsehtml, printitems,	validitems, freeitems, freedocinfo, dimenkind,	html(2)	496
env – environment		env(3)	690
getenv, putenv – access environment		getenv(2)	486
	vblade - virtual AoE target	vblade(8)	
0c, 1c, 2c, 5c, 6c, 7c, 8c, kc, qc,	vc – C compilers	2c(1)	5
/midpt3, lerp3, reflect3, nearseg3, pldist3,	vdiv3, vrem3, pn2f3, ppp2f3, fff2p3, pdiv4,/	arith3(2)	375
vac, unvac - create, extract a vac archive on	Venti	vac(1)	324 650
	venti – archival storage serverventi – archival storage server	venti(2) venti(6)	897
	venti – archival storage server	venti(8)	
/tobackup_dumparenas_restore - backup	venti arenas to blu-ray discs or restore from/ .	backup(8)	932
	Venti block cache		651
	Venti block truncation	venti-zero(2)	666
	Venti client /vtreadpacket, vtwritepacket,	venti-client(2)	653
	Venti clients	venti(1)	326
	venti configuration file	venti.conf(6)	900
	venti data formats /vtputstring, vtrootpack,	venti-fcall(2)	657
vtfiletruncate, vtfileunlock, vtfilewrite –	Venti files /vtfilesetentry, vtfilesetsize,	venti-file(2)	659
	Venti logs /vtlogopen, vtlogprint,	venti-log(2)	661
	Venti network connections /vtfreeconn, venti server /fmtarenas, fmtbloom, fmtindex,	venti-conn(2) venti-fmt(8)	655
	Venti server		665
	venti servers		
	Venti-based file system	vacfs(4)	822
	venti.conf – a venti configuration file	venti.conf(6)	900
/vtwritepacket, vtsync, vtping, vtrpc,			653
vtlogopen, vtlogprint, vtlogremove, vtlogopen,	ventilogging - Venti logs /vtlognames,	venti–log(2)	661
systems spin –	verification tool for models of concurrent	spin(1)	278
passwd, netkey - change or		passwd(1)	211
- initialize 9P connection and negotiate	version fversion	fversion(2)	484
channel pushssl – attach SSL	version – negotiate protocol version	version(5)	844
filter, list, deliver, token,		pushssl(2) filter(1)	582 98
	vfprint, vsnprint, vseprint, vsmprint,/	print(2)	576
formatted/ fprintf, printf, sprintf, snprintf,	vfprintf, vprintf, vsprintf, vsnprintf – print	fprintf(2)	474
fscanf, scanf, sscanf,		fscanf(2)	481
	vga – configure a VGA card	vga(8)	1079
	vga – VGA controller device	vga(3)	745
	vgadb - VGA controller and monitor database	vgadb(6)	901
5i, ki,		vi(1)	327
togeordi, togif, toppm, topng, totif, toico -	view and convert pictures /ico, tga, tojpg,	jpg(1)	156
and typesetter output files page - gview - interactive graph	view FAX, image, graphic, PostScript, PDF,	page(1) gview(1)	208 119
	viewer	vnc(1)	331
grot, scale, move, xform, ixform, persp, look,	viewport – Geometric transformations /rot,	matrix(2)	534
vblade -	virtual AoE target	vblade(8)	
segdetach, segfree - map/unmap a segment in	virtual memory segattach,	segattach(2)	617
- remote frame buffer server and viewer for	Virtual Network Computing (VN) vncs, vncv	vnc(1)	331
vmx –	virtual PC	vmx(1)	329
	virtualization interface	vmx(3)	747
0l, 1l, 2l, 5l, 6l, 8l, kl, ql,		21(1)	8
	vmx - virtual PC	vmx(1)	329 747
viewer for Virtual Network Computing (VN)	vncs, vncv – remote frame buffer server and	vmx(3) vnc(1)	331
rtc – real-time clock and	volatile RAM	rtc(3)	722
tinc – mesh peer to peer	VPN	tinc(8)	
fprintf, printf, sprintf, snprintf, vfprintf,	vprintf, vsprintf, vsnprintf – print formatted/	fprintf(2)	474
/lerp3, reflect3, nearseg3, pldist3, vdiv3,	vrem3, pn2f3, ppp2f3, fff2p3, pdiv4, add4,/	arith3(2)	375
/runesmprint, vfprint, vsnprint, vseprint,	vsmprint, runevsnprint, runevseprint,/	print(2)	576

/printf, sprintf, snprintf, vfprintf, vprintf,	vsprintf, vsnprintf – print formatted output	fprintf(2)	474
vt – emulate a	VT-100 or VT-220 terminal	vt(1)	333
vtblockput, vtblockwrite,/ VtBlock, VtCache,	vtblockcopy, vtblockdirty, vtblockduplock,		651
vtfree - error-checking memory allocators	vtbrk, vtmalloc, vtmallocz, vtrealloc, vtstrdup,	venti-mem(2)	662
/vtblockduplock, vtblockput, vtblockwrite,	vtcachealloc, vtcacheallocblock,/	venti-cache(2)	651
/vtblockwrite, vtcachealloc, vtcacheallocblock,	vtcacheblocksize, vtcachefree, vtcacheglobal,/	venti-cache(2)	651
/vtcacheblocksize, vtcachefree, vtcacheglobal,	vtcachelocal, vtcachesetwrite, vtglobaltolocal,/	venti-cache(2)	651
vtversion, vtdebug, vthangup - Venti/ VtConn,	vtconn, vtdial, vtfreeconn, vtsend, vtrecv,	venti-conn(2)	655
vtreadpacket, vtwritepacket, vtsync, vtping,/	vtconnect, vthello, vtread, vtwrite,	venti-client(2)	653
vtentryunpack, vtfcallclear, vtfcallfmt,/	VtEntry, VtFcall, VtRoot, vtentrypack,	venti-fcall(2)	657
vtfcallfmt,/ VtEntry, VtFcall, VtRoot,	vtentrypack, vtentryunpack, vtfcallclear,	venti-fcall(2)	657
/vtentryunpack, vtfcallclear, vtfcallfmt,	vtfcallpack, vtfcallunpack, vtfromdisktype,/	venti-fcall(2)	657
vtfilecreate, vtfilecreateroot, vtfileflush,/	VtFile, vtfileblock, vtfileblockscore, vtfileclose,	venti-file(2)	659
vtfilecreate, vtfilecreateroot, / VtFile,	vtfileblock, vtfileblockscore, vtfileclose,	venti-file(2)	659
/vtfileclose, vtfilecreate, vtfilecreateroot,	vtfileflush, vtfileflushbefore, vtfilegetdirsize,/	venti-file(2)	659
/vtfileflush, vtfileflushbefore, vtfilegetdirsize,	vtfilegetentry, vtfilegetsize, vtfileincref,/	venti-file(2)	659
/vtfilegetentry, vtfilegetsize, vtfileincref,	vtfilelock, vtfilelock2, vtfileopen,/	venti-file(2)	659
/vtfileincref, vtfilelock, vtfilelock2, vtfileopen,	vtfileopenroot, vtfileread, vtfileremove,/	venti-file(2)	659
/vtfileopenroot, vtfileread, vtfileremove,	vtfilesetdirsize, vtfilesetentry, vtfilesetsize,/	venti-file(2)	659
/vtfilesetdirsize, vtfilesetentry, vtfilesetsize,	vtfiletruncate, vtfileunlock, vtfilewrite - Venti/ .	venti-file(2)	659
vtbrk, vtmalloc, vtmallocz, vtrealloc, vtstrdup,	vtfree - error-checking memory allocators	venti-mem(2)	662
vtdebug, vthangup -/ . VtConn, vtconn, vtdial,	vtfreeconn, vtsend, vtrecv, vtversion,	venti–conn(2)	655
vtsrvhello, vtlisten,	vtgetreq, vtrespond - Venti server	venti-server(2)	665
/vtfcallunpack, vtfromdisktype, vttodisktype,	vtgetstring, vtputstring, vtrootpack,/	venti-fcall(2)	657
/vtcacheglobal, vtcachelocal, vtcachesetwrite,	vtglobaltolocal, vtlocaltoglobal - Venti block/ .	venti-cache(2)	651
/vtfreeconn, vtsend, vtrecv, vtversion, vtdebug,	vthangup - Venti network connections	venti–conn(2)	655
vtwritepacket, vtsync, vtping,/ vtconnect,	vthello, vtread, vtwrite, vtreadpacket,	venti-client(2)	653
vtsrvhello,		venti-server(2)	665
/vtcachelocal, vtcachesetwrite, vtglobaltolocal,	vtlocaltoglobal - Venti block cache	venti-cache(2)	651
vtlogdump, vtlognames, vtlogopen,/	VtLog, VtLogChunk, vtlog, vtlogclose,	venti-log(2)	661
vtlogopen, vtlogprint,/ VtLog, VtLogChunk,	vtlog, vtlogclose, vtlogdump, vtlognames,	venti-log(2)	661
/vtlogdump, vtlognames, vtlogopen, vtlogprint,	vtlogremove, vtlogopen, ventilogging – Venti/	venti-log(2)	661
error-checking memory/ vtbrk, vtmalloc,	vtmallocz, vtrealloc, vtstrdup, vtfree	venti-mem(2)	662
/uitomp, mptoi, itomp, uvtomp, mptouv,	vtomp, mptov, mptod, dtomp, mpdigdiv,/	mp(2)	547
/vtputstring, vtrootpack, vtrootunpack,	vtparsescore, vtscorefmt - venti data formats	venti-fcall(2)	657
/vtfromdisktype, vttodisktype, vtgetstring,	vtputstring, vtrootpack, vtrootunpack,/	venti-fcall(2)	657
vtsync, vtping, vtrpc,/ vtconnect, vthello,	vtread, vtwrite, vtreadpacket, vtwritepacket,	venti-client(2)	653
memory allocators vtbrk, vtmalloc, vtmallocz,	vtrealloc, vtstrdup, vtfree - error-checking	venti-mem(2)	662
VtConn, vtconn, vtdial, vtfreeconn, vtsend,	vtrecv, vtversion, vtdebug, vthangup - Venti/	venti-conn(2)	655
vtsrvhello, vtlisten, vtgetreq,	vtrespond – Venti server	venti-server(2)	665
vtfcallclear, vtfcallfmt,/ VtEntry, VtFcall,	VtRoot, vtentrypack, vtentryunpack,	venti-fcall(2)	657
/vttodisktype, vtgetstring, vtputstring,	vtrootpack, vtrootunpack, vtparsescore,/ vtrpc, ventidoublechecksha1 – Venti client	venti-fcall(2)	657
<pre>/vtreadpacket, vtwritepacket, vtsync, vtping, vtrootpack, vtrootunpack, vtparsescore,</pre>	vtscorefmt – venti data formats . /vtputstring,	venti-client(2) venti-fcall(2)	653 657
Venti/ VtConn, vtconn, vtdial, vtfreeconn,	vtsend, vtrecv, vtversion, vtdebug, vthangup –	venti-conn(2)	655
Venti server		venti-server(2)	665
venti server	vtstrdup, vtfree – error-checking memory/	venti-mem(2)	662
/vtread, vtwrite, vtreadpacket, vtwritepacket,	vtsync, vtping, vtrpc, ventidoublechecksha1 -/	venti-client(2)	653
/vtfcallpack, vtfcallunpack, vtfromdisktype,	vttodisktype, vtgetstring, vtputstring,/	venti-fcall(2)	657
/vtconn, vtdial, vtfreeconn, vtsend, vtrecv,	vtversion, vtdebug, vthangup – Venti network/	venti-conn(2)	655
/vthello, vtread, vtwrite, vtreadpacket,			653
vtzerotruncate, vtzeroextend,		venti-zero(2)	666
faces, seemail,	vwhois - mailbox interface	faces(1)	94
	wadfs - WAD file system	wadfs(4)	823
await,		wait(2)	667
rc, cd, eval, exec, exit, flag, rfork, shift,	wait, whatis, ., ~ - command language	rc(1)	239
	wake-on-lan Ethernet packet	wol(8)	1081
synchronisation sleep,		sleep(9)	1104
	walk - descend a directory hierarchy	walk(5)	845
	walk – walk a path	walk(1)	334
/freetree, File, createfile, closefile, removefile,		9pfile(2)	357
keyfs,	5	keyfs(4)	787
error, nexterror, poperror,		error(9)	
	wasters /life, mandel, mahjongg, memo,	games(1)	109
/oggdec, oggenc, flacdec, flacenc, sundec,		audio(1)	26
	wc - word count	wc(1)	336
msexceltables - extract/ doc2txt, doc2ps,		doc2txt(1)	77
abaca brows the Morth Mide	weather – print weather report	weather(1)	337
abaco – browse the World-Wide		abaco(1)	11
webfs – world wide	web file	httpfile(4)	783 826
mothra – retrieve and display World-Wide	Web files	webfs(4) mothra(1)	826 186
webpaste, urlencode – retrieve, post to a		hget(1)	145
webpuste, unencode Tetrieve, post to a	webcookies – HTTP cookie manager		825
			525

	una la fan an una al al unida una la filla an astanta	\dots hf (A)	020
httpd, save, imagemap, man2html,	webfs – world wide web file system	webfs(4) httpd(8)	826 977
page corresponding to a url hget, hpost,	webpaste, urlencode – retrieve, post to a web	hget(1)	145
			448
errstr, rerrstr, rc, cd, eval, exec, exit, flag, rfork, shift, wait,	werrstr - description of last system call error .	errstr(2)	239
panic – abandon hope, all ye	whatis, ., ~ - command language	rc(1) panic(9)	
panic – abandon nope, an ye	who enter here	who(1)	338
aliasmail – expand system	who, whois - who is using the machine wide mail aliases		926
	Wide Web	aliasmail(8)	
webfs - world	wide web file system	abaco(1) webfs(4)	11 826
mothra – retrieve and display	Wide Web files		186
	Wide Web files	mothra(1)	
wpa –		wpa(8)	
2,000	wikifs, wikipost – wiki file system	wikifs(4)	828
acme,		acme(1)	16
- display a bar graph or status message		statusbar(8)	
topwindow, topnwindows, originwindow -	window management /bottomnwindows,	window(2)	668
rio - rio labal	window system files	rio(4)	806
rio, label,		rio(1)	250
	windows	acme(1)	16
	windows	acme(4)	750
winwatch – monitor rio cifs – Microsoft™		winwatch(1)	339
	Windows network filesystem client	cifs(4)	758
/memltofrontn, memltorear, memltorearn -	windows of memory-resident images	memlayer(2)	540
interviewerted singuit (12C) interviewerter	winwatch – monitor rio windows	winwatch(1)	339
inter-integrated circuit (I ² C) interface twsi -		twsi(3)	739
rio, label, window,	wloc – window system	rio(1)	250
/canqlock, qunlock, rlock, canrlock, runlock,	wlock, canwlock, wunlock, rsleep, rwakeup,/	lock(2)	526
qlock, qunlock, canqlock, rlock, runlock,	wlock, wunlock – serial synchronisation	qlock(9)	
	wol - send wake-on-lan Ethernet packet	wol(8)	
WC -	word count	wc(1)	336
/Memdata, Memdrawparam, memimageinit,	wordaddr, byteaddr, memimagemove,/	memdraw(2)	536
bullshit – assemble a stream of bullshit from	words in a file	bullshit(1)	40
writing/ /readimage, writeimage, bytesperline,	wordsperline – allocating, freeing, reading,	allocimage(2)	367
chdir – change	working directory	chdir(2)	399
pwd, pbd -	working directory	pwd(1)	232 256
rwd, conswdir – maintain remote – webfs		rwd(1)	230 826
	world wide web file system	webfs(4)	
abaco – browse the	World Wide Web files	abaco(1)	11
mothra - retrieve and display		mothra(1)	186 762
cwfs64, cwfs64x, fs64 -	worm file server, dump cwfs,	cwfs(4)	
rdarana	wpa – Wi–Fi Protected Access setup wrarena – copy arenas between venti servers	wpa(8)	
rdarena,	write	readv(2)	596
preadv, pwritev - scatter/gather read and read,	write – transfer data from and to a file	read(5)	840
read.	write, copy – simple Venti clients	venti(1)	326
read, readn,	write, pread, pwrite – read or write file	read(2)	594
bzfs – compressed	write ram filesystem	bzfs(4)	754
RGB, readcolmap,	writecolmap – access display color map	readcolmap(2)	595
/cloadimage, unloadimage, readimage,	writeimage, bytesperline, wordsperline –/	allocimage(2)	367
/readmemimage, creadmemimage,	writememimage, freememimage, /	memdraw(2)	536
- optical disc (CD, DVD, B) track reader and	writer file system cdfs, cddb	cdfs(4)	755
- spin locks, queueing rendezvous locks,	writer locks, rendezvous points, and/ /decref	lock(2)	526
/subfontname, readsubfont, readsubfonti,	writesubfont, stringsubfont, strsubfontwidth,/	subfont(2)	633
and write readsubionit, readsubionit,	writev, preadv, pwritev – scatter/gather read	readv(2)	596
open, create, close – open a file for reading or	writing, create file	open(2)	566
wordsperline – allocating, freeing, reading,	writing images /writeimage, bytesperline,	allocimage(2)	367
/enable, disable, authsrv, guard.srv, debug,	wrkey, login, newns, none, as – maintain or/	auth(8)	930
stat,	wstat – inquire or change file attributes	stat(5)	842
dirfwstat, nulldir – get and put file/ stat, fstat,	wstat, fwstat, dirstat, dirfstat, dirwstat,	stat(2)	626
qunlock, canglock, rlock, runlock, wlock,	wunlock – serial synchronisation glock,	glock(9)	
/rlock, canrlock, runlock, wlock, canwlock,	wunlock, rsleep, rwakeup, rwakeupall, incref,/	lock(2)	526
/ecpubfree, X509toECpub, X509ecdsaverify,	X509ecdsaverifydigest – elliptic curve/	ec(2)	441
/X509rsagen, X509rsareg, X509rsaverify,	X509rsaverifydigest – RSA encryption/	rsa(2)	601
ecencodepub, ecdecodepub, ecpubfree,	X509toECpub, X509ecdsaverify, / /ecdsaverify,	ec(2)	441
/rsaprivtopub, rsapuballoc, rsapubfree,	X509toRSApub, X509rsagen, X509rsareq,/	rsa(2)	601
vmx -	x86 virtualization interface	vmx(3)	747
memory management xalloc,	xallocz, xspanalloc, xfree, xsummary - basic .	xalloc(9)	1106
,	xargs - construct argument list and execute	xargs(1)	340
	xd – hex, octal, decimal, or ASCII dump	xd(1)	341
/adjoint, invertmat, xformpoint, xformpointd,	xformplane, pushmat, popmat, rot, qrot,/	matrix(2)	534
management xalloc, xallocz, xspanalloc,	xfree, xsummary - basic memory	xalloc(9)	1106
<pre>- extract/ doc2txt, doc2ps, wdoc2txt,</pre>	xls2txt, olefs, mswordstrings, msexceltables .	doc2txt(1)	77
file transfer con, telnet, rx, hayes, xms,	xmr - remote login, execution, and XMODEM	con(1)	53
xalloc, xallocz, xspanalloc, xfree,	xsummary - basic memory management	xalloc(9)	1106

This book was typeset by the authors; the input text was characters from the Unicode Standard encoded in UTF-8.

The fonts used were Lucida Sans, in a special version incorporating over 1700 characters from the Unicode Standard, along with Lucida Sans Italic, Lucida Sans DemiBold, and Lucida Typewriter, designed by Bigelow & Holmes, Atherton, California. The hinted Adobe Type 1 representation of the fonts was provided by Y&Y Inc., 45 Walden Street, Concord, MA, 01742, USA.